

Employee Data Sync with SCIM to WorkInSync/Moveinsync (OKTA)

Document Control	
Document Name	Employee Data Sync with SCIM to WorkInSync/Moveinsync (OKTA)
Version No	1.1
Classification	Confidential
Date	Jul 15, 2022

Version Control				
Ver No.	Author	Approved by	Approved Date	Description
1.0	Rishabh	Ujjwal		First Version

WorkInSync application supports automatic synchronization of employee data between source identity management system of client and WorkInSync systems. WorkInSync provides SCIM (System for cross domain identity management <https://datatracker.ietf.org/doc/html/rfc7644>) compliant API interface for this purpose.

Entities Supported

1. Users

Entities not supported

1. Groups


The process below describes the steps to enable employee data sync between WorkInSync and OKTA. However, this can be extended to any SCIM compliant source system such as a HRMS or a Identity provider.

Prerequisite


Please reach out to KDV to get the token to be shared with the client in the next steps.

Configuring WorkInSync app on your OKTA


1. Login to your OKTA Portal <https://developer.okta.com/login/> with a developer account.
2. Select **Applications > Applications**




3. Click **Browse App Catalog**




4. Search for SCIM 2.0. After searching you see template applications for each of the three authentication methods used to connect to your SCIM implementation: Basic Auth, Header Auth, or OAuth Bearer Token. Please select **SCIM 2.0 Test App (Header Auth)**



5. Click on **add integration**



6. On the General Settings page: Set the name of your application, choose if it's hidden from general and mobile users, and choose if users' are automatically signed in from the landing page. Click Next.



7. Go to the Provisioning tab and click on “Configure API Integration”

Q Search...

?

deepanshu.tyagi@...

okta-dev-69919717

SCIM

Active

View Logs Monitor Imports

i

Once you have a working SCIM integration, submit it for Okta review to use in production and to publish in the OAN.

Submit your app for review

General

Sign On

Provisioning

Import

Assignments

Push Groups

Settings

Integration

Provisioning is not enabled

Enable provisioning to automate SCIM 2.0 Test App (Header Auth) user account creation, deactivation, and updates.

Configure API Integration

8. In the Base URL field, enter <https://scim.workinsync.io/scim/v2> for AWS Singapore hosted tenants.
For EU hosted tenants use <https://scim.eu.workinsync.io/scim/v2/>
And secret token as the unique token generated and shared by your WorkInSync account manager with you.

Once you have a working SCIM integration, submit it for Okta review to use in production and to publish in the OAN.

Submit your app for review

General

Sign On

Provisioning

Import

Assignments

Push Groups

Settings

Integration

Cancel

☒ Enable API integration

Enter your SCIM 2.0 Test App (Header Auth) credentials to enable user import and provisioning features.

Base URL

API Token

Test API Credentials

Save

- Click on **Test API Credentials** to ensure they are working fine.
- Go to the provisioning tab again and select the actions that you want to perform. Ideally, Create, Update and Delete of users is enabled.

If you experience an issue with the email delivery and if allow list is configured in your infrastructure. Please see this [link](#) for details on adding the IP addresses. ✕

Search...



deepanshu.tyagi@...
okta-dev-69919717

General Sign On **Provisioning** Import Assignments Push Groups

Settings

To App

To Okta

Integration

okta



SCIM

Provisioning to App

Cancel

Create Users

☒ Enable

Creates or links a user in SCIM 2.0 Test App (Header Auth) when assigning the app to a user in Okta.

The [default username](#) used to create accounts is set to **Okta username**.

Update User Attributes

☒ Enable

Okta updates a user's attributes in SCIM 2.0 Test App (Header Auth) when the app is assigned. Future attribute changes made to the Okta user profile will automatically overwrite the corresponding attribute value in SCIM 2.0 Test App (Header Auth).

Deactivate Users

☒ Enable

Deactivates a user's SCIM 2.0 Test App (Header Auth) account when it is unassigned in Okta or their Okta account is deactivated. Accounts can be reactivated if the app is reassigned to a user in Okta.

Sync Password

☐ Enable

11. There is also an attribute settings section, which helps you to decide which field will map to which field.

SCIM 2.0 Test App (Header Auth) Attribute Mappings

Select a(n) SCIM 2.0 Test App (Header Auth) attribute to set its value based on values stored in Okta.

[Go to Profile Editor](#)
[Force Sync](#)

Attribute	Attribute Type	Value	Apply on
Username userName	Personal	Configured in Sign On settings	
Given name givenName	Personal	user.firstName	Create ✎ ✕
Family name familyName	Personal	user.lastName	Create ✎ ✕
Middle name middleName	Personal	user.middleName	Create ✎ ✕
Honorific prefix honorificPrefix	Personal	user.honorificPrefix	Create ✎ ✕
Honorific suffix honorificSuffix	Personal	user.honorificSuffix	Create ✎ ✕
Email email	Personal	user.email	Create ✎ ✕
Primary email type emailType	Personal	(user.email != null && user.email != "") ? 'work' : ""	Create ✎ ✕

Primary email type emailType	Personal	(user.email != null && user.email != '') ? 'work' : ''	Create		
Title title	Personal	user.title	Create		
Display name displayName	Personal	user.displayName	Create		
Nickname nickName	Personal	user.nickName	Create		
Profile Url profileUrl	Personal	user.profileUrl	Create		
Primary phone primaryPhone	Personal	user.primaryPhone	Create		
Primary phone type primaryPhoneType	Personal	(user.primaryPhone != null && user.primaryPhone != '') ? 'work' : ''	Create		
Address type addressType	Personal	(user.streetAddress != null && user.streetAddress != '') ? 'work' : ''	Create		
Street address streetAddress	Personal	user.streetAddress	Create		
Locality locality	Personal	user.city	Create		
Region region	Personal	user.state	Create		
Postal Code postalCode	Personal	user.zipCode	Create		
Country country	Personal	user.countryCode	Create		

WorkInSync supports following attributes out of the box as described in the table below. Any extra field even if present in the mapping is not captured or processed by WorkInSync.

AD Attribute	SCIM Attribute	WorkInSync field or description of how we use it
userPrincipalName	userName	Primary unique ID in Workinsync
displayName	displayName	used as is for name field in workinsync, if not available, given name + last name is used

mail	emails[type eq "work"].value	email
givenName	name.givenName	First name
surname	name.familyName	Last name
physicalDeliveryOfficeName	addresses[type eq "work"].formatted	office
streetAddress	addresses[type eq "work"].streetAddress	Applicable only for commute clients
city	addresses[type eq "work"].locality	Applicable only for commute clients
state	addresses[type eq "work"].region	Applicable only for commute clients
postalCode	addresses[type eq "work"].postalCode	Applicable only for commute clients
country	addresses[type eq "work"].country	Applicable only for commute clients
telephoneNumber	phoneNumbers[type eq "work"].value	Applicable only for commute clients
mailNickname	externalId	required by SCIM protocol
employeeId	urn:ietf:params:scim:schemas:extension:enterprise:2.0:User:employeeNumber	Optional Employee ID
department	urn:ietf:params:scim:schemas:extension:enterprise:2.0:User:department	team
manager	urn:ietf:params:scim:schemas:extension:enterprise:2.0:User:manager	manager (foreign key relationship to the user object which is manager)

If any additional field is present in default attribute mapping, and the client doesn't want to send it to WorkInSync, they should delete the mappings.

WorkInSync only will be concerned with the mapped SCIM attribute. So if the required information is being stored in a different field than the one specified above in the source system, the same mapping should be created instead of the sample mapping specified.

- In the 'Settings' section you can configure an email address which can be notified in case of errors. Leave scope to 'all users and groups'

Save changes and Turn on provisioning.

Once setup, by default data is synced every 40 minutes. The 'Provisioning' option against the app you just created will give you an overview of the current state of sync and any errors which have happened recently.

You can also turn on and off employee sync to workinsync from here.

For any specific records which failed, you can retry with the 'Provision on Demand' option to resync a specific employee record with WorkInSync.