


COMPUTER NETWORKS

INTRODUCTION TO CN AND IP ADDRESS



join us on
TELEGRAM
@freeCBCB4all

⇒ The service that is used to convert the Domain name to IP Address is called Domain Name Service

⇒ port number is used to identify a particular process in the host, for well known services the port num are already predefined and fixed

$$\text{http} \Rightarrow \text{port num} = 80$$

$$\text{SMTP port num} = 25$$

$$\text{ftp} \Rightarrow \text{port num} = 21$$

⇒ Even though your intention is to reach google.com you are visiting DNS first and then getting the IP Address of google.com and then visiting the google home page. This is actually a overhead which is also called "DNS overhead". So this problem of overhead can be rectified by, when you get the IP Address of google.com you store it actually on your computer for some time, and if you again want to visit google you can directly get IP Address from your computer. If your IP Address in computer expires, there is no another alternative, you have to go to DNS.

Binary = 0, 1

$$2^2 = 4$$

Binary = 0, 1

Octal = 0, 1, 2, ..., 7

$$2^{10} = 1024 = K$$

Decimal = 0, 1, 2, ..., 9

$$M = 2^{20}$$

Hexa decimal = 0, 1, 2, ..., 9

$$G = 2^{30}$$

A, B, ..., F
10, 11, 12

$$T = 2^{40}$$

$K = 2^{10}$
$M = 2^{20}$
$G = 2^{30}$
$T = 2^{40}$

Now, the possible binary numbers with 1 Bit, 2 Bits, 3 Bits are

<u>1 Bit</u>	<u>2 Bits</u>	<u>3 Bits</u>
0	0 0	0 0 0
1	0 1	0 0 1
	1 0	0 1 0
	1 1	0 1 1
		1 0 0
		1 0 1
		1 1 0
		1 1 1

PART 1 (Having 00 in first 2 digits)

PART 2 (Having 01 in first 2 digits)

PART 3 (Having 10 in first 2 digits)

PART 4 (Having 11 in first 2 digits)

⇒ No. of possible sets formed by 1 bit = 2


⇒ If i choose 1 bit I am going to divide the number space into 2 parts = 2

⇒ If i choose 2 bits I am going to get 4 parts = 2^2

⇒ If i choose K bits the number space / Address space will be divided into

2^K parts

⇒ So, if i have 'n' bits the no. of possible ways are 2^n




2^n combinations

Now, if i choose 'K' bits the entire space will be divided into 2^K parts

⇒ 2^K parts = 2^n numbers

⇒ 1 part = $2^n / 2^K$ numbers

⇒ 1 part = 2^{n-K} numbers




⇒ Size of Each NID = 2^{n-K}

⇒ In operating system 'n' bits = Address, K = page offset / Blk no / Segment no

⇒ In computer organization 'K' = TAG, (n-K) = Block SIZE.


⇒ IP Address size = 32 bits in CN. $\Rightarrow 2^{32}$ IP Address are possible

CLASS FULL IP ADDRESS CLASSIFICATION



The no. of IP Addresses possible in a N/w of class A = 2^{31} class C = 2^{29}
 class B = 2^{30} class D = 2^{28}

Now, the popular Representation of IP Address = Binary Notation, Dotted decimal Notation(4 octets)



CA = starts with '0'


CD = starts with 1110

CB = starts with 10

CE = starts with 1111

CC = starts with 110

CLASS A



⇒ The No. of possible N/w's of class A = $2^7 = 128$

⇒ size of each Network = $2^{24} = 16M$ (NASA/PENTAGON)

USES CA]

⇒ No. of hosts = $(2^{24} - 2)$

⇒ But practically 126 N/w's are possible in CA


$$\begin{array}{r} 0 \dots \\ \text{bit 0} \text{ of NID} \quad \text{bit 0} \text{ of HID} \\ \hline 00000000 = 0 \\ 00000001 = 1 \\ \vdots \\ 11111111 = 127 \end{array}$$

⇒ we don't use the starting Address (All 0s) and last Address (all ones)

⇒ ∴ No. of N/w's in CA = $128 - 2 = 126$ practically.

RANGE = 0-126

CLASS B



$$\Rightarrow \text{No. of IP Addresses} = 2^{30}$$

$$\Rightarrow \text{No. of N/w's of CB} = 2^4 \approx 16,000 = 16\text{K N/w}$$

$$\Rightarrow \text{Size of each network} = 2^{16} \text{ IP Address in one N/w}$$

$$\Rightarrow \text{No. of hosts} = (2^{16} - 2) \quad \text{N/w's of CB}$$

$$\Rightarrow 10 \dots \dots \dots$$


$$00\ 00\ 00 = 128$$

$$00\ 00\ 01 =$$

$$11\ 11\ 11 = 191$$

$$\Rightarrow \boxed{\text{RANGE} = 128-191}$$

CLASS C



$$\Rightarrow \text{No. of IP Addresses} = 2^{29}$$

$$\Rightarrow \text{No. of N/w's of CC} = 2^1 \text{ N/w's} = 2\text{million}$$

$$\Rightarrow \text{Size of Each N/w} = 2^8 \text{ IP Address are in one N/w of CC}$$

$$\Rightarrow 110 \dots \dots$$

$$00\ 00\ 00 = 192$$

$$00\ 00\ 01 = 193$$

A 229

$$\Rightarrow 111 \dots \dots = 223 \Rightarrow \text{No. of hosts} = (2^8 - 2)$$

$$\Rightarrow \boxed{\text{RANGE} = 192-229}$$

CLASS D

There is nothing called as N/w ID and HID in CD and CE

CD

$$\begin{array}{r} 1110 \dots \dots \\ 00\ 00 = 224 \end{array}$$

$$111 \dots \dots = 239$$

$$\boxed{\text{RANGE} = 224-239}$$

1) Used for Multicasting

2) Group Emailing, Group Broadcasting

CE

$$\begin{array}{r} 111 \dots \dots \\ 00\ 00 = \end{array}$$

$$111 \dots \dots = 255$$

$$\boxed{\text{RANGE} = 240-255}$$

1) Used for Military Applications


2. TYPES OF CASTING - UNICAST, LIMITED BROADCAST, DIRECTED BROADCAST

CASTING

1. Unicast - one host to one host
2. Broadcast - one host to many hosts


Limited Broadcasting

Directed Broadcasting



⇒ when I have All 0s in the HID part it represents NID that is the reason we don't use 1st IP Address as the valid IP Address to any host


LIMITED BROADCASTING



⇒ If Destination Address =

255.255.255.255 then the packet will be sent to all the hosts in the Net. LBA = 255.255.255.255

DIRECTED BROADCASTING



⇒ we are not going to use the IP Address Containing all 1s in HID part, it is used for DIRECTED BROADCASTING (DBA).

DBA: NID, HID= all 1s

IP Address

NID

DBA

LBA

1.2.3.4

1.0.0.0

1.255.255.255

255.255.255.255

10.16.20.60

10.0.0.0

10.255.255.255

255.255.255.255

130.1.2.3

130.1.0.0

130.1.255.255

255.255.255.255

150.0.150.150

150.0.0.0

150.0.255.255

255.255.255.255

200.1.10.100

200.1.10.0

200.1.10.255

255.255.255.255

220.15.1.10

200.15.1.0

200.15.1.255

255.255.255.255

250.0.1.2

X

X

X

300.1.2.3

X

X


X

3 SUBNETS, SUBNET MASK, ROUTING


→ when the size of the Network is Big then the maintenance will be difficult.

→ Lack of security when the size of Network is Big, so we divide the Network into small parts and this process is called Subnetting.

→ "SUBNETTING" is the process of dividing the Network into Smaller Networks.




Now, ambiguity arises in the above subnetting, if it is say 200.1.2.0 it means the whole network or only the first subnet and if it is say 200.1.2.255 then there is a dilemma whether to transfer the packet to all the hosts in the Network or only to the hosts present in the subnet A. So this depends upon where we are standing. If we are outside the network then we assume that the packet should be transmitted to all the hosts in the network; if I am standing inside the packet will be transmitted to the hosts in subnet A.




* There will be loss of IP addresses due to "SUBNETTING".

FOUR SUBNETS



The practical view is:



SUBNET MASK

SM: 32-bit Number

1's: SID, NID part

0's: HID part

Now, the subnet mask for the above NID will

be $\frac{\text{NID}}{200.1.2.0} \rightarrow 255.255.255.192$

$$SM = 255.255.255.192$$

Given an IP Address, if you bitwise AND with SM you will get NID for which the IP belongs to.

SM & IP = NID for which the given IP Belongs


$$IP: 11001000.00000001.00000010.10000020 = 200.1.2.130$$

$$SM: 11111111.11111111.11111111.11000000 = 255.255.255.192$$


$$NID: 11001000.00000001.00000010.10000000$$

$$200.1.2.128$$

ROUTING TABLE



4. VARIABLE LENGTH SUBNET MASKING



Step 1: Divide the entire NID into 2 parts choosing 1 bit

Step 2: Divide the subnet (your choice) into 2 parts by choosing another bit
then you will get 3 subnets

⇒ The NIDs that are having same sizes have the same "Subnet mask".

⇒ when the NID size is Big then the SM will be small.

when the NID size is small then the SM will be Big.

ROUTING TABLE

<u>NID</u>	<u>SM</u>	<u>INTERFACE</u>
200.1.2.0	255.255.255.128	a
200.1.2.128	255.255.255.192	b
200.1.2.192	255.255.255.192	c
0.0.0.0	0.0.0.0	d

Now, Given Subnet mask : 255.255.255.192

$$= (11111111.11111111.11111111.00000000) = (2618, 6\text{ bits})$$

$$0 - 00000000$$

$$\therefore \text{NID} + \text{SID} = \text{No. of 1s}$$

$$128 - 10000000$$

$$\therefore \text{NID} + \text{SID} = 26 \rightarrow \text{if class A is subnetted, then,}$$

$$192 - 11000000$$

$$8 + \text{SID} = 26 \Rightarrow \boxed{\text{SID} = 18}$$

$$224 - 11100000$$

$$\therefore \text{No. of Subnets} = 2^{18}$$

$$240 - 11110000$$

$$\rightarrow \text{if CB, NID} + \text{SID} = 26$$

$$248 - 11111000$$

$$\boxed{\text{SID} = 26 - 16 = 10} = 2^{10} \text{ Subnets}$$

$$252 - 11111100$$

$$\rightarrow \text{if CC, NID} + \text{SID} = 26$$

$$254 - 11111110$$

$$\boxed{\text{SID} = 26 - 24 = 2} = 2^2 \text{ subnets}$$

$$255 - 11111111$$


5. SUBNET MASKING QUESTION

<u>SUBNET MASK</u>	<u>No. of Hosts</u>	<u>SUBNETS IN CA</u>	<u>CB</u>	<u>CC</u>
CA 255.0.0.0	$2^{24} - 2$	2^{24}	-	-
255.128.0.0	$2^{23} - 2$	2^1	-	-
255.192.0.0	$2^{22} - 2$	2^2	-	-
255.240.0.0	$2^{20} - 2$	2^4	2^{20}	2^{20}
255.255.0.0	$2^{16} - 2$	2^8	2^{16}	2^{16}
255.255.254.0	$2^{12} - 2$	2^5	2^{12}	2^5
255.255.255.0	$2^8 - 2$	2^6	2^8	1
255.255.255.24	$2^5 - 2$	2^4	2^5	2^3
255.255.255.240	$2^1 - 2$	2^0	2^12	2^4

CLASSLESS INTER DOMAIN ROUTING (L-6)

IANA = Internet Assigned Number Authority

→ Generally the IP Addresses in CIDR Notation



is represented as a.b.c.d/n

→ n = NID bits → if n=20, NID = 20 bits

HID = 12 bits

→ n = Slash Number

32 bits
48 bits

FORMATION OF CIDR BLOCKS

These are the Rules for forming CIDR Blocks

1) All the IP Addresses should be contiguous

2) The Block size should be a power of 2

3) The Starting Address should be divisible by evenly
size of the Block.

$\frac{(n-k) \text{ bits}}{k \text{ bits}}$
← n-bit → Binary Number

$[n/2^k]$ ⇒ last k bits = Remainder
last $(n-k)$ bits = Quotient

100.1.2.32 100.1.2.33 100.1.2.47

Whether these IP Addresses form a CIDR Block?

Rule 1 ✓

Rule 2: No. of IP Addresses = 16 = 2^4 ✓ ⇒ HID = 4, BID = 28

Rule 3: $100.1.2.00100000 \div 2^4 = \text{LSB (4 bits)}$ {Least significant bits} = 0000 ✓

∴ They form CIDR Block

2) 20.10.30.32

20.10.30.33

20.10.30.34

20.10.30.63

Rule 1 = ✓

Rule 2: $(63-32)+1 = 32 = 2^5$ ✓ (In powers of 2) HID = 5 bits

Rule 3: $20.10.30.00100000 \div 2^5 = \text{last 5 bits}$

= 00000 ✓

∴ They form CIDR Block

3>

$150 \cdot 10 \cdot 20 \cdot 64$

$150 \cdot 10 \cdot 20 \cdot 65$

$150 \cdot 10 \cdot 20 \cdot 66$

!

$150 \cdot 10 \cdot 20 \cdot 127$

Rule 1 ✓

Rule 2: $(127 - 64) + 1 = 64 = 2^6 \Rightarrow \text{HID} = 6, \text{BID} = 26 \text{ Bits}$

Rule 3: $150 \cdot 10 \cdot 20 \cdot 01000000 \div 2^6 = 000000 \checkmark$

FORM
CIDR
BLOCK ✓

4>

$20 \cdot 10 \cdot 30 \cdot 35 / 27$ Derive the Range of CIDR Block?

$\Rightarrow \text{BID} = 27 \text{ bits}$

$\text{HID} = 5 \text{ bits}$

BID HID
 $20 \cdot 10 \cdot 30 \cdot 001 \underline{00011}$

$0000 = 32$


$0001 = 33$

!

$1111 = 63$

$01010000 \underline{00000000}$
 00000000
 $\Rightarrow \text{Block} = 20 \cdot 10 \cdot 30 \cdot 32$
 $20 \cdot 10 \cdot 30 \cdot 33$
!

$20 \cdot 10 \cdot 30 \cdot 63$



5>

$100 \cdot 1 \cdot 2 \cdot 35 / 28$

$\text{BID} = 27 \text{ bits}$

$\text{HID} = 5 \text{ bits}$

BIK NO=BIKID

$100 \cdot 1 \cdot 2 \cdot 0010 \underline{0011}$

$100 \cdot 1 \cdot 2 \cdot 32$

$100 \cdot 1 \cdot 2 \cdot 33$

!

$100 \cdot 1 \cdot 2 \cdot 47$

6> $100 \cdot 1 \cdot 2 \cdot 35 / 20$


BID
 $100 \cdot 1 \cdot 000000010 \cdot 00100011$

$0000 \cdot 000000000 = 0 \Rightarrow 100 \cdot 1 \cdot 0 \cdot 0$

$11 \underline{11} \cdot 1111111 = 100 \cdot 1 \cdot 15 \cdot 255$


15

7. SUBNETTING IN CIDR, VLSM IN CIDR



VLSM IN CIDR BLOCKS

i) $20 \cdot 30 \cdot 40 \cdot 10 / 25$



Now, BLK ID

$20 \cdot 30 \cdot 40 \cdot 0 \quad 0000 \ 10 \ 10$

$0000 \ 0000 = 0$

$1111 \ 1111 = 127$


10000000

01

10000000 00 . 01 . 00

$20 \cdot 30 \cdot 40 \cdot 0 / 26$

$\frac{0}{2}$



$20 \cdot 30 \cdot 40 \cdot 10 / 25$

$\frac{1}{2} \Rightarrow 20 \cdot 30 \cdot 40 \cdot 64 / 27$

$\frac{1}{2}$

$20 \cdot 30 \cdot 40 \cdot 96 / 27$

CA = $20 \cdot 30 \cdot 40 \cdot 0 / 26$

CB = $20 \cdot 30 \cdot 40 \cdot 64 / 27$


Customers = $20 \cdot 30 \cdot 40 \cdot 96 / 27$

8. SOME INTERESTING PROBLEM ON SUBNET MASK

⇒ Subnet mask is sometimes called as "Network mask".

⇒ whenever you open "ipconfig" in your computer you will see these things

- 1> IPv4 Address: provided by ISP
- 2> Default Gateway: Default Router connected to your n/w
- 3> Subnet Mask: Subnet mask which you should use
- 4> DNS: conversion of IP address.



Let I_A = Ip Address of A

I_B = Ip Address of B

S_A = Subnetmask of A

S_B = Subnetmask of B

⇒ Now if you want send a packet from 'A' to 'B' there are 2 cases possible

1: 'B' may be in different network and you want to send first to DGW and

DGW will forward the packet to 'B'

2. 'B' may be in same Network so that you can send the packet directly

Now what 'A' does is

A: I_A

S_A

B: I_B

S_B

$$\text{Bitwise AND} = \frac{((\text{NID})_A)}{\text{Acc to A}}$$

$$\frac{((\text{NID})_B)}{\text{Acc to A}}$$

If

$$\frac{((\text{NID})_A)}{\text{Acc to A}} = \frac{((\text{NID})_B)}{\text{Acc to A}}$$

then A, B are in same NW

$I_A: 200.1.2.10$

$I_B: 200.1.2.130$

$S_A: 255.255.255.128$


Now, $I_A: 11001000.00000001.00000010.00001010$

$S_A: 11111111.00000000.11111111.10000000$

$$\frac{((\text{NID})_A)}{\text{Acc to A}} = \frac{200.1.2.0}{255.255.255.128}$$

$I_B: 200.1.2.130$

$$\frac{S_A}{((\text{NID})_B)} = \frac{255.255.255.128}{200.1.2.128}$$



$$\frac{((\text{NID})_A)}{\text{Acc to A}} \neq \frac{((\text{NID})_B)}{\text{Acc to A}}$$

∴ 'A' assumes that 'B' is in diff Network.

② $I_A: 200.1.2.10$

$I_B: 200.1.2.69$

$S_A: 255.255.255.128$

$S_B: 255.255.255.192$

I_A	I_B
S_A	S_B
$200.1.2.0 \in \frac{((\text{NID})_A)}{\text{Acc to A}}$	$\frac{((\text{NID})_B)}{\text{Acc to A}} \rightarrow 200.1.2.0$

I_B	I_A
S_B	S_A
$200.1.2.64 \in \frac{((\text{NID})_B)}{\text{Acc to B}}$	$\frac{((\text{NID})_A)}{\text{Acc to B}} = 200.1.2.0$

If $\frac{((\text{NID})_A)}{\text{Acc to A}} = \frac{((\text{NID})_B)}{\text{Acc to B}} \Rightarrow 'A' \text{ think } 'B' \text{ is in same NW.}$

$\Rightarrow 'B' \text{ think } 'A' \text{ is in another NW.}$

9. SUPERNETTING OR AGGREGATION

→ If we look at the Routing table, it contains a single entry for all networks, now if the networks are large then the size of the routing table may grow exponentially, so that router takes lot of time to process the Routing table, hence we need to Aggregate / combine / super the Networks.

RULES FOR AGGREGATION

- 1) All the Networks should be contiguous. (Network Id's)
- 2) Size of each Network should be same and in turn they should be in powers of 2.
- 3) 1st Address should be divisible by size of Block

Aggregate the following Networks

1) 200.1.0.0/24

Rule 1 ✓

Total Size of Network = 4×2^3
 $= 2^{10}$

2) 200.1.1.0/24


Rule 2: ✓

3) 200.1.2.0/24

Rule 3: ✓ $200.1.00000000.00000000 \div 2^{10}$

4) 200.1.3.0/24

= Divisible



The Routing table at R2 looks like

NID	SM	INTERFACE
200.1.0.0	255.255.255.0	a
200.1.1.0	255.255.255.0	a
200.1.2.0	255.255.255.0	a
200.1.3.0	255.255.255.0	a

SUPERNET MASK

Supernet mask : 32 bits

: No of 1's = Fixed part

: No. of 0's = Variable part


FIXED PART	VARIABLE PART
200.1.000000	00.00000000
200.1.000000	01.00000000
200.1.000000	10.00000000
200.1.000000	11.00000000
255.255.111111	00.00000000

$$\text{Supernet mask} = 255.255.252.0$$

Now, the N/w id of the Aggregated N/w is same as the starting IP address
 $= 200.1.0.0/24$ (8)

SHORTCUT TO FIND FIXED AND VARIABLE PARTS

Size of all N/w = $2^3 + 2^3 + 2^3 + 2^3 = 2^{10}$ \Rightarrow Host id part should contain 10 bits
 (with principle, all at least one bit) \Rightarrow SID part contains 22 bits



NID SM INTERFACE

\Rightarrow Now, the Routing table at R₂ look like

200.1.0.0	255.255.252.0	a
-----------	---------------	---

2)

100.1.2.0/25

100.1.2.128/26

100.1.2.192/26

Consider all the available subnets

Aggregate them!

These can be aggregated first

Rule 1 ✓

Rule 2 ✓

Rule 3 ✓

\Rightarrow All the Address are contiguous ✓, but of diff sizes

\Rightarrow The N/w 100.1.2.128/26 } These can be Aggregated first
 100.1.2.192/26 }

\Rightarrow Total size of N/w = $2^6 \times 2 = 2^7$ \Rightarrow NID=7 \Rightarrow NID=25 bits

\Rightarrow The N/w of the above Aggregated N/w = 100.1.2.128/25 and now combine
 with 1st N/w 100.1.2.0/25

\Rightarrow 100.1.2.0/25 } Rule 1 ✓

100.1.2.128/25 } Rule 2 ✓

Rule 3 ✓


N/w id of Supernet = 100.1.2.0/24

Supernet mask = 255.255.255.0

Now size of N/w = 2×2^7

$$= 2^8 \Rightarrow \text{NID}=24, \text{SID}=8$$

for broadcast of 1st subnet bits 200.1.0.0/24 A node at id 0 get atleast 2nd bit



"while propagating" bits of 2nd bit

so broadcast of 1st subnet bits 200.1.0.0/24


propagation of 2nd subnet bits 200.1.0.0/24

2. FLOW CONTROL METHODS

DELAYS IN CN (L-1)

TRANSMISSION DELAY (T_t):

The time taken to transmit the packet from a host to the outgoing link is called "transmission delay".



Bandwidth = 1 bps (In one second we can transmit 1 bit to the outgoing link)

Data = 10 bits

$$\Rightarrow \text{Transmission delay} = 10 \text{ sec (for 10 bits)}$$

So, If size of datapacket is 'L' bits and Bandwidth is 'B' bps then the

$$\text{Transmission delay} = \frac{L}{B} \text{ sec}$$

$$T_t = \frac{L}{B} \text{ sec}$$

1) If $L = 1000 \text{ bits}$, $Bw = 1 \text{ Kbps}$ $\Rightarrow T_t = \frac{L}{B} = \frac{1000}{1000} = 1 \text{ sec}$

2) $L = 1 \text{ Kb}$, $Bw = 1 \text{ Kbps}$ $\Rightarrow T_t = \frac{L}{B} = \frac{1024}{1000} = 1.024 \text{ sec}$

DATA

$$K = 1024 \text{ bits}$$

BANDWIDTH

$$K = 1000$$

$$M = 1024 \times 1024$$


$$M = 1000 \times 1000 = 10^6$$

$$G = 1024 \times 1024 \times 1024$$

$$G = 1000 \times 1000 \times 1000 = 10^9$$

PROPAGATION DELAY (T_p):

The time taken by a bit to reach from one end of the link to other end of the link is called "propagation delay".



The propagation delay depends upon 1) distance

2) velocity

$$T_p = \frac{d}{v}$$

⇒ In case of optical fibers the speed of the signal is approximately 70% of speed of light $\Rightarrow v = \frac{70}{100} \times 3 \times 10^8 \text{ m/s}$

$$\Rightarrow v = 2.1 \times 10^8 \text{ m/s}$$


∴ $d = 2.1 \text{ km}$

$$v = 2.1 \times 10^8 \text{ m/s}$$

$$T_p = \frac{d/v}{100} = \frac{2.1 \times 10^3 \text{ m}}{2.1 \times 10^8 \text{ m/s}} = 10^{-5} \text{ sec} = \frac{10^{-5} \times 10^3}{10^3} = 10^{-2} \text{ msec}$$

Now, the total time taken to send a packet from source to Destination = $T_t + T_p$


QUEUING DELAY (T_q):

⇒ The amount of time the packet sits in the Queue before it gets processed is called queuing delay (T_q). 

⇒ Whenever the packet is received by the Receiver, it may or may not get immediately processed they are going to sit in Buffer (Queue).

2. FLOW CONTROL STOP AND WAIT

⇒ Stop and wait is the simplest flow control mechanism in which the sender sends a packet and then stop and wait for the acknowledgement from the Receiver, before sending the next packet.



$$\text{Total time} = T_t(\text{data}) + T_p(\text{data}) + T_q +$$

$$T_p(\text{process}) + T_t(\text{ACK}) + T_p(\text{ACK})$$

$$= T_t(\text{data}) + 2 * T_p + T_t(\text{ACK})$$

$$\boxed{\text{Total time} = T_t + 2 * T_p \text{ for sending 1 packet}}$$

$$\eta = \frac{\text{useful time}}{\text{Total cycle time}} = \frac{T_t}{T_t + 2 * T_p} = \frac{T_t}{T_t(1 + 2 * \frac{T_p}{T_t})} = \frac{1}{1 + 2a} \quad (\text{where } \frac{T_p}{T_t} = a)$$

Throughput = No. of bits we can send in a second using this protocol

$$\Rightarrow \text{Throughput} / = \frac{L}{T_t + 2 \cdot T_p} \Rightarrow \frac{L \times B \times (\eta_B)}{T_t + 2 \cdot T_p} = \frac{T_t}{T_t + 2 \cdot T_p} * B_W$$

Effective Bandwidth / Bandwidth Utilisation / Link Utilisation

$$\Rightarrow \frac{1}{1+2\alpha} * B_W = \eta \times B_W$$

$$\therefore \boxed{\text{Throughput} = \eta \times B_W}$$

1)

$$T_t = 1 \text{ msec} \quad \text{Efficiency } (\eta) = \frac{T_t}{T_t + 2 \cdot T_p} = \frac{1}{1+2} = \frac{1}{3}$$

$$T_p = 1 \text{ msec}$$

2)

$$T_t = 2 \text{ msec} \quad \eta_B = \frac{T_t}{T_t + 2 \cdot T_p} = \frac{2}{2+2(1)} = \frac{2}{4} = \frac{1}{2} = 0.5 = 50\%$$

$$T_p = 1 \text{ msec}$$

3) Now if the efficiency has to be 50%, what is the relation between T_t ?

$$\eta = 50\% = \frac{1}{2} \Rightarrow \frac{T_t}{T_t + 2 \cdot T_p} \geq \frac{1}{2}$$

MIN CONTROL STOP AND WAIT

$$\Rightarrow 2T_t \geq T_t + 2T_p$$

$$\Rightarrow T_t \geq 2T_p \Rightarrow \frac{1}{B} \geq 2T_p$$

$$\Rightarrow L \geq 2 \cdot T_p \cdot B$$

4) $B_W = 4 \text{ Mbps}$

$$T_p = 1 \text{ msec}$$

$$L = ? \text{ so that } \eta = \text{atleast } 50\% ?$$

$$L \geq 2 \cdot T_p \cdot B_W$$


$$L \geq 2 \times 1 \times 10^3 \times 4 \times 10^6$$

$$\boxed{L \geq 8 \times 10^9 \text{ bits}}$$

$$\Rightarrow \text{Now, } \eta = \frac{1}{1+2\alpha} = \frac{1}{2 + 2(\frac{TP}{T_E})} = \frac{\frac{1}{2} \cdot \frac{1}{1+\alpha}}{1 + 2 \cdot \frac{d}{V} \cdot \frac{B}{L}} \Rightarrow \boxed{\eta \approx \frac{1}{d}}, \text{ SAW is best for LANs}$$

(10)

67




∴ STOP AND WAIT + TIMEOUT TIMER

⇒ STOP AND WAIT ARQ {Automatic Repeat Request}

DATA PACKET LOSS PROBLEM ⇒ {overcome by TOTIMER}

68 ACK LOST PROBLEM




⇒ Acc to sender both the data packets are same but

Acc to Receiver both the packets are different.

DUPLICATE PACKET PROBLEM ⇒ {To overcome this have sequence numbers}


SAW + TOTIMER + SEQ. NO TO DATA PACKET

69 DELAYED ACKNOWLEDGEMENT




⇒ This problem can be overcome by having sequence on ACK also.

⇒ If the Receiver receives D1 successfully then it sends ACK A2 which means {"I have successfully received D1, please send D2"}



⇒ SAW + TOTIMER + SEQ. NO TO DATA AND ACK

8) Using SAW we have to send 10 packets from Sender to Receiver of which every 4th packet is lost then how many packets are we going to send totally?



$\therefore \text{Total} = 13$, (4,7,8) \rightarrow packets are Retransmitted

9) $S \rightarrow R$, Now there are some problems in the channel due to which some of bits are lost, let us say error probability of channel is $0.2 = 20\%$. Now if I send 400 packets, then how many packets are transmitted totally.

$$\text{sol} \Rightarrow 400 + 400(0.2) + [400(0.2)](0.2) + \dots$$

$$\Rightarrow n + np + np^2 + \dots \Rightarrow n(1+p+p^2+p^3+\dots)$$

$$\Rightarrow n \left(\frac{1}{1-p} \right) = \frac{n}{1-p}$$

Here $n=400$, $\frac{400}{1-0.2} = \frac{400}{0.8} = \frac{4000}{8} = 500$ packets totally.

3. CAPACITY OF PIPE AND PIPELINING

CAPACITY OF A CHANNEL / WIRE / LINK

The capacity of channel depends on Bandwidth and propagation delay

Capacity of the channel = $Bw \times Tp$ \rightarrow Increase of Half-duplex

Capacity = $2 \times Bw \times Tp$ \rightarrow Increase of full duplex

Pipelining

$$T_t \text{ sec} = 4 \text{ packets}$$

$$1 \text{ sec} = \frac{1}{T_t} \text{ packets}$$

Now time taken to transmit one packet of data in Stop-and-wait protocol is $T_t + 2 \cdot T_p$. Now,


$$\Rightarrow (T_t + 2 \cdot T_p) = \frac{T_t + 2 \cdot T_p}{T_t} \text{ packets}$$

$$\Rightarrow T_t + 2 \cdot T_p = (1 + 2a) \text{ packets } (a = T_p/T_t)$$

Given,


$$T_t = 1 \text{ msec}$$

$$T_p = 1.5 \text{ msec}$$




$$\eta = \frac{T_t}{T_t + 2 \cdot T_p} = \frac{1}{1 + 2(1.5)} = \frac{1}{4} = 25\%$$

Now to increase the efficiency of stop-and-wait protocol,



\Rightarrow The sequence nos have to be stored in the header field of packets in a field called sequence no. field.



$T_t = 1 \text{ msec}$ } what is the sender window size to get max efficiency?
 $T_p = 49.5 \text{ msec}$

$$\underline{\approx} \quad w_s = 1+2a \Rightarrow 1+2\left(\frac{T_p}{T_t}\right) = 1+2(49.5) = 100$$


$$\text{Min. no. of sequence nos.} = 100 = (1+2a)$$

$$\text{Min. no. of bits in seq.no field} = \lceil \log_2(1+2a) \rceil = \lceil \log_2(100) \rceil = 7,$$

\Rightarrow Now, in the above problem if the min. no. of bits in seq.no field is "6", then we can get 64 seq.no(2^6) ranging from 0 - 63

$$\Rightarrow \eta = \frac{64}{100} \rightarrow \text{But I am sending only 64 due to lack of seq.no}$$


\hookrightarrow I can send 100 packets in the time available



\therefore The window size in the stop-and-wait protocol is limited by seq.no available

$$\therefore w_s = \min(1+2a, 2^n) \quad \{n = \text{no. of bits in seq.no field}\}$$

GO BACK - N (L-4)



GO BACK - N ($N > 1$)

i) Sender window size in GBN is " N "

$$T_t = 1 \text{ msec}$$

$$T_p = 49.5 \text{ msec}$$

GOBACK - 10

$$\text{Max window size} = (1+2a)$$

$$= 1+2(49.5)$$

$$= 100$$

$$BW = 40 \text{ mbps}$$

$$\text{Throughput} = ?$$


$$Th \Rightarrow \eta \times BW$$

$$= 40 \times \frac{10}{100}$$


$$Th = 4 \text{ mbps}$$

$$\eta = \frac{10}{100} = 10\%$$


2) Receiver window size = 1




3) In GoBack-3 if every 5th packet that is being transmitted is lost and if we have to send 10 packets, then how many transmissions are required?



4) GIB-4, Every 6th packet is lost, I should send 10 packets, how many transmissions?




5) Acknowledgements: There are 2 kinds of ACK
 1) Cumulative ACK
 2) Independent ACK



Advantages: Less traffic


Disadvantages: Less Reliability



Advantages: Reliability is high


Disadvantage: More Traffic

⇒ GoBack-N uses cumulative Acknowledgements.




RELATIONSHIP BETWEEN WINDOW SIZES AND SEQUENCE NOS IN GBN

GBN-4 ⇒ Sender window size = 4 ⇒ No of sequence no.



∴ This scenario ⇒ (having the sequence nos = window size) don't work

2) GB-4, N=5 (Seq. Nos.)



\Rightarrow In general if the sender window size = 'N' and if the Receiver window size = 1 then to detect the Duplicate packets in GBN the No. of Seq. nos. should be $(N+1)$.

⇒ In any sliding window protocol if it has to work without any problem the condition is $(w_s + w_r) \leq ASN$ (Available Sequence nos).

\Rightarrow If $w_S = N$, $w_R = 1 \Rightarrow$ Seq. No. = $N+1 \Rightarrow$ No. of bits in seq. no. field = $\lceil \log_2(N+1) \rceil$

\Rightarrow If $\text{Seq Nds} = N$ then what is the max value of $w_2 = N-1$ $w_2 = 1$

\Rightarrow No. of bits in Seq No field = K then $w_1 = 2^K - 1$, $w_2 = 1$, No. of Seq Nos = 2^K

5. SELECTIVE REPEAT AND COMPARISON BETWEEN ALL SLIDING

WINDOW PROTOCOLS

10 21 > 1

$$T_f = 1 \text{ msec}, T_p = 19.5 \text{ msec}, w_2 = 50, \text{ In SR-protocol } \eta_b = ?$$

$$\underline{50} \quad \eta = \frac{50}{100} \Rightarrow \boxed{\eta = 50\%}$$

$$\text{Max window size} = 1 + 2a$$

of sender = $1 + 2(49.5)$

$$BW = 4 \text{ Mbps} \Rightarrow \text{Throughput} = \eta \times BW \\ = \frac{1}{2} \times 4 = 2 \text{ Mbps}$$

$w_r = w_s$

⇒ This protocol is called Selective Repeat protocol, because whenever a packet is lost there will be a timeout at the sender side and sender is going to select that packet (which is lost) and selectively repeat it.

$w_s = 3$, 10 packets are sent, every 5th packet is lost, How many transmissions in SR protocol?

seq = 1 2 3 4 5 6 7 8 9 10

↑

SR ≈ GBN in terms of efficiency

= 1 2 3 4 5 5 6 7 8 9 10

= 1 2 3 4 5 5 6 7 8 9 9 10

SR ≈ SAW in terms of Retransmissions

= 12 transmissions

3) The Ack rule independent in SR-protocol

⇒ In case of packet loss both GBN and SR protocol behaves same way but in case of corrupted Data packets SR is going to send "NACK" (Negative Acknowledgement).

	SAW	GBN	SR
Efficiency	$\frac{1}{(1+2a)}$	$\frac{N}{(1+2a)}$	$\frac{N}{(1+2a)} \rightarrow \text{Sender window size}$

Buffers

Sequence Numbers	Min window	Max window
	$1+1=2$	$N+1$
	$(N+1)$	$(N+N)=2N$

Retransmissions (1 packet is lost)	1	N	1
---------------------------------------	---	---	---

Bandwidth	Low	High (More Retrans)	Moderate
-----------	-----	---------------------	----------


CPU	Low	Moderate	High
-----	-----	----------	------

Implementation	Easy	Moderate	Difficult/complex
----------------	------	----------	-------------------

⇒ The maximum window size for data transmission using Selective Repeat protocol with n-bit frame sequence numbers is 2^{n-1} .

PRACTICAL SCENARIO WHERE SR AND GBN ARE USED

(14)



- ⇒ Generally the Intermediate Routers are connected with Thick wires.
- ⇒ Bandwidth is high and error rate is low, out of order are not possible, CPU's are powerful and there are always busy in processing the pkts
- ⇒ The availability of CPU is very less.

⇒ For all the above scenarios GBN is used.


- ⇒ When we consider near our mobile phone / Laptop, Error rate ↑, BW ↓ and out of order packets are possible, CPU is available: CPU ↑

⇒ SR protocol is used.

∴ Link to Link protocols like HDLC-(DLC) uses "GBN".
End to End protocols like TCP - uses - "SR" TCP-(Transport Layer)


6. INTRODUCTION TO ACCESS CONTROL METHODS, TDM, POLLING

The are two types of Links



TDM

- ⇒ TDM stands for Time Division Multiplexing.
- ⇒ Divide the timeline into slots and allot a station to each slot in Round Robin manner.



$$\eta_b = (\text{cycle time})^{-1} \times (\text{useful time})$$

$$\eta = (\text{useful time}) / (\text{cycle time})$$

$$\eta = \frac{T_t}{T_t + T_p} \Rightarrow \boxed{\eta = \frac{1}{1+a}} \quad (a = T_p/T_t)$$

If $T_t = 1\text{ msec}$ and $T_p = 1\text{ ms}$ and η_b of TDm: $\eta_b = \frac{1}{1+a} = \frac{1}{1+1} = \frac{1}{2} = 50\%$.
 $BW = 4\text{ mbps}$ Throughput = $\eta \times BW = \frac{1}{2} \times 4 = 2\text{ mbps}$.

Now, if 'N' stations are connected to the channel and each station Requisite 2 kbps BW then what is the max value of N?

$$\Rightarrow N * 2\text{ kbps} = 2\text{ mbps}$$


$$\Rightarrow \boxed{N = 1000}$$

Disadvantages

1. The problem with Reservation method in TDm is, whenever you reserve a slot for a station, the station might not use it completely the reason is it is not always true that every station might have data to transmit then the slot allotted will be wasted.

INTRODUCTION TO ACCESS CONTROL METHODS: TDm polling

POLLING



$$\eta = (\text{useful time}) / \text{cycle time}$$



$$\eta = \frac{T_t}{T_{poll} + T_t + T_p}$$

$$\boxed{\eta = \frac{T_t}{T_{poll} + T_t + T_p}} \quad \text{Throughput} = \eta \times BW$$

\Rightarrow The disadvantage is the polling time (T_{poll}). Before transmitting we should actually construct polling.

1. CSMA/CD

→ The CSMA/CD stands for carrier sense multiple Access / collision Detection.



$t = 10:00 \text{ AM}$, A, B starts transmitting


$t = 10:30 \text{ AM}$, collision

$t = 11:00 \text{ AM}$, collision signals observed by A/B

→ Now, if A/B must be aware about their data (mean whether the data that they are transmitting, got collided or others data) the condition is

$$T_t > T_p$$

⇒ At worst case, if A starts transmitting at 10:00 AM after how much time will 'A' get the collision signal back.



10:00:00 AM, A starts transmitting

10:59:59 AM, B starts transmitting

11:00:00 AM, collision

12:00:00 AM, A sees the collision signal.

∴ The time at which 'A' sees the collision signal is $2\text{hrs} = 2*T_p$

∴ If 'A' has to detect collision (be sure about whether its own data) got collided or others data) it should be transmitting the data in worst case also


$$\Rightarrow T_t > 2*T_p \Rightarrow L_B > 2*T_p$$

$$\Rightarrow L \geq 2*T_p * B = \text{This is the min size of packet to detect collision}$$

⇒ There are NO ACK in CSMA/CD

⇒ CSMA/CD is used in Ethernet

EFFICIENCY OF CSMA/CD / ETHERNET



The efficiency of CSMA/CD is

$$\eta = \frac{\text{useful time}}{\text{cycle time}}$$

$$\eta_b = \frac{T_t}{[C * 2 * t_p] + T_t + T_p} \Rightarrow \eta_b = \frac{\text{Transmission delay}}{[(\text{No. of contention slots}) * 2 * pD] + TD + PD}$$

- If there are 'n' stations connected to CSMA/CD and every station wants to send the data with probability 'p'.

Now, There will be a successful transmission if only one station transmits the data and other stations Refrain = prob for successful trans =

$$P_{\text{success}} = n_p p * (1-p)^{n-1}$$

$$P_{\text{success}} = np * (1-p)^{n-1}$$

Now, $\frac{dP_{\text{success}}}{dp} = 0 \Rightarrow p = \frac{1}{n}$. At value of $p = \frac{1}{n}$ the success probability will be maximum.

$$\Rightarrow P_{\text{max}} = \left(1 - \frac{1}{n}\right)^{n-1}$$

$$\text{Now, } \lim_{n \rightarrow \infty} \left(1 - \frac{1}{n}\right)^{n-1} = \frac{1}{e}$$

- No. of tries or times we should try before getting first success = $\frac{1}{P_{\text{max}}} = e$

$$\eta_b = \frac{T_t}{C * 2 * T_p + T_t + T_p}$$

$$\eta_b = \frac{1}{1 + 6.44 \alpha} \quad (\alpha = \frac{T_p}{T_t})$$

$$\eta_b = \frac{1}{1 + 6.44 \left(\frac{d}{v} \times \frac{B}{L}\right)}$$

⇒ The max amount of data that can be sent through Ethernet = 1500 Bytes


⇒ $\eta_b \downarrow$ as $d \uparrow$ {NOT SUITABLE FOR WANS}

⇒ $\eta_b \uparrow$ as $L \uparrow$ {Send bigger pkts for good efficiency!}


8. BACK OFF ALGORITHM FOR CSMMA-CD

(16)




⇒ The Back-off Algorithm is used to give waiting time of a station before it starts Retransmitting after involved in a collision. This waiting time is called Backoff time.



⇒ This Algo says both the stations 'A' and 'B' should randomly choose a no between $(0+2^n-1)$



Now, suppose let us Assume 'A' wins the Backoff Race \Rightarrow 'A' has successfully transmitted its 1st Data packet and is steady with 2nd Data packet



$$\Rightarrow \text{Waiting Time} = K \times T_{slot} \quad K \in (0, 2^n - 1) \quad n = \text{collision number}$$

- ⇒ collision probability is decreasing exponentially.
- ⇒ If 'A' has won first collision the prob that it wins 2nd collision is high (Capture Effect)
- ⇒ Applicable only for 2 stations.
- ⇒ Binary Backoff Algo or Binary exponential Backoff Algo.


9. TOKEN PASSING ACCESS CONTROL METHOD

Bits → Seconds

÷ BW

Meters → seconds

÷ velocity




How many meters 10 bits Equivalent to, given that BW = 4Mbps, $v = 2 \times 10^8 \text{ m/s}$

$$\text{Sol: } \text{Bits} = 10 \text{ bits}$$

$$\frac{\text{Bits}}{\text{BW}} = \frac{10}{4} = \frac{2.5 \text{ sec}}{10^6} \times 2 \times 10^8 \text{ m/s}$$

$$= \frac{5 \times 10^8 \text{ m}}{10^6}$$

$$\boxed{\text{Ans} = 500 \text{ m}}$$



1. Unidirectional flow of data

2. only one station can transmit at a time

3. If i leave a bit at some point in the ring the time taken by it to take one complete rotation is called "RING LATENCY".

$$\text{Ring latency} = \left(\frac{d}{v} \right) + (N * b)$$

$$\begin{cases} d = \text{length of Ring} \\ v = \text{velocity} \end{cases}$$

$$\boxed{\text{Ring Latency} = \frac{d}{v} + \frac{(N * b)}{\text{BW}}}$$

seconds (m)

$$\boxed{RL = \frac{d}{v} * \text{BW} + \frac{N * b}{\text{BITS}}}$$

THT = Token Holding time \geq THT \Rightarrow Time for which each station holds the token

(17)

$$\text{Cycle time} = \frac{d}{v} + (N * \text{THT}) = T_p + (N * \text{THT})$$

$$\eta = \frac{N * T_b}{T_p + (N * \text{THT})}$$

There are two strategies that are present in token passing mechanism they are

i) Delayed Token Reinsertion $\Rightarrow \text{THT} = T_t + T_p \Rightarrow \eta_b = \frac{1}{1 + \frac{(N+1)}{N} a} \quad (a = T_p/T_t)$


ii) Early token Reinsertion $\Rightarrow \text{THT} = T_t \Rightarrow \eta_b = \frac{1}{1 + (a/N)}$

10. ALOHA AND DIFFERENCES BETWEEN CLOW AND ACCESS CONTROL

i) Any station could transmit data at any time - No carrier sensing.

ii) collisions are possible, acknowledgements are there \Rightarrow collision detection X

iii) Retransmissions ✓ after some time (Backoff time) not after listening



TELEGRAM
@freeCBCB4all

Pure Aloha

i) Vulnerable time $= 2T_t$

$$\Rightarrow \eta = G_1 * e^{-2G_1} \quad (G = \text{No of stations})$$

who wants to transmit in 1 slot

$$\Rightarrow \frac{d\eta}{dG} = 0 \Rightarrow G_1 = \frac{1}{2}$$

If $G_1 = \frac{1}{2}$, $\eta = \max$

$$\Rightarrow \eta_{\max} = \frac{1}{2} * e^{-1}$$

$$\therefore \eta_{\max} = 0.184$$

$$\therefore \eta_{\max} = 18.4\%$$

Slotted Aloha

i) Vulnerable time $= T_t$

$$2) \eta_b = G_1 * e^{-G_1} \Rightarrow \frac{d\eta_b}{dG_1} = 0 \Rightarrow G_1 = 1$$

$$\Rightarrow \eta_b = 0.368$$

$$\eta_{\max} = 36.8\%$$

FC

$$\text{SAW} = \frac{1}{(1+2a)}, \text{SOP} = \frac{N}{(1+2a)}$$

$$\text{GRN} = \frac{N}{(1+2a)}$$

$$\text{SR} = \frac{N}{(1+2a)}$$

AC

$$\text{TOM} = \frac{1}{N}, \text{Polling} = \frac{T_t}{T_t + T_{\text{poll}}}$$

$$\text{CSMA/CD} = \frac{1}{1+6.44a}$$

$$\text{Aloha} \left\{ \begin{array}{l} \text{Pure} \\ \text{G}_1 e^{-2G_1} = 18.4\% \\ \text{Slotted} \\ \text{G}_1 e^{-G_1} = 36.8\% \end{array} \right.$$

3. ERROR CONTROL METHODS

I. ERROR CONTROL AND CRC

⇒ The main reason for packet loss is "congestion".

⇒ Error Handling is mainly of 2 types → Error Detection → (D+D), parity check, Check
→ Error Correction → Hamming code { Not used IN CD

CRC (CYCLIC REDUNDANCY CHECK)

⇒ CRC is mainly used at Hardware Level

<u>Sender</u>	<u>CRCG</u>	<u>Receiver</u>
1011011	1101	

Appended Data = 1011011000

→ If CRC Generator is m bits we
are going to append $(m-1)$ bits (All 0s)
to the data.

$\Rightarrow \oplus = \text{Exclusive OR} @ \mod 2 \text{ sum}$

$$\begin{array}{l} 1 \oplus 1 = 0 \\ 0 \oplus 0 = 0 \end{array} \quad \begin{array}{l} 1 \oplus 0 = 1 \\ 0 \oplus 1 = 1 \end{array}$$

Nano

1101) 1011011000 (... \Rightarrow If $CRC\ G = n$ bits then $CRC = \frac{(n-1)}{b+1}$

$$\begin{array}{r} 1101 \\ \hline 0110011000 \\ 1101 \\ \hline 000111000 \\ 1101 \\ \hline 001100 \\ 1101 \\ \hline 00011 \end{array}$$

\Rightarrow Always start Applying xor from the Leading 1 (Starting 1)

Now the least significant 3 bits

⇒ Already start Applying xor from the leading 1 (Starting 1)

Now the least significant 3 bits will be the "CRC" = 001.

∴ The zeros that you appended at the beginning will be replaced by CRC and gets transmitted.

∴ The data that will be sent to Receiver is = Actual data + CR

$$= \underline{1011011001} \text{ CRC}$$

At Receiver side, whether the data that is transmitted is Right or wrong

$$\begin{array}{r} 1101)1011011001(\\ \underline{1101} \\ 0110011001 \\ \underline{1101} \\ 000111001 \\ \underline{1101} \\ 00000 \\ \text{CRC} \end{array}$$

If you get all zeros as CRC
then the data that is transferred
is error free

2. CRC EXAMPLE

$$\text{CRC: } x^3 + x + 1 = 1 \cdot x^3 + 0 \cdot x^2 + 1 \cdot x + 1 \cdot x^0 = 1011 \text{ is the CRC}$$

If the degree of the polynomial = 3 the no. of bits in CRC Generator are 4
and we append '3' bits \therefore Degree of the CRC polynomial = Size of CRC generated.

At Sender

Data: 11010

$$\text{CRC: } x^3 + x + 1 = 1011$$

\therefore Appended data = 11010 000

At Receiver Side

$$\begin{array}{r} 1011)11010000(\\ \underline{1011} \\ 01100000 \\ \underline{1011} \\ 0111000 \\ \underline{1011} \\ 010100 \\ \underline{1011} \\ 00010 \\ \text{CRC} = 010 \end{array}$$


$$\begin{array}{r} 1011)11010010(\\ \underline{1011} \\ 01100010 \\ \underline{1011} \\ 0111010 \\ \underline{1011} \\ 010110 \\ \underline{1011} \\ 00000 \\ \text{CRC} = \text{All 0's} \checkmark \end{array}$$

3. CHECKSUM


\Rightarrow TCP, IP, UDP uses 16 bit checksum, and checksum is used at software level.

\Rightarrow The entire stream of data (bits) are divided into many parts of equal sizes which is equal to the size of checksum that you need i.e. If you are using 8 bit checksum then divide the entire stream of data into equal parts and size of each part should be 8.

→ Now encode the decimal values of all the points and add them all, finally than ans you get must be Negotiated (if we get 34 you should write -34) and add this value (-34) to the checksum field.




→ suppose if i add two 8 bit nos in the above checksum then i may get a 9 digit Binary number then you take the LSB and add it to the obtained number, This is called "Wrap Around".



4. CN - SUMMARY


- ⇒ No method is actually Reliable, the data may be corrupted (or) the Error handling bits may be corrupted.
- ⇒ Meaningful errors are nothing but, data is being corrupted in such a way that no one is able to detect it because error handling bits are also changed.



4. ISO/OSI STACK

(19)

1. ISO - OSI LAYERS




⇒ To implement all the above functionalities there are various Reference models which classify all the above functionalities and define what functions are carried out at a particular layer. One of the Reference model is "ISO-OSI STACK".

- 1> ISO-OSI
- 2> TCP/IP
- 3> ATM
- 4> X.25
- 5> IEEE (Mainly deals with LAN Technologies)

} Various Reference models

⇒ ISO-OSI stands for "International Standard Organisation - open system interconnection".

⇒ The various layers in the OSI model are:



- 1> 1 Advantage of Layering is
- 1. Divide and conquer
 - 2. Encapsulation is possible.
 - 3. Abstraction.
 - 4. Testing is made easy


{ Google out: RFC (Request for comments) for learning CN }

2. PHYSICAL LAYER


⇒ physical layer deals with Electrical, Mechanical, Functional, procedural characteristics of physical links.

- ⇒ Transmission modes:
- $S \rightarrow R$ (simplex / half duplex)
 - $S \rightleftarrows R$ (walkie talkies)
 - $S \leftrightarrow R$ (full duplex)


⇒ Deals with Topologies.




BUS



STAR



RING



HYBRID/TREE




MESH

⇒ Deals with Encoding (Bits → Signals, waves) 1010


MANCHESTER ENCODING

- 1 - Represented by \square
- 0 - Represented by \square



DIFFERENTIAL MANCHESTER ENCODING

- 0 - Represented by $\square \cdot \square$



- 1 - Represented by $\square \cdot \square$

In both the Encodings (Manchester and Differential Manchester)

$$\boxed{\text{Baud Rate} = 2 * \text{Bit rate}}$$

$$\begin{cases} \text{Baud} = \text{a letter with 4 letters} \\ \text{Bit} = \text{a letter with 3 letters} \end{cases}$$

Baud Rate = No. of voltages that are being sent per second

Bit Rate = No of Bits that are sent per second.


3. INTRODUCTION TO DATA LINK LAYER

25


- The main functions of DLL are
- 1> Flow control (SAW, GBN, SR)
 - 2> Error control (CRC, checksum)
 - 3> Framing
 - 4> physical Addressing
 - 5> Access control (CSMA/CD, Token passing...)
- ↓
DLL ↓
TCP/IP

4. FRAMING AT DLL

- ⇒ At DLL we are mainly talking about LANs and all the LANs are multi-access channels (All the stations are connected to a single Broadcast medium)
- ⇒ Framing is nothing but taking the data from the above layer (NL) and putting it in a frame and sending it



⇒ The starting of the packet is seen by B and it will discard it as the destination Address is 'C', so every station should know that a frame is Beginning so it has a special field called "SFD" (Starting Frame Delimiter)



⇒ Now, SFD Represents that the frame is coming and Alerts all the stations, generally "SFD" is a sequence of bits that is entirely different from the data.

The bits in the "SFD" can be represented with the help of Regular Expression

$(01010\ldots 11)(0+1)^*$


SFD The data that is present

Now we can convert

Regular Expression \rightarrow DFA \rightarrow Sequential Circuit
(Built using flip-flops)

Now, this sequential circuit has the capability of Recognising the Bits/RE

i.e. $(01010\ldots 11)(0+1)^*$ so,



At this point the Sequential circuit alerts the station and says that see a frame is going, if it is true.

- It is not just enough that you identify the start of the frame (SOF). it is important to find where the frame ends.
- Traditionally framing has been divided into two types
 - Fixed Length
 - Variable Length
- The disadvantage of Fixed Length framing is It has Internal Fragmentation.



Ex: $L = 1000 \text{ Bytes}$ \Rightarrow The min and max amount of data that can be sent is 1000 Bytes, if I have to send 100B then ??
 100B + 900 Bytes
 Dummy bits
 Added [This procedure is called padding].

FRAMING AT DLT

- To identify the ending of frame there are two methods they are,

1. Having a field saying the Length of the frame

2. Having an Ending Delimiter




→ Fixed Length frames are used in "ETHERNET."

→ Variable Length frames are used in "TOKEN RING."


→ The problem with having the length field is, if it gets corrupted then Receiver reads only the data upto the modified value of length field.

→ The problem with End delimiter is if ED pattern matches with Data(part) then the receiver cannot scan the entire data available




⇒ End Delimiter can be dealt in 2 ways they are : character stuffing
Bit stuffing.

CHARACTER STUFFING




⇒ so, add a null character after \$ so that the Receiver thinks / sees a '0' followed by a '\$' then it assumes it is not the end of data and it discard the Null character and scans the entire data.



→ So, adding a Null character for each and every match with the character present in the ED is called "character stuffing".

BIT STUFFING (v. imp for GATE)



If $\text{ED} = \text{O}(1))$

Sender side

• 金川公司

SD: 0111100 (After four ones add a zero) SD: 0111101

Receiving side

D. OIII 80

on the

SD= Structured Data

∴ ED = 01111

D = 0111 000 1110

Now, what is the data after Bit stuffing?

So Data = 0111 000 1110

Stuffed Data = 0111 0 000 111010

∴ ED = 0111111

Data → At the sender after the Run of 6 ones im going to add 1010

= 0111111010

→ At the Receiver side after a '0' followed by '6' ones im going to delete a zero.

4. PHYSICAL ADDRESSING

There are two types of Addresses

physical address - static, constant
Logical Address.

→ Now physical Address should be unique within the Network

→ Logical Address should be unique in the entire World wide web.

→ IP Address = 32bit Number, software num.

→ MAC Address = 48bit Number, hardware num pointed on our "NIC" → ROM → MAC


The MAC Address is divided into three parts (inequal lengths) they are

1. The Manufacturer ID or VendorID

2. What is the date of manufacturing

3. Serial No. of the device on that day

UNIQUE GLOBALLY



→ Conceptually Both IP, MAC Addresses can be logical but only IP Address is used for Logical Address because the info in the IP Address (NID/HID) are sufficient for Routing the packets, whereas this is not the case in MAC Addressing.

→ MAC is a physical Address.

TALK
⇒ "APPLE INC" is the NW in the world that does not use the MAC Address it artificially generates a random Number and assigns to the users.



- ⇒ Data Link Layer is divided into two parts they are :
 1) Logical Link Control
 2) Medium Access Control
- ⇒ LLC takes care of Error control, flow control,
 ⇒ MAC takes care of framing, access control, Error control, physical Address

L-6: INTRODUCTION TO NETWORK LAYER

The main Responsibilities of Network layers is

- 1) Host to Host connectivity
- 2) Logical Addressing
- 3) Switching (connecting various Networks together)

- 4) Routing




⇒ Building the Routing table = Routing

⇒ Using the Routing table = switching

- 5) Congestion control

- 6) Fragmentation.



7. TRANSPORT LAYER


The main Responsibilities are

- 1) End to End communication using port numbers (port nos are also called Service point Addressing).

- 2) Flow control (SR)

- 3) Error control (checksum)

- 4) Segmentation



- 5) Multiplexing and Demultiplexing.

- 6) Congestion control


8. HOW ALL THE LAYERS WORK TOGETHER

⇒ The protocol used to convert IP Address to MAC Address is 'ARP'.

⇒ Router will have only three layers (NL, DLL, PL)


⇒ In general, the physical layer and Datalink layer are present on NIC, and Network layer is present in the operating system.

⇒ In IP there are no Acknowledgements. (connectionless datagram service)



Imp points for Gate

⇒ Router have only 3 layers 1.PL 2.DL 3.NL



- The no of times a packet hit the DataLink layer = 4
- The no of times a packet hit the Network layer = 3.
- Depending on No. of Routers we have the no of time each layer hits depend.

9. SESSION LAYER AND PRESENTATION LAYER

SESSION LAYER


- 1) passwords and usernames will be dealt by session layer
- 2) Main Responsibility Authorization and Authentication (using Digital signatures)
- 3) check pointing (Torrentz example).
- 4) Synchronization.
- 5) Dialog control
- 6) Logical Grouping of operations

PRESNTATION LAYER

- 1) character translation
- 2) Encryption and Decryption.
- 3) Compression (.Zip)

GATE - 2014

TELEGRAM
@freeCBCB4all




X	M	P	M	S	C	T	
N							
D							
P							
-							

These are the situations when the packet reaches "R2." ⇒ Intruder could find IP's of Q, H and port numbers of Q, H

5. LAN - TECHNOLOGIES

ETHERNET (IEEE 802.3)

- 1) Topology: Bus topology 
- 2) Access control method: CSMA/CD
- 3) No Acknowledgement
- 4) Data Rates (Bandwidth): 10Mbps — 100Mbps — 1Gbps
 (Fast Ethernet) (Gigabit Ethernet)
- 5) Encoding technique: Manchester Encoding (Baud Rate = 2 * Bit Rate)
- 6) "Ethernet" operates at Data Link Layer. (LAN technologies are dealt at DLL)

AL = Message


TL = Segment

NL = Datagram

DLL = Frame

PL = Single protocol Data Unit. (I-PDU)

FRAME FORMAT OF ETHERNET (OR) IEEE 802.3 FRAME FORMAT



PREAMBLE: 7bytes : 10 10 10 10 10 ----- 10

→ used to alert all the stations

SFD: [Start frame Delimiter]: 1Byte : 10 10 10 11

→ Indicate Start of frame,
Synchronization.

DA: 6Bytes } MAC Address

SA: 6Bytes

CRC: 4 Bytes

TYPES OF MAC ADDRESS

Ex: 1A:2B:34:48:56:6F

1. UNICAST MAC ADDRESS: [LSB of 1st byte is 0] 00011010:00101011:


2. MULTICAST MAC ADDRESS: [1st Byte's LSB is 1]

3. BROADCAST MAC ADDRESS: [All the bits are ones in MAC Address] FF:FF:FF:FF:FF:FF

⇒ The multicasting MAC Address is implemented in this way

(24)

⇒ Consider a LAN containing many stations. Now, I want to send a message to two stations A and B (or) Repeatedly I want to send messages to some set of stations inside my LAN. Let us assume that A, B are my stations and if I send a message both of them should receive it. Then it is always better that you create a group for them and for that group you are giving a Group ID and that ID should be a multi cast Address, and inform A and B that see you both are present in a Multicast Group with some Address then Both A, B will configure their NIC's in such a way that whenever any packet is sent to that particular Multicast Address both of them will automatically Read and others will disregard it.



LENGTH : 2 Bytes = 16 bits

: The main reason for including Length field is ETHERNET follows variable length frames

: In CSMA/CD : $L \geq 2 \cdot T_p \cdot B_w$ substituting the standard values of T_p, B_w
 $L \geq 64$ Bytes for Ethernet we get

: Max Length : 1500 Bytes

	MIN	MAX
DATA	46B	1500B
FRAME	64B	1518B

DISADVANTAGES

- 1) Not applicable to Real-time Applications
- 2) Not applicable to Interactive Applications [chatting].
- 3) No priorities so not suitable for Client Server Applications.


$$\therefore \text{PREAMBLE} = 7B \quad \text{LENGTH} = 2B$$

$$SFB = 1B \quad \text{CRC} = 4B$$

$$SA = DA = 6B$$


6. SWITCHING

1. INTRODUCTION TO SWITCHING



⇒ Switching is done at Network Layer

2. COMPARISON BETWEEN CIRCUIT SWITCHING AND PACKET SWITCHING



Let M = size of total message that 'A' wants to send to 'B'.

B = Bandwidth of the entire channel

X = No. of Hops

d = Length of Each hop

v = Velocity of signal

Total time taken to send

$$\text{message } m \text{ to } B \text{ is} = \text{Setup time (connection establish time)} + T_c + \frac{xd}{v}$$

$$= \text{Setup time} + \frac{M}{B} + \frac{xd}{v} + TD \quad \left\{ \begin{array}{l} T_p \text{ b/w two hops} = d/v \\ \text{In b/w } x \text{ hops} = x \cdot d/v \end{array} \right\}$$

\rightarrow Teardown the link

$$TT = \text{Setup time} + \frac{M}{B} + \frac{xd}{v} + TD$$


In the above scenario Headers are not Required.

\Rightarrow Inorder ✓ (NO Reordering of packets) \Rightarrow NO sequence no's are Required. (25)

technology

PACKET SWITCHING

\Rightarrow Multiplexors are used.




$$\text{Total time} = \frac{M}{B} + \frac{d}{v}$$

No setup and Teardown time in P.S.

CS	PS
Setup time + Teardown time	$(x-1) \frac{M}{B}$

on Bursty data.
If M = Big = go for circuit switching
If M = less go for packet switching



3. PACKETIZATION AND PACKET SWITCHING

Data = 1000 Bytes

Bw = 1MBps = 10^6 Bps

Header = 100 Bytes

No. of packets = 1

$$\begin{aligned} \text{Packet size} &= \frac{\text{Data}}{1} + \text{Header} \\ &= 1000 + 100 \\ &= 1100 \text{ B.} \end{aligned}$$

$$\frac{xd}{v}$$

$$= \frac{d}{v}$$

$$= \frac{d}{v}$$

$$T_t = \frac{d}{v} = \frac{1100}{10^6} = 1.1 \text{ msec}$$

$$TT = 3 * T_t = 3 * 1.1 = 3.3 \text{ msec}$$

$$TT = 3.3 \text{ msec}$$

Data = 1000 Bytes

Bw = 1MBps = 10^6 Bps

Header = 100 Bytes

No. of packets = 5

$$\begin{aligned} \text{Packet size} &= \frac{\text{Data}}{5} + \text{Header} \\ &= \frac{1000}{5} + 100 \\ &= 300 \end{aligned}$$

$$T_t = \frac{d}{v} = \frac{300}{10^6} = 0.3 \text{ msec}$$

$$\text{Remaining 4 packets} = 4 * T_t$$

$$= 4 * 0.3$$

$$= 1.2 \text{ msec}$$

$$TT = 2.1 \text{ msec}$$

Data = 1000 Bytes

Bw = 16 Bps = 1mbps

Header = 100 Bytes

No. of packets = 10

$$\text{Each packet size} = \frac{1000}{10^6} + 100$$

$$PS = 200$$

$$1^{\text{st}} \text{ packet} = 3 * T_t = 3 * 0.2$$

$$= 0.6 \text{ ms}$$

$$\text{Remaining 9 packets} = 9 * 0.2$$

$$= 1.8 \text{ ms}$$

$$TT = 2.4 \text{ ms}$$

Time out

► Basic

► Header

► Body

► Total

► Time

► Distance

► Latency

► Jitter

► Loss

► Delay

► Throughput

► Efficiency

► Reliability

► Security

► Cost

► Energy

► Scalability

► Manageability

► Performance

► Flexibility

► Portability

► Interoperability

► Standardization

► Interconnection

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Flow Control

► Addressing

► Routing

► Switching

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

► Congestion Control

► Multiplexing

► Segmentation

► Reassembly

► Error Detection

► Error Correction

► Flow Control

► Congestion Control

► Quality of Service

► Resource Utilization

► Error Recovery

►

packetization is the process of dividing the data into packets and transmitting.

⇒ The packetization process helps in reducing the total transmission time and the size of the packet should not be too small if it is the case the total time taken to transmit the data will increase. So the packet size must be chosen appropriately.


4. VIRTUAL CIRCUITS AND DATAGRAMS

There are two types of packet switching they are Virtual circuits, Datagrams


⇒ Our phone call is going through virtual circuit.

⇒ Our Data usage is going through Datagram circuit.

Virtual circuit



Datagram circuit



1> Headers are not Required

2> for the 1st packet, Global Header
for other packets, local header

3> Connection oriented (Resource Reservation) if Resources are Reserved then it is connection oriented. (Buffer, CPU, BW)

4> Same path → Inside packets

5> Highly Reliable

6> Costly

7> ATM (Asynchronous Transfer mode)

Network uses ATM, VC.

1> Headers are reqd for all packets

2> Connectionless oriented

3> No guarantee, they may follow diff path, they may appear out of order.

4> Not Reliable

5> Not very costly.

6> Viber, whatsapp call have voip (VOICE OVER INTERNET PROTOCOL)

7> IP Network uses Datagram.

1. INTRODUCTION

IPv4 Header

Version (4)
Identifier
TTL(8)
Protocol
Header Length

HL:

Here the min.

HL is of 4

so we use th

length of 5b. He

→ 1100 0000 0000 0000

2 3 4

bullet points 4

5 6 7

bullet points 8

9 10 11

bullet points 12

13 14 15

bullet points 16

17 18 19

bullet points 20

21 22 23

bullet points 24

25 26 27

bullet points 28

29 30 31

bullet points 32

33 34 35

bullet points 38

39 40 41

bullet points 44

45 46 47

bullet points 48

49 50 51

bullet points 52

53 54 55

bullet points 58

59 60 61

bullet points 64

65 66 67

bullet points 71

72 73 74

bullet points 78

79 80 81

bullet points 84

85 86 87

bullet points 91

92 93 94

bullet points 98

99 100 101

bullet points 104

105 106 107

bullet points 111

112 113 114

bullet points 121

122 123 124

bullet points 128

129 130 131

bullet points 135

136 137 138

bullet points 144

153 154 155

bullet points 158

159 160 161

bullet points 164

165 166 167

bullet points 168

169 170 171

bullet points 174

175 176 177

bullet points 178

179 180 181

bullet points 184

185 186 187

bullet points 188

189 190 191

bullet points 194

195 196 197

bullet points 198

199 200 201

bullet points 204

205 206 207

bullet points 208

209 210 211

bullet points 214

215 216 217

bullet points 218

219 220 221

bullet points 224

225 226 227

bullet points 228

229 230 231

bullet points 234

235 236 237

bullet points 238

239 240 241

bullet points 244

245 246 247

bullet points 248

249 250 251

bullet points 254

255 256 257

bullet points 258

259 260 261

bullet points 264

265 266 267

bullet points 268

269 270 271

bullet points 274

275 276 277

bullet points 278

279 280 281

bullet points 284

285 286 287

bullet points 288

289 290 291

bullet points 294

295 296 297

bullet points 298

299 300 301

bullet points 304

305 306 307

bullet points 308

309 310 311

bullet points 314

315 316 317

bullet points 318

319 320 321

bullet points 324

325 326 327

bullet points 328

329 330 331

bullet points 334

335 336 337

bullet points 338

339 340 341

bullet points 344

345 346 347

bullet points 348

349 350 351

bullet points 354

355 356 357

bullet points 358

359 360 361

bullet points 364

365 366 367

bullet points 368

369 370 371

bullet points 374

375 376 377

bullet points 378

379 380 381

bullet points 384

385 386 387

bullet points 388

389 340 341

bullet points 344

345 346 347

bullet points 348

349 350 351

bullet points 354

355 356 357

bullet points 358

359 360 361

bullet points 364

365 366 367

bullet points 368

369 370 371

bullet points 374

375 376 377

bullet points 378

379 380 381

bullet points 384

385 386 387

bullet points 388

389 390 391

bullet points 394

395 396 397

bullet points 398

399 400 401

bullet points 404

405 406 407

bullet points 408

409 410 411

bullet points 414

415 416 417

bullet points 408

409 410 411

bullet points 414

409 410 411

bullet points 414

415 416 417

bullet points 418

419 420 421

bullet points 424

425 426 427

bullet points 428

429 430 431

bullet points 434

435 436 437

bullet points 438

439 440 441

bullet points 444

445 446 447

bullet points 448

449 450 451

bullet points 444

445 446 447

bullet points 448

449 450 451

bullet points 444

455 456 457

bullet points 458

459 460 461

bullet points 464

465 466 467

bullet points 468

469 470 471

bullet points 474

475 476 477

bullet points 478

479 480 481

bullet points 484

485 486 487

bullet points 488

489 490 491

I. INTERNET PROTOCOL

1. INTRODUCTION TO IP HEADER

IPv4 Header

Version (4)	HL (4)	Type of service(8)	Total Length (16)	= 32 bits = 4 Bytes
Identification (16)	O D M	Fragment offset (13)	= 4 Bytes	
TTL (8)	Protocol (8)	Header checksum(16)	= 4 B	
		Source IP (32)	= 4 B	
		Destination IP(32)	= 4 B	
		Options (0-40) Bytes		
		Data		
				Max. Header length = 20 + 40 = 60B

HL:

Here the min size of the Header is 20B but the Header Length field HLF is of 4 bits \therefore only the numbers ranging from (0-15) can be represented so we use the process called scaled Arithmetic (divide by 4)

\therefore If Header Length = 20B \Rightarrow HLF contain (5)

$$\begin{array}{ccc} \text{HL} & & \text{HLF} \\ 20B & \longrightarrow & 5 \\ 32B & \longrightarrow & 8 \\ 40B & \longrightarrow & 10 \end{array}$$


\Rightarrow In exam if a number is given, and if you want to identify it whether it is a Header Length or Header Length field the below steps are followed
process is convert to decimal and check the ranges HLF (20B-60B) and HLF (5-15).

VERSION : The version of the Ip Address IPv4 / IPv6. If version = 0100 = IPv4 if version = 0110 \Rightarrow IPv6 \Rightarrow the packet must be parsed by the parsers appropriately.

2. IDENTIFICATION, MF, DF AND FRAGMENT OFFSET


\Rightarrow Identification number is used to number every datagram that is going out of a host. This field is mainly used when we do Fragmentation, when we do fragmentation all the fragments are going to get same identification number.

\Rightarrow DF: Don't fragment



⇒ Fragment offset is no. of data bytes ahead of this particular fragment

In this particular Datagram.




Ans: 26

3. TTL, PROTOCOL, HEADER CHECKSUM

TTL (8):

consider the following scenario,



→ A, B, C are the routers and when a packet gets to router A then the router takes the IP address of the packet and tries to 'AND' with SM if it does not match it is going to send to default entry.

⇒ Let us say, Router A's default entry = Router B and Router B's default entry goes/leads the packet go to Router C and Router C's default entry = Router A; then the packet will fall in an infinite loop and will be entirely circulating and there may be some thousands of such packets, then as a result, the buffers are full, routers will be busy.

⇒ In order to overcome the above problem there is a concept called "TTL (TIME TO LIVE)" in which a packet is made to circulate only upto certain no. of hops after that many hops the packet will be discarded.

⇒ The main purpose of TTL is to discard the packet that falls in infinite loop.

⇒ THE TTL VALUE WILL BE DECREMENTED ONLY AT THE INTERMEDIATE ROUTERS AND THE DESTINATION.

GATE -14 paper 02

In the diagram shown below, L1 is an Ethernet LAN and L2 is a Token Ring LAN. An IP packet originates from sender 'S' and traverses to 'R', as shown.

The links within each ISP and across the two ISP are all point-point optical links. The initial value of TTL field is "32". The max possible value of TTL when R receives the datagram is _____.



PROTOCOL


TL	TCP
NL	ICMP
IP	

⇒ Now consider
Buffers at t
at their fu
Buffers are
It is better
packet is T
is a Reliable
instead ch
ICMP, IGMP

of more S
in which the

HEADER CHECKS






SOURCE IP AND DESTINATION IP

SIP = Source IP Add.

DIP = Destination IP Add.

NID	HID
✓	✓ - Valid IP Address (SIP, DIP)
✓	0's = NID (SIPx, DIPx)
✓	1's = DBA (SIPx, DIPv)
1's	1's = LBA (SIPx, DIPv)
1's	0's = SM or NM (SIPx, DIPx)
0's	✓ = Host within a NW (SIPv, DIPv)
0's	0's = I don't have Sp (SIPv, DIPx)
127	✓ = Loop back Address (SIPx, DIPv)



I. DIFFERENCE

MTU = Maximum frame size

⇒ The next field

: The max size

Message = AL

Segment = TL

Datagram = NL


Frame = DL

IPDU = PL

5. OPTIONS

⇒ This field is optional

Record Route:



The max no. of Sp Address that could be recorded on a packet is '9'.

⇒ Sp Address length = 4B

⇒ optional field max length = 40B ⇒ Max no. of Sp Add = 10 IPs

But one field is used to indicate the type of options

⇒ IP is a protocol

the max size of

⇒ If we remove payload/Datap

⇒ Here we are concern at each and every = 20B

⇒ Now Application

now it is the

given by AL int


the process of

⇒ Now the data f

the problem is D

Ethernet then !

SOURCE ROUTING



⇒ You will specify the entire path in which a packet must go in Strict Source Routing

⇒ In loose source routing you will indicate the Router(s) from which your packet must definitely go

⇒ In the diagram, packet may go as R₁, R₂, R₄, D

R₁, R₂, R₃, R₄, D.

⇒ An addition padding is also done at 'options' in order to make Header Length multiple of '2'.


8. FRAGMENTATION

I. DIFFERENCE BETWEEN SEGMENTATION AND FRAGMENTATION

MTU = Maximum Transmittable Unit (The max amount of data that DLL frame can carry is called MTU)

⇒ The next field in the Header format = Total Length = 16b

- ∴ The max possible number with 16 bits = $2^{16} - 1$ = 65,535
- ∴ The max size of datagram that could be present in Ethernet in these days = 65,535



⇒ IP is a protocol that operates at Network layer. And now, at NL layer the max size of datagram is 65,535 ⇒ Total amount of data + Header = 65,535

⇒ If we remove the Header from the data then the remaining data is called payload/datapoint at that layer.


⇒ Here we are calculating the max amount of data that can be accommodated at each and every layer, to get max. data the Header length should be min = 20B

⇒ Now Application Layer could give any amount of data to transport layer, now it is the responsibility of the Transport layer to divide that packet given by AL into parts so that each part could sit in 65,495B. And the process of dividing the packet into parts is called "Segmentation".

⇒ Now the data from the TL can easily fit into NL but here there is a problem, the problem is DLL has also some limitations, if the underlying LAN is Ethernet then the max size of data that can be fit is only 1500B.


which means NL is going to give you a data of 65,535 B, But DLL can hold a maximum of 1500 Bytes only. Now, NL should divide the datagram into parts so that each part could go and sit into 1500B and that process is called "FRAGMENTATION".

- ⇒ Now, once the Datagram is received by the DLL which is already fragmented, it will add Header and Tail along with preamble, SFD... and this process is called "FRAMING".
- ⇒ The problem here is either the Network Layer is going to be Bottleneck or DLL is going to be bottleneck, sometimes DLL can hold the data sent by NL without fragmentation, the bottleneck will be NL. So at the same host if we don't want to do segmentation, fragmentation then what transport layer will do is, TL will find out what is the capacity of NL and DLL and it will calculate who is the bottleneck and accordingly TL will divide the segment such that it will easily fit in DLL without any problem.



2. FRAGMENTATION EXPLAINED WITH NUMERICAL EXAMPLE

- ⇒ At source we do only segmentation in such a way that there is no need of fragmentation
- ⇒ MTU = Max amount of data that can sit in DLL frame





→ Now the problem scenario is, fragment offset = 13 bits \Rightarrow the max no in offset field = $2^{13}-1 \approx 8000$


→ The worst case fragment offset in Ipdatagram = $\frac{65,515}{120} = 545.125$
 $\frac{65,515}{120} = 545,514 \approx 545,515$

Now, At worst case I have to put a number = 2^{16} but my fragment offset contains only 13 bits $\Rightarrow 2^{13}$, \therefore [scale down factor for offset = 8] [$\because \frac{2^{16}}{2^{13}} = 2^3$]

→ \therefore The offset must be divided by 8. But the problem with this is we get decimal points. So In order to avoid floating point numbers we should always see that the datapart in the fragment should be divisible by 8.



3. THEORY ABOUT FRAGMENTATION



→ Fragmentation is done at Router, not at the source

→ The fragments are reassembled at Destination not routers because, it is a Datagram service and all the routers may not meet at the same router, and there might be a further need for fragmentation.

4. REASSEMBLY ALGORITHM

⇒ Depending on MF and offset the Receiver will identify that the Datagram is fragmented.

MF	offset	
1	0	→ 1st fragment
1	!0	→ Intermediate fragment
0	!0	→ Last fragment
0	0	→ Only Single Datagram = No Fragmentation.

Step-1: Destination should identify that Datagram is fragmented (MF, offset)

Step-2: Destion should also identify that what fragments belong to a particular datagram by using Identification number.


Step-3: Identify the first fragment (MF=1, offset=0) $\frac{[TL - (HL * 4)]}{8}$

Step-4: Identify the subsequent fragments $\frac{[Data + HL]}{8}$ = offset of 2nd fragment

Step-5: Repeat this procedure for all the subsequent packets where MF=0

9. PROTOCOLS AND CONCEPTS AT NL


I. IMPLEMENTATION OF BROADCASTING



- ⇒ Even though Broadcasting is done at NL it cannot be done without the Broadcasting features of Data Link layer.
- ⇒ For Direct Broadcasting the field where LRA is present in above figure will be Replaced by DBA and DMFC will be filled by the next router and then router routes the packet as Unicast message and when the Router forwards to the Network, then the DBA will be changed to LRA and DMFC will be all f's.

2. ARP

ARP (IP Address → MAC Address)




⇒ ARP Request is a Broadcasting packet

⇒ ARP Reply is a unicast packet

⇒ ARP is applied when a router wants to find Mac address of a host. \rightarrow Ppt Lec 7-8

3 SPECIAL ADDRESS - 127



⇒ If you send a packet with destination address as 127 then the packet is again going to come back to same host.

PL

⇒ The command to test is ping 127.0.0.1 {you should not use 127.0.0.0
127.255.255.255} then we are supposed to see RTT as $\geq 15\text{ms}$ instead if it sees something like Time out the something is wrong in our NIC and you should start troubleshooting.

⇒ It is also called Loop Back Address

4. RARP

RARP = Reverse ARP (MAC \rightarrow IP)

NFS = Network File Server

MAC \rightarrow ROM

IP \rightarrow RAM



i) The disadvantages of RARP are, i) overhead for implementation of link layer

- Every Host should have a RARP server OBSELETE TECHNOLOGY
- Static mapping ($\text{#IP} > \text{no. of Hosts}$)

AL

TL

RARP Request

NL

MAC 0.0.0.0

DLL


[MAC 0.0.0.0] MAC [FF:FF:FF:FF:FF:FF]

PL

MAC	IP
M1	I1
M2	I2
Mn	In

RARP Server


MAC	IP
M1	I1
M2	I2
Mn	In



5. BootP AND DHCP

⇒ The main difference between BootP and RARP is, BootP works at AL, and RARP works at DLL.

BootP = BOOTSTRAP PROTOCOL



⇒ Now the hosts present in other N/w are never going to reach the BootP server, this problem is solved by Relay Agent.

⇒ The Relay Agent knows the IP Address of the BootP server and the packet that is Broadcasted by Station B will be Read by RA and RA will ask the BootP server by sending a Unicast packet.

⇒ Only one BootP server is Required


⇒ Mapping table is static.

DHCP

The main diff between the BootP and DHCP is the table is not static in DHCP


⇒ DHCP has table at DHCP server and the table has two parts they are static part and dynamic part.

⇒ Generally the servers will be given permanent IP's.



→ Let us say, A host M_A wants its IP Address then the Dynamic part look like this


(2)



⇒ only one DHCP Server is Enough

⇒ The State is a Dynamic table (No. of IP Address = No. of stations online)

⇒ To make DHCP backward compatible with BOOTP, both DHCP, BOOTP should have same port numbers.



⇒ DHCP is operated at Application layer

⇒ DHCP cannot be implemented on Router as Router has only 3 layers




⇒ But practically DHCP can be applied on the routers also, if you buy Cisco's **C1925E** Router you are going to be provided with DHCP facility at Router itself.


5. INTRODUCTION TO ICMP (V Imp for GATE)

⇒ ICMP works at Network layer

⇒ ICMP = Internet control message protocol

(whenever something is wrong then we get ICMP packet)






→ Suppose you are sending an IP packet from Source to Receiver but on the way the IP packet is discarded because of heavy congestion at Router R3. Now the Router R3 sends ICMP packet (R3, S) to say to the source that I discarded your packet. Now, the Router R3 sends "ICMP (R2, S)" first to Router R2 but because of heavy congestion at R2 the ICMP packet (R2, S) is discarded at 'R2' so R2 again sends an ICMP packet to R3 and because of heavy congestion at R3 again the ICMP packet is discarded. This scenario will lead to infinite loop.


⇒ IP packet is lost the ICMP packet should be generated but if ICMP packet is lost then no ICMP packet should be generated

∴ ICMP + IP UNRELIABLE

7. ICMP FEEDBACK MESSAGING




SOURCE QUENCH




when R1 sends lots of packets then R2 cannot handle them and say please stop sending i could not handle them. This is called source quench.

PARAMETER PROBLEM



⇒ Suppose you used strict source routing and D-R2-R1. But if the link between R1 and R2 is broken then down the Router R1 discards the packet and sends ICMP message.

BESTINATION UNREACHABLE



→ Destination unreachable is of 2 types they are
③


1. Destination Host unreachable

2. Destination port unreachable

→ R2 send ARP Req for getting mac add

If the host is down then there won't be reply then the Router R2 sends ICMP

DH unreachable error message).




DHU = Destination Host unreachable

DF = Don't fragment = 1

FR = Fragmentation Required.

SOURCE REDIRECT



→ Now source sends a packet to

R₁ and at R₁ due to some errors in the Routing table if it has chosen Router R₂ (actually the best path is "R₁, R₂, D") then


If there is some manual mechanism in R₃ which knows that there is a better path b/w 's' and 'D' then

R₃'s send temp packet saying "see there is another better path so you please redirect don't send me next time!"


8. ICMP REQUEST AND REPLY MESSAGING

→ The ICMP Request and Reply messaging is used to test whether the NL of destination and the intermediate routers are working or not.

PING : PACKET INTERNET GOFER



⇒ It is not enough just that you get the IP Address from DHCP when you are connected to internet, it is also important to discover the default Router for your connection and start communicating.



- ⇒ The station present in the Network sends a Broadcasting message to all the Routers which are connected to that particular Network then the Routers reply saying "See I am available, you can use me as your default gateway / default router. This type of Broadcasting the message is called "Router solicitation" [we are asking the Routers]
- ⇒ The other scenario is "Router Advertisement" in which a router connected to a NW, says "See I am available you can use me as your default router.


Time Stamp Req and Reply

Generally various Networking devices are placed at different parts of the world. The challenge here is Synchronisation which means it is important to check whether they work at same time, in order to that there is a special type of ICMP message called "Time Stamp Req and Reply" message. This is a obsolete technology and now we are using "Network time protocol".


9. TRACE ROUTE, APPLICATION OF ICMP

- ⇒ In order to find the intermediate Routers present in the route between source and destination the trick is, send a packet with TTL=1 in order to get the Router present in one hop, and send a packet with TTL=2 to get the Router present at 2nd hop. When TTL=0 at the router it sends "ICMP TTL exceed" error to the source / end.

→ when the packet reaches the destination, TTL will be zero and the destination is going to accept it but it doesn't generate ICMP message, it does not guarantee that when we don't receive a ICMP message the packet is delivered to the destination, the ICMP may be lost. So in order to be sure whether the packet reached the destination insert a UDP packet into the IP packet and put dummy port numbers so that when the packet reaches destination it is going to accept it and return an "ICMP message" "Destination port unreachable".




⇒ The Trace route might not give you the actual path, but in almost majority cases we get Actual path. for example




10. PMTUD APPLICATION OF ICMP

PMTDU = PATH MTU DISCOVERY



10. ROUTING

1. DIFFERENCE BETWEEN ROUTING AND FLOODING



→ How does the Router R1 comes to know about the destination, i mean which is the path that it should send the packet so that it will reach destination.

→ The process of building the routing table is called "Routing"

→ If you don't know which way to send, send it in all possible paths, this process is called flooding.

Flooding

- 1> NO Routing tables are Required
- 2> Shortest path is guaranteed.
- 3> Highly Reliable

Disadv

- 1> More Traffic
- 2> Duplicate packets are possible


Routing

- 1> Routing tables are needed
- 2> shortest path is not guaranteed
- 3> Less Reliable

Adv

- 1> Less traffic
- 2> No Duplicate packets.

2. TYPES OF ROUTING ALGORITHMS



3. DISTANCE VECTOR ROUTING

(35)

⇒ In the DVR every node is going to know only about its Neighbours.

⇒ The Routing table at a node contains three fields: Destination, Distance, Nexthop


Step 1:

Des	DIS	NH
A	1	A
B	7	B
C	11	C
D	0	D

↳ DV

Des	DIS	NH
A	α	-
B	3	B
C	0	C
D	11	D

↳ DV



→ Building Local Routing table with knowledge of Neighbours.

Des	DIS	NH
A	0	A
B	2	B
C	α	-
D	1	D

Des	DIS	NH
A	2	A
B	0	B
C	3	C
D	7	D

↳ Distance vector

Step 2:

⇒ Every Router will take their distance vectors and exchange with their Neighbours.

⇒ Now at every node the new distance vectors will be newly created.

⇒ A' Receives Distance vector from BxD. ⇒ C Receives DV from BxD.

⇒ B' Receives Distance vector from AxC,D ⇒ D Receives DV from AxB,C

At A:

DVs from BxD

From B

From D

⇒ Using these two the new DV of Router A will be

2	1	
0	7	
3	11	
7	0	


	A	B	C	D
A	0	A	-	-
B	2	B	-	-
C	5	B	-	-
D	1	D	-	-

$$A \rightarrow B = \min \left\{ \begin{array}{l} \textcircled{1} A \xrightarrow{D} D \xrightarrow{\textcircled{2}} B \\ \textcircled{3} A \xrightarrow{B} B \xrightarrow{B} B \end{array} \right. \quad A \rightarrow D = \min \left\{ \begin{array}{l} \textcircled{1} A \xrightarrow{D} D \xrightarrow{\textcircled{2}} D \\ \textcircled{3} A \xrightarrow{B} B \xrightarrow{B} D \end{array} \right.$$

$$A \rightarrow C = \min \left\{ \begin{array}{l} \textcircled{1} A \xrightarrow{D} D \xrightarrow{\textcircled{2}} C \\ \textcircled{3} A \xrightarrow{B} B \xrightarrow{C} C \end{array} \right. = 5$$

The shortcut is

At A:



A	0	A
B	2	B
C	5	B
D	1	D

→ Exception

Take the min of "2"

$$2+0=2 \\ 7+1=8$$

min = 2 from 'B' table

∴ NH = Next Hop = B

At B:

DIVS from A,C,D

At B:

From A

A	0
B	2
C	5
D	1

AB: 2
By

From C

B	0
C	3
D	11

BC: 3 add

From D

A	1
B	7
C	11
D	0

BD: 7 add

The New Routing table At B is

A	2	A
B	0	B
C	3	C
D	3	A

$$= \min\{2, (3+1), (1+7)\}$$

$$= \{2, 4, 8\} = \{2\} \text{ from A}$$

⇒ Repeat this procedure at every node and do it for 3 times (3 Rounds)

because the shortest path is of 3 edges. ⇒ no. of (nodes - 1). So

Repeat the rounds for $(n-1)$ times {n = no. of nodes}

The final Routing table is after everything converges is,

At A:

A	0	A
B	2	B
C	5	B
D	1	D

At B:

A	2	A
B	0	B
C	3	C
D	3	A

At C:

A	5	B
B	3	B
C	0	C
D	6	B,A

At D:

A	1	A
B	3	A
C	6	A,B
D	0	D


After the Routing table converges the edges that are unused is D→C, D→B.

(36)





4. COUNT TO INFINITY

⇒ There is a problem with DVR the problem is called Count to Infinity

Initially




Step-1
Suppose if 'B' is connected to A




Exchange of DV's

Suppose if Everything is stabilized



Now, suddenly if the link between A, B is down, then it is a Bad news



1 2 3 (Initial values before the link is broken)

$\infty \leftrightarrow 2 \leftrightarrow 3$. (Here is the trap, we know that the Routing tables dist from 3 $\leftrightarrow 4 \leftrightarrow 3$ are exchanged in neighbours. Here, B says i cannot reach A via C. B says don't worry i'm able to reach A in 2 hops).

5 $\leftrightarrow 4 \leftrightarrow 5$

5 $\leftrightarrow 6 \leftrightarrow 5$

7 $\leftrightarrow 6 \leftrightarrow 7$

Distances $\leftarrow 7 \leftrightarrow 8 \leftrightarrow 7$


from that node 9 $\leftrightarrow 8 \leftrightarrow 9$

to A: 9 10 9

$\infty \leftrightarrow \infty \leftrightarrow \infty$

→ This will execute till the value that you have chosen for infinity

Now the above explanation can be understood by the explanation given below. This Question is asked in GATE



At N₃:

From N₂

1
0
6
7
3

N₃ N₂: 2

From N₄

8
7
2
0
4

N₃ N₄: 2

New routing table at N₃ is


N1	3	N2
N2	2	N2
N3	0	N3
N4	2	N4
N5	5	N2

Ans: 3 2 0 2 5

5. SPLIT HORIZON

⇒ The solution to count to infinity is split horizon.

⇒ The count to infinity also creates some loops.



The routing tables at A, B, and C will be

A	∞	-
	!	!
	!	!


A	2	B
!	!	!
!	!	!

Initially

A	3	C
!	!	!
!	!	!

→ This procedure repeats until all the values are stabilized.

So this problem can be solved by sending the Next hops also and this procedure is called split horizon.




→ Now, At 'C', C is depending on B in order to goto 'A'. ∴ when 'C' is already depending on 'B' to goto 'A', it should not say i can take u in some hops; i am already depending on you. ∴ please don't do that.

- By using the method of split horizon convergence is fast, no loops are formed.
- In case of DVR convergence is slow and loops will occur. (27)

6. LINK STATE ROUTING

- Every Router will create something called as Link state packets.
- In the first round, Every node creates a Link state packets with the help of "Hello packets".




- In Round 2, EVERY NODE IS SUPPOSED TO FLOOD THE INFO TO EVERY OTHER NODE. THEREFORE WE WILL HAVE GLOBAL DATABASE AT EACH NODE.

DVR - Local Knowledge (Knows only about the Neighbours)

LSR - Global Knowledge (Knows about all the nodes)

AAA: Best effort delivery, delivery reliability is not guaranteed.




→ Then at 'A', 'A' will start applying single source shortest path (Dijkstra Algo) and 'A' comes to know all the shortest path to all nodes and 'A' will construct its Routing table.

DES	DIS	NH
A	0	A
B	2	B
C	5	B
D	1	D

⇒ LSR converges faster compared to DSR

⇒ There are some problems in the LSR, since we are flooding, it is going to lead heavy traffic.

⇒ Now, consider the following scenario,



Now if a packet is flooded from 'A' to all the nodes then the packet will reach 'D' in less time when compared with the other path (A-B-C-D), so the arrived packet (which has arrived quickly) is the latest packet but depending on the time of arrival we may think that the packet which came late is the latest packet and the packet arrived quickly is the old packet. So in order to correct that we have sequence numbers.

(A, 10) ✓ } latest packet
(A, 5) ✗ } old packet - discarded.


Therefore At A, it maintains a table having the Router name and latest sequence numbers.

Router	Latest
B	10/15
C	20
D	30

(B, 8) ✗ - discarded
(B, 15) ✓ - Accepted
(B, 11) - discarded

1	2	3
4	5	6
7	8	9

Now,



⇒ The packet that is already sent to 'D' from 'A' is going to come again to the same destination via another route (A-B-C-D) so there is a problem of falling in infinite loop. This can be overcome by having TTL field.

I. DIFFERENCE BETWEEN DVR, LSR, RIP AND OSPF

DVR

- 1) used in 1980's
- 2) BW required is less
- 3) local knowledge
- 4) Bellman Ford Algo
- 5) less Traffic
- 6) periodic updates
- 7) converges slowly
- 8) count to infinity
- 9) persistent loops
- 10) RIP

LSR


1. used in 1990's
2. High Bandwidth
3. Global knowledge
4. Dijkstra Algo
5. high Traffic
6. periodic updates
7. converges fast
8. No count to infinity
9. Transient Looping
10. OSPF

RIP (ROUTING INFORMATION PROTOCOL)

- ⇒ RIP is the implementation of (DVR) Simple to Implement but it is slow
- ⇒ Metric = Hopcount (weights)
- ⇒ Infinity cannot be represented in programming language hence the value 16 is used as infinity.

OSPF

- ⇒ OSPF is the implementation of the (LSR) computation is complex
- ⇒ OSPF divides all the routers into some Regions and flooding is restricted to that Region, and there will be one router designated as "Border Router" (It will take all the flooded packet and summarize the info).
- ⇒ Border Router is connected to "Area 0" or "Zone 0" or "Back Bone Zone".
- ⇒ "EIGRP" PROTOCOL INVENTED BY CISCO $EIGRP = RIP + OSPF$



II. TCP

1. TCP HEADER

SOURCE PORT (16)	DESTINATION PORT (16)	= 4 Bytes
SEQUENCE NUMBER (32)		= 4 Bytes
ACKNOWLEDGE NUMBER (32)		= 4 Bytes
HEADERS 6 BITS LENGTH RESER VED	URG P R S F R C S S Y I C K H T N N ADV WINDOW (16)	= 4 Bytes
CHECK SUM(16)	(16) URGENT POINTER	= 4 Bytes
OPTIONS (0-40) Bytes		= 40 Bytes
DATA		

4 bits

∴ Max header length
 in TCP = 60 Bytes

∴ Min. header length
 in TCP = 20 Bytes

2. SOURCE PORT, DESTINATION PORT AND SOCKET

⇒ TCP is End-End protocol because of having port numbers.

⇒ Port numbers are used for multiplexing and Demultiplexing.

⇒ SP DP
16 16

[0 to $(2^{16}-1)$] ports can be represented

$$= (0, 65535)$$

Http: 80	well known services port numbers
FTP: 21	
Telnet: 23	
Smtp: 25	Reserved 49, 151
49, 152	General public 65, 535
65, 535	


⇒ Open your browser and type "Net stat" to see all the connections, and

port numbers (source port number, destination port number)

⇒ TCP is connection oriented protocol (Resources are Reserved).


$$\Rightarrow \boxed{\text{Socket} = \text{IP} + \text{Portnum}} = 32 + 16 = 48 \text{ bits}$$

⇒ Sockets are used to identify a connection uniquely.




3. SEQ.NO, ACK.NO., RANDOM INITIAL SEQ.NO

- ⇒ TCP is a Byte Stream protocol.
- ⇒ IP is a packet Stream protocol.
- ⇒ HDLC (DLL) is a Bit Stream protocol.



⇒ In TCP the data bits are numbered. The seq.no field contains the value of starting data bit.

⇒ Ack field is used when the sender sends the TCP packet and is waiting for acknowledgement. Ack field contains the value of the data bit that is expected next (seq.no of the byte expected to come next).



4. WRAP AROUND TIME AND PROBLEMS ON WRAP AROUND TIME

⇒ Wrap around is nothing but using up all the seq.nos present and reusing the seq.nos that have already been used is called wraparound. From this we get "wrap Around time".

WAT

⇒ Wrap Around Time (WAT) depends on the Bandwidth.

⇒ Seq. No's field contain 32 bits $\Rightarrow 2^{32}$ seq.nos are possible.

⇒ Now, Let us say Bandwidth = 1 MBps

$$\Rightarrow 1 \text{ sec} - 1 \text{ MB}$$

$$\text{WAT of } n \text{ seq.nos} = \frac{n}{\text{Bandwidth}}$$

$$\Rightarrow 10^6 \text{ B} - 1 \text{ sec}$$


$$\Rightarrow 10^6 \text{ seq.nos} - 1 \text{ sec}$$

$$\Rightarrow 1 \text{ seq.no} - \frac{1}{10^6} \text{ sec}$$

$$\Rightarrow 2^{32} \text{ seq.no} - \frac{2^{32}}{10^6} \text{ sec} = 4296.967296 \text{ sec}$$

→ In today's internet there is a concept called Lifetime which means if you send a packet now the packet will be alive for sometime (3 min) which means at worst case it will reach after 3 minutes after you send it.

$$LT = 3\text{ min} = 180\text{ sec}$$




II.

Let us consider $WAT = 2^{32} = 4,294\text{ sec}$

$$BW = 1\text{ Gbps} = 10^9\text{ bps}$$

$$\text{Life time} = 180 \text{ seconds}$$

$$\Rightarrow \text{Here } WAT \ll LT$$



$$\Rightarrow 1\text{ sec} - 1\text{ GB}$$

$$\Rightarrow 180\text{ sec} - 180\text{ GB}$$

$$\Rightarrow 1\text{ sec} - 10^9\text{ seq.no}$$

$$\Rightarrow 180\text{ sec} - \frac{2^{32}}{10^9} \text{ seq.no}$$

Now, to solve the above problem, the possible solution is Decreasing the Bandwidth, But this is not possible because we are interested in having high Bandwidth (The speed at which the data gets transferred) so the other possible solution is increasing the ^{bits in the} sequence no field.

$WAT > LT \Rightarrow$ No problem.

$WAT < LT \Rightarrow$ problem \Rightarrow so calculate how many seq.nos are transmitted in 180 sec

$$\Rightarrow 1\text{ sec} - 1\text{ GB}$$

$$\Rightarrow 180\text{ sec} - 180\text{ GB}$$

$$\Rightarrow 180\text{ sec} - 180 \times (10^9 \text{ seq.nos})$$

∴ The min seq.nos required to avoid wraparound within Life time

$$= 180 \times 10^9 \text{ seq.no}$$

$$\therefore \text{The No.of bits in seq.no field is } = \lceil \log_2(180 \times 10^9) \rceil = 42$$

$$\therefore \text{The no.of additional bits needed to avoid above problem} = 42 - 32 = 10$$


[These 10 bits are used in option and called as Time stamp]

→ The no. of bits in the sequence no field such that there won't be any problem with WAT and LT, given at bandwidth Bw is $\lceil \log_2(LT * Bw) \rceil$

5. HEADER LENGTH AND CALCULATION OF ACKNOWLEDGMENT NUMBERS

→ Header length field is 4 bits, but the min size of the header is 20B

→ Scaling factor of $\frac{60}{15} = 4$ is used. $\left\{ \begin{array}{l} \text{max size of header} \\ \text{largest no by 4 bits} \end{array} \right. = \text{scale factor}$



SEQ.NO: Seq.no of 1 Byte

ACK.NO: Seq. no of Byte expected next.



PROBLEM

$$TL = 1000 \text{ B} \quad \left. \begin{array}{l} \text{for IP Datagram} \\ \text{HLF} = 5 \end{array} \right.$$

$$\left. \begin{array}{l} \text{HLF} = 5 \\ \text{Seqno of TCP Segment} = 1000 \text{ B} \end{array} \right\} \text{for TCP Segment}$$

then what is the seq.no of the next byte expected?

Ans: TCP segment will be in the IP Datagram



⇒ Next Byte seq.no = $1059 + 1$

$$= \underline{\underline{1060}}$$

6. TCP CONNECTION ESTABLISHMENT

⇒ Flags are nothing but 1 bit information, TCP is connection oriented.

SYN (SYNCHRONIZATION FLAG)

ACK (ACKNOWLEDGEMENT FLAG)




Now, TCP is connection oriented protocol and it has 3 phases,

1) Connection Establishment

2) Data Transfer

3) Connection Termination.

CONNECTION ESTABLISHMENT



⇒ MSS is included in options field.

⇒ TCP is full duplex (Data transfers in both direction).

⇒ window size : Capacity of the host as a receiver (flow control).

⇒ "SYN" PACKET WILL EATUP 1 SEQ NUMBER.

⇒ TCP uses "piggy Backing" Acknowledgements, and also pure Acknowledgments.


⇒ "ACK=1" TAKE '0' NO OF SEQ.NOS

⇒ "FIN=1" TAKE '1' SEQ.NOS.

⇒ 1 DATA BYTE TAKES '1' SEQ.NOS.

⇒ THIS METHOD OF CONNECTION ESTABLISHMENT IS CALLED "3-WAY HANDSHAKE" PRINCIPLE.

7. TCP DATA TRANSFER AFTER CONNECTION ESTABLISHMENT



SYN


- ACK
- 1 0 → 1st packet = 1st Segment = Request Segment
- 1 1 → 2nd segment = Reply Segment
- 0 1 → pure acknowledgement (Ack is present in the header)
- 0 0 → (Not possible)

⇒ sender is not going to send Acknowledgements immediately, he is going to wait for some time

⇒ The Receiver also waits for some time before transmitting the data.

⇒ If u don't have data to send immediately we should not wait because there will be a timer at the other end. So we should send PURE ACK.

8. TCP CONNECTION TERMINATION




SYN: Synchronising Seq numbers

ACK: Indicate whether Ack num field is valid/not

FIN: Request for connection termination.

⇒ FIN = FINISH FLAG (used

to terminate the Connection)



⇒ After client sending FIN packet the events that are possible and not possible are

→ Data C → S X

→ Data S → C ✓

→ ACK C → S ✓ (pure ACK)


→ ACK S → C (piggy Backed)

9. PSH FLAG

PSH = PUSH FLAG


⇒ Interactive Applications = chat, Telnet (Remote Login), Putty, SSH, Rlogin.

⇒ PUSH is used to say TCP not to Buffer it, push it (data). (Don't collect the data until you reach your MSS send the data received from AL at the same time without Buffering).



10. URG FLAG AND URGENT POINTER

URG = URGENT FLAG




⇒ Let us assume that there is a Telnet connection between the two hosts 'A' and 'B'.

⇒ You have some data to send. Let us say that you are sending the data in the form of files F1 F2 F3 and they are going to sit in Buffer at host B. All those core existing files which you want to modify


⇒ Now, suddenly you realised that what you did was wrong and you want to execute the command (Ctrl+c)(c+c) before all the files. [Ctrl+c is used for stopping]

⇒ So Urgent flag is used here, which means you have to say that last command is urgent when compared to other things.

⇒ So for "(Ctrl+c) send URG=1"




→ Now, In a Tcp segment if URG=1 then it indicates that some part of the data in this segment is important and the next one is urg pointer this urg pointer indicates till what posit the data is urgent.




1ST FLAG

⇒ RESET flag is used when there is a wrong in the connection. If you see anything unexpected then you are going to use Reset flag.



12. TCP FLOW CONTROL USING ADVERTISEMENT WINDOW

⇒ Flow control, a sender should never send what a receiver can't receive.
for that reason we are going to use window size.



⇒ The window size is 16 bits \Rightarrow Max no. $= 2^{16}-1 = 65,535$


$$\begin{aligned} & \text{Window size} = 16 \\ & = 16 + 14 \text{ (options)} \\ & = 30 \text{ bits} = 2^{30} = 1GB. \end{aligned}$$

⇒ Adv window is used for flow control.

13. TCP CHECKSUM

⇒ TCP Header has 16-bit checksum.

⇒ In TCP the checksum is calculated both on the data and header.



⇒ Checksum is calculated on TcpHeader, TcpData, IpHeader. Calculate checksum only on the fields in pseudo IP header.

PIP:	SIP(32)
	DIP(32)
Pseudo IP Header.	000 Protocol Length
	(8) (8) (16)


Because other fields will change when the packet is received by receiver.

14. OPTIONS IN TCP HEADER


- ⇒ Time Stamp (WAT < LT)
- ⇒ Window size Extension
- ⇒ Parameter Negotiation
- ⇒ Padding

15. RETRANSMISSIONS IN TCP

- ⇒ TCP USES SR + GBN
- ⇒ $w_s = w_R \rightarrow$ Acknowledgements are cumulative
- ⇒ out of order packets are possible $\rightarrow 25\% \text{ GBN}$
- 75% SR



16. INTRODUCTION TO TCP CONGESTION CONTROL




⇒ Assume that the receiver has said that sender can send 16B of data in the Advertising window. $\rightarrow w_s = 16B, w_p = 16B$

⇒ The problem here is even though the Receiver can hold 16B of data the underlying Network cannot hold 1024 packets.

→ So the sender should not dump the data ON the Network without finding the capacity of the Network(w_c).

→ A sender should always send $\min(w_c, w_R)$ data to the Network & Receive so we should stop the traffic at sender side.



→ Even though you can send 8 segments at a time don't do it because the underlying Netw may not be in a position to handle the segments. So send segments one by one in some order.

→ The Algorithm goes like this whenever the Receiver capacity = 8 then find the threshold value = $w_{s/2} = 8/2 = 4$

Threshold value = 4

→ Now increase the no. of segments that are being sent, exponentially upto the threshold value and after that send the packets Linearly.

→ How does this congestion window grow is initially congestion window is going to send 1 segment, if we get the acknowledgements back then we send 2 segments, and then 4 segments (increase exponentially till the threshold value) and then increase Linearly.

1
2 } Exponential
4 → Threshold
5
6
7 } → Linear Growth of No. of Transmissions.
8

V. IMP

1) AFTER HOW MANY RTT'S ARE WE GOING TO REACH THE MAX SENDER WINDOW SIZE (8)?

Ans 6 Roundtrip times.

1	2	4	5	6	7	8
1RTT	2RTT	3RTT	4RTT	5RTT	6RTT	7RTT

17 Adv Win = 16KB

MSS = 1KB



W_R = 16 Segments \rightarrow Threshold = $16 \times 2 = 8$

W_S = 1 Segment

AFTER HOW MANY RTT'S WILL WE REACH TOTAL CAPACITY?

1	2	4	8	9	10	11	12	13	14	15	16
1RTT	2RTT	3RTT	4RTT	5RTT	6RTT	7RTT	8RTT	9RTT	10RTT	11RTT	

$\Rightarrow 11$ RTT's



SS PHASE = "EXPONENTIAL GROWTH".

CA PHASE = "LINEAR GROWTH".

17. TCP CONGESTION CONTROL ALGORITHM WITH EXAMPLE

⇒ The congestion control algorithm has three steps they are

1. Slow start phase
2. Congestion avoidance phase
3. Congestion detection phase


⇒ There are 3 ways to detect congestion they are

- ✓ 1. Time out (Severe Congestion) ⇒ (SS PHASE)
- ✓ 2. Three Duplicate Acknowledgements (Mild congestion) = (CA PHASE)
- * 3. ICMP Messaging (source Quench). (Most of the Implementations don't consider it)

1) $W_R = 64 \text{ KB}$

$\text{MSS} = 1 \text{ KB}$


$W_R = 64 \text{ Segments} \Rightarrow Th = 64 / 2 = 32 \text{ MSS}$



2) $W_R = 64 \text{ KB}$

$\text{MSS} = 1 \text{ KB}$


$W_R = 64 \text{ MSS} \Rightarrow Th = 32 \text{ mss}$



GATE

Consider an instance of TCP Additive Increase Multiplicative decrease (AIMD) Algorithm where the window size at the start of ssphase is '2' MSS and the threshold at the start of 1st transmission is '8'mss. Assume timeout occurs during 5th transmission, find the Congestion window size at the end of 10th transmission?


- (A) 8mss (B) 14mss (C) 7mss (D) 12mss



18. TCP TIMER MANAGEMENT

- 1) Time-wait timer \Rightarrow Don't close the connection immediately wait for $2 \times LT$
- 2) Keep-Alive timer \Rightarrow close All the idle connections
- 3) persistent timer \Rightarrow For finding the capacity of Receiver
- 4) Acknowledgement timer \Rightarrow cumulative Acknowledgement and Piggy Backing
- 5) Time-out timer \Rightarrow


19. INTRODUCTION TO TIME-OUT TIMER




$$\left\{ \begin{array}{l} RTT = 2 \times T_p \\ TO = 2 \times RTT \end{array} \right.$$

REMARKS AND NOTES FOR TIME-OUT TIMER

\Rightarrow At TCP static time out timers cannot be used in scenarios where




\Rightarrow Initially there is no congestion but after that because of your timeout timer settings it might lead to congestion so have a large timeout timer, but the disadvantage of having large TO is if a packet is lost you have to wait for a long time before retransmitting it.



20. BASIC ALGORITHM FOR TOT COMPUTATION

⇒ The first Algorithm used to set timeout timer dynamically at TCP is

"BASIC ALGORITHM"



$$IRTT = 10ms \text{ (Guessing)}$$

$$TOT = 2 * IRTT = 20ms$$

$$ARIT = 15ms$$

$$NRTT = \alpha * IRTT + (1-\alpha) ARIT$$

α = Smoothing Factor

$$0 < \alpha \leq 1 \quad \alpha = 0.5$$

TIME MANAGEMENT

$$NRTT = 0.5 * 10 + 0.5 * 15$$

$$NRTT = 12.5ms \Rightarrow TOT = 25ms$$

⇒ This Algorithm is Dynamic Nature

⇒ The disadvantage is $TOT = 2 * RTT$

No logic why we are using "2"

IRTT = INITIAL ROUNDTRIP TIME

ARIT = ACTUAL ROUNDTRIP TIME

NRTT = NEXT ROUNDTRIP TIME

for Next packet IRTT = 12.5ms

$$TOT = 2 * IRTT = 25ms$$

$$ARIT = 20ms$$

$$NRTT = (0.5)(12.5) + (0.5)(20)$$

$$NRTT = 16.25ms$$

for Next packet IRTT = 16.25

$$TOT = 32.5ms$$

$$ARIT = 10ms$$

$$NRTT = (0.5)(16.25) + (0.5)(10)$$

$$NRTT = 13.125$$

21. JACOBSON'S ALGORITHM FOR TIMEOUT COMPUTATION AND KARN'S MODIFICATION

⇒ The Jacobson's Algorithm is used to set the timeout timer.

① Initialization on the start of connection

$$IRTT = 10ms \quad NRTT = \alpha * (IRTT) + (1-\alpha) (ARIT)$$

$$ID = 5ms$$

$$AD = 15ms \quad (\alpha = 0.5)$$

$$TOT = 4 * ID + NRTT$$

$$= 4 * 5 + 10$$

$$= 30ms \quad \text{interval for retransmission}$$

$$ND = \alpha * (ID) + (1-\alpha) (AD)$$

$$= 7.5ms$$

$$ARIT = 20ms$$

$$ID = \text{Initial deviation}$$

$$AD = 10ms (IRTT - ARIT)$$

$$XD = \text{deviation}$$

for the 2nd segment that you are sending

$$IRTT = 15 \text{ ms}$$

$$ID = 7.5 \text{ ms}$$

$$TO = 4 * ID + IRTT$$

$$= 4 * 7.5 + 15$$

$$ID = 45 \text{ ms}$$

$$ARTT = 30 \text{ ms}$$

$$AD = (30 \text{ ms} - 15 \text{ ms}) = 15 \text{ ms}$$

$$NRTT = \alpha (IRTT) + (1-\alpha)(ARTT) \quad \{\alpha=0.5\}$$

$$= (0.5)(15) + (0.5)(30)$$

$$= 7.5 + 15 = 22.5 \text{ ms}$$

$$ND = \alpha (ID) + (1-\alpha)(AD)$$

$$= (0.5)(7.5) + (0.5)(15)$$

$$= 11.25 \text{ ms}$$

for the 3rd segment that you are sending

$$IRTT = 22.5 \text{ ms}$$

$$ID = 11.25 \text{ ms}$$

$$TO = 4 * ID + IRTT$$

$$= 4 * 11.25 + 22.5$$

$$= 67.5$$

$$ARTT = 10 \text{ ms}$$

$$AD = 12.5$$

$$NRTT = \alpha (IRTT) + (1-\alpha)(ARTT) \quad \{\alpha=0.5\}$$

$$= (0.5)(22.5) + (0.5)(10)$$

$$= 16.25$$

$$ND = \alpha (ID) + (1-\alpha)(AD)$$


$$= 0.5(11.25) + 0.5(12.5)$$

$$= 11.875$$

$$TO = 4 * D + RST = 63.75$$

⇒ Karn's modification says when you receive the acknowledgement for the packet after the timeout, keep doubling the TO for the next packets.

2. SILLY WINDOW SYNDROME



⇒ Nagles Algo says that if sender is very slow the TL should not send 1B of data, the TL should wait for 1RTT and collect the data that has come in 1RTT time and send that data in one Segment.

⇒ Clarke Algo says that Receiver should not advertise 1 it should wait until it gets a size of 1mss or half of the Buffer.

13. UDP

1. NEED FOR UDP

⇒ TCP is going to be disadvantageous for some applications they are


1> If Application needs 1 Request and 1 Reply Ex: DNS, BOOTP, DHCP, NTP
(Network Time protocol),

NNP (Network News protocol), "out of
day" protocol,
TFTP, RIP, OSPF

2> Broadcast or Multicast

3> Fastness rather than Reliability (Multimedia Applications) (online game)

UDP HEADER



⇒ Checksum is calculated on
UDP Header + UDP Data +
pseudo Header from IP.

⇒ UDP should communicate the options to the IP Datagram, the various options are 1> Trace route 2> Record Route 3> Time Stamp


⇒ Additional Responsibilities of UDP is, if we get any ICMP error packets
UDP should inform Application Layer

14. APPLICATION PROTOCOLS


1. INTRODUCTION TO APPLICATION LAYER

⇒ Application Layer is responsible for all the services that internet provide


⇒ The Application Layer protocols are DNS, HTTP, FTP, SMTP, POP



- DNS**
- DNS PORT NO: 53
- ⇒ DNS = DOMAIN NAME SERVICE (DNS uses UDP at Transport Layer)
- ⇒ To convert Domain name to IP Address we use DNS.
- ⇒ The various domains are
- Generic Domains (.com, .edu, .mil, .org, .net)
 - Country Domains (.in, .us, .uk...)
 - Inverse Domain (Given IP Address → find Domain Name)
- ⇒ To find the IP Address of a website type "NSlookup www.google.com"
- ⇒ DNS is also used for Load Balancing
- ⇒ DNS Database is organized in this way (Distributed Database)



⇒ what if the Root DNS Server fails, so IETF (INTERNET ENGINES TASK FORCE) made 13 Root servers across the world.



3. HTTP

[HTTP → PORT NO = 80]

- ⇒ Hypertext transfer protocol (For getting web pages).
- ⇒ Http always need Reliability.
- ⇒ Http uses "Tcp" at Transport layer.
- ⇒ Http is Inband protocol (Both data and commands go in one connection).
- ⇒ Http is stateless protocol.
- ⇒ The two popular versions of Http are : Http 1.0 (Non-persistent connection) and Http 1.1 (Persistent connection).
- ⇒ The popular methods that are used by Http are
 - a) Head ⇒ Get the Header of webpage (metadata).
 - b) Get } Used with forms
 - c) post
 - d) put ⇒ To upload an object
 - e) Delete ⇒ To delete the object
 - f) Trace ⇒ Trace the servers which are sending data to you.
 - g) options
 - h) Connect ⇒ https uses it. (For Authentication).

4. FTP


FTP = File Transfer Protocol.

[FTP PORT NUM = 21]

- ⇒ Tectia, filezilla are the two most popular FTP's.

- ⇒ FTP is used to transfer files.

(filezilla file client)



- ⇒ FTP is called out-of-band protocol and requires Reliability.

- ⇒ FTP uses Tcp as the underlying protocol.

- ⇒ FTP is stateful protocol.

5. SMTP AND POP

(48)


SMTP - Simple Mail Transfer Protocol, POP = Post office protocol.

⇒ E-mails are transferred using SMTP.

⇒ We cannot transfer the files using FTP because to transfer the files using FTP both server and client should be online.

⇒ Gmail is the web based mail.


⇒ MTA = Mail Transfer Agent



Non-Text → Text
 Text → Non-Text

→ MIME (Multipurpose Internet Mail Extension) protocol To deal with Non-Text.

What Gmail does ?



⇒ SMTP and POP are Inband protocols.


19. NETWORK SECURITY

909 21A TUE

I. INTRODUCTION TO CRYPTOGRAPHY


- ⇒ The main aim of cryptography is to convert a message from plain text into some unreadable form before you send it over the wires.
- ⇒ The process of converting the plain text to Cipher text is called Encryption.
- ⇒ The process of converting the Cipher text to plain text is called Decryption, we need these two mechanisms in such a way that Sender can only do Encryption and Receiver can do Decryption.
- ⇒ There are 2 types of Cryptography they are
 1. Symmetric Key Cryptography (or) shared Key
 2. Asymmetric Key Cryptography (or) public Key Private Key Cryptography

⇒ Symmetric Key Cryptography deals like this



⇒ Before sending the data we must send Key (Share the Key with the Receiver, so anyone can tamper our signal).

⇒ The solution to the above problem comes in form of public, private keys




public, private Keys works Analogous this way.

2. ENCRYPTION USING PUBLIC KEY PRIVATE KEY


⇒ Before transmission of Data both sender and Receiver should generate a pair of keys called public key and private key. These keys work this way,

⇒ If you encrypt anything with public key of A, you can Decrypt only with private key of 'A' and vice versa.


⇒ Now after generating pair of keys ,Now both public key of A, public Key of B should be known Globally and the private key will only be known only to that party. Now, the sender (A) has 3 Keys they are (PUA, PUB, PRA).



3. AUTHENTICATION USING PUBLIC KEY PRIVATE KEY



4. ENCRYPTION AND AUTHENTICATION TOGETHER



⇒ Initially we have to generate public Key private Key pairs. This can be generated using Number theory and from that we should do some Basics and from that two Algorithms, from that Algo's we get the public key private key pair.

5. FERMAT THEOREM

⇒ The entire public key and private keys are based on prime numbers

⇒ This theorem states that if 'p' is a prime number and $a \in \mathbb{Z}^+$ in such a way that 'p' does not divide 'a'; then we can say that $a^{p-1} \equiv 1 \pmod{p}$

$$a^{p-1} \equiv 1 \pmod{p} \quad \Rightarrow \quad a^p \equiv a \pmod{p}$$

Ex:

$$a=2, p=7$$

⇒ used in primality testing (to check whether a given no. is prime)

$$a^p = 2^7 = 128$$

$$a^{p-1} = 2^6 = 64$$

$$a^{p-1} \pmod{p} = 1$$

EULER'S TOTIENT THEOREM

⇒ Euler Totient function says that if we have a number n , then the Euler totient function $\phi(n)$ is defined as the nof integers ' k ' in the range $1 \leq k \leq n$ which are relatively prime to ' n ', $[\text{gcd}(k, n) = 1]$

$$n=9 \rightarrow 1, 2, 4, 5, 7, 8 \Rightarrow \phi(9) = \boxed{\phi(9)=6} \quad \left\{ \begin{array}{l} 1, 2, 4, 6, 7, 8 \text{ are Relatively Prime} \\ \text{to } 9. \rightarrow \text{gcd}(1, 9) = \text{gcd}(2, 9) = \end{array} \right.$$

$$n=5 \rightarrow 1, 2, 3, 4, 5 \Rightarrow \boxed{\phi(5)=4} \quad \text{gcd}(4, 9) = \text{gcd}(5, 9) = \text{gcd}(7, 9) =$$

$$n=7 \rightarrow 1, 2, 3, 4, 5, 6 \Rightarrow \boxed{\phi(7)=6} \quad \therefore \left\{ \begin{array}{l} \text{If } n \text{ is prime nos then} \\ \phi(n) = (n-1) \end{array} \right.$$

$$n=10 \rightarrow 1, 3, 7, 9 = \boxed{\phi(10)=4}$$

⇒ $\phi(n)$ is Multiplicative ⇒ If n can be written as product of two nos m, l such that m, l are relatively prime then

$$\phi(n) = \phi(m) \times \phi(l)$$

$$\Rightarrow \phi(10) = \phi(2) \times \phi(5) \quad \text{Relatively prime numbers to each other.} \\ = 1 \times 4$$

$$\Rightarrow \boxed{\phi(10)=4}$$

$$\Rightarrow \phi(35) = \phi(5) \times \phi(7)$$

$$= 4 \times 6$$

$$\boxed{\phi(35) = 24}$$

⇒ If p, q are prime numbers then $\phi(p \times q) = \phi(p) \times \phi(q)$

$$\boxed{\phi(p \times q) = (p-1)(q-1)}$$

1. CHINESE REMAINDER THEOREM

⇒ Chinese Remainder theorem says, Let us say we have set of numbers

$\{n_1, n_2, n_3, \dots, n_k\} \in \mathbb{Z}^+$ and they are pair wise coprimes ($\text{gcd}=1$) then

we can take an integer ' x ' and we can represent it uniquely and such ' x ' should be in the range of less than or equal to product of $\{n_1, n_2, \dots, n_k\}$

$$\Rightarrow x \cong (1 \dots n_1 \times n_2 \times n_3 \dots \times n_k)$$

$$x \equiv a_1 \pmod{n_1}$$

$$x \equiv a_2 \pmod{n_2}$$

FIRST TOTAL THEOREM

Now let us say I have two relatively prime numbers (2), (5). Now I can take $2 \times 5 = 10$ and I can write all the nos between 1 to 10 uniquely as set of remainders when divided with 2 and with 5.

$\begin{array}{r} \text{÷ by } 2 \\ \text{÷ by } 5 \end{array} \quad \begin{array}{c} 2 \\ \text{rem} \\ 5 \end{array} \quad \begin{array}{c} 1 \\ 1 \\ 1 \\ 1 \\ 1 \\ 1 \\ 1 \\ 1 \\ 1 \\ 1 \end{array} \quad \begin{array}{c} 0 \\ 2 \\ 1 \\ 0 \\ 1 \\ 0 \\ 0 \\ 3 \\ 1 \\ 0 \end{array} \quad \begin{array}{c} \text{Remainder} \\ 1 \\ 2 \\ 3 \\ 4 \\ 5 \\ 6 \\ 7 \\ 8 \\ 9 \end{array}$

⇒ Mainly used in Encryption.

1 - 0 1

2 - 0 2

3 - 1 3

4 - 0 4

5 - 1 0

6 - 0 1

7 - 1 2

8 - 0 3

9 - 1 4

10 - 0 0

11 - 1 1

12 - 0 2

8. PRIMITIVE ROOT

⇒ If 'a' and 'n' are Relatively prime numbers then there exists atleast one number 'm' such that $a^m \equiv 1 \pmod{n}$.

If $a=7, n=19$ then $m=?$ (Take the smallest value)

$$\Rightarrow 7^m \equiv 1 \pmod{19}$$

$$\Rightarrow m=3 \Rightarrow 7^3/19=1 \Rightarrow m=3 \quad \{ \text{option verification method} \}$$

9. CHINESE REMAINDER THEOREM

③ If $a=3, n=7, m=?$

$$\Rightarrow 3^m \equiv 1 \pmod{7}$$

$$\Rightarrow m=6$$

$$\begin{array}{ll}
 \rightarrow \text{Now, } 3 \bmod 7, \Rightarrow & \begin{array}{l} 3^1 \bmod 7 = 3 \\ 3^2 \bmod 7 = 2 \\ 3^3 \bmod 7 = 6 \\ 3^4 \bmod 7 = 4 \end{array} \quad \begin{array}{l} 3^5 \bmod 7 = 5 \\ 3^6 \bmod 7 = 1 \\ 3^7 \bmod 7 = 3 \\ 3^8 \bmod 7 = 6 \end{array} \\
 \left. \begin{array}{l} 3^9 \bmod 7 = 4 \\ 3^{10} \bmod 7 = 2 \end{array} \right\} & \begin{array}{l} \text{I got all numbers from (1 to 6).} \\ \therefore \text{The repeating sequence } (3, 2, 6, 4, 5, 1) \text{ is called period = 6 (total nos).} \end{array} \\
 \rightarrow 2 \bmod 7 \rightarrow 2^1 \bmod 7 = 2 & \begin{array}{l} 2^5 \bmod 7 = 4 \\ 2^6 \bmod 7 = 1 \\ 2^7 \bmod 7 = \end{array} \\
 \left. \begin{array}{l} 2^2 \bmod 7 = 4 \\ 2^3 \bmod 7 = 1 \\ 2^4 \bmod 7 = 2 \end{array} \right\} & \begin{array}{l} \text{The Repeating sequence is } (2, 4, 1) \Rightarrow \text{period = 3.} \\ \text{Hence, } 2^8 \bmod 7 = 2 \end{array}
 \end{array}$$

\Rightarrow Now, if I find $(a \bmod b)$ to all powers of upto b^1 and the period is $\phi(b)$ then 'a' is called as primitive root of 'b'.

9. RSA ALGORITHM (RIVEST SHAMIR ADLEMAN ALGORITHM)

\Rightarrow The most popular Algorithm to generate public key, private key \rightarrow 1977 proposed.

Step-1: CHOOSE TWO DISTINCT PRIME NUMBERS 'P' AND 'Q' (VERY BIG NUMBERS)

Step-2: COMPUTE $N = P \times Q$

Step-3: FIND $\phi(n) = (P-1) * (Q-1) = (P \times Q) - (P+Q-1) = N - (P+Q-1)$.

Step-4: CHOOSE AN INTEGER 'E' SUCH THAT $1 < e < \phi(n)$ & $\gcd(e, \phi(n)) = 1$
 $(e, n) \Rightarrow$ PUBLIC KEY

Step-5: DETERMINE 'd' as $d \cong e^{-1} \pmod{\phi(n)}$ $\Rightarrow ed \cong 1 \pmod{\phi(n)}$

$(d, n) \Rightarrow$ PRIVATE KEY

EXAMPLE


1) $P = 61, Q = 53$

2) $N = 61 \times 53 = 3233$

3) $\phi(n) = 60 \times 52 = 3120$

4) $e \Rightarrow 1 < e < 3120 \Rightarrow e = 17 \xrightarrow{\text{chosen}} \text{PUBLIC KEY} = (17, 3233)$

5) $d \Rightarrow ed \bmod \phi(n) = 1 \Rightarrow [(ed) \bmod \phi(n)] = 1 \Rightarrow d = 2753 \Rightarrow (2753, 3233) = \text{PRIVATE KEY}$



$$m = 65$$

$$CT \rightarrow (65)^{17} \bmod 3233$$

$$CT = 2790$$

A.

$$PU_A = (17, 3233)$$

$$PR_A = (2790, 3233)$$

Encryption

$$\text{Cipher Text} = (m)^e \bmod n \rightarrow \text{To Encrypt}$$

$$\text{Plain Text} = (CT)^d \bmod n \rightarrow \text{At Decryptor}$$

$$\Rightarrow \text{At Receiver } m = (2790)^{2753} \bmod 3233$$

$$m = 65$$

10. DIFFIE HELLMANN ALGORITHM

⇒ This Algorithm is based on the concept of primitive Root

⇒ This Algo is used for generated public and private keys

⇒ This Algo is used to share the key securely. Key Exchange

Alice

Bob

1) Both Alice and Bob Agreed to use a prime number 'p' and base 'g'.

2) Alice chooses a secret key (secret integer) 'a', then sends $A = g^a \bmod p$ to Bob

3) Bob also chooses a secret integer 'b' then he too sends $B = g^b \bmod p$ to Alice

4) Both Alice and Bob compute the secret key like this.

$$\text{Alice computes } S = B^a \bmod p = 19^6 \bmod 23 = 2$$

$$5) \quad \text{Bob computes as } S = A^b \bmod p = 8^{15} \bmod 23 = 2$$

Alice

Bob

$$p = 23, g = 5$$

$$a = 6$$

$$A = 5^6 \bmod 23 = 8$$

$$b = 15$$

$$B = 5^{15} \bmod 23 = 19$$

$$A = 8$$

$$B = 19$$

⇒ Not used for Encryption and Decryption used only for Key exchange.

20. IPV6 AND WIFI

↓ Need for IPV6:

- IPv4 Address depletion (Not Available no. of IP Address)
- Realtime Audio/video transmissions
- Encryption (provided at Network Level).
- Authentication
- fast processing (Avoid the process that makes the routers work (Busy))
- Additional Functionalities. (Extend Headers concept is used)
- IPV6 is called IPng (ng = Next Generation)

IPV6 HEADER

BASE HEADER (40B) Fixed Size	VER (4)	PRIORITY / (8) TRAFFIC CLASS	FLOWLABEL (20 bits)		= 4 Bytes	
	(16)	PAYLOAD LENGTH	NEXT HEADER	HOP LIMIT (8)	= 4 Bytes.	
	SOURCE ADDRESS (128)		= 16 Bytes			
	DESTINATION ADDRESS (128)		= 16 Bytes			
	EXTENSION HEADER 1					
	EXTENSION HEADER 'N'					
	DATA					

VER → what type of version we are holding. (If VERSION = 0110: IPV6
0100: IPV4)

PAYLOAD LENGTH:

BH	Payload
----	---------

 → IPV6 packet
↓
Base Header

NEXT HEADER: It says what type of Extension Header is just next to the destination address (Extension Header '1') (same as options)

Hop Limit: Is same as TTL.

Questions that might be possible one

- 1) what are the fields that are present in both IPV4 and IPV6? (VERSION)
- 2) what is the size of Source IP field.
- 3) TRUE / FALSE QUESTIONS!
- 4) Which of the following has static header IPV6 / IPV4? (Ans: IPV6)

3. TRAFFIC CLASS

19114091 2020 03

The traffic can be classified into 2 types

Traffic → Congestion controlled Traffic: The protocols that are sending the data observes there will be congestion and they will adjust their sizes (window sizes) appropriately.

uncontrolled Traffic: No such above facility.

Ex: Audio video Traffic, (Live streaming)

→ Now the first 4 bits of Traffic field will be given to priority [4 bits (0-15)]
(0-7)(8-15)

Pri	Meaning	
0-	No Specific Traffic	Congestion controlled
1-	Background data - News transmission is example	↓ uncontrolled
2-	Unattended data traffic - Email data	8-least priority
3-	Reserved	15-High priority
4 -	Attend Bulk data traffic - FTP, HTTP	low definition videos.
5-	Reserved	
6-	Interactive traffic - Remote login, putty, ssh	
7-	control traffic. - Highest priority among all (SNmp, Routing data)	


Simple Network management protocol

- The priorities are set by the upper layers, (above Nw layer) and IPv6 should provide an interface to the above layers by which priorities can be set.
- Source can set priority, Routers can change priority
- Destination should not assume the packet received is of same priority as set by source.


4. FLOW LABEL FIELD

Now, Assume, there are two process within hosts. The stream of packets that go from source - destination is called "flow". And all the packets that belong to same flow have the same requirements. They are

1. Source Address
2. Destination Address
3. priority of all packets should be same
4. Extension headers should be same



→ This says that whenever you are sending the flow before sending inform all the intermediate routers to allocate appropriate resources for a flow. Generally for informing the routers that you are going to send the data, there are 2 ways.



1. Control packets

Resource Reservation protocol

Real time transport protocol.

2. Extension Headers: You can specify the routers to allocate resources.

→ For all the packets in the flow we use a label called flow label.

(Randomly chosen)

→ The advantage of flow label is whenever a packet with label no. 10 arrives at the router, now router will form the flowtable and the contents are

Source Address	Flowlabel	Information	
A	10	BW, Buffers, CPU	→ one entry is enough for all the packets

→ Hashing is used on flow table

Question might be asked:

→ Between a source and destination there could be more than one flow.

→ All the packets need not have flow label, a packet can have flowlabel=0.

→ Router can ignore this facility.

5. PAYLOAD LENGTH

The entire thing that is present after Base header is called payload.


The payload contains: Extension Header, upper layer packets. **

→ Header is fixed in Spv6.

6. NEXT HEADER FIELD




Now, consider an Spv6 packet that contains a TCP packet (TCP Header, TCP Data).

then Next Header field should contain '6' which indicates the packet next is TCP packet.



Next Header Codes:

Code	Next header
0	Hop by Hop option
2	ICMP
6	TCP
17	UDP
43	Source routing
44	Fragmentation
50	Encapsulated security payload
51	Authentication
59	NONE (No Next header)
60	Destination option.



7. ORDERING OF EXTENSION HEADER

The order in which the Extension Headers should be placed after Base header are defined by RFC, and the order is:


1. Hop by Hop options Header
2. Destination option Header
3. Routing Header
4. Fragment Header
5. Authentication Header
6. Encapsulating Security payload Header
7. Destination Header
8. Upper layer Header.

- This order is not mandatory but it is a general convention. 64
- Each Extension Header should not appear more than once, except "Destination options header" *** (Almost 2 times)
 - If Hop-by-Hop options is even present in a packet then it should always be present immediately after Base Header (Mandatory Rule).

HOP BY HOP OPTIONS HEADER

The importance of Hop by Hop options header is whenever a source is sending the IPv6 packet via some intermediate routers then the packet should be examined by all the intermediate routers and the destination, and check if any functions are specified that must be carried out.

The Hop-by-Hop options look like.



Jumbo packet : payload size > 65535 then we use "Jumbo packet"


pad i: we have to see all the options of 8 bytes in length if we are having an option < 8B then we pad some bits.

ROUTING EXTENSION HEADERS - I

Source Routing option Header: source takes the control over the path in which its' packet should be transmitted.

Assume that source (A) wants to send a packet to destination (B) via two 3 intermediate routers (R_1, R_2, R_3) : $(A \rightarrow R_1 \rightarrow R_2 \rightarrow R_3 \rightarrow B)$

⇒ Now, say the IPv6 contains the Base Header and Routing Header (RH) and we know that the Base Header contains (source Address and Destination Address)



⇒ Along with BH, RH we will have a field called "Segments left" which represent the no. of intermediate nodes which are left to be visited before we reach the final destination. In this case, when the packet starts, its SL value = 3 (No. of intermediate routers that have to be visited before reaching B).

⇒ Let 'n' represent the no. of extension Headers / Address that are present in Extension Header


⇒ Let 'i' represent the no. of nodes that must be visited before we reach final destination. ($i = SL - 1$)

⇒ Now, $(n - i)$ gives the index of address that must be visited next.

⇒ Now, swap DA and the $A[i]$

A	R_1	R_2	R_3	B
$SA = A$	$SA = A$	$SA = A$	$SA = A$	$SA = A$
$DA = R_1$	$DA = R_1, R_2$	$DA = R_2, R_3$	$DA = R_3, B$	$DA = B$
$SL = 3$	$SL = 2$	$SL = 1$	$SL = 0$	$SL = 0 = \text{Accept}$
$A[1] = R_2$	$A[0] = R_1, R_1$	$A[1] = R_1$	$A[1] = R_2, R_3$	$A[1] = R_1$
$A[2] = R_3$	$A[2] = R_3$	$A[2] = R_3, R_2$	$A[2] = R_2$	$A[2] = R_1$
$A[3] = B$	$A[3] = B$	$A[3] = B$	$A[3] = B, R_3$	$A[3] = R_3$
$n=3, i=2$	$n=3, i=1$	$n=3, i=0$	$n=3, i=0$	$n=3, i=0$
$n-i=1$	$n-i=2$	$n-i=3$	$n-i=3$	
↓				
Swap DA & $A[i]$	Swap DA & $A[i]$	Swap DA & $A[i]$	Swap DA & $A[i]$	
$\Rightarrow DA = R_2$	$\Rightarrow DA = R_3$	$\Rightarrow DA = B$	$\Rightarrow DA = B$	
$A[1] = R_1$	$A[2] = R_2$	$A[3] = R_3$	$A[3] = R_3$	

ROUTING EXTENSION HEADER-2



⇒ HEL represent the size of header in terms/units/multiples of 8!

⇒ Now, say HEL=8 then what no. of Addresses that are present?

Each Address will contribute 2 to the HEL ⇒ $\frac{16}{2} = 8$ → Address size in IPv6

∴ HEL=8 ⇒ No. of Addresses = $\frac{HEL}{2} = \frac{8}{2} = 4$ Addresses are present.

$$\therefore \text{No. of IPv6 Addresses} = \frac{HEL}{2}$$


II. FRAGMENTATION EXTENSION HEADER


⇒ Not required for all packets

⇒ In IPv4 the fragmentation is done both at the "routers" and at "source".

⇒ In IPv6 the fragmentation is done only at the source. ***
The Routers are not supposed to the fragmentation.

⇒ The sender finds the path MTU before sending the packet and fragment it appropriately and starts the transmission. But there is no guarantee that the packet follows the path for which we calculated the MTU.
In that case, an icmp packet will be generated and sent to the sender.





12. NEED FOR SECURITY AT NETWORK LAYER



The main things that we need while sending the packet is

- 1> Confidentiality - No one should be able to read 'my message'.
- 2> Message Integrity / Message Authentication - Receiver should be able to find if the msg is changed on the way.
- 3> Source Authentication - If the msg is from the genuine source.
- 4> Reply attack problem - corrupt the data / copies of the same packet.

→ The protocol that is used to provide the above features, is called

"IP Security" protocol (or) "IPSEC"

collection of protocols.



13. MODES OF IP SECURITY


There are two modes in which IP security operates, they are

1. Transport mode
2. Tunnel mode

Transport mode :


Consider a Transport layer packet is passed to the NL then in the NL, first the packet is received by IPSEC and it adds IPSEC Header and IPSEC Trailer and again it is passed to the IP in NL, Now, IP adds IP Header and IP Trailer and transmits the packet.

Transport mode



→ The main point to note is the modification is done only on the payload part but not on the Transport, Network layer Headers.

Tunnel mode




→ The transformation is done on both the Headers and payload.

→ This is called tunneling because an IP packet is kept inside another IP packet and the two IP headers need not be same.

→ In IPv6 the Tunneling is used in between routers.

14. AUTHENTICATION HEADER

→ Authentication Header mainly provides us with message Integrity, Source Authentication.




⇒ NH : (8-bit) = Tells what is present in the next field if Top data is present then NH = 6.

⇒ payload length : (8-bit) : The length of the "Authentication Header." The Authentication Header size is measured in size of 4 Bytes. (scale factor 4)

15. ESP

Encapsulation Security payload protocol.

→ If the protocol field of IpHeader contains the number 50 then it represents that the next field is ESP.



→ The AH and ESP are operated under Transport mode.

16. IPV6 ADDRESSES


Size: 128 Bits

→ Unicast


→ Multicast

→ Anycast

Unicast: Every interface is going to have an Sp Address.




Multicast: we group many interfaces together (across the world) and assign an IP Address to the group, it is called multicasting, when a packet is sent at having the destination IP as multicast address then everyone in the Group is going to receive it.



Anycast:

Same as multicast but the difference is, In anycast if you send a packet having destination Sp as Anycast address the packet will be delivered to the closest host and it is the responsibility of that host to distribute the packet to every host in the group.



11. IPv6 ADDRESS REPRESENTATION

Colon Hexa Representation

⇒ IPv4 was using dotted decimal Representation.

⇒ IPv6 uses colon-Hexa decimal Representation.

$$\begin{array}{c}
 \text{ABCD : EF01 : 2345 : 6789 : ABCD : 2345 : 6789} \\
 \downarrow \quad \downarrow \quad \downarrow \quad \downarrow \quad \downarrow \quad \downarrow \quad \downarrow \\
 4\text{bits} \quad 4\text{bits} \quad 4\text{bits} \quad 4\text{bits} \quad = 2B + 2B \\
 \quad \quad \quad \quad \quad \quad = 16B \\
 \quad \quad \quad \quad \quad \quad = 16 \times 8\text{bits} = 128\text{bits} \\
 4+4+4+4=16\text{bits} \\
 = 2B
 \end{array}$$

⇒ Most of the parts of IPv6 are Zeros.

$$\text{ABCD : EF01 : 0000 : 6789 : 0000 : FF01 : 2345 : 6789}$$

⇒ They have used short hand representation by deleting the leading 0s and if all 4 0s are present they used a single '0'.

$$\text{Actual IP: ABCD : EF01 : } \underbrace{0000}_{\text{short hand}} : 6789 : \underbrace{0000}_{\text{short hand}} : \underbrace{\text{FF01}}_{\text{short hand}} : \underbrace{2345}_{\text{short hand}} : \underbrace{6789}_{\text{short hand}}$$

$$\text{Short Hand: } \text{ABCD : EF01 : } 0 : 6789 : 0 : \text{FF01 : } 2345 : 6789$$

12. TYPES OF IPv6 ADDRESSES

When an IPv6 Address is given then by looking at first few bits we can decide what type of IP Address it is.


prefix	Type
First 8 bits = <u>00000000</u>	Reserved - Loopback address, I don't have IP.
<u>00000001</u>	unassigned
<u>00000010</u>	unassigned
<u>00000011</u>	unassigned
<u>0000 1</u>	unassigned
<u>0001</u>	Reserved
<u>0001</u> <u>100</u>	Reserved
* <u>010</u>	provider based unicast Address
<u>011</u>	unassigned
* <u>001</u>	Geographic based unicast

* 111111010 = link local address

2222:1111:010:8765:3212:3456:0000:0000 = site local address

* 11111111 = multicast address

19. PROVIDER BASED UNICAST ADDRESS




SID HID

Registry ID Registry

10000	Multiregional
01000	RIPE NCC
11000	INTERNIC
00100	APNIC

Geography Based unicast Address



contains Latitude and Longitude locations.

Multicast Address: first 8 bits determines.

Flag: 0000 = permanent group

0001 = Transient group

Scope: 4 bits = 0000 = Reserved

0001 = Node local


0010 = Link local

0011 = Site Local

1000 = Organizational

1110 = Global

1111 = Reserved



0000 = permanent

0001 = Transient

Anycast:



Assign the same IP address to one of the interfaces of the each node and send the packet with that address.

20. SOME SPECIAL ADDRESS

Unspecified: All 0's = 128 bits core id.

Loopback Address: Test self connectivity = All 0's except last bit (=1)

= 127(0's) and last '1'.

IPv4 compatible: First 96 bits 0's and last 32 bits represent IPv4 Address.

IPv4 mapped: First 80 bits = 0, next 16 bits = 1's, remaining 32 bits = IPv4 Address

IPv4 vs IPv6

(58)

- 1) No operation and end of options in IPv4 is replaced by PADI and PADN in IPv6
- 2) No Record Route option in IPv6
- 3) No time stamp option in IPv6
- 4) The source route option is called source route extension in IPv6
- 5) fragmentation fields of IPv4 base header are moved to fragmentation extension header in IPv6
- 6) The authentication extension header is new in IPv6
- 7) The encrypted security payload extension header is new in IPv6

TELEGRAM
@freeCBCB4all