MuPDF Explored

Robin Watts

June 2, 2017

Preface

This is the beginnings of a book on MuPDF. It is far from complete, but offers useful information as far as it goes. We offer it with the latest release of MuPDF (currently 1.11) in the hopes it will be useful.

Any feedback, corrections or suggestions are welcome. Please visit bugs. ghostscript.com and open a bug with "MuPDF" as the product, and "Documentation" as the component.

We will endeavour to make new versions available from the Documentation section of mupdf.com as they appear.

Contents

Pı	efac	е	i							
1	1 Introduction									
	1.1	What is MuPDF?	1							
	1.2	License	1							
	1.3	Dependencies	3							
2	Qui	ck Start	4							
	2.1	How to open a document and render some pages	4							
3	The	Context	5							
	3.1	Overview	5							
	3.2	Creation	6							
	3.3	Custom Allocators	7							
	3.4	Multi-threading	7							
	3.5	Cloning	9							
	3.6	Destruction	10							
	3.7	Tuning	11							
	3.8	Summary	12							
4	Erre	or handling	14							
	4.1	Overview	14							
	4.2	Throwing exceptions	17							
	4.3	Handling exceptions	18							
	4.4	Summary	19							
5	Mei	mory Management and The Store	20							
	5.1	Overview	20							
	5.2	Reference Counting	21							
		5.2.1 Implementation	21							
	5.3	Creating the Store	22							
	5.4	Using the store	22							
		5.4.1 Overview	22							
		5.4.2 Handling keys	23							

CONTENTS	iii
----------	-----

		5.4.4 Key storable items	24 25
			26
	5.5	0 0 1	26
	5.6	Reacting to Out of Memory events	27
6	The	Document interface 2	8
	6.1		28
	6.2		8
	6.3		80
	6.4		80
	6.5		1
	6.6		32
	6.7		34
	0.7	Itendering Lages	·±
7			7
	7.1		7
	7.2		8
			8
		7.2.2 Text	8
		7.2.3 Images	9
		7.2.4 Shadings	9
		7.2.5 Clipping and Masking	0
			0
			1
		· · · · · · · · · · · · · · · · · · ·	1
	7.3	9	2
			3
		0	3
			4
	7.4	1 9	4
	7.5		6
	1.0		6
			6
			17
		The state of the s	8
			9
		-	9
			0
		7.5.8 Trace Device	2
8	Bui	lding Blocks 5	3
	8.1	_	3
	8.2		3
		-	3
	8.3	-	4
			_

CONTENTS	iv

		8.3.1	Overview
		8.3.2	Saving
	8.4	Bitma	ps
	8.5		${ m nes}$
	8.6		s
		8.6.1	Compressed Images
		8.6.2	Pixmap Images
	8.7	Buffers	s
	8.8		Forms
	8.9	Paths	
	0.0	8.9.1	Creation
		8.9.2	Reference counting
		8.9.3	Storage
		8.9.4	Transformation
		8.9.5	
			9
		8.9.6	Stroking
	0.40	8.9.7	Walking
	8.10		
			Overview
		8.10.2	
			Population
			Measurement
		8.10.5	Cloning
			Language
		8.10.7	Implementation
	8.11	Shadin	ngs
		8.11.1	Overview
		8.11.2	Creation
			Bounding
			Painting
			Decomposition
			•
9	\mathbf{Disp}	olay Li	ists 90
		9.0.1	Overview
		9.0.2	Creation
		9.0.3	Playback
		9.0.4	Reference counting
		9.0.5	Miscellaneous operations
10			m interface 94
			iew
			on
	10.3	Usage	
			Reading bytes
		10.3.2	Reading objects
		10.3.3	Reading hits 90

CONTENTS

		10.3.4 Reading whole streams																100
		10.3.5 Seeking																101
		10.3.6 Meta data																102
		10.3.7 Destruction																103
	10.4	Implementing an fz_stream																
11	The	Output interface																106
		Overview																
		Creation																
	11.3	Usage																
		11.3.1 Writing bytes																
		11.3.2 Writing objects																
		11.3.3 Writing strings																
		11.3.4 Seeking																
	11.4	Implementing a fz_output																111
19	Don	dered Output Formats																113
14		Overview																
		Band Writers																
		PNM																
		PAM																
		PBM																
		PKM																
		PNG																
	12.0	PWG/CUPS																
	10.0	12.8.2 Mono																
		TGA																
	12.10)PCL																
		12.10.1 Color																
		12.10.2 Mono																
	12.11	Postscript		•	•	•	•	•	•	٠	٠	•	•	٠	•		•	124
13	The	Image interface																126
		Overview																126
		Standard Image Types																
		13.2.1 Compressed																
		13.2.2 Decoded																
		13.2.3 Display List																
	13.3	Creating Images																131
		Implementing an Image Type																
		Image Caching																
	_5.5		•	•	- '	•	•	- '	•	•	•	-	-	-	-	-	-	
14		Document Handler interface																137
		Overview																137
	14.2	Implementing a Document Handler	· .															138

CONTENTS vi

		14.2.1	Recognize and	l Open										138
		14.2.2	Document Le	vel Func	tion	S								140
		14.2.3	Page Level Fu	inctions										143
	14.3	Standa	ard Document	Handler	s									146
		14.3.1	PDF											146
		14.3.2	XPS											147
		14.3.3	EPUB											147
		14.3.4	HTML											147
		14.3.5	SVG											147
		14.3.6	Image											147
		14.3.7	CBZ											147
15	The	Docu	ment Writer	interfa	ce									148
	15.1	Usage												148
	15.2	Impler	mentation											150
16	Pro	gressiv	e Mode											153
			lew											153
			nentation											
		-	Progressive St											
			Rough render											
			Directed down											
		16.2.4	Example imple	lementat	ion									157
17	Font	ts												159
	17.1	Overvi	lew											
			Fonts											
			nentation											
18	Buil	d conf	iguration											162
			lew											162
			uration file											
			r selection											
			nent handlers .											
			2000 support											
			$ript \dots \dots$											
	18.7	Fonts.					•		 •					165
19	PDI	Inter	preter Detai	ls										167
		Overvi												167
	19.2	PDF I	Document											167
			Objects											168
			Arrays											169
	19.4		Operator Proce											170
			Run processor											171
			Filter process											171

CONTENTS	vii
----------	-----

	19.4.3 Buffer processor 19.4.4 Output processor 19.5 Copying objects between PDF documents 19.5.1 The problem 19.5.2 Grafting objects 19.5.3 A further problem 19.5.4 Graft maps	173 173 174 175 176
20	XPS Interpreter Details 20.1 Overview	1 79 179
21	EPub/HTML Interpreter Details 21.1 CSS rules	181
22	SVG Interpreter Details	182
23	MuTool 23.1 Overview 23.2 Clean 23.3 Create 23.4 Draw 23.5 Extract 23.6 Info 23.7 Merge 23.8 Pages 23.9 Portfolio 23.10Poster 23.11Run 23.12Show	184 185 187 187 187 188 188 189
24	24.1 Android viewer 24.2 Desktop Java	190 190 190 190 190 190
A	Naming conventions and style	191

Chapter 1

Introduction

1.1 What is MuPDF?

MuPDF is a portable C library for opening, manipulating and rendering documents in a variety of formats, including PDF, XPS, SVG, e-pub, and many common image formats.

This core C library provides an API (known as the MuPDF API) that allows a wide range of actions to be performed on those documents. The exact actions available depend on the format of the document, but always includes rendering of those files.

As well as this library, the MuPDF distribution includes various tools built on top of this API. These tools include simple viewers, tools to manipulate documents, to add, remove or resize pages, and to extract resources and other information from the documents. These tools are deliberately kept as 'thin' as possible. The heavy lifting is all performed by the core library, so as to be as reusable as possible.

Finally, the MuPDF distribution includes bindings to reflect the MuPDF C API into other languages, such as Java and Javascript.

1.2 License

MuPDF is released under two licenses.

Firstly, it is available under the GNU Afferro General Purpose License (henceforth the GNU AGPL). This is a complex license worthy of careful study and more words than we have space for here. Some key points, however are:

- You are free to use MuPDF within a piece of software written entirely
 for your own use with no problems. The moment you pass that software
 to any other person, or make it available to any other person as part of
 a "Software as a service" installation, you must abide by the following
 terms.
- If you link MuPDF into your own software, then the entirety of that software must be licensed under the GNU AGPL.
- If you use MuPDF as part of a "Software as a service" installation, then you must license the entirety of that installation under the GNU AGPL.
- Releasing a piece of software under the GNU AGPL requires you to be prepared to give full source code to any user that receives a copy of the software. No charge (other than nominal media costs) may be made for this.
- You must ensure that all end users of that system have the ability to update the software with an updated version of MuPDF. This includes embedded systems.
- Using MuPDF under the GNU AGPL, you receive no warranty and no support.

There are other terms too, and we strongly recommend that you read the license in full and understand your obligations under it before developing code based upon MuPDF.

If you find that you can abide by all the terms of the GNU AGPL, you can use MuPDF in your own projects without any license fee.

These terms, however, are generally stringent enough that they are inappropriate for people producing commercial products - giving the source code to a commercial product away is generally unacceptable, and the 'relinking' requirements of the GNU AGPL are too cumbersome for embedded users.

It is for this reason that Artifex (the developers of MuPDF) offer commercial licenses. Contact sales@artifex.com for a quote tailored to your exact needs.

The Artifex commercial license removes all the onerous terms of the GNU AGPL, including the need to license your entire app, to give away source, and to ensure relinking capabilities.

If you find yourself unable to accept and comply with the terms of the GNU AGPL, and unwilling to obtain a Commercial license from Artifex, you cannot legally use MuPDF in any software that you distribute.

1.3 Dependencies

The core MuPDF library makes use of various software libraries.

Freetype Renderer for various font types.

Harfbuzz OpenType Font shaper built upon freetype, required for e-pub files.

JBig2dec Image decoder for JBIG2 images.

JpegLib Image decoder for JPEG images.

MuJS Javascript engine used for PDF files.

OpenJPEG Image decoder for JPEG2000 images.

ZLib Compression library.

In addition, the MuPDF library can optionally make use of:

OpenSSL Encryption library, required for Digital Signatures support.

Finally, the MuPDF viewer for Linux and Windows can optionally make use of:

Curl An http fetcher used for displaying files as they download.

These libraries are packaged with MuPDF, either in the distribution archives or as git submodules. From time to time, these libraries may include bug fixes that have not been accepted back into the upstream repositories. We therefore strongly recommend using the versions of the libraries that we ship, rather than any other versions you may find on your system.

Chapter 2

Quick Start

2.1 How to open a document and render some pages

For a simple example of how to open a document and render some pages, see <code>docs/example.c.</code>

Chapter 3

The Context

3.1 Overview

The core MuPDF library is designed for simplicity, portability, and ease of integration. For all these reasons, it has no global variables, has no thread library dependencies, and has a well defined exception system to handle runtime errors. Nonetheless, in order to be as useful as possible, clearly the library must have some state and needs to be able to take advantage of multi-threaded environments.

The solution to these seemingly conflicting requirements is the Context (fz_context).

Every caller to MuPDF should create a Context at the start of its use of the library, and destroy it at the end. This Context (or one 'cloned' from it) will then be passed in to every MuPDF API call.

Global State At its simplest, the Context contains global settings for the library. For instance, the levels of Antialiasing used by the text and line art rendering routines are set in the Context, as is the default style sheet for Epub or FB2 files. In addition, the library stores its own private information there too.

Error handling All error handling within MuPDF is done using the fz_try/fz_catch constructs; see chapter 4 Error handling for more details.

These constructs can be nested, so rely on an exception stack maintained within the context. As such it is vitally important that no two threads use the same context at the same time. See section 3.4 Multi-threading for more information.

Allocation When embedding MuPDF into a system it is often desirable to

control the allocators used. A set of allocator functions can be provided to the Context at creation time, and all allocations will be performed using these. See chapter 5 Memory Management and The Store for more information.

The Store MuPDF uses a memory cache to aid performance, and to avoid repeated decoding of resources from the file. The store is maintained using the context, and shared between a context and its clones. See chapter 5 Memory Management and The Store for more information.

Multi-threading MuPDF does not rely on threading itself, but it can be used in a multi-threaded environment to give significant performance improvements. Any thread library can be used with MuPDF. A set of locking/unlocking functions must be passed to the context at creation time, and the library will use these to ensure it is thread safe. See section 3.4 Multi-threading for more information.

3.2 Creation

To create a context, use fz_new_context:

/*

fz_new_context: Allocate context containing global state.

The global state contains an exception stack, resource store, etc. Most functions in MuPDF take a context argument to be able to reference the global state. See fz_drop_context for freeing an allocated context.

alloc: Supply a custom memory allocator through a set of function pointers. Set to NULL for the standard library allocator. The context will keep the allocator pointer, so the data it points to must not be modified or freed during the lifetime of the context.

locks: Supply a set of locks and functions to lock/unlock them, intended for multi-threaded applications. Set to NULL when using MuPDF in a single-threaded applications. The context will keep the locks pointer, so the data it points to must not be modified or freed during the lifetime of the context.

max_store: Maximum size in bytes of the resource store, before it will start evicting cached resources such as fonts and images. FZ_STORE_UNLIMITED can be used if a hard limit is not desired. Use FZ_STORE_DEFAULT to get a reasonable size.

Does not throw exceptions, but may return NULL.

```
*/
fz_context *fz_new_context(const fz_alloc_context *alloc, const
    fz_locks_context *locks, unsigned int max_store);
```

For example, a simple, single threaded program using the standard allocator can just use:

```
fz_context *ctx = fz_new_context(NULL, NULL, FZ_STORE_UNLIMITED);
```

3.3 Custom Allocators

In some circumstances it can be desirable to force all allocations through a set of 'custom' allocators. These are defined as an fz_alloc_context structure whose address is passed in to fz_new_context. This structure must exist for the life time of the returned fz_context (and any clones).

```
typedef struct
{
    void *user;
    void *(*malloc)(void *, size_t);
    void *(*realloc)(void *, void *, size_t);
    void (*free)(void *, void *);
} fz_alloc_context;
```

The malloc, realloc and free function pointers have essentially the same semantics as the standard malloc, realloc and free standard functions, with the exceptions that they take an additional initial argument - that of the user value specified in the fz_alloc_context.

3.4 Multi-threading

MuPDF itself does not rely on a thread system, but it will make use of one if one is present. This is crucial to ensure that MuPDF can be called from multiple threads at once.

A typical example of this might be in a multi-core processor on a printer. We can interpret the PDF file to a display list, and then render 'bands' from that display list to send to the printer. By using multiple threads we can render multiple bands at once, thus vastly improving processing times.

In this example, although each thread will be rendering different things, they will probably share some information - for instance the same font is likely to be used in multiple bands. Rather than have every thread render all the glyphs that

it needs from the font independently, it would be nice if they could collaborate and share results.

We therefore arrange that data structures such as the font cache can be shared between the different threads. This, however, brings dangers; what if two threads try to write to the same data structure at once?

To save this being a problem, we rely on the user providing some locking functions for us.

```
/*
   Locking functions
   MuPDF is kept deliberately free of any knowledge of particular
   threading systems. As such, in order for safe multi-threaded
   operation, we rely on callbacks to client provided functions.
   A client is expected to provide FZ_LOCK_MAX number of mutexes,
   and a function to lock/unlock each of them. These may be
   recursive mutexes, but do not have to be.
   If a client does not intend to use multiple threads, then it
   may pass NULL instead of a lock structure.
   In order to avoid deadlocks, we have one simple rule
   internally as to how we use locks: We can never take lock n
   when we already hold any lock i, where 0 <= i <= n. In order
   to verify this, we have some debugging code, that can be
   enabled by defining FITZ_DEBUG_LOCKING.
typedef struct
   void *user:
   void (*lock)(void *user, int lock);
   void (*unlock)(void *user, int lock);
} fz_locks_context;
enum {
   FZ_LOCK_MAX
};
```

If MuPDF is to be used in a multi-threaded environment, then the user is expected to define FZ_LOCK_MAX locks (currently 4, though this may change in future), together with functions to lock and unlock them.

In pthreads, a lock might be implemented by pthread_mutex_t. In windows, either Mutex or a CriticalSection might be used (the latter being more lightweight).

These locks are not assumed to be recursive (though recursive locks will work just fine).

To avoid deadlocks, MuPDF guarantees never to take lock n if that thread already holds lock m (for $n \neq m$).

There are 3 simple rules to follow when using MuPDF in a multi threaded environment:

1. No simultaneous calls to MuPDF in different threads are allowed to use the same context.

Most of time it is simplest just to use a different context for every thread; just create a new context at the same time as you create the thread. See section 3.5 Cloning for more information.

2. No simultaneous calls to MuPDF in different threads are allowed to use the same document.

Only one thread can be accessing an document at a time. Once display lists are created from that document, multiple threads can operate on them safely.

The document can safely be used from several different threads as long as there are safeguards in place to prevent the usages being simultaneous.

3. No simultaneous calls to MuPDF in different threads are allowed to use the same device.

Calling a device simultaneously from different threads will cause it to get confused and may crash. Calling a device from several different threads is perfectly acceptable as long as there are safeguards in place to prevent the calls being simultaneous.

3.5 Cloning

The context contains the exception stack for the fz_try/fz_catch constructs. As such trying to use the same context from multiple threads at the same time will lead to crashes.

The solution to this is to 'clone' the context. Each clone will share the same underlying store (and will inherit the same settings, such as allocators, locks etc), but will have its own exception handle. Other settings, such as anti-alias levels, will be inherited from the original at the time of cloning, but can be changed to be different if required.

For example, in a viewer application, we might want to have a background process that runs through the file generating page thumbnails. In order for this not to interfere with the foreground process, we would clone the context, and

use the cloned context in the thumbnailing thread. We might choose to disable anti-aliasing for the thumbnailing thread to trade quality for speed.

Any images decoded for the thumbnailing thread would live on in the store though, and would hence be available should the viewers normal render operations need them.

To clone a context, use fz_clone_context:

```
/*
    fz_clone_context: Make a clone of an existing context.

This function is meant to be used in multi-threaded applications where each thread requires its own context, yet parts of the global state, for example caching, is shared.

ctx: Context obtained from fz_new_context to make a copy of. ctx must have had locks and lock/functions setup when created. The two contexts will share the memory allocator, resource store, locks and lock/unlock functions. They will each have their own exception stacks though.

Does not throw exception, but may return NULL.

*/
fz_context *fz_clone_context(fz_context *ctx);

For example:
fz_context *worker_ctx = fz_clone_context(ctx);
```

In order for cloned contexts to work safely, they rely on being able to take locks around certain operations to make them atomic. Accordingly, fz_clone_context will return NULL (to indicate failure) if the base context did not have locking functions defined.

3.6 Destruction

Once you have finished with an fz_context (either your original one, or a 'cloned' one) you can destroy it using fz_drop_context.

```
/*
    fz_drop_context: Free a context and its global state.

The context and all of its global state is freed, and any
buffered warnings are flushed (see fz_flush_warnings). If NULL
is passed in nothing will happen.
```

```
Does not throw exceptions.
*/
void fz_drop_context(fz_context *ctx);
For example:
fz_drop_context(ctx);
```

3.7 Tuning

Some of MuPDF's functionality relies on heuristics to make decisions. Rather than hard code these decisions in the library code, the tuning context allows callers to override the defaults with their own 'tuned' versions.

Currently, we have just 2 calls defined here, both to do with image handling, but this may expand in future.

The first tuning function enables fine control over how much of an image MuPDF should decode if it only requires a subarea:

```
/*
    fz_tune_image_decode_fn: Given the width and height of an image,
    the subsample factor, and the subarea of the image actually
    required, the caller can decide whether to decode the whole image
    or just a subarea.

arg: The caller supplied opaque argument.

w, h: The width/height of the complete image.

l2factor: The log2 factor for subsampling (i.e. image will be
    decoded to (w>>l2factor, h>>l2factor)).

subarea: The actual subarea required for the current operation.
    The tuning function is allowed to increase this in size if required.

*/
typedef void (fz_tune_image_decode_fn)(void *arg, int w, int h, int
    l2factor, fz_irect *subarea);
```

Having defined a function of this type to implement the desired strategy, it can be set into the context using:

```
/*
  fz_tune_image_decode: Set the tuning function to use for
  image decode.

image_decode: Function to use.
```

```
arg: Opaque argument to be passed to tuning function.
*/
void fz_tune_image_decode(fz_context *ctx, fz_tune_image_decode_fn
    *image_decode, void *arg);
```

The second function allows fine control over the scaling used when images are scaled:

```
/*
    fz_tune_image_scale_fn: Given the source width and height of
    image, together with the actual required width and height,
    decide whether we should use mitchell scaling.

arg: The caller supplied opaque argument.

dst_w, dst_h: The actual width/height required on the target device.

src_w, src_h: The source width/height of the image.

Return 0 not to use the Mitchell scaler, 1 to use the Mitchell scaler. All other values reserved.

*/
typedef int (fz_tune_image_scale_fn)(void *arg, int dst_w, int dst_h, int src_w, int src_h);
```

Having defined a function of this type to implement the desired strategy, it can be set into the context using:

```
/*
    fz_tune_image_scale: Set the tuning function to use for
    image scaling.

image_scale: Function to use.

arg: Opaque argument to be passed to tuning function.
*/
void fz_tune_image_scale(fz_context *ctx, fz_tune_image_scale_fn
    *image_scale, void *arg);
```

3.8 Summary

The basic usage of Contexts is as follows:

1. Call fz_new_context to create a context. Pass in any custom allocators required. If you wish to use MuPDF from multiple threads at the same

time, you must also pass in locking functions. Set the store size appropriately.

- 2. Call fz_clone_context to clone the context as many times as you need; typically once for each 'worker' thread.
- 3. Perform the operations required using MuPDF within ${\tt fz_try/fz_catch}$ constructs.
- 4. Call fz_drop_context with each cloned context.
- 5. Call fz_drop_context with the original context.

Things to remember:

- 1. A fz_context can only be used in 1 thread at a time.
- 2. A fz_document can only be used in 1 thread at a time.
- 3. A fz_device can only be used in 1 thread at a time.
- 4. A fz_context shares the store with all the fz_contexts cloned from it.

Chapter 4

Error handling

4.1 Overview

MuPDF handles all its errors using an exception system. This is superficially similar to C++ exceptions, but (as MuPDF is written in C) it is implemented using macros that wrap the setjmp/longjmp standard C functions.

It is probably best not to peek behind the curtain, and just to think of these constructs as being extensions to the language. Indeed, we have worked very hard to ensure that the complexities involved are minimised.

Unless otherwise specified, all MuPDF API functions can throw exceptions, and should therefore be called within an fz_try/fz_always/fz_catch construct.

The general anatomy of such a construct is as follows:

```
fz_try(ctx)
{
    /* Do stuff in here that might throw an exception.
    * NEVER return from here. 'break' can be used to
    * continue execution (either in the always block or
    * after the catch block). */
}
fz_always(ctx)
{
    /* Anything in here will always be executed, regardless
    * of whether the fz_try clause exited normally, or an
    * exception was thrown. */
}
fz_catch(ctx)
{
    /* This block will execute if (and only if) anything in
    * the fz_try block calls fz_throw. We should clean up
```

```
* anything we need to. If we are in a nested fz_try/
* fz/catch block, we can call fz_rethrow to propagate
* the error to the enclosing catch. */
}
```

The fz_always block is completely optional. The following is perfectly valid:

```
fz_try(ctx)
{
    /* Do stuff here */
}
fz_catch(ctx)
{
    /* Clean up from errors here */
}
```

In an ideal world, that would be all there is to it. Unfortunately, there are 2 wrinkles.

The first one, relatively simple, is that you must not return from within a fz_try block. To do so will corrupt the exception stack and cause problems and crashes. To mitigate this, you can safely break out of the fz_try, and execution will pass into the fz_always block (if there is one, or continue after the fz_catch block if not).

The second one, is more convoluted. If you do not wish to understand the long and complex reasons behind this, skip forward to the summary and just follow the rules there.

As stated before fz_try/ fz_catch are implemented using setjmp/longjmp, and these can 'lose' changes to variables.

For example:

```
house_t *build_house(fz_context *ctx)
{
    walls_t *w = NULL;
    roof_t *r = NULL;
    house_t *h = NULL;

    fz_try(ctx)
    {
        w = make_walls();
        r = make_roof();
        h = combine(w, r); /* Note, NOT: return combine(w,r); */
    }
    fz_always(ctx)
    {
        drop_walls(w);
        drop_roof(r);
    }
}
```

```
}
fz_catch(ctx)
{
    return NULL; /* Or fz_rethrow if we're nested */
}
return h;
}
```

In the above code (as well as throughout MuPDF), we follow the convention that destructors always accept NULL. This makes cleanup code much simpler.

Reading through this code, it is fairly obvious what will happen if everything works correctly. First we'll make some walls, w, and a roof, r. Then we combine the walls and the roof, to get our house, h. Next we tidy up the walls and the roof, and we return the completed house to our caller.

It's more interesting to consider what will happen if we have failures.

First let's consider what happens if the make_walls fails. This will fz_throw an exception, and control will jump immediately to the fz_always. This will drop w and r (both of which are still NULL). The fz_catch can then handle the error, either by returning NULL, to indicate failure, or perhaps by fz_rethrowing the error to an enclosing fz_try/fz_catch construct. No problems there.

So what happens when the failure occurs in make_roof fails? Let's run through the code again.

This time, make_walls succeeds, and w is set to this new value. Then make_roof fails, fz_throwing an exception, and control will jump immediately to the fz_always. This will then try to drop w (now a valid value) and r (which is still NULL). The fz_catch can then handle the error, either by returning NULL, to indicate failure, or perhaps by fz_rethrowing the error to an enclosing fz_try/fz_catch construct. All sounds quite plausible.

Unfortunately, if you try it, on some systems you will find that you have a memory leak (or worse). When drop_walls is called, sometimes you will find that w has 'lost' its value.

This is due to an obscure part of the C specification that states that any changes to local variables made between a set jmp and a long jmp can be lost.

In fz_try/fz_catch terms, this means that any local variables set within the fz_try block can be 'lost' when either fz_always or fz_catch are reached.

Fortunately, there is a fix for this, fz_var. By calling fz_var(w); we can 'protect' variable w from such unwanted behaviour.

It's not really necessary to know how this works, but for those interested, a quick explanation. The 'loss' of the value occurs because the compiler can postpone writing the value back into the storage location for the variable (or can choose to just hold it in a register). The call to fz_var passes the address of the variable

out of scope; this forces the compiler not to hold it in a register. Further, the compiler has no way of knowing whether any functions it call might access that location, so it needs to make sure that the variable value is written back on every function call - such as longjmp. Hence the variable is magically protected.

Calls to fz_var are very low cost (but are not NOPs), so erring on the side of caution and calling fz_var on more than you need to will probably not hurt.

A corrected version of the above example is therefore:

```
house_t *build_house(fz_context *ctx)
   walls_t *w = NULL;
   roof t *r = NULL:
   house_t *h = NULL;
   fz_var(w);
   fz_var(r);
   fz_try(ctx)
       w = make_walls();
       r = make_roof();
       h = combine(w, r); /* Note, NOT: return combine(w,r); */
   }
   fz_always(ctx)
   {
       drop_walls(w);
       drop_roof(r);
   }
   fz_catch(ctx)
       return NULL; /* Or fz_rethrow if we're nested */
   }
   return h;
}
```

4.2 Throwing exceptions

Most client code need never worry about anything more than catching exceptions thrown by the core core. If you are implementing your own devices or extending the core of MuPDF, then you will need to know how to generate (and pass on) your own exceptions.

An exception is constructed and thrown from an integer code and a **printf** like string:

enum

```
{
    FZ_ERROR_NONE = 0,
    FZ_ERROR_GENERIC = 1,
    FZ_ERROR_SYNTAX = 2,
    FZ_ERROR_TRYLATER = 3,
    FZ_ERROR_ABORT = 4,
    FZ_ERROR_COUNT
};

void fz_throw(fz_context *ctx, int errcode, const char *, ...);

In almost all cases, you should be using FZ_ERROR_GENERIC, for example:
fz_throw(ctx, FZ_ERROR_GENERIC, "Failed to open file '%s'", filename);
```

4.3 Handling exceptions

Once you have caught an exception, most code will simply tidy up any loose resources (to prevent leaks), and rethrow the exception up to a higher layer handler.

At the top level of the program, clearly this is not an option. The catch clause needs to return the error using whatever process the calling program is using for error handling.

Details of the message from the caught error can be read using:

```
const char *fz_caught_message(fz_context *ctx);
```

The error will remain readable in this way until the next use of fz_try/fz_catch on that same context.

Some code may choose to swallow the error and retry the same code again in a different manner. To facilitate this, we can find out the type of error using:

```
int fz_caught(fz_context *ctx);
```

See section 4.2 Throwing exceptions for a list of the possible exception types.

To simplify the job of deciding whether to pass on exceptions of a given type, we have a convenience function that with rethrow just a particular type.:

```
void fz_rethrow_if(fz_context *ctx, int errcode);
```

4.4 Summary

The basic exception handling rules are as follows:

- All MuPDF functions except those that explicitly state otherwise, throw exceptions on errors, and must therefore be called from within an fz_try/ fz_catch construct.
- 2. A fz_try block must be paired with an fz_catch block, and optionally an fz_always block can appear between them.
- 3. Never return from an fz_try block.
- An fz_try block will terminate when control reaches the end of the block, or when break is called.
- 5. Any variable that is changed within an fz_try block may lose its value if an exception occurs, unless protected by fz_var call.
- 6. The contents of the fz_always block will always be executed (after the fz_try block and before the fz_catch block, if appropriate).
- 7. If an exception is thrown during the fz_try block, control will jump to the fz_always block (if there is one) and then continue to the fz_catch block.

Chapter 5

Memory Management and The Store

5.1 Overview

While MuPDF is running, it holds various objects in memory, and passes them between its various components. For instance, MuPDF might read a path definition in the PDF interpreter, and pass it first into the display list and then on into the renderer.

To avoid needless copying of data, a reference counting scheme is used. Each significant object has a reference count, so that when one area of the code retains a reference to something (perhaps the display list), the data need not be copied wholesale. In the above example, the PDF interpreter might hold one reference, and first the display list and then the renderer might take others. Some references are held just for a short length of time, but others can persist for a much longer period.

During the course of displaying files, MuPDF loads various resources into memory, such as fonts and images. By holding these resources in memory throughout the processing of the file we can avoid reloading them each time they are required.

As the document is rendered, more memory is needed to hold rendered versions of glyphs from the font, or decoded versions of images. By keeping these decoded versions around in memory, we can avoid the need to redecode them the next time we need the same glyph, or the same image.

Keeping all this data around can end up using a large amount of memory, which may be unfeasible for some systems. Equally, not keeping any of it around will result in a drastic performance drop.

The solution is to keep as much around as can conveniently fit in memory. MuPDF achieves this using a mechanism known as "The Store".

The Store is a mechanism for holding blocks of data likely to be reusable. Whenever MuPDF needs such a block of data, it checks the Store to see if the data is there already - if it is, it can be instantly reused. If not the code forms the data itself, and then puts it into the store.

The MuPDF allocation code is tied into the store, so that if an allocation ever fails, objects are evicted from the store, and the allocation retried. This 'scavenging' of memory means that we can safely keep lots of cached data around without ever worrying that it will cause us to run out of memory.

5.2 Reference Counting

As mentioned above, most MuPDF objects are reference counted. This means that on creation (typically with an fz_new_... call), they have a reference count of 1. Think of these object pointers as 'handles'.

If a 'copy' of the object is required, a new handle can be generated using the appropriate fz_keep_... call. This is a very low cost operation that just involves incrementing the reference count, so no physical copying of the data is involved. Accordingly it is vital that objects that have multiple handles do not have their contents altered.

Once a reference is finished with, it should be disposed of using the appropriate fz_drop_... call. This is true regardless of whether the handle was created by a fz_new_... or a fz_keep_... call. This drops the reference count by 1.

Once the reference count hits 0, the storage used by the object is freed.

As an implementation detail, certain objects within MuPDF are allocated statically and have a reference count of -1. These are unaffected by reference counting operations, and will never be freed. Nonetheless, these should be treated exactly as for normal objects and kept/dropped as usual.

5.2.1 Implementation

These keep and drop calls for simple objects are generally implemented by using one of a set of standard functions. There are a range of these, depending on the expected size of the reference counts, and all handle the locking required to ensure thread safety:

```
void *fz_keep_imp(fz_context *ctx, void *p, int *refs);
void *fz_keep_imp8(fz_context *ctx, void *p, int8_t *refs);
void *fz_keep_imp16(fz_context *ctx, void *p, int16_t *refs);
int fz_drop_imp(fz_context *ctx, void *p, int *refs);
```

```
int fz_drop_imp8(fz_context *ctx, void *p, int8_t *refs);
int fz_drop_imp16(fz_context *ctx, void *p, int16_t *refs);
As an example, an fz_path structure is defined as:
typedef struct {
  int8_t refs;
} fz_path;
and thus appropriate keep and drop functions can be defined simply:
fz_path *fz_keep_path(fz_context *ctx, fz_path *path)
{
   return fz_keep_imp8(ctx, &path->refs);
}
void fz_drop_path(fz_context *ctx, fz_path *path)
   if (!fz_drop_imp8(ctx, &path->refs))
       return;
   <code to free the contents of the path structure>
}
```

More complex variations of these functions are available to cope with 'storable' objects, and still more complex versions to cope with 'key storable' objects - these are explained in the following sections.

However they are implemented, these objects all look basically the same to most users - they can simply be 'kept' and 'dropped' as required.

5.3 Creating the Store

The Store is created as part of the fz_new_context call, (see the Context chapter) and is shared with any contexts obtained with fz_clone_context. The 'store limit' is specified as a byte size as part of this call. A special value of FZ_STORE_UNLIMITED (0) is used to indicate that no amount of memory is too much.

5.4 Using the store

5.4.1 Overview

Every "storable piece of information" in MuPDF is held in a data structure that begins with an fz_storable structure. Rather than repeatedly say "a storable

piece of information", we shall henceforth just say "an fz_storable".

MuPDF uses reference counting for most of its data structures (see section 5.2 Reference Counting), and fz_storables are no exception.

Whenever MuPDF needs to use a fz_storable, it first checks to see if there is one in the Store already. It does this by forming a unique 'key' and scanning the Store for an object of a given type, with that key. If the object exists within the Store, the fact that the object has been used is noted, a reference is taken, and returned to the caller.

If no reference is returned, the code creates its own version of the fz_storable. It calculates its size, and puts it into the Store, together with the same key as before. The Store takes a reference to the object, links it into its data structure, and updates its running total of the size of all the objects within it.

If placing a new object into the store would take it over the limit, it runs through and looks for the least recently used objects to evict to bring the limit down. In order for an object to be considered for eviction, their refcount must be 1. We know that the Store is holding 1 reference to the object - if anything else is, then removing it from the Store won't actually save us any memory.

Regardless of whether the Store can be reduced to a suitable size, the object is always placed into the store. This ensures that the Store's figure for "amount of memory used by fz_storable's" remains correct (thus ensuring that should objects become evictable, the store size will fall correctly). It also does no harm, because clearly we have managed to allocate enough memory to form the fz_storable in the first place.

Regardless of whether a caller finds the object in the Store, or has to store it itself, it then proceeds identically. It uses the object for whatever purpose it needed it, and then calls the appropriate fz_drop function to lose its reference. The object will live on in the Store until it needs to be evicted to make room.

5.4.2 Handling keys

As discussed above, the Store is basically a set of key/value pairs. While the values are always fz_storables, the keys can be of many different types, due to coming from many disparate parts of the system.

Accordingly, we need a mechanism to allow us to safely know what 'type' a given key is, and to compare 2 keys of identical type.

We solve this, by using an fz_store_type structure:

```
typedef struct fz_store_type_s
{
  int (*make_hash_key)(fz_context *ctx, fz_store_hash *, void *);
  void *(*keep_key)(fz_context *,void *);
```

```
void (*drop_key)(fz_context *,void *);
int (*cmp_key)(fz_context *ctx, void *, void *);
void (*print)(fz_context *ctx, fz_output *out, void *);
int (*needs_reap)(fz_context *ctx, void *);
} fz_store_type;
```

We will have just one instance of this for each type - normally a static const structure defined in the code. Whenever we insert (or lookup) something in the store, we pass the address of that 'types' structure.

We only compare items if they have the same type pointer, and any comparison is done using the cmp_key function pointer therein. In common with normal C idioms, 0 means match, non zero means different.

The keep_key and drop_key entries are used to implement reference counting of keys. Because keys can be an amalgam of several reference counted objects, the keep and drop functions provided here can take and drop these in sync.

The print function is purely for debugging purposes as part of calls to fz_print_store - it should generate a human readable summary of the key to the given fz_output stream.

The make_hash_key and needs_reap functions are explained in the following subsections.

5.4.3 Hashing

In order to ensure the Store performs well, we must ensure that certain processes run efficiently - notably searching for an existing entry, insertion and deletion.

Accordingly, the Store is implemented based on a hash table. For every 'key', we need to be able to form a hash, but this process is complicated slightly by the fact that every different fz_storable has a different type for the key.

We solve this by having the make_hash_key member of the fz_store_type structure convert whatever its key data is into a common structure:

```
const void *ptr;
    int i;
    fz_irect r;
} pir;
struct
{
    int id;
    float m[4];
} im;
} u;
} fz_store_hash;
```

The caller will always arrange for this structure to be zero filled on entry to the make_hash_key call. On exit, it should have been updated with the key details. Implementers may extend the union found in this structure as required, though ideally the size of the overall structure should be minimised to avoid unnecessary work.

Once the Store has formed a fz_store_hash it can then generate the required hash for the hashtable as required.

5.4.4 Key storable items

Some objects can be used both as values within the Store, and as a component of keys within the Store. We refer to these objects as "key storable" objects. In this case, we need to take additional care to ensure that we do not end up keeping an item within the store, purely because its value is referred to by another key in the store.

An example of this are fz_images in PDF files. Each fz_image is placed into the Store to enable it to be easily reused. When the image is rendered, a pixmap is generated from the image, and the pixmap is placed into the Store so it can be reused on subsequent renders. The image forms part of the key for the pixmap.

When we close the pdf document (and any associated pages/display lists etc), we drop the images from the Store. This may leave us in the position of the images having non-zero reference counts purely because they are used as part of the keys for the pixmaps.

We therefore use special reference counting functions to implement these fz_key_storable items, fz_keep_key_storable and fz_drop_key_storable rather than the more usual fz_keep_storable and fz_drop_storable.

The sole difference is that these enable us to store the number of references to these items that are used in keys. This is achieved by callers taking and dropping references for use in keys with fz_keep_key_storable_key and fz_drop_key_storable_key.

This means that key storable items need to provide two sets of keep and drop functions, one for 'normal' callers, and one for use during key handling. For example:

```
fz_image *fz_keep_image(fz_context *ctx, fz_image *image);
void fz_drop_image(fz_context *ctx, fz_image *image);

fz_image *fz_keep_image_store_key(fz_context *ctx, fz_image *image);
void fz_drop_image_store_key(fz_context *ctx, fz_image *image);
```

The purpose of this extra work is to allow us to spot when we may need to check the Store for 'dead' entries - those that can never be 'found' by looking in the store.

5.4.5 Reap passes

When the number of references to a key storable object equals the number of references to an object from keys in the Store, we know that we can remove all the items which have that object as part of the key. This is done by running a pass over the store, 'reaping' those items.

If a key does not consist of any storable objects, then the needs_reap entry in its fz_store_type can safely be left as NULL. If it does, however, it must provide an implementation to check whether a reap pass is required. Essentially this needs to check if any of its constituent fz_key_storable objects need reaping, which can be done by a call to:

```
int fz_key_storable_needs_reaping(fz_context *ctx, const fz_key_storable
   *ks);
```

Reap passes are slower than we would like as they touch every item in the store. We therefore provide a way to 'batch' such reap passes together, using fz_defer_reap_start and fz_defer_reap_end to bracket a region in which many may be triggered.

5.5 Scavenging memory allocator

All allocations within MuPDF (and its sub-libraries) call fz_malloc and family. These functions ultimately call down to the custom allocator functions passed into the fz_new_context call (or to malloc and family if no custom allocators were supplied). (See chapter 3 The Context for details).

If a call to the underlying custom allocator fails, MuPDF will automatically seek to evict the least recently used objects from the store that are not currently being

used, and then will retry the allocation. This can happen several times, with more and more objects being freed between each attempt.

Allocation failures are therefore only fatal to MuPDF if there are no remaining objects to be freed in the store.

This 'just in time' scavenging of memory means that the store limit can safely be set to a high level (or to be unlimited), and MuPDF will still operate within safe bounds.

5.6 Reacting to Out of Memory events

As a last resort, applications using MuPDF can react to low memory events by changing their strategy. For example, if we fail to render a band of data due to an allocation failure, we might back off and try a smaller band size. Alternatively, we might choose to dispense with the display list, and to reinterpret the underlying file directly each time, trading speed for memory.

To this end, all exceptions thrown due to allocation failures have the FZ_ERROR_OOM type, enabling callers to easily distinguish them using fz_caught and to react accordingly.

Chapter 6

The Document interface

6.1 Overview

Although MuPDF handles multiple different file formats, it offers a unified API for dealing with them. The fz_document API allows all the common operations to be performed on a document, hiding the implementation specifics away from the caller.

Not all functions are available on all document types (for instance, JPEG files do not support annotations), but the API returns sane values.

6.2 Opening/Closing a document

The simplest way to load a document is to load it from the local filing system:

```
/*
    fz_open_document: Open a PDF, XPS or CBZ document.

Open a document file and read its basic structure so pages and objects can be located. MuPDF will try to repair broken documents (without actually changing the file contents).

The returned fz_document is used when calling most other document related functions.

filename: a path to a file as it would be given to open(2).

*/
fz_document *fz_open_document(fz_context *ctx, const char *filename);
```

For embedded systems, or secure applications, the use of a local filing system may be inappropriate, so an alternative is available whereby documents can be opened from an fz_stream. See chapter 10 The Stream interface for more details on fz_streams.

```
/*
    fz_open_document_with_stream: Open a PDF, XPS or CBZ document.

Open a document using the specified stream object rather than opening a file on disk.

magic: a string used to detect document type; either a file name or mime-type.

*/
fz_document *fz_open_document_with_stream(fz_context *ctx, const char *magic, fz_stream *stream);
```

Almost any data source can be wrapped up as an fz_stream; see chapter 10 The Stream interface for more details.

In common with most other objects in MuPDF, fz_documents are reference counted:

```
/*
    fz_keep_document: Keep a reference to an open document.

Does not throw exceptions.
*/
fz_document *fz_keep_document(fz_context *ctx, fz_document *doc);

/*
    fz_drop_document: Release an open document.

The resource store in the context associated with fz_document is emptied, and any allocations for the document are freed when the last reference is dropped.

Does not throw exceptions.
*/
void fz_drop_document(fz_context *ctx, fz_document *doc);
```

Once the last reference to the document is dropped, all resources used by that document will be released, including those in the Store.

6.3 Handling password protected documents

Some document types (such as PDF) can require passwords to allow the file to be opened. After you have obtained an fz_document, you should therefore check whether it needs a password using fz_needs_password:

```
/*
    fz_needs_password: Check if a document is encrypted with a
    non-blank password.

Does not throw exceptions.
*/
int fz_needs_password(fz_context *ctx, fz_document *doc);

If a password is required, you can supply one using fz_authenticate_password:

/*
    fz_authenticate_password: Test if the given password can
    decrypt the document.

password: The password string to be checked. Some document
    specifications do not specify any particular text encoding, so
    neither do we.

Does not throw exceptions.
*/
int fz_authenticate_password(fz_context *ctx, fz_document *doc, const
    char *password);
```

6.4 Handling reflowable documents

Some document types (such as Epub) require the contents to be laid out before they can be rendered. This is done by calling fz_layout_document:

```
/*
    fz_layout_document: Layout reflowable document types.

w, h: Page size in points.
    em: Default font size in points.

*/
void fz_layout_document(fz_context *ctx, fz_document *doc, float w, float h, float em);
```

Any non-reflowable document types (such as PDF) will ignore this layout request. The results of the layout will depend both upon a target width and

height, a given font size, the CSS styles in effect. Documents can be laid out multiple times to allow changes in these properties to take effect.

MuPDF provides its own default CSS style sheet, but this can be overridden by the user CSS style sheet in the context:

```
/*
    fz_user_css: Get the user stylesheet source text.
*/
const char *fz_user_css(fz_context *ctx);
/*
    fz_set_user_css: Set the user stylesheet source text for use with
        HTML and EPUB.
*/
void fz_set_user_css(fz_context *ctx, const char *text);
```

The user CSS style sheet is supplied as a null terminated C string.

When the CSS or the screen size is changed, and the document relaid out, content moves. In order for applications to be able to not lose the readers place, MuPDF offers a mechanism for making a bookmark and then looking it up again after the content has been laid out to a new position.

```
/*
    Create a bookmark for the given page, which can be used to find the
    same location after the document has been laid out with different
    parameters.
*/
fz_bookmark fz_make_bookmark(fz_context *ctx, fz_document *doc, int
    page);

/*
    Find a bookmark and return its page number.
*/
int fz_lookup_bookmark(fz_context *ctx, fz_document *doc, fz_bookmark
    mark);
```

6.5 Getting Pages from a document

Once you have a laid out document, you presumably want to be able to do something with it. The first thing to know is how many pages it contains. This is achieved by calling fz_count_pages:

```
/*
fz_count_pages: Return the number of pages in document
```

```
May return 0 for documents with no pages.
*/
int fz_count_pages(fz_context *ctx, fz_document *doc);
```

For document types like images, they appear as a single page. If you forget to lay out a reflowable document, this will trigger a layout for a default size and return the required number of pages.

Once you know how many pages there are, you can fetch the fz_page object for each page required:

```
/*
    fz_load_page: Load a page.

After fz_load_page is it possible to retrieve the size of the page using fz_bound_page, or to render the page using fz_run_page_*. Free the page by calling fz_drop_page.

number: page number, 0 is the first page of the document.
*/
fz_page *fz_load_page(fz_context *ctx, fz_document *doc, int number);
The pages of a document with n pages are numbered from 0 to n-1.
```

In common with most other object types, fz_pages are reference counted:

```
/*
    fz_keep_page: Keep a reference to a loaded page.

Does not throw exceptions.
*/
fz_page *fz_keep_page(fz_context *ctx, fz_page *page);
/*
    fz_drop_page: Free a loaded page.

Does not throw exceptions.
*/
void fz_drop_page(fz_context *ctx, fz_page *page);
```

Once the last reference to a page is dropped, the resources it consumes are all released automatically.

6.6 Anatomy of a Page

In MuPDF terminology (largely borrowed from PDF) Pages consist of Page Contents, Annotations, and Links.

Page Contents (or just Contents) are typically the ordinary printed matter that you would get on a page; the text, illustrations, any headers or footers, and maybe some printers marks.

Annotations are normally extra information that is overlaid on the top of these page contents. Examples include freehand scribbles on the page, highlights/underlines/strikeouts overlaid on the text, sticky notes etc. Annotations are typically added to a document by people reading the document after it has been published rather than by the original author.

Annotations can be enumerated from the page one at a time, by first calling fz_first_annot, and then fz_next_annot:

```
/*
    fz_first_annot: Return a pointer to the first annotation on a page.
    Does not throw exceptions.
*/
fz_annot *fz_first_annot(fz_context *ctx, fz_page *page);
/*
    fz_next_annot: Return a pointer to the next annotation on a page.
    Does not throw exceptions.
*/
fz_annot *fz_next_annot(fz_context *ctx, fz_annot *annot);
```

Annotations are reference counted and can be kept and dropped as usual. They can also be bounded, by passing a rectangle to fz_bound_annot:

```
/*
    fz_bound_annot: Return the bounding rectangle of the annotation.

Does not throw exceptions.
*/
fz_rect *fz_bound_annot(fz_context *ctx, fz_annot *annot, fz_rect *rect);
```

On return, the rectangle is populated with the bounding box of the annotation.

Links describe 'active' regions on the page; if the user 'clicks' within such a region typically the viewer should respond. Some links move to other places in the document, others launch external clients such as mail or web sites.

The links on a page can be read by calling fz_load_links:

```
/*
   fz_load_links: Load the list of links for a page.

Returns a linked list of all the links on the page, each with its clickable region and link destination. Each link is
```

```
reference counted so drop and free the list of links by
calling fz_drop_link on the pointer return from fz_load_links.

page: Page obtained from fz_load_page.
*/
fz_link *fz_load_links(fz_context *ctx, fz_page *page);
```

This returns a linked list of fz_link structures. link->next gives the next one in the chain.

6.7 Rendering Pages

To render a page, you first need to know how big it is. This can be discovered by calling fz_bound_page, passing an fz_rect in to be populated:

```
/*
    fz_bound_page: Determine the size of a page at 72 dpi.

Does not throw exceptions.
*/
fz_rect *fz_bound_page(fz_context *ctx, fz_page *page, fz_rect *rect);
```

MuPDF operates on page contents (and annotations) by processing them to a Device. There are various different devices in MuPDF (and you can implement your own). See chapter 7 The Device interface for more information. For now, just consider devices to be things that are called with each of the graphical items on the page in turn.

The simplest way to process a page is to call fz_run_page:

```
fz_run_page: Run a page through a device.

page: Page obtained from fz_load_page.

dev: Device obtained from fz_new_*_device.

transform: Transform to apply to page. May include for example scaling and rotation, see fz_scale, fz_rotate and fz_concat. Set to fz_identity if no transformation is desired.

cookie: Communication mechanism between caller and library
```

cookie: Communication mechanism between caller and library rendering the page. Intended for multi-threaded applications, while single-threaded applications set cookie to NULL. The caller may abort an ongoing rendering of a page. Cookie also communicates progress information back to the caller. The fields inside cookie are continually updated while the page is

```
rendering.
*/
void fz_run_page(fz_context *ctx, fz_page *page, fz_device *dev, const
    fz_matrix *transform, fz_cookie *cookie);
This will cause each graphical object from the page contents and annotations
in turn to be transformed, and fed to the device.
For finer control, you may wish to run the page contents, and the annotations
separately:
   fz_run_page_contents: Run a page through a device. Just the main
   page content, without the annotations, if any.
   page: Page obtained from fz_load_page.
   dev: Device obtained from fz_new_*_device.
   transform: Transform to apply to page. May include for example
   scaling and rotation, see fz_scale, fz_rotate and fz_concat.
   Set to fz_identity if no transformation is desired.
   cookie: Communication mechanism between caller and library
   rendering the page. Intended for multi-threaded applications,
   while single-threaded applications set cookie to NULL. The
   caller may abort an ongoing rendering of a page. Cookie also
   communicates progress information back to the caller. The
   fields inside cookie are continually updated while the page is
   rendering.
void fz_run_page_contents(fz_context *ctx, fz_page *page, fz_device
    *dev, const fz_matrix *transform, fz_cookie *cookie);
   fz_run_annot: Run an annotation through a device.
   page: Page obtained from fz_load_page.
   annot: an annotation.
   dev: Device obtained from fz_new_*_device.
   transform: Transform to apply to page. May include for example
   scaling and rotation, see fz_scale, fz_rotate and fz_concat.
```

cookie: Communication mechanism between caller and library rendering the page. Intended for multi-threaded applications, while single-threaded applications set cookie to NULL. The

Set to fz_identity if no transformation is desired.

```
caller may abort an ongoing rendering of a page. Cookie also
  communicates progress information back to the caller. The
  fields inside cookie are continually updated while the page is
  rendering.
*/
void fz_run_annot(fz_context *ctx, fz_annot *annot, fz_device *dev,
      const fz_matrix *transform, fz_cookie *cookie);
```

All three of these functions (fz_run_page, fz_run_page_contents, fz_run_annot) take an fz_cookie pointer. The Cookie is a lightweight way of controlling the processing of the page. For more details, see section 7.3 Cookie. For most simple cases this can be NULL.

Chapter 7

The Device interface

7.1 Overview

In many ways, the Device interface is the heart of MuPDF.

When any given document handler is told to run the page (fz_run_page) the appropriate document interpreter serialises the page contents as a series of graphical operations, and calls the device interface to perform these actions.

Many different implementations of the device interface exist within MuPDF. The most obvious one is the Draw device. When this is called, it renders the graphical objects in turn into a Pixmap.

Alternatively we have the Structured Text device that captures the text output and forms it into an easily processable structure (for searching, or text extraction).

Some devices, such as the SVG Output device, repackage the graphical objects into a different format. The end product of these devices is a new document with (as much as possible) the same overall appearance as the initial page.

Finally, devices such as the Display List device manage to be both implementers of the interface, and callers of it. Callers can run page contents to the Display List device just once, and then replay it quickly many times over to other devices; ideal for rendering pages in bands, or repeatedly redrawing as a viewer pans and zooms around a document.

By implementing new devices callers can tap the power of MuPDF in new and interesting ways, perhaps to harness specific hardware facilities of a device.

7.2 Device Methods

Every Device in MuPDF is an extension of the fz_device structure. This contains a series of function pointers to implement the handling of different types of graphical object.

These function pointers are exposed to callers via convenience functions. These convenience functions should **always** be used in preference to calling the function pointers direct, as they perform various behind the scenes housekeeping functions. They also cope with the function pointers being NULL, as can permissibly happen when a device is not interested in a particular class of graphical object.

We describe the convenience functions here; implementers of devices can trivially extrapolate the behaviour of the function pointers from these descriptions. For example, the fz_fill_path function described here is implemented by the fill_path function pointer in the fz_device that takes the identical arguments and has the same return conditions.

7.2.1 Line Art

Line Art is handled by the device functions to plot paths. See section 8.9 Paths for more information.

```
void fz_fill_path(fz_context *ctx, fz_device *dev, const fz_path *path,
    int even_odd, const fz_matrix *ctm, fz_colorspace *colorspace,
    const float *color, float alpha);

void fz_stroke_path(fz_context *ctx, fz_device *dev, const fz_path
    *path, const fz_stroke_state *stroke, const fz_matrix *ctm,
    fz_colorspace *colorspace, const float *color, float alpha);

void fz_clip_path(fz_context *ctx, fz_device *dev, const fz_path *path,
    int even_odd, const fz_matrix *ctm, const fz_rect *scissor);

void fz_clip_stroke_path(fz_context *ctx, fz_device *dev, const fz_path
    *path, const fz_stroke_state *stroke, const fz_matrix *ctm, const
    fz_rect *scissor);
```

7.2.2 Text

Text is handled by the device functions to plot text. See section 8.10 Text for more information.

```
void fz_stroke_text(fz_context *ctx, fz_device *dev, const fz_text
    *text, const fz_stroke_state *stroke, const fz_matrix *ctm,
    fz_colorspace *colorspace, const float *color, float alpha);
void fz_clip_text(fz_context *ctx, fz_device *dev, const fz_text *text,
    const fz_matrix *ctm, const fz_rect *scissor);
void fz_clip_stroke_text(fz_context *ctx, fz_device *dev, const fz_text
    *text, const fz_stroke_state *stroke, const fz_matrix *ctm, const
    fz_rect *scissor);
void fz_ignore_text(fz_context *ctx, fz_device *dev, const fz_text
    *text, const fz_matrix *ctm);
```

The fz_clip_text and fz_clip_stroke_text functions are used to start a clip. Subsequent operations will be clipped through the areas delimited by these, until an fz_pop_clip is seen. See subsection 7.2.5 Clipping and Masking for more details.

7.2.3 Images

Images are handled by the device functions to plot images. See section 8.6 Images for more information.

The fz_clip_image_mask function is used to start a clip. Subsequent operations will be clipped through the area delimited by this, until an fz_pop_clip is seen. See subsection 7.2.5 Clipping and Masking for more details.

7.2.4 Shadings

Shaded areas (such as radial, linear and mesh based shadings) are rendered by filling a (normally) clipped region with a shade. This is achieved by calling fz_fill_shade. See section 8.11 Shadings for more details.

7.2.5 Clipping and Masking

Graphical objects can be restricted to a given area using Clipping. The area to clip to can be specified as paths, text, or images as explained in subsection 7.2.1 Line Art, subsection 7.2.2 Text, and subsection 7.2.3 Images.

Each call to such a function starts a clipping group, which will be terminated by calling:

```
void fz_pop_clip(fz_context *ctx, fz_device *dev);
```

Clipping groups can be nested, allowing complex graphical effects.

A related concept to clipping, is that of masking. Whereas clipping regions are simple on or off things, where content is chopped off at hard edges, masking allows for regions that allow just some proportion of the content to show through.

Masking operations take place in 2 stages; first the mask itself is defined, then the content to be masked.

Stage 1 begins by calling fz_begin_mask to start a mask definition group. Any series of graphical operations can now be sent to the device which will combine together to create the mask.

Stage 1 is terminated and Stage 2 begins by calling fz_end_mask. This converts the mask definition into a 'soft clip'. Any series of graphical operations can now be sent to the device which will combine together to create the mask contents.

The whole process is then completed by calling fz_pop_clip. This renders the mask contents through the soft clip, giving the final results.

```
void fz_begin_mask(fz_context *ctx, fz_device *dev, const fz_rect *area,
    int luminosity, fz_colorspace *colorspace, const float *bc);
void fz_end_mask(fz_context *ctx, fz_device *dev);
```

7.2.6 Groups and Transparency

Some document formats (such as PDF) offer a rich transparency model that allows graphical objects to be 'Grouped' together and imposed upon the page as if they have a given opacity, using a variety of different blend modes.

MuPDF implements this by using the fz_begin_group and fz_end_group calls.

```
void fz_begin_group(fz_context *ctx, fz_device *dev, const fz_rect
    *area, int isolated, int knockout, int blendmode, float alpha);
void fz_end_group(fz_context *ctx, fz_device *dev);
```

The exact details of PDF transparency are too complex to explain here; for a full explanation see The PDF Reference Manual.

7.2.7 Tiling

Many document formats allow for content to be tiled repeatedly. Frequently this is used to implement patterns for filling other graphical operations.

MuPDF implements this by allowing a group of content to be defined that is then tiled repeatedly across an area.

The content definition begins by calling fz_begin_tile_id, giving the area of the page to be filled (area), the area of a single tile (view), the x and y steps between repeats of the tile (xstep and ystep), the transformation to take all of these measurements out of pattern space to device space (ctm) and an integer id.

The purpose of id is to allow for efficient caching of rendered tiles. If id is 0, then no caching is performed. If it is non-zero, then it assumed to uniquely identify this tile. The tile can be safely placed into the Store (see chapter 5 Memory Management and The Store) and future uses of this tile can short circuit the tile definition/rendering phase.

If a tile is found in the store, then fz_begin_tile_id will return non-zero and the caller can proceed directly to the call to fz_end_tile.

Any graphical operations sent to the device will be taken as part of the tile content, until fz_end_tile is called, whereupon these graphical operations will be imposed upon the output.

For the convenience of the caller, if no id is available (and hence no caching is possible), the fz_begin_tile variant can be used instead.

7.2.8 Render Flags

Every device has a set of render flags (a simple int, in which bits can be set or cleared).

These flags tend to have meanings specific to individual devices. In an ideal world they would not be required, but having this mechanism here can provide noticeable quality improvements.

```
void fz_render_flags(fz_context *ctx, fz_device *dev, int set, int
    clear);
```

The function basically does:

```
flags = (flags | set) & ~clear;
```

That is to say, the bits given in set are set, and then the bits given in clear are cleared.

The current only documented use of this is for the GProof device to request the Draw device to grid fit its tiled images.

The reason for using Render Flags rather than Device Hints (see section 7.4 Device Hints) is that Render Flags can be carried forward though display lists.

7.3 Cookie

The cookie is a lightweight mechanism for controlling and detecting the behaviour of a given interpretation call (i.e. fz_run_page, fz_run_page_contents, fz_run_annot, fz_run_display_list etc).

To use the cookie, a caller should simply define:

```
fz_cookie *cookie = { 0 };
set any required fields, for example:
cookie.incomplete_ok = 1;
```

and then pass &cookie as the last parameter to the interpretation call, for example:

```
fz_run_page(ctx, page, dev, transform, &cookie);
```

The contents and definition of fz_cookie are even more subject to change than other structures, so it is important to always initialise all the subfields to zero. The safest way to do this is as given above. If new fields are added to the structure, callers code should not need to change, and the default behaviour of zero-valued new fields will always remain the same.

7.3.1 Detecting errors

When displaying a page, if we hit an error, what should we do?

We could choose to stop interpretation entirely, but that would mean that a relatively unimportant error (such as a missing or broken font) would prevent us getting anything useful out of a page.

We could choose to ignore the errors and continue, but that would be a problem for (say) a print run, where it would undesirable for us to print 1000 copies of a document only to discover that it's missing an image.

The strategy taken by MuPDF is to swallow errors during interpretation, but keep a count of them in the errors field within the cookie. That way callers can check that cookie.errors == 0 at the end to know whether a run completed without incident.

7.3.2 Using the cookie with threads

Content interpretations can take a (relatively) long time. Once one has been started, it can be useful a) to know how far through processing we are, and b) to be able to abort processing should the results of a run no longer be required.

As a run progresses, 2 fields in the cookie are updated. Firstly, progress will be set to a number that increases as progress is made. Think of this informally as being the number of objects that have been processed so far. In some cases (notably when processing a display list) we can know an upper bound for this value, and this value will be given as progress_max. In cases where no upper bound is known, progress_max will be set to -1. It is possible that the upper bound may start as -1, and then change to a known value later.

These values are intended to enable user feedback to be given, and should not be taken as guarantees of performance.

While running content, the interpreter periodically checks the abort field of the cookie. If it is discovered to be non zero, the rest of the content is ignored.

If the caller decides that it does not need the results of a run once it has been started (perhaps the user changes the page, or closes the file), then it should therefore set the abort field of the cookie to 1.

No guarantees are made about how often the cookie is checked, nor about how fast an interpreter will respond to the abort field once it is set. Setting the abort flag will never hurt, and will frequently help, however. Once the flag has been set to 1, it should never be reset to 0, as the results will be unpredictable.

Resources used by a run cannot be released until the end of a run, regardless of the setting of abort. Callers still need to wait for the fz_run_page (or other) call to complete before the page etc can be safely dropped.

7.3.3 Using the cookie to control partial rendering

The cookie also has a role to play when working in Progressive Mode. The incomplete_ok and incomplete fields are used for this. See chapter 16 Progressive Mode) for more details.

7.4 Device Hints

Device Hints are a mechanism that enables control over the behaviour of a device, and to interpreters calling to that device. Informally they offer hints about what a device is going to do and therefore what callers need to worry about.

Device hints take the form of bits in an int that can be enabled (set) or disabled (cleared). Callers can query these hints to customise their behaviour.

```
/*
    fz_enable_device_hints : Enable hints in a device.
    hints: mask of hints to enable.

For example: By default the draw device renders shadings. For some purposes (perhaps rendering fast low quality thumbnails) you may want to tell it to ignore shadings. For this you would enable the FZ_IGNORE_SHADE hint.
*/
void fz_enable_device_hints(fz_context *ctx, fz_device *dev, int hints);

/*
    fz_disable_device_hints : Disable hints in a device.
    hints: mask of hints to disable.

For example: By default the text extraction device ignores images.
    For some purposes however (such as extracting HTML) you may want to enable the capturing of image data too. For this you would disable the FZ_IGNORE_IMAGE hint.
*/
void fz_disable_device_hints(fz_context *ctx, fz_device *dev, int hints);
```

Some devices set the hints to non-zero default values.

For example, when running a text-extraction operation (as used to implement text search), there is little point in handling images, or shadings. The text extraction device therefore sets FZ_IGNORE_IMAGE and FZ_IGNORE_SHADE. The interpretation functions (such as fz_run_page or fz_run_display_list can then not bother to prepare images for calling into the device, improving performance.

If, however, you wish to extract the page content to an html file, you might want to include images in this output. So for this, you would disable the FZ_IGNORE_IMAGE hint before running the extraction, and the text extraction device would know to include them in its output structures.

The set of hints is subject to expansion in future, but is currently defined to be:

```
enum
{
    /* Hints */
    FZ_IGNORE_IMAGE = 1,
    FZ_IGNORE_SHADE = 2,
    FZ_DONT_INTERPOLATE_IMAGES = 4,
    FZ_MAINTAIN_CONTAINER_STACK = 8,
    FZ_NO_CACHE = 16,
};
```

FZ_IGNORE_IMAGE being enabled implies that a device will (or should) make no effort to handle images. For example, when playing back a display list (with fz_run_display_list), if the target device sets FZ_IGNORE_IMAGE, no image related calls will be made.

FZ_IGNORE_SHADE being enabled implies that a device will (or should) make no effort to handle shadings. For instance, if you are doing a quick pass across files trying to generate low quality thumbnail images, you may choose to disable shadings for speed.

FZ_DONT_INTERPOLAGE_IMAGES being enabled prevents the draw device performing interpolation. MuTool Draw uses this to inhibit interpolation when antialiasing is disabled. Finer control over this can now be given using the Tuning Context (see section 3.7 Tuning).

FZ_MAINTAIN_CONTAINER_STACK being enabled helps devices by causing MuPDF to maintain a stack of containers. This effectively moves some logic that would have to be in several devices into a place where it can be easily reused. Currently the only device that makes use of this is the SVG device, but it is hoped that more will use it in future.

FZ_NO_CACHE being enabled tells the interpreter to try to avoid caching any objects after the end of the content run. This can be used, for example, when searching a PDF for a text string to avoid pulling all the images, shadings, fonts etc and other resources for pages into memory at the expense of those that are used on the current page.

7.5 Inbuilt Devices

MuPDF comes with a selection of devices built in, though this should not be taken as a definitive list. It is expected that other devices will be written to extend MuPDF - indeed some embeddings of MuPDF already include their own devices.

7.5.1 BBox Device

The BBox device is a simple device that calculates the bbox of all the marking operations on a page.

```
/*
    fz_new_bbox_device: Create a device to compute the bounding
    box of all marks on a page.

The returned bounding box will be the union of all bounding
    boxes of all objects on a page.
*/
fz_device *fz_new_bbox_device(fz_context *ctx, fz_rect *rectp);
```

The fz_rect passed to the fz_new_bbox_device must obviously stay in scope for the duration of the life of the device as it will be updated on exit with the bounding box for the contents.

7.5.2 Draw Device

The Draw device is the core renderer for MuPDF. Every draw device instance is constructed with a destination Pixmap (see section 8.3 Pixmaps for more details), and each graphical object passed to the device is rendered into that pixmap.

```
/*
    fz_new_draw_device: Create a device to draw on a pixmap.

dest: Target pixmap for the draw device. See fz_new_pixmap*
    for how to obtain a pixmap. The pixmap is not cleared by the
    draw device, see fz_clear_pixmap* for how to clear it prior to
    calling fz_new_draw_device. Free the device by calling
    fz_drop_device.

*/
fz_device *fz_new_draw_device(fz_context *ctx, fz_pixmap *dest);
```

Most of the time we render complete pixmaps, but a mechanism exists to allow us to render a given bbox within a pixmap:

```
/*
    fz_new_draw_device_with_bbox: Create a device to draw on a pixmap.

dest: Target pixmap for the draw device. See fz_new_pixmap*
    for how to obtain a pixmap. The pixmap is not cleared by the
    draw device, see fz_clear_pixmap* for how to clear it prior to
    calling fz_new_draw_device. Free the device by calling
    fz_drop_device.

clip: Bounding box to restrict any marking operations of the
    draw device.

*/
fz_device *fz_new_draw_device_with_bbox(fz_context *ctx, fz_pixmap
    *dest, const fz_irect *clip);
```

This can be useful for updating particular areas of a page (for instance when an annotation has been edited or moved) without redrawing the whole thing.

During the course of rendering, the draw device may create new temporary internal pixmaps to cope with transparency and grouping. This is invisible to the caller, and can safely be considered an implementation detail, but should be considered when estimating the memory use for a given rendering operation. The exact number and size of internal pixmaps required depends on the exact complexity and makeup of the graphical objects being displayed.

To limit memory use, a typical strategy is to render pages in bands; rather than creating a single pixmap the size of the page and rendering that, create pixmaps for 'slices' across the page, and render them one at a time. The memory savings are not just seen in the cost of the basic pixmap, but also serve to limit the sizes of the internal pixmaps used during rendering.

The cost for this is that the page contents do need to be run through repeatedly. This can be achieved by reinterpreting directly from the file, but that can be expensive. The next device provides a route to help with this.

7.5.3 Display List Device

The Display list device simply records all the calls made to it in a list. This list can then be played back later, potentially multiple times and with different transforms, to other devices.

```
/*
    fz_new_list_device: Create a rendering device for a display list.

When the device is rendering a page it will populate the
    display list with drawing commsnds (text, images, etc.). The
    display list can later be reused to render a page many times
    without having to re-interpret the page from the document file
```

```
for each rendering. Once the device is no longer needed, free
it with fz_drop_device.

list: A display list that the list device takes ownership of.
*/
fz_device *fz_new_list_device(fz_context *ctx, fz_display_list *list);
```

For more details of the uses of Display Lists, see chapter 9 Display Lists.

7.5.4 PDF Output Device

The PDF Output device is still a work in progress, as its handling of fonts is incomplete. Nonetheless for certain classes of files it can be useful.

End users will probably prefer to use the document writer interface (see /rj-wrefDocumentWriter) which wraps this class up, rather than call it directly. Nonetheless this can be useful in specific circumstances when generating particular sections of a PDF file (such as appearance streams for annotations).

The PDF Output device takes the sequence of graphical operations it is called with, and forms it back into a sequence of PDF operations, together with a set of required resources. These can then be formed into a completely new PDF page (or a PDF annotation) which can then be inserted into a document.

```
pdf_page_write: Create a device that will record the
  graphical operations given to it into a sequence of
  pdf operations, together with a set of resources. This
  sequence/set pair can then be used as the basis for
  adding a page to the document (see pdf_add_page).

doc: The document for which these are intended.

mediabox: The bbox for the created page.

presources: Pointer to a place to put the created
  resources dictionary.

pcontents: Pointer to a place to put the created
  contents buffer.

*/
fz_device *pdf_page_write(fz_context *ctx, pdf_document *doc, const
  fz_rect *mediabox, pdf_obj **presources, fz_buffer **pcontents);
```

For more information about page manipulation in PDF documents, see ?? ??.

7.5.5 Structured Text Device

The Structured Text device is used to extract the text from a given graphical stream, together with the position it inhabits on the output page. It can also optionally include details of images and their positions within its output.

```
fz_new_stext_device: Create a device to extract the text on a page.

Gather and sort the text on a page into spans of uniform style,
    arranged into lines and blocks by reading order. The reading order
    is determined by various heuristics, so may not be accurate.

sheet: The text sheet to which styles should be added. This can
    either be a newly created (empty) text sheet, or one containing
    styles from a previous text device. The same sheet cannot be used
    in multiple threads simultaneously.

page: The text page to which content should be added. This will
    usually be a newly created (empty) text page, but it can be one
    containing data already (for example when merging multiple pages, or
    watermarking).

*/
fz_device *fz_new_stext_device(fz_context *ctx, fz_stext_sheet *sheet,
    fz_stext_page *page);
```

This can be used as the basis for searching (including highlighting the text as matches are found), for exporting text files (or text and image based files such as HTML), or even to do more complex page analysis (such as spotting what regions of the page are text, what are graphics etc).

An (initially empty) fz_stext_sheet should be created using fz_new_stext_sheet, and an empty fz_stext_page created using fz_new_stext_page. These are used in the call to fz_new_stext_device. After the contents have been run to that device, the sheet will be populated with the common styles used by the page, and the page will be populated with details of the text extracted and its position.

7.5.6 SVG Output Device

The SVG output device is used to generate SVG pages from arbitrary input.

End users will probably prefer to use the document writer interface (see /rj-wrefDocumentWriter) which wraps this class up, rather than call it directly.

```
fz_new_svg_device: Create a device that outputs (single page)
SVG files to the given output stream.
```

```
output: The output stream to send the constructed SVG page
to.

page_width, page_height: The page dimensions to use (in
points).

*/
fz_device *fz_new_svg_device(fz_context *ctx, fz_output *out, float
    page_width, float page_height);
```

The device currently generates SVG 1.1 compliant files. SVG Fonts are NOT used due to poor client support. Instead glyphs are sent as reusable symbols. Shadings are sent as rasterised images. JPEGs will be passed through unchanged, and all other images will be converted to PNG.

7.5.7 Test Device

The Test device, as its name suggests, tests a given set of page contents for which features are used. Currently this is restricted to testing for whether the graphical objects used are greyscale or colour. Testing for additional features may be added in future.

```
fz_new_test_device: Create a device to test for features.
Currently only tests for the presence of non-grayscale colors.
is color: Possible values returned:
   0: Definitely greyscale
   1: Probably color (all colors were grey, but there
   were images or shadings in a non grey colorspace).
   2: Definitely color
threshold: The difference from grayscale that will be tolerated.
Typical values to use are either 0 (be exact) and 0.02 (allow an
imperceptible amount of slop).
options: A set of bitfield options, from the FZ_TEST_OPT set.
passthrough: A device to pass all calls through to, or NULL.
If set, then the test device can both test and pass through to
an underlying device (like, say, the display list device). This
means that a display list can be created and at the end we'll
know if its color or not.
In the absence of a passthrough device, the device will throw
an exception to stop page interpretation when color is found.
```

The expected purpose of the colour detecting functionality is to allow applications (e.g. printers) to easily detect if a given page requires the use of colour inks, or whether a greyscale rendering will suffice.

This device can either be used by itself, or in the form of a pass-through device.

Standalone use

In the simplest form, the device can be created standalone, by passing passthrough as NULL.

As each subsequent device call is made, the device will test the graphic object passed to it to see if it is within the given threshold of being a neutral colour. If it is, then the device continues. If not, then it sets the int pointed to by is_color to be non zero.

For graphical objects such as paths or text, this is an easy evaluation that takes almost no time. For Images or Shadings however, it is slightly trickier. An image may be defined in a colour space capable of non-neutral colours (perhaps RGB or CMYK) and yet the image itself may only use neutral colours within that space. To properly establish whether colours are required or not, requires much more CPU intensive processing.

Accordingly, the device will, by default, just look at the colour space. The value of <code>is_color</code> returned at the end may be examined to establish the confidence level of the test. 0 means "definitely greyscale", 1 means "probably colour" (i.e. "an image or shading was seen that potentially contains non neutral colours"), and 2 means "definitely colour".

If the caller wishes to spend the CPU cycles to get a definite answer, options can be set to FZ_TEXT_OPT_IMAGES | FZ_TEXT_OPT_SHADINGS and images and shadings will be exhaustively checked.

As an optimisation, given how much faster is is to check non-images and shadings, it can be worth running the device once without the options set, and then only running it again with them set if required.

If the device is run with passthrough as NULL, then as soon as it encounters a "definite" non-neutral colour, it will throw a FZ_ABORT error.

Passthrough use

As discussed above, the envisaged use case for this device is to detect whether page contents require colour or not to allow printers to decide whether to rasterise for colour inks or a faster/cheaper greyscale pass.

Such printers will normally be operating in banded mode, which requires (or at least greatly benefits from) the use of a display list. By using the device in passthrough mode, the testing can be performed at the same time as the list is built.

Simply create the display list device as you would normally, and pass it into fz_new_test_device as passthrough. Then run the page contents through the returned test device. The test device will pass each call through to the underlying list device and so the display list be built as normal.

When run in this mode, the device can no longer use the 'early-exit' optimisation of throwing a **FZ_ABORT** error.

7.5.8 Trace Device

The Trace device is a simple debugging device that allows an XML-like representation of the device calls made to be output.

```
/*
    fz_new_trace_device: Create a device to print a debug trace of all
        device calls.
*/
fz_device *fz_new_trace_device(fz_context *ctx, fz_output *out);
```

This is a useful tool to visualise the contents of display lists.

Chapter 8

Building Blocks

8.1 Overview

MuPDF uses many constructs and concepts that, while not deserving of chapters in their own rights, do deserve mention.

8.2 Colorspaces

In order to represent a given color for a graphical object, we need both the color component values and details of the colorspace that the color is specified in. Color values are defined simply as floats (between 0 and 1 inclusive), and colorspaces are defined using the fz_colorspace structure.

As with many other such structures in MuPDF, these are reference counted objects (see section 5.2 Reference Counting).

8.2.1 Basic Colorspaces

MuPDF contains a set of inbuilt color spaces that cover most simple requirements. These can

8.3 Pixmaps

8.3.1 Overview

The fz_pixmap structure is used to represent a 2 dimensional array of contone pixels. This is used throughout MuPDF, as the target of rendering from the draw device, as internal buffers during processing, and during image decoding.

A pixmap can have an arbitrary number of colour components, together with an optional alpha plane. Every component sample is represented by an unsigned char.

The number of colour components corresponds to the colour space of a pixmap; pixmaps without a colour space must contain no colour planes, just a single alpha plane.

The data within a pixmap is always stored packed in 'chunky' format. For instance, an RGB pixmap would have data in the form: RGBRGBRGBRGB...

Alpha data is always sent as the last byte in the set corresponding to a pixel. An RGB pixmap with an alpha plane would be therefore have data of the form: RGBARGBARGBA...

To allow pixmaps to sensibly 'subset' one another, pixmaps have a 'stride' field. This gives the number of bytes difference from the address of the start of the representation of a pixel to the address of the start of the representation of the same pixel on the scanline below.

Normally you'd expect stride to be the same as width multiplied by the number of components in the image (including alpha), but for 'sub areas' of larger pixmaps this can be much larger.

Pixmaps can frequently map onto operating system specific bitmap representations, but these sometimes require each scanline to be word aligned - again the provision of stride allows for this. Bottom up bitmaps can be implemented using a negative stride.

8.3.2 Saving

Various functions exist to either save pixmaps to files, or to (more generally) write them to fz_output streams.

In general, these functions fall into 3 categories of increasing complexity.

Firstly, functions of the form fz_save_pixmap_to_... take a pixmap and write it to a given filename in the local filesystem.

Secondly, functions of the form fz_write_pixmap_to.... take a pixmap and write it to a given fz_output. The use of an fz_output allows for writing to

memory buffers, or even potentially to encrypt or compress further as the write progresses.

Finally, we have an fz_band_writer class, that allows images to be written to file in 'bands', thus minimising the amount of memory required at any one time. Typically a band writer is created using a call such as fz_new_png_band_writer:

```
fz_new_png_band_writer: Obtain a fz_band_writer instance
   for producing PNG output.
fz_band_writer *fz_new_png_band_writer(fz_context *ctx, fz_output *out);
First, an image header is written, using this writer:
   fz_write_header: Cause a band writer to write the header for
   a banded image with the given properties/dimensions etc. This
   also configures the bandwriter for the format of the data to be
   passed in future calls.
   w, h: Width and Height of the entire page.
   n: Number of components (including alphas).
   alpha: Number of alpha components.
   xres, yres: X and Y resolutions in dpi.
   pagenum: Page number
   Throws exception if incompatible data format.
void fz_write_header(fz_context *ctx, fz_band_writer *writer, int w, int
    h, int n, int alpha, int xres, int yres, int pagenum);
This has the effect of setting the size and format of the data for the complete
image. The caller then proceeds to render the page in horizontal strips from the
top to the bottom, and pass them in to fz_write_band:
/*
   fz_write_band: Cause a band writer to write the next band
   of data for an image.
   stride: The byte offset from the first byte of the data
   for a pixel to the first byte of the data for the same pixel
   on the row below.
```

band_height: The number of lines in this band.

```
samples: Pointer to first byte of the data.
*/
void fz_write_band(fz_context *ctx, fz_band_writer *writer, int stride,
    int band_height, const unsigned char *samples);
```

The band writer keeps track of how much data has been written, and when an entire page has been sent, it writes out any image trailer required.

For formats that can accommodate multiple pages, a new call to fz_write_header will start the process again. Otherwise (or after the final image), the band writer can be neatly discarded by calling:

```
void fz_drop_band_writer(fz_context *ctx, fz_band_writer *writer);
```

8.4 Bitmaps

The fz_bitmap structure is used to represent a 2 dimensional array of monochrome pixels. They are the 1 bit per component equivalent of the fz_pixmap structure.

The core rendering engine of MuPDF does not currently make use of fz_bitmaps, but rather they are used as a step along the way for outputting rendered information.

Functions exist within MuPDF to create fz_bitmaps from fz_pixmaps by half-toning. See section 8.5 Halftones.

Both functions work by applying a fz_halftone to the contone values to make the bitmap. The latter function is a more general version of the former, that allows for correct operation when rendering in bands - namely that the correct offset into the halftone table is used.

The data for each Bitmap is packed into bytes most significant bit first. Multiple components are packed into the same byte, so a CMYK pixmap converted to a bitmap would have 2 pixels worth of data in the first byte, CMYKCMYK, with the first pixel in the highest nibble.

The usual reference counting behaviour applies to fz_bitmaps, with fz_keep_bitmap and fz_drop_bitmap claiming and releasing references respectively.

8.5 Halftones

The fz_halftone structure represents a set of tiles, one per component, each of a potentially different size. Each of these tiles is a 2-dimensional array of threshold values (actually implemented as a single component fz_pixmap). During the halftoning (bitmap creation) process, if the contone value is smaller than the threshold value, then it remains unset in the output. If it is larger or equal then it is set in the output.

For convenience, a NULL pointer can be used to signify the default halftone. The default halftone can also be fetched by using:

```
/*
    fz_default_halftone: Create a 'default' halftone structure
    for the given number of components.
    num_comps: The number of components to use.

Returns a simple default halftone. The default halftone uses
    the same halftone tile for each plane, which may not be ideal
    for all purposes.
*/
fz_halftone *fz_default_halftone(fz_context *ctx, int num_comps);
```

The creation of halftones is a specialised field upon which much research has been done. The mechanisms in MuPDF are designed to allow people the freedom to create and tune the halftones for their particular application.

The usual reference counting behaviour applies to fz_halftones, with fz_keep_halftone and fz_drop_halftone claiming and releasing references respectively.

8.6 Images

The fz_image structure is used to represent a generic Image object in MuPDF. It can be viewed as an encapsulation from which both a rendering of an image (as an fz_pixmap) and (often) the original source data can be retrieved.

The primary use of an fz_image is to allow a rendered pixmap to be retrieved. This is done by calling:

```
fz_get_pixmap_from_image: Called to get a handle to a pixmap from
   an image.
   image: The image to retrieve a pixmap from.
   subarea: The subarea of the image that we actually care about (or
   NULL to indicate the whole image).
   trans: Optional, unless subarea is given. If given, then on entry
   this is the transform that will be applied to the complete image.
   It should be updated on exit to the transform to apply to the given
   subarea of the image. This is used to calculate the desired
   width/height for subsampling.
   w: If non-NULL, a pointer to an int to be updated on exit to the
   width (in pixels) that the scaled output will cover.
   h: If non-NULL, a pointer to an int to be updated on exit to the
   height (in pixels) that the scaled output will cover.
   Returns a non NULL pixmap pointer. May throw exceptions.
*/
fz_pixmap *fz_get_pixmap_from_image(fz_context *ctx, fz_image *image,
    const fz_irect *subarea, fz_matrix *trans, int *w, int *h);
```

Frequently this will involve decoding the image from its source data, so should be considered a potentially expensive call, both in terms of CPU time, and memory usage.

To minimise the impact of such decodes, fz_images make use of the Store (see chapter 5 Memory Management and The Store) to cache decoded versions in. This means that (subject to enough memory being available) repeated calls to get a fz_pixmap from the same fz_image (with the same parameters) will return the same fz_pixmap each time, with no further decode being required.

The usual reference counting behaviour applies to fz_images, with fz_keep_image and fz_drop_image claiming and releasing references respectively.

Depending on the size at which an fz_image is to be used, it may not be worth decoding it at full resolution; instead, decoding it at a smaller size can save memory (and frequently time). In addition, subsequent rendering operations can often be faster due to having to handle fewer pixels for no quality loss in the final output.

To facilitate this, fz_images will subsample images as appropriate. Subsampling involves an image being decoded to a size an integer power of 2 smaller than their native size. For instance, if an image has a native size of 400x300, and is to be rendered to a final size of 40x30, fz_get_pixmap_from_image may subsample the returned image by up to 8 in each direction, resulting in a 50x37 image.

Subsequent operations (such as smooth scaling and rendering) will proceed much faster due to fewer pixels being involved, and around one sixteenth of the memory will be required.

Various different implementations of fz_image exist within MuPDF.

8.6.1 Compressed Images

The fz_compressed_image structure is a specialisation of fz_image, that holds the source data for an image in an fz_compressed_buffer. This is the usual form for images created from PDF and XPS files.

The data for a compressed image can be retrieved by calling:

If the supplied fz_image is not an fz_compressed_image then it will return NULL.

8.6.2 Pixmap Images

The fz_pixmap_image structure is a specialisation of fz_image, that has an fz_pixmap as its source data. This exists to allow fz_pixmaps from other sources to be easily fed into the MuPDF rendering engine.

8.7 Buffers

The fz_buffer structure is used to represent arbitrary buffers of data. Essentially they are a representation for arbitrary blocks of bytes (in whatever encoding required), with simple functions for extending, concatenating, and writing in byte, char, utf8 and bitwise fashion.

Both the internals and API level functions of MuPDF use fz_buffers extensively.

The usual reference counting behaviour applies to fz_buffers, with fz_keep_buffer and fz_drop_buffer claiming and releasing references respectively.

8.8 Transforms

The fz_matrix structure is used to represent 2 dimensional matrices used for transforming points, shapes and other geometry.

The six fields of the fz_matrix structure correspond to a matrix of the form:

$$\left(\begin{array}{ccc}
a & b & 0 \\
c & d & 0 \\
e & f & 1
\end{array}\right)$$

Such transformation matrices can be used to represent a wide range of different operations, including translations, rotations, scales, sheers, and any combination thereof.

Typically, a matrix will be created for a specific purpose, such as a scale, or a translation. For this reason, we have dedicated construction calls.

```
/*
    fz_scale: Create a scaling matrix.

The returned matrix is of the form [ sx 0 0 sy 0 0 ].

m: Pointer to the matrix to populate

sx, sy: Scaling factors along the X- and Y-axes. A scaling factor of 1.0 will not cause any scaling along the relevant axis.

Returns m.

Does not throw exceptions.
*/
fz_matrix *fz_scale(fz_matrix *m, float sx, float sy);

/*
    fz_shear: Create a shearing matrix.

The returned matrix is of the form [ 1 sy sx 1 0 0 ].
```

```
m: pointer to place to store returned matrix
   sx, sy: Shearing factors. A shearing factor of 0.0 will not
   cause any shearing along the relevant axis.
   Returns m.
   Does not throw exceptions.
*/
fz_matrix *fz_shear(fz_matrix *m, float sx, float sy);
   fz_rotate: Create a rotation matrix.
   The returned matrix is of the form
   [ cos(deg) sin(deg) -sin(deg) cos(deg) 0 0 ].
   m: Pointer to place to store matrix
   degrees: Degrees of counter clockwise rotation. Values less
   than zero and greater than 360 are handled as expected.
   Returns m.
   Does not throw exceptions.
*/
fz_matrix *fz_rotate(fz_matrix *m, float degrees);
   fz_translate: Create a translation matrix.
   The returned matrix is of the form [ 1 0 0 1 tx ty ].
   m: A place to store the created matrix.
   tx, ty: Translation distances along the X- and Y-axes. A
   translation of 0 will not cause any translation along the
   relevant axis.
   Returns m.
   Does not throw exceptions.
fz_matrix *fz_translate(fz_matrix *m, float tx, float ty);
```

Mathematically, points are transformed by multiplying them (extended to 3 elements long). For example (x',y'), the point given by mapping (x,y) through such a matrix is calculated as follows:

$$\left(\begin{array}{ccc} x' & y' & 1 \end{array}\right) = \left(\begin{array}{ccc} x & y & 1 \end{array}\right) \left(\begin{array}{ccc} a & b & 0 \\ c & d & 0 \\ e & f & 1 \end{array}\right)$$

There are various functions in MuPDF to perform such transformations:

Rectangles can be transformed using the following function, which allows for the fact that the image of a rectangle may be flipped:

```
fz_transform_rect: Apply a transform to a rectangle.

After the four corner points of the axis-aligned rectangle have been transformed it may not longer be axis-aligned. So a new axis-aligned rectangle is created covering at least the area of the transformed rectangle.

transform: Transformation matrix to apply. See fz_concat, fz_scale and fz_rotate for how to create a matrix.

rect: Rectangle to be transformed. The two special cases fz_empty_rect and fz_infinite_rect, may be used but are returned unchanged as expected.

Does not throw exceptions.

*/
fz_rect *fz_transform_rect(fz_rect *restrict rect, const fz_matrix)
```

*restrict transform);

Also, it can be useful to transform a point, ignoring the translation components of a transformation, so we have a convenience function for this:

```
/*
    fz_transform_vector: Apply a transformation to a vector.

transform: Transformation matrix to apply. See fz_concat,
    fz_scale and fz_rotate for how to create a matrix. Any
    translation will be ignored.

vector: Pointer to vector to update.

Does not throw exceptions.
*/
fz_point *fz_transform_vector(fz_point *restrict vector, const fz_matrix
    *restrict transform);
```

Transformations can be combined by multiplying their representative matrices together. Transforming a point by applying matrix A then matrix B, will give identical results to transforming the point by AB.

MuPDF provides an API for combining matrices in this way:

```
/*
    fz_concat: Multiply two matrices.

The order of the two matrices are important since matrix
    multiplication is not commutative.

Returns result.

Does not throw exceptions.
*/
fz_matrix *fz_concat(fz_matrix *result, const fz_matrix *left, const
    fz_matrix *right);
```

Alternatively, operations can be specifically applied to existing matrices. Because of the non-commutative nature of matrix operations, it matters whether the new operation is applied before or after the existing matrix.

For example, if you have a matrix that performs a rotation, and you wish to combine that with a translation, you must decide whether you want the translation to occur before the rotation ('pre') or afterwards ('post').

MuPDF has various API functions for such operations:

```
/*
   fz_pre_scale: Scale a matrix by premultiplication.
   m: Pointer to the matrix to scale
```

```
sx, sy: Scaling factors along the X- and Y-axes. A scaling
   factor of 1.0 will not cause any scaling along the relevant
   axis.
   Returns m (updated).
   Does not throw exceptions.
*/
fz_matrix *fz_pre_scale(fz_matrix *m, float sx, float sy);
   fz_post_scale: Scale a matrix by postmultiplication.
   m: Pointer to the matrix to scale
   sx, sy: Scaling factors along the X- and Y-axes. A scaling
   factor of 1.0 will not cause any scaling along the relevant
   Returns m (updated).
   Does not throw exceptions.
fz_matrix *fz_post_scale(fz_matrix *m, float sx, float sy);
   fz_pre_shear: Premultiply a matrix with a shearing matrix.
   The shearing matrix is of the form [ 1 sy sx 1 0 0 ].
   m: pointer to matrix to premultiply
   sx, sy: Shearing factors. A shearing factor of 0.0 will not
   cause any shearing along the relevant axis.
   Returns m (updated).
   Does not throw exceptions.
*/
fz_matrix *fz_pre_shear(fz_matrix *m, float sx, float sy);
   fz_pre_rotate: Rotate a transformation by premultiplying.
   The premultiplied matrix is of the form
   [ cos(deg) sin(deg) - sin(deg) cos(deg) 0 0 ].
   m: Pointer to matrix to premultiply.
```

```
degrees: Degrees of counter clockwise rotation. Values less
   than zero and greater than 360 are handled as expected.
   Returns m (updated).
   Does not throw exceptions.
*/
fz_matrix *fz_pre_rotate(fz_matrix *m, float degrees);
   fz_pre_translate: Translate a matrix by premultiplication.
   m: The matrix to translate
   tx, ty: Translation distances along the X- and Y-axes. A
   translation of 0 will not cause any translation along the
   relevant axis.
   Returns m.
   Does not throw exceptions.
fz_matrix *fz_pre_translate(fz_matrix *m, float tx, float ty);
Finally, sometimes it is useful to find the matrix that would represent the reverse
of a given transformation. This can be achieved by 'inverting' the matrix.
This is not possible in all cases, but can be achieved for most 'well-behaved'
transformations.
   fz_invert_matrix: Create an inverse matrix.
   inverse: Place to store inverse matrix.
   matrix: Matrix to invert. A degenerate matrix, where the
   determinant is equal to zero, can not be inverted and the
   original matrix is returned instead.
   Returns inverse.
   Does not throw exceptions.
fz_matrix *fz_invert_matrix(fz_matrix *inverse, const fz_matrix *matrix);
   fz_try_invert_matrix: Attempt to create an inverse matrix.
   inverse: Place to store inverse matrix.
```

```
matrix: Matrix to invert. A degenerate matrix, where the
  determinant is equal to zero, can not be inverted.

Returns 1 if matrix is degenerate (singular), or 0 otherwise.

Does not throw exceptions.
*/
int fz_try_invert_matrix(fz_matrix *inverse, const fz_matrix *matrix);
```

8.9 Paths

Postscript (or PDF) style paths are represented using the fz_path structure. A postscript path consists of a sequence of instructions describing the movement of a 'pen' around a given path.

The first instruction is always a 'move' to a specified location. Subsequent instructions move the pen position onwards to new positions on the page, either via straight lines, or via curves described by given control points. Such instructions can either be made with the pen up or down.

Once created paths can then be rendered by MuPDF either by being filled, or by being stroked. The path itself has no knowledge of how it will be used - the details of the fill or the stroke attributes are supplied externally to this structure. A description of the exact rules used for filling and stroking are beyond the scope of this document. For more information see "The PDF Reference Manual" or "The Postscript Language Reference Manual".

Paths are reference counted objects, with the implicit understanding that once more than one reference exists to a path, it will no longer be modified.

8.9.1 Creation

A reference to a new empty path can be created using fz_new_path:

```
/*
   fz_new_path: Create an empty path, and return
   a reference to it.

   Throws exception on failure to allocate.
*/
fz_path *fz_new_path(fz_context *ctx);
```

Once a path exists, commands can be added to it. The first command must always be a 'move'.

```
/*
   fz_moveto: Append a 'moveto' command to a path.
   path: The path to modify.
   x, y: The coordinate to move to.
   Throws exceptions on failure to allocate.
*/
void fz_moveto(fz_context *ctx, fz_path *path, float x, float y);
Once we have moved to a point, subsequent commands can be added, such as
lines, quads (quadratic beziers) and curves (cubic beziers).
   fz_lineto: Append a 'lineto' command to a path.
   path: The path to modify.
   x, y: The coordinate to line to.
   Throws exceptions on failure to allocate.
void fz_lineto(fz_context *ctx, fz_path *path, float x, float y);
/*
   fz_quadto: Append a 'quadto' command to a path. (For a
   quadratic bezier).
   path: The path to modify.
   x0, y0: The control coordinates for the quadratic curve.
   x1, y1: The end coordinates for the quadratic curve.
   Throws exceptions on failure to allocate.
void fz_quadto(fz_context *ctx, fz_path *path, float x0, float y0, float
    x1, float y1);
   fz_curveto: Append a 'curveto' command to a path. (For a
   cubic bezier).
   path: The path to modify.
   x0, y0: The coordinates of the first control point for the
   curve.
```

float x2, float y2);

```
x1, y1: The coordinates of the second control point for the
   curve.
   x2, y2: The end coordinates for the curve.
   Throws exceptions on failure to allocate.
*/
void fz_curveto(fz_context *ctx, fz_path *path, float x0, float y0,
    float x1, float y1, float x2, float y2);
In addition, we have 2 functions for adding curves (cubic beziers) where one
of the control points is coincident with the neighbouring endpoints. These
functions mirror the usage in PDF, but offer no benefits other than convenience
as such curves are detected automatically as part of an fz_curveto call.
   fz_curvetov: Append a 'curvetov' command to a path. (For a
   cubic bezier with the first control coordinate equal to
   the start point).
   path: The path to modify.
   x1, y1: The coordinates of the second control point for the
   curve.
   x2, y2: The end coordinates for the curve.
   Throws exceptions on failure to allocate.
void fz_curvetov(fz_context *ctx, fz_path *path, float x1, float y1,
    float x2, float y2);
   fz_curvetoy: Append a 'curvetoy' command to a path. (For a
   cubic bezier with the second control coordinate equal to
   the end point).
   path: The path to modify.
   x0, y0: The coordinates of the first control point for the
   curve.
   x2, y2: The end coordinates for the curve (and the second
   control coordinate).
   Throws exceptions on failure to allocate.
*/
void fz_curvetoy(fz_context *ctx, fz_path *path, float x0, float y0,
```

At any point after the initial move, we can close the path using fz_closepath:

```
/*
    fz_closepath: Close the current subpath.

path: The path to modify.

Throws exceptions on failure to allocate, and illegal path closes.
*/
void fz_closepath(fz_context *ctx, fz_path *path);
```

After a path has been closed, the only acceptable next command is a move. A path need not be closed before a second or subsequent move is sent.

Finally, we have one additional path construction function, fz_rectto. This appends a rectangle to the current path. This rectangle is equivalent to a move, 3 lines and a closepath, and so is the one exception to the rule that paths must begin with a move (as one is implicit within the rectangle command).

```
/*
    fz_rectto: Append a 'rectto' command to a path.

The rectangle is equivalent to:
    moveto x0 y0
    lineto x1 y0
    lineto x1 y1
    lineto x0 y1
    closepath

path: The path to modify.

x0, y0: First corner of the rectangle.

x1, y1: Second corner of the rectangle.

Throws exceptions on failure to allocate.

*/
void fz_rectto(fz_context *ctx, fz_path *path, float x0, float y0, float x1, float y1);
```

Finally, during path construction, the coordinate at which the notional path cursor has reached can be read using the fz_currentpoint function.

```
fz_currentpoint: Return the current point that a path has
reached or (0,0) if empty.

path: path to return the current point of.
```

```
*/
fz_point fz_currentpoint(fz_context *ctx, fz_path *path);
```

8.9.2 Reference counting

As stated before, fz_paths are reference counted objects. Once one has been created, references can be created/destroyed using the standard keep/drop conventions:

```
/*
    fz_keep_path: Take an additional reference to
    a path.

No modifications should be carried out on a path
    to which more than one reference is held, as
    this can cause race conditions.

Never throws exceptions.

*/
fz_path *fz_keep_path(fz_context *ctx, const fz_path *path);

/*
    fz_drop_path: Drop a reference to a path,
    destroying the path if it is the last
    reference.

Never throws exceptions.

*/
void fz_drop_path(fz_context *ctx, const fz_path *path);
```

A path with more than one reference is considered to be 'frozen' or 'immutable'. It is not safe to modify such a path, as the other holder of a reference to it may not expect it to be being changed. That is to say that modification operations on paths are not atomic between threads.

If you have a path that you wish to be able to modify, simply call fz_clone_path to obtain a reference to a copy of the path that is safe to modify:

```
/*
    fz_clone_path: Clone the data for a path.

This is used in preference to fz_keep_path when a whole
    new copy of a path is required, rather than just a shared
    pointer. This probably indicates that the path is about to
    be modified.

path: path to clone.
```

```
Throws exceptions on failure to allocate.

*/
fz_path *fz_clone_path(fz_context *ctx, fz_path *path);
```

8.9.3 Storage

Because Paths are such a crucial part of MuPDF, and are used so widely in document content, we take particular care to allow them to be expressed and accessed efficiently.

This means that at path construction time, we spot simple cases where we can optimise the path representation. For example, a move immediately following a move can cause the first move to be dropped. Similarly, a curve with both control points coincident with the endpoints can be expressed as a line.

This means that if you read a path out after construction (see subsection 8.9.7 Walking) you cannot rely on the exact representation being the same.

In addition, after constructing a path, there are some simple things that can be done to minimise the memory used.

As paths are constructed, the data buffers within them grow. For efficiency, these grow with some slack in them, so at the end of construction there can be a non-trivial amount of space wasted.

If you intend to simply use the path, and then discard it, this does not matter. If instead you intend to keep the path around for a while, it may be worth calling fz_trim_path to shrink the storage buffers as much as possible.

```
/*
    fz_trim_path: Minimise the internal storage
    used by a path.

As paths are constructed, the internal buffers
    grow. To avoid repeated reallocations they
    grow with some spare space. Once a path has
    been fully constructed, this call allows the
    excess space to be trimmed.

Never throws exceptions.
*/
void fz_trim_path(fz_context *ctx, fz_path *path);
```

MuPDF automatically calls this function when fz_keep_path is called for the first time as having more than one reference to a path is considered a good indication of it being kept around for a while.

For cases where large numbers of paths are kept around for a long period of time, for example in a fz_display_list (see chapter 9 Display Lists), it can be advantageous to 'pack' paths to further minimise the space they use.

To pack a path, first call fz_packed_path_size to obtain the number of bytes required to pack a path:

```
/*
    fz_packed_path_size: Return the number of
    bytes required to pack a path.

    Never throws exceptions.
*/
int fz_packed_path_size(const fz_path *path);
```

Then, call fz_pack_path with some (suitably aligned) memory of the appropriate size to actually pack the path:

```
/*
fz_pack_path: Pack a path into the given block.
```

To minimise the size of paths, this function allows them to be packed into a buffer with other information.

pack: Pointer to a block of data to pack the path into. Should be aligned by the caller to the same alignment as required for an fz_path pointer.

max: The number of bytes available in the block.
If max < sizeof(fz_path) then an exception will
be thrown. If max >= the value returned by
fz_packed_path_size, then this call will never
fail, except in low memory situations with large
paths.

path: The path to pack.

Paths can be 'unpacked', 'flat', or 'open'. Standard paths, as created are 'unpacked'. Paths that will pack into less than max bytes will be packed as 'flat', unless they are too large (where large indicates that they exceed some private implementation defined limits, currently including having more than 256 256 coordinates or commands).

Large paths are 'open' packed as a header into the given block, plus pointers to other data blocks. Paths can be used interchangably regardless of how they are packed.

Returns the number of bytes within the block used. Callers can access the packed path data by casting the value of pack on

```
entry to be an fz_path *.

Throws exceptions on failure to allocate, or if
  max < sizeof(fz_path).

*/
int fz_pack_path(fz_context *ctx, uint8_t *pack, int max, const fz_path
  *path);</pre>
```

After a successful call to fz_pack_path, the pointer to the block of memory can be cast to an fz_path * and used as normal.

All the path routines recognise packed paths and will use them interchangeably. Packed paths may not be modified once created, however.

8.9.4 Transformation

Once a path has been constructed, a common operation is to apply a transformation to it. This is equivalent to transforming every point in the existing path. A path can be transformed using fz_transform_path.

```
/*
    fz_transform_path: Transform a path by a given
    matrix.

path: The path to modify (must not be a packed path).

transform: The transform to apply.

Throws exceptions if the path is packed, or on failure
    to allocate.

*/
void fz_transform_path(fz_context *ctx, fz_path *path, const fz_matrix
    *transform);
```

This counts as modifying a path of course, so ensure that you are the only reference holder, or fz_clone_path it first.

8.9.5 Bounding

Sometimes it can be desirable to know the area covered by a path. The fz_bound_path function enables exactly this, both for filled and stroked path. For details of the fz_stroke_state structure, see subsection 8.9.6 Stroking.

```
/*
fz_bound_path: Return a bounding rectangle for a path.
```

```
path: The path to bound.

stroke: If NULL, the bounding rectangle given is for
the filled path. If non-NULL the bounding rectangle
given is for the path stroked with the given attributes.

ctm: The matrix to apply to the path during stroking.

r: Pointer to a fz_rect which will be used to hold
the result.

*/
fz_rect *fz_bound_path(fz_context *ctx, const fz_path *path, const
fz_stroke_state *stroke, const fz_matrix *ctm, fz_rect *r);
```

8.9.6 Stroking

Where filling a path simply requires details of the fill to be used, stroking a path can radically alter its appearance. The details of the stroke attributes are passed in a fz_stroke_state structure.

Stroke states are created and managed with reference counting using the functions described below, but unlike other structures, the definition of the structure itself is public. Callers are expected to alter the different fields in the structure themselves. The sole exception to this is the refs field, that should only be altered using the usual fz_keep_stroke_state and fz_drop_stroke_state mechanisms.

```
typedef struct fz_stroke_state_s fz_stroke_state;
typedef enum fz_linecap_e
   FZ_LINECAP_BUTT = 0,
   FZ_LINECAP_ROUND = 1,
   FZ_LINECAP_SQUARE = 2,
   FZ_LINECAP_TRIANGLE = 3
} fz_linecap;
typedef enum fz_linejoin_e
   FZ_LINEJOIN_MITER = 0,
   FZ_LINEJOIN_ROUND = 1,
   FZ_LINEJOIN_BEVEL = 2,
   FZ_LINEJOIN_MITER_XPS = 3
} fz_linejoin;
struct fz_stroke_state_s
{
   int refs;
```

```
fz_linecap start_cap, dash_cap, end_cap;
fz_linejoin linejoin;
float linewidth;
float miterlimit;
float dash_phase;
int dash_len;
float dash_list[32];
};
```

It is hoped that the meaning of the individual fields within a fz_stroke_state structure are self evident to anyone working in this field. If you are unfamiliar with any of the concepts here, see "The PDF Reference Manual" or "The Postscript Language Reference Manual" for more details.

Most simply a reference to a stroke state structure can be obtained by calling fz new stroke state:

```
fz_new_stroke_state: Create a new (empty) stroke state
   structure (with no dash data) and return a reference to it.
   Throws exception on failure to allocate.
fz_stroke_state *fz_new_stroke_state(fz_context *ctx);
For stroke states that include dash information, call:
   fz_new_stroke_state_with_dash_len: Create a new (empty)
   stroke state structure, with room for dash data of the
   given length, and return a reference to it.
   len: The number of dash elements to allow room for.
   Throws exception on failure to allocate.
*/
fz_stroke_state *fz_new_stroke_state_with_dash_len(fz_context *ctx, int
    len);
Once obtained, references can be kept or dropped in the usual fashion:
   fz_keep_stroke_state: Take an additional reference to
   a stroke state structure.
   No modifications should be carried out on a stroke
   state to which more than one reference is held, as
   this can cause race conditions.
```

```
Never throws exceptions.
*/
fz_stroke_state *fz_keep_stroke_state(fz_context *ctx, const
    fz_stroke_state *stroke);

/*
    fz_drop_stroke_state: Drop a reference to a stroke
    state structure, destroying the structure if it is
    the last reference.

Never throws exceptions.
*/
void fz_drop_stroke_state(fz_context *ctx, const fz_stroke_state
    *stroke);
```

Once more than one reference is held to a stroke state, it should be considered 'frozen' or 'immutable' as other reference holders may be confused by changes to it. Accordingly, we provide functions to ensure that we are holding a reference to an 'unshared' stroke state:

```
fz_unshare_stroke_state: Given a reference to a
   (possibly) shared stroke_state structure, return
   a reference to an equivalent stroke_state structure
   that is guaranteed to be unshared (i.e. one that can
   safely be modified).
   shared: The reference to a (possibly) shared structure
   to unshare. Ownership of this reference is passed in
   to this function, even in the case of exceptions being
   thrown.
   Exceptions may be thrown in the event of failure to
   allocate if required.
*/
fz_stroke_state *fz_unshare_stroke_state(fz_context *ctx,
    fz_stroke_state *shared);
/*
   fz_unshare_stroke_state_with_dash_len: Given a reference to a
   (possibly) shared stroke_state structure, return a reference
   to a stroke_state structure (with room for a given amount of
   dash data) that is guaranteed to be unshared (i.e. one that
   can safely be modified).
   shared: The reference to a (possibly) shared structure
   to unshare. Ownership of this reference is passed in
```

to this function, even in the case of exceptions being

thrown.

```
Exceptions may be thrown in the event of failure to
    allocate if required.
*/
fz_stroke_state *fz_unshare_stroke_state_with_dash_len(fz_context *ctx,
        fz_stroke_state *shared, int len);

Finally, we have a simple function to clone a stroke state and return a new
reference to it:

/*
    fz_clone_stroke_state: Create an identical stroke_state
    structure and return a reference to it.

stroke: The stroke state reference to clone.

Exceptions may be thrown in the event of a failure to
    allocate.
*/
fz_stroke_state *fz_clone_stroke_state(fz_context *ctx, fz_stroke_state
    *stroke);
```

8.9.7 Walking

Given a path, it can be useful to be able to read it out again. MuPDF uses this internally in a output devices such as the PDF or SVG devices (see subsection 7.5.4 PDF Output Device or subsection 7.5.6 SVG Output Device) to convert paths to a new representation, and in the draw device (see subsection 7.5.2 Draw Device) for rendering.

To isolate callers from the implementation specifics of paths, MuPDF offers a mechanism to 'walk' an fz_path, getting a callback for each command in the path.

```
void (*curvetoy)(fz_context *ctx, void *arg, float x1, float y1,
        float x3, float y3);
   void (*rectto)(fz_context *ctx, void *arg, float x1, float y1, float
       x2, float y2);
} fz_path_walker;
   fz_walk_path: Walk the segments of a path, calling the
   appropriate callback function from a given set for each
   segment of the path.
   path: The path to walk.
   walker: The set of callback functions to use. The first
   4 callback pointers in the set must be non-NULL. The
   subsequent ones can either be supplied, or can be left
   as NULL, in which case the top 4 functions will be
   called as appropriate to simulate them.
   arg: An opaque argument passed in to each callback.
   Exceptions will only be thrown if the underlying callback
   functions throw them.
void fz_walk_path(fz_context *ctx, const fz_path *path, const
    fz_path_walker *walker, void *arg);
```

This function is called by giving a pointer to a structure containing callback functions, one for each type of path segment type. The function will walk the path structure and call a for each 'segment' of the path in turn.

Callers of this function should not rely on getting exactly the same sequence of path segments out as was used to construct the path; the internal representation may have been optimised to an equivalent form on construction, and this will be reflected in the callbacks received. The path passed back will however be entirely identical (modulo possible infinitesimal rounding issues).

For example, MuPDF is capable of spotting that a cubic or quadratic bezier is actually a line; in such cases it may represent it as a line internally, saving memory and processing power.

Not all path consumers can cope with the full range of segment types that MuPDF natively supports, so some of the callback entries may be left blank (i.e. set to NULL). Rather than calling such an entry, MuPDF will decompose the path segment into one of the more basic types.

For example, if a path contains a quadratic segment and the quadto callback entry is NULL, MuPDF will automatically decompose it to a bezier segment and call the curveto entry instead.

8.10 Text

8.10.1 Overview

MuPDFs central text type is an fz_text structure. The exact definition of this structure has evolved considerably in the past to accommodate the needs of different input formats, and it is possible this will continue in future. Accordingly we have hidden the implementation behind an interface.

Nonetheless, it is worthwhile mentioning some of the design goals that have influenced the development of this area of the code.

As fz_text objects are the only text objects passed across the device interface, they need to encode several layers of information. For simple rendering devices, they need to be expressive enough to allow us to exactly render the exact specified glyphs. For text output devices, they need to be expressive enough to allow the unicode values to be extracted.

Ideally, given any input format we would like to be able to output any output format from it (including the same format) with no loss of data. This means that our fz_text objects need to be expressive enough to represent the super-set of functionality of all input formats out there, even if we do not currently make use of all the information.

Some input formats only specify glyph ids, whereas some only specify unicode values. In order to allow us to transmute one format into another, we require fz_text objects to encapsulate both forms of data at the same time.

Some formats, that make use of glyph shaping, require us to cope with unicode and glyph id equivalents that have no direct 1-1 correspondence.

For bidirectional text, the order in which text may be displayed on the page may not be trivially related to the order in which it is specified in the source file. We both need to render efficiently, and to maintain the ability to recreate the initial logical order of the text.

Accordingly, our fz_text object represents a block of text in logical order, including font style and position, together with both unicode and glyph data (subject to the availability of the information in the original file).

If more information is required, then details of the current implementation are included in subsection 8.10.7 Implementation, otherwise just use it as a simple black box.

```
typedef struct fz_text_s fz_text;
```

Text objects are reference, with the implicit understanding that once more than one reference exists to an object, it will no longer be modified.

8.10.2 Creation

```
Empty fz_text objects can be created using the fz_new_text call:
/*
   fz_new_text: Create a new empty fz_text object.
   Throws exception on failure to allocate.
*/
fz_text *fz_new_text(fz_context *ctx);
Additional references can be taken/released in the usual manner:
   fz_keep_text: Add a reference to an fz_text.
   text: text object to keep a reference to.
   Return the same text pointer.
*/
fz_text *fz_keep_text(fz_context *ctx, const fz_text *text);
   fz_drop_text: Drop a reference to the object, freeing
   if if is the last one.
   text: Object to drop the reference to.
void fz_drop_text(fz_context *ctx, const fz_text *text);
```

8.10.3 Population

Once created, characters can be added to the fz_text object either singly:

```
*
fz_show_glyph: Add a glyph/unicode value to a text object.

text: Text object to add to.

font: The font the glyph should be added in.

trm: The transform to use for the glyph.

glyph: The glyph id to add.

unicode: The unicode character for the glyph.

wmode: 1 for vertical mode, 0 for horizontal.
```

```
bidi_level: The bidirectional level for this glyph.
   markup_dir: The direction of the text as specified in the
   markup.
   language: The language in use (if known, 0 otherwise)
   (e.g. FZ_LANG_zh_Hans).
   Throws exception on failure to allocate.
*/
void fz_show_glyph(fz_context *ctx, fz_text *text, fz_font *font, const
    fz_matrix *trm, int glyph, int unicode, int wmode, int bidi_level,
    fz_bidi_direction markup_dir, fz_text_language language);
or a (unicode) string at a time:
   fz_show_string: Add a UTF8 string to a text object.
   text: Text object to add to.
   font: The font the string should be added in.
   trm: The transform to use. Will be updated according
   to the advance of the string on exit.
   s: The utf-8 string to add.
   wmode: 1 for vertical mode, 0 for horizontal.
   bidi_level: The bidirectional level for this glyph.
   {\tt markup\_dir}\colon {\tt The\ direction\ of\ the\ text\ as\ specified\ in\ the}
   markup.
   language: The language in use (if known, 0 otherwise)
   (e.g. FZ_LANG_zh_Hans).
   Throws exception on failure to allocate.
*/
void fz_show_string(fz_context *ctx, fz_text *text, fz_font *font,
    fz_matrix *trm, const char *s, int wmode, int bidi_level,
    fz_bidi_direction markup_dir, fz_text_language language);
```

8.10.4 Measurement

Once a fz_text object has been created we can measure the area it will cover on the page:

```
/*
    fz_bound_text: Find the bounds of a given text object.

text: The text object to find the bounds of.

stroke: Pointer to the stroke attributes (for stroked text), or NULL (for filled text).

ctm: The matrix in use.

r: pointer to storage for the bounds.

Returns a pointer to r, which is updated to contain the bounding box for the text object.

*/
fz_rect *fz_bound_text(fz_context *ctx, const fz_text *text, const fz_stroke_state *stroke, const fz_matrix *ctm, fz_rect *r);
```

8.10.5 Cloning

As stated before, fz_text objects are referenced counted. Changes or manipulations cannot safely be carried out on an object which might be shared with someone else, so we provide a mechanism to clone an object. Once cloned an object is guaranteed to be safe to modify.

```
/*
    fz_clone_text: Clone a text object.

text: The text object to clone.

Throws an exception on allocation failure.
*/
fz_text *fz_clone_text(fz_context *ctx, const fz_text *text);
```

8.10.6 Language

Some formats include a declaration of which language is being used for a given piece of text. This can be used to influence aspects of the text layout, including the exact choice of glyphs used in a given font. While we make relatively

little use of this at present, we try to preserve the information as part of our philosophy of not losing any information unnecessarily.

Accordingly, we use ISO 639 language specification strings, for example:

```
typedef enum fz_text_language_e
{
   FZ_LANG_UNSET = 0,
   FZ_LANG_ur = FZ_LANG_TAG2('u','r'),
   FZ_LANG_urd = FZ_LANG_TAG3('u','r','d'),
   FZ_LANG_ko = FZ_LANG_TAG2('k','o'),
   FZ_LANG_ja = FZ_LANG_TAG2('j','a'),
   FZ_LANG_zh = FZ_LANG_TAG2('z','h'),
   FZ_LANG_zh_Hans = FZ_LANG_TAG3('z','h','s'),
   FZ_LANG_zh_Hant = FZ_LANG_TAG3('z','h','t'),
} fz_text_language;
```

To save space we pack these into 15 bits. Accordingly, we provide a way to pack/unpack these to/from the more normal string representations:

```
/*
    Convert ISO 639 (639-{1,2,3,5}) language specification
    strings losslessly to a 15 bit fz_text_language code.

    No validation is carried out. Obviously invalid (out
    of spec) codes will be mapped to FZ_LANG_UNSET, but
    well-formed (but undefined) codes will be blithely
    accepted.

*/
fz_text_language fz_text_language_from_string(const char *str);

/*
    Recover ISO 639 (639-{1,2,3,5}) language specification
    strings losslessly from a 15 bit fz_text_language code.

    No validation is carried out. See note above.

*/
char *fz_string_from_text_language(char str[8], fz_text_language lang);
```

8.10.7 Implementation

A fz_text structure represents a block of text. At the lowest level the constituents of a block are fz_text_items.

```
typedef struct fz_text_item_s fz_text_item;
struct fz_text_item_s
```

```
float x, y;
  int gid; /* -1 for one gid to many ucs mappings */
  int ucs; /* -1 for one ucs to many gid mappings */
};
```

The items can be thought of as the individual 'characters' that make up the display, together with their position. Where possible, we attempt to give both the glyph id (gid) and the unicode value (ucs) for the character, but there are various cases where a 1-1 mapping is not possible.

Some unicode characters can result in a string of glyphs. The glyph ids will be sent in a series of fz_text_items, in which the first ucs value will be the source unicode character, and subsequent ones will be -1.

Some sequences of unicode characters can result in a single glyph. Again, a sequence of fz_text_items will be sent listing the unicode values, but all but the first item will have the gid value set to -1.

In more complex cases, sequences of unicode characters can be transformed into a sequence of glyphs, with no direct correspondence between the source text and the output characters. In this case as many fz_text_items as are required are used, with either the gid or ucs values padded out by -1s as necessary.

Different input formats offer the text in different forms. With PDF, the data within the file is (typically) in the form of glyph ids, and mechanisms are optionally provided to infer unicode values from them. Glyphs are sent in any order, and absolutely positioned on the page.

With XPS the input can be either in the form of unicode or glyph ids, and directionality information is encoded in the file. This means that the logical ordering of the glyphs is well defined.

Some formats, such as EPub and HTML, send unicode text with even less positioning information, and rely on the interpreter to perform layout. Part of this process involves inferring directional information from the source text, and then using shaping mechanisms embedded within the font to do complex conversions to give the final positioned glyph sequences.

In all such cases MuPDF will preserve the logical ordering of the unicode entries, at the cost of drawing glyphs non-monotonically onto the page.

Sequences of fz_text_items that share the same characteristics are gathered together into fz_text_spans:

```
struct fz_text_span_s
{
   fz_font *font;
   fz_matrix trm;
   unsigned wmode : 1;  /* 0 horizontal, 1 vertical */
```

8.11 Shadings

8.11.1 Overview

One of the most powerful graphical effects within PDF and other input formats is that of Shadings. Our central type representing shadings, fz_shade is all that we have to pass details of shadings across the fz_device interface.

Consequently, we need fz_shade to be expressive enough to cope with shadings from all possible sources, and yet we would like to avoid having to reproduce the shade handling code in all devices.

Accordingly, fz_shade is defined to be expressive enough to encapsulate all the different shading representations found in PDF with the data essentially unchanged. PDF is currently the super-set of shadings found in other formats. If this changes, fz_shade will be extended as required.

```
int use_function;
   float function[256][FZ_MAX_COLORS + 1];
   int type; /* function, linear, radial, mesh */
   {\tt union}
   {
       struct
       {
           int extend[2];
           float coords[2][3]; /* (x,y,r) twice */
       } l_or_r;
       struct
           int vprow;
           int bpflag;
           int bpcoord;
           int bpcomp;
           float x0, x1;
           float y0, y1;
           float c0[FZ_MAX_COLORS];
           float c1[FZ_MAX_COLORS];
       } m;
       struct[]
       {
           fz_matrix matrix;
           int xdivs;
           int ydivs;
           float domain[2][2];
           float *fn_vals;
       } f;
   } u;
   fz_compressed_buffer *buffer;
} fz_shade;
```

8.11.2 Creation

Currently, there is no defined API for creating a shading due to the public nature of the structure. Just call fz_malloc_struct(ctx, fz_shade) and initialise the fields accordingly.

We may look to add convenience functions in the future, as this is likely to be desirable for the JNI (and other) bindings.

Shading objects are reference counted, with the implicit understanding that once more than one reference exists to a fz_shade, it will no longer be modified.

Additional references can be taken and dropped as usual:

```
/*
    fz_keep_shade: Add a reference to an fz_shade.
    shade: The reference to keep.
    Returns shade.
*/
fz_shade *fz_keep_shade(fz_context *ctx, fz_shade *shade);
/*
    fz_drop_shade: Drop a reference to an fz_shade.
    shade: The reference to drop. If this is the last reference, shade will be destroyed.
*/
void fz_drop_shade(fz_context *ctx, fz_shade *shade);
```

We also provide a function to process a given shading, by calling

8.11.3 Bounding

Once created, we can ask for the bounds of a given shade under a given transformation. This can sometimes be infinite.

```
/*
    fz_bound_shade: Bound a given shading.
    shade: The shade to bound.

    ctm: The transform to apply to the shade before bounding.
    r: Pointer to storage to put the bounds in.

Returns r, updated to contain the bounds for the shading.
*/
fz_rect *fz_bound_shade(fz_context *ctx, fz_shade *shade, const fz_matrix *ctm, fz_rect *r);
```

8.11.4 Painting

For devices that require shadings as rasterised objects, we provide a function to paint a shading to an ${\tt fz_pixmap}$:

/*

```
fz_paint_shade: Render a shade to a given pixmap.
shade: The shade to paint.

ctm: The transform to apply.

dest: The pixmap to render into.

bbox: Pointer to a bounding box to limit the rendering of the shade.

*/
void fz_paint_shade(fz_context *ctx, fz_shade *shade, const fz_matrix *ctm, fz_pixmap *dest, const fz_irect *bbox);
```

This is currently used by the draw and SVG devices.

8.11.5 Decomposition

For devices that wish to get access to a higher level representation of a shading, but do not wish to access the internals of a shading directly, we provide a function to decompose a shading to a mesh.

This is called with functions to 'prepare' and 'fill' vertices respectively. The mesh is decomposed to triangles internally, each vertex is 'prepared' and each triangle 'filled' in turn.

The ordering of these calls is not guaranteed, other than the fact that a vertex will always be prepared before it is used as part of a triangle to be filled.

```
typedef struct fz_vertex_s fz_vertex;

struct fz_vertex_s
{
    fz_point p;
    float c[FZ_MAX_COLORS];
};

/*
    fz_shade_prepare_fn: Callback function type for use with fz_process_shade.
    arg: Opaque pointer from fz_process_shade caller.
    v: Pointer to a fz_vertex structure to populate.
    c: Pointer to an array of floats to use to populate v.
*/
```

```
typedef void (fz_shade_prepare_fn)(fz_context *ctx, void *arg, fz_vertex
    *v, const float *c);
   fz_shade_process_fn: Callback function type for use with
   fz_process_shade.
   arg: Opaque pointer from fz_process_shade caller.
   av, bv, cv: Pointers to a fz_vertex structure describing
   the corner locations and colors of a triangle to be
   filled.
*/
typedef void (fz_shade_process_fn)(fz_context *ctx, void *arg, fz_vertex
    *av, fz_vertex *bv, fz_vertex *cv);
   fz_process_shade: Process a shade, using supplied callback
   functions. This decomposes the shading to a mesh (even ones
   that are not natively meshes, such as linear or radial
   shadings), and processes triangles from those meshes.
   shade: The shade to process.
   ctm: The transform to use
   prepare: Callback function to 'prepare' each vertex.
   This function is passed an array of floats, and populates
   an fz_vertex structure.
   process: This function is passed 3 pointers to vertex
   structures, and actually performs the processing (typically
   filling the area between the vertexes).
   process_arg: An opaque argument passed through from caller
   to callback functions.
void fz_process_shade(fz_context *ctx, fz_shade *shade, const fz_matrix
    *ctm,
          fz_shade_prepare_fn *prepare, fz_shade_process_fn *process,
               void *process_arg);
```

This function is used internally as part of fz_paint_shade, but is intended to also allow extraction of arbitrary shading data.

Chapter 9

Display Lists

9.0.1 Overview

While MuPDF is engineered to be as fast as possible at interpreting page contents, there is inevitably some overhead in converting from the documents native format to the stream of graphical operations (calls over the fz_device interface).

If you are planning to redraw the same page several times (perhaps because you are panning and zooming around a page in a viewer), then it can be advantageous to use a display List.

A display list is simply a way of packaging up a stream of graphical operations so that they can be efficiently played back, possibly with different transforms or clip rectangles.

Display lists are optimised to use as little memory as possible, but clearly are (typically) a greater user of memory than just reinterpreting the file. The big advantage of display lists, other than their speed, is that they can safely be played back without touching the underlying file. This means they can be used in other threads without having to worry about contention.

Display lists are implemented within using MuPDF using the fz_display_list type.

9.0.2 Creation

An empty display list can be created by the fz_new_display_list call.

```
/*
fz_new_display_list: Create an empty display list.
A display list contains drawing commands (text, images, etc.).
```

Once created it can be populated by creating a display list device instance that writes to it.

```
/*
    fz_new_list_device: Create a rendering device for a display list.
    When the device is rendering a page it will populate the
    display list with drawing commands (text, images, etc.). The
    display list can later be reused to render a page many times
    without having to re-interpret the page from the document file
    for each rendering. Once the device is no longer needed, free
    it with fz_drop_device.
    list: A display list that the list device takes ownership of.
*/
fz_device *fz_new_list_device(fz_context *ctx, fz_display_list *list);
```

Once you have created such a display list device, any calls made to that device (such as by calling fz_run_page or similar) will be recorded into the display list.

When you have finished writing to the display list (remembering to call fz_close_device), you dispose of the device as normal (by calling fz_drop_device). This leaves you holding the sole reference to the display list itself.

Writing to a display list is not thread safe. That is to say, do not attempt to write to a display list from more than one thread at a time. Similarly, do not attempt to read from display lists while write operations are ongoing.

9.0.3 Playback

To playback from a list, just call fz_run_display_list.

```
/*
   fz_run_display_list: (Re)-run a display list through a device.
list: A display list, created by fz_new_display_list and
populated with objects from a page by running fz_run_page on a
device obtained from fz_new_list_device.
```

```
dev: Device obtained from fz_new_*_device.
   ctm: Transform to apply to display list contents. May include
   for example scaling and rotation, see fz_scale, fz_rotate and
   fz_concat. Set to fz_identity if no transformation is desired.
   area: Only the part of the contents of the display list
   visible within this area will be considered when the list is
   run through the device. This does not imply for tile objects
   contained in the display list.
   cookie: Communication mechanism between caller and library
   running the page. Intended for multi-threaded applications,
   while single-threaded applications set cookie to NULL. The
   caller may abort an ongoing page run. Cookie also communicates
   progress information back to the caller. The fields inside
   cookie are continually updated while the page is being run.
void fz_run_display_list(fz_context *ctx, fz_display_list *list,
    fz_device *dev, const fz_matrix *ctm, const fz_rect *area,
    fz_cookie *cookie);
```

9.0.4 Reference counting

In common with most other objects in MuPDF, fz_display_lists are reference counted. This means that once you have finished with a reference to a display list, it can safely be disposed of by calling fz_drop_display_list.

```
/*
    fz_drop_display_list: Drop a reference to a display list, freeing it
    if the reference count reaches zero.

Does not throw exceptions.
*/
void fz_drop_display_list(fz_context *ctx, fz_display_list *list);

Should you wish to keep a new reference to a display list, you can generate one
using fz_keep_display_list.

/*
    fz_keep_display_list: Keep a reference to a display list.

Does not throw exceptions.
*/
fz_display_list *fz_keep_display_list(fz_context *ctx, fz_display_list
    *list);
```

In general, it is rare for you to want to make a new reference to a display list until write operations on one have finished. It is good form to avoid this.

9.0.5 Miscellaneous operations

There are a few other operations that can be performed efficiently on a display list. Firstly, one can request the bounds of a list.

```
/*
    fz_bound_display_list: Return the bounding box of the page recorded
    in a display list.
*/
fz_rect *fz_bound_display_list(fz_context *ctx, fz_display_list *list,
    fz_rect *bounds);
```

Secondly, one can create a new fz_image from a display list. This is useful for creating scalable content to embed in other document types; for instance MuPDF makes use of this to turn SVG files embedded within epub files (for illustrations and cover pages etc) into convenient objects for adding into the flow of text.

```
/*
    Create a new image from a display list.
    w, h: The conceptual width/height of the image.
    transform: The matrix that needs to be applied to the given list to make it render to the unit square.
    list: The display list.
*/
fz_image *fz_new_image_from_display_list(fz_context *ctx, float w, float h, fz_display_list *list);

Finally, it is possible to very quickly check if a given display list is empty or not.
/*
    Check for a display list being empty
    list: The list to check.
    Returns true if empty, false otherwise.
*/
int fz_display_list_is_empty(fz_context *ctx, const fz_display_list *list);
```

Chapter 10

The Stream interface

10.1 Overview

MuPDF is designed to run in a variety of different environments. As such, this means input can come from many different sources. On desktop computers input may come as files on backing store. For web served files, input may be streamed over a network. For systems with DRM embedded, the data may need to be decoded on the fly.

Similarly, data can be encapsulated within different formats in different ways, with multiple layers of encoding.

Accordingly, MuPDF abstracts the idea of an 'input stream' to a reusable class, fz_stream. Many implementations of fz_streams are given by default in the core library, but the abstract nature of this class allows callers to provide implementations of their own to seamlessly extend the systems capabilities as required.

10.2 Creation

The exact mechanism for creating a stream depends upon the source for that particular stream, but typically it will involve a call to a creation function, such as fz_open_file.

```
fz_open_file: Open the named file and wrap it in a stream.

filename: Path to a file. On non-Windows machines the filename should be exactly as it would be passed to fopen(2). On Windows machines, the path should be UTF-8 encoded so that non-ASCII characters can be
```

```
represented. Other platforms do the encoding as standard anyway (and
   in most cases, particularly for MacOS and Linux, the encoding they
   use is UTF-8 anyway).
fz_stream *fz_open_file(fz_context *ctx, const char *filename);
Alternative functions exist to allow creating streams from C level FILE pointers:
   fz_open_file: Wrap an open file descriptor in a stream.
   file: An open file descriptor supporting bidirectional
   seeking. The stream will take ownership of the file
   descriptor, so it may not be modified or closed after the call
   to fz_open_file_ptr. When the stream is closed it will also close
   the file descriptor.
fz_stream *fz_open_file_ptr(fz_context *ctx, FILE *file);
from direct memory blocks:
   fz_open_memory: Open a block of memory as a stream.
   data: Pointer to start of data block. Ownership of the data block is
   NOT passed in.
   len: Number of bytes in data block.
   Returns pointer to newly created stream. May throw exceptions on
   failure to allocate.
fz_stream *fz_open_memory(fz_context *ctx, unsigned char *data, size_t
    len);
and from fz_buffers:
   fz_open_buffer: Open a buffer as a stream.
   buf: The buffer to open. Ownership of the buffer is NOT passed in
   (this function takes its own reference).
   Returns pointer to newly created stream. May throw exceptions on
   failure to allocate.
*/
fz_stream *fz_open_buffer(fz_context *ctx, fz_buffer *buf);
```

There are too many other options for creating streams to list them all here, but

their use should be self evident from the header file definitions. Once created, all streams can be used in the same ways.

10.3 Usage

10.3.1 Reading bytes

The simplest way to read bytes from a stream is to call fz_read_byte to read the next byte from a file. Akin to the standard fgetc, this returns -1 for end of data, or the next byte available.

```
/*
    fz_read_byte: Read the next byte from a stream.
    stm: The stream t read from.
    Returns -1 for end of stream, or the next byte. May throw exceptions.
*/
int fz_read_byte(fz_context *ctx, fz_stream *stm);
```

To read more than 1 byte at a time, there are two different options.

Firstly, and most efficiently, bytes can be read directly from the streams underlying buffer. For a given fz_stream *stm, the current position in the stream is pointed to by stm->rp. Bytes can simply be read out, and the pointer incremented by the number read.

To do this, you must first know how many bytes there are available to be read out. This is achieved by calling fz_available. If there are no bytes already decoded and awaiting reading, this call will trigger a refill of the underlying buffer, which may take noticeable time.

```
fz_available: Ask how many bytes are available immediately from
a given stream.

stm: The stream to read from.

max: A hint for the underlying stream; the maximum number of
bytes that we are sure we will want to read. If you do not know
this number, give 1.
```

Returns the number of bytes immediately available between the read and write pointers. This number is guaranteed only to be 0 if we have hit EOF. The number of bytes returned here need have no relation to max (could be larger, could be smaller).

```
*/
size_t fz_available(fz_context *ctx, fz_stream *stm, size_t max);
```

To avoid needless work, a 'max' value can be supplied as a hint, telling any buffer refill operation that is triggered how many bytes are actually required. Specifying a max value does **not** guarantee you anything about the number of bytes actually made available.

Some callers may find this awkward - the need to potentially repeatedly call until you get enough bytes to fill a buffer of the required length may be tedious. Therefore as an alternative, we provide a simpler call, fz_read.

Designed to be similar to the standard fread call, this attempts to read as many bytes as possible into a supplied data block, returning the actual number of bytes successfully read.

```
/*
    fz_read: Read from a stream into a given data block.

stm: The stream to read from.

data: The data block to read into.

len: The length of the data block (in bytes).

Returns the number of bytes read. May throw exceptions.
*/
size_t fz_read(fz_context *ctx, fz_stream *stm, unsigned char *data, size_t len);
```

Typically the only reason that fz_read will not return the requested number of bytes is if we hit the end of the stream. This implies that calls to fz_read will block until such data is ready. For streams based on 'fast' sources like files or memory, this is an unimportant distinction.

For streams based on (say) an http download, this might result in significant delays, and an unacceptable user experience. To alleviate this problem we have a mechanism whereby such streams can signal a temporary end of data by throwing the FZ_ERROR_TRYLATER error. See chapter 16 Progressive Mode for more details.

To facilitate reading without blocking (or using buffers larger than required), fz_available can be called to find out the number of bytes that can safely be requested.

If data within a stream is not required, it can be skipped over using fz_skip:

```
/*
   fz_skip: Read from a stream discarding data.
```

```
stm: The stream to read from.
len: The number of bytes to read.

Returns the number of bytes read. May throw exceptions.
*/
size_t fz_skip(fz_context *ctx, fz_stream *stm, size_t len);

As a special case, after a single byte is read, it can be pushed back into the stream, using fz_unread_byte:

/*
    fz_unread_byte: Unread the single last byte successfully read from a stream. Do not call this without having successfully read a byte.
*/
void fz_unread_byte(fz_context *ctx FZ_UNUSED, fz_stream *stm);

The act of reading a byte, and then, if successful pushing it back again is encapsulated in a convenience function, fz_peek_byte:
```

fz_peek_byte: Peek at the next byte in a stream. stm: The stream to peek at. Returns -1 for EOF, or the next byte that will be read. */ int fz_peek_byte(fz_context *ctx, fz_stream *stm);

10.3.2 Reading objects

Often, when parsing different document formats, it can be useful to read specific objects from streams, so convenience functions exist for this too. Firstly, integers of different size and endianness are catered for:

```
/*
    fz_read_[u]int(16|24|32|64)(_1e)?

Read a 16/32/64 bit signed/unsigned integer from stream,
in big or little-endian byte orders.

Throws an exception if EOF is encountered.
*/
uint16_t fz_read_uint16(fz_context *ctx, fz_stream *stm);
uint32_t fz_read_uint24(fz_context *ctx, fz_stream *stm);
uint32_t fz_read_uint32(fz_context *ctx, fz_stream *stm);
```

```
uint64_t fz_read_uint64(fz_context *ctx, fz_stream *stm);
uint16_t fz_read_uint16_le(fz_context *ctx, fz_stream *stm);
uint32_t fz_read_uint24_le(fz_context *ctx, fz_stream *stm);
uint32_t fz_read_uint32_le(fz_context *ctx, fz_stream *stm);
uint64_t fz_read_uint64_le(fz_context *ctx, fz_stream *stm);
int16_t fz_read_int16(fz_context *ctx, fz_stream *stm);
int32_t fz_read_int32(fz_context *ctx, fz_stream *stm);
int64_t fz_read_int64(fz_context *ctx, fz_stream *stm);
int16_t fz_read_int16_le(fz_context *ctx, fz_stream *stm);
int32_t fz_read_int32_le(fz_context *ctx, fz_stream *stm);
int64_t fz_read_int64_le(fz_context *ctx, fz_stream *stm);
We have functions to read both C style strings, and newline/return terminated
lines:
   fz_read_string: Read a null terminated string from the stream into
   a buffer of a given length. The buffer will be null terminated.
   Throws on failure (including the failure to fit the entire string
   including the terminator into the buffer).
void fz_read_string(fz_context *ctx, fz_stream *stm, char *buffer, int
/*
   fz_read_line: Read a line from stream into the buffer until either a
   terminating newline or EOF, which it replaces with a null byte
        ('\0').
   Returns buf on success, and NULL when end of file occurs while no
       characters
   have been read.
*/
char *fz_read_line(fz_context *ctx, fz_stream *stm, char *buf, size_t
    max);
```

10.3.3 Reading bits

Streams (or sections of streams) can be treated as a string of bits, packed either most significant or least significant bits first.

To read from an msb packed stream, use fz_read_bits:

```
/*
fz_read_bits: Read the next n bits from a stream (assumed to
```

```
be packed most significant bit first).
   stm: The stream to read from.
   n: The number of bits to read, between 1 and 8*sizeof(int)
   inclusive.
   Returns (unsigned int)-1 for EOF, or the required number of bits.
*/
unsigned int fz_read_bits(fz_context *ctx, fz_stream *stm, int n);
Conversely, to read from a lsb packed stream, use fz_read_rbits:
   fz_read_rbits: Read the next n bits from a stream (assumed to
   be packed least significant bit first).
   stm: The stream to read from.
   n: The number of bits to read, between 1 and 8*sizeof(int)
   inclusive.
   Returns (unsigned int)-1 for EOF, or the required number of bits.
*/
unsigned int fz_read_rbits(fz_context *ctx, fz_stream *stm, int n);
```

Whichever of these is used, reading n bits will return the results in the lowest n bits of the returned value.

After reading bits using these functions, if a return to reading bytewise (or objectwise) is required, then fz_sync_bits must be called.

```
/*
    fz_sync_bits: Called after reading bits to tell the stream
    that we are about to return to reading bytewise. Resyncs
    the stream to whole byte boundaries.
*/
void fz_sync_bits(fz_context *ctx FZ_UNUSED, fz_stream *stm);
```

10.3.4 Reading whole streams

As a convenience function, MuPDF provides a mechanism for reading the entire contents of a stream into an fz_buffer.

```
/*
fz_read_all: Read all of a stream into a buffer.
```

```
stm: The stream to read from
initial: Suggested initial size for the buffer.

Returns a buffer created from reading from the stream. May throw exceptions on failure to allocate.
*/
fz_buffer *fz_read_all(fz_context *ctx, fz_stream *stm, size_t initial);
```

This will throw an error (and hence not return any data) if an error is encountered during the decode of the stream. Sometimes it can be preferable to 'do the best we can' and tolerate problematic data. For such cases, we provide fz_read_best:

```
fz_read_best: Attempt to read a stream into a buffer. If truncated
   is NULL behaves as fz_read_all, otherwise does not throw exceptions
   in the case of failure, but instead sets a truncated flag.
   stm: The stream to read from.
   initial: Suggested initial size for the buffer.
   truncated: Flag to store success/failure indication in.
   Returns a buffer created from reading from the stream.
*/
fz_buffer *fz_read_best(fz_context *ctx, fz_stream *stm, size_t initial,
   int *truncated);
```

10.3.5 Seeking

Most stream operations simply advance the stream pointer as the stream is read. The current stream position can always be obtained using fz_tell (deliberately similar to the standard ftell call):

```
/*
    fz_tell: return the current reading position within a stream
*/
fz_off_t fz_tell(fz_context *ctx, fz_stream *stm);
```

Some streams allow you to seek within them, that is, to change the current stream pointer to a given offset. To do this, use fz_seek (deliberately similar to fseek):

/*

```
fz_seek: Seek within a stream.

stm: The stream to seek within.

offset: The offset to seek to.

whence: From where the offset is measured (see fseek).

*/

void fz_seek(fz_context *ctx, fz_stream *stm, fz_off_t offset, int whence);
```

In the event that a stream does not support seeking, an error will be thrown.

10.3.6 Meta data

Occasionally, it can be useful to interrogate the properties of a stream, for example the length of the stream, or whether it is coming from a progressive source (see chapter 16 Progressive Mode).

While not implemented currently, perhaps in future a particular stream user might want to interrogate information about the Mimetype of the stream, or its compression ratios.

To allow this, we have an extensible system to request Meta operations on a stream. The fz_stream_meta function allows such calls to be made, with a reason code to identify the required operation, and pointer and size parameters to identify data to be passed:

```
fz_stream_meta: Perform a meta call on a stream (typically to
    request meta information about a stream).

stm: The stream to query.

key: The meta request identifier.

size: Meta request specific parameter - typically the size of
    the data block pointed to by ptr.

ptr: Meta request specific parameter - typically a pointer to
    a block of data to be filled in.

Returns -1 if this stream does not support this meta operation,
    or a meta operation specific return value.

*/
int fz_stream_meta(fz_context *ctx, fz_stream *stm, int key, int size,
    void *ptr);
```

10.3.7 Destruction

In common with most other MuPDF objects, fz_streams are reference counted.

As such additional references can be taken using fz_keep_stream and they can be destroyed using fz_drop_stream.

Note that care must be taken not to use fz_stream objects simultaneously in more than one thread. Not only does the act of reading in one thread upset the point at which the next read will happen in another thread, no protection is provided to make operations atomic - thus the internal data can become corrupted and cause crashes.

10.4 Implementing an fz_stream

The above, relatively rich, set of functions are implemented on a fairly simple basic structure.

To implement your own fz_stream, simply define a creation function, of the form:

```
fz_stream *fz_new_stream_foo(fz_context *ctx, <more parameters here>)
{
    fz_stream *stm;
    foo_state *state;

    state = <create structure to hold foo specific stream state>
        stm = fz_new_stream(ctx, state, foo_next, foo_close);
        <set stm->seek if required>
        <set stm->meta if required>
        return stm;
}
```

Note that some fz_try/fz_catch-ery may be required as part of the setup for state.

The hard work for this function is done using fz_new_stream, and two 'foo' specific functions, foo_next and foo_close. First let's look at fz_new_stream:

```
fz_new_stream: Create a new stream object with the given
internal state and function pointers.

state: Internal state (opaque to everything but implementation).

next: Should provide the next set of bytes (up to max) of stream
data. Return the number of bytes read, or EOF when there is no
more data.
```

```
close: Should clean up and free the internal state. May not
    throw exceptions.
*/
fz_stream *fz_new_stream(fz_context *ctx, void *state, fz_stream_next_fn
    *next, fz_stream_close_fn *close);
```

This creates the main fz_stream structure, populates it with the given pointers (state, foo_next and foo_close) and sets the internal buffer pointers up to indicate an empty buffer.

As soon as anyone tries to read from the buffer (or to find out how many bytes are available), the MuPDF stream functions will cause foo_next to be called. This is a function of the following type:

```
/*
    fz_stream_next_fn: A function type for use when implementing
    fz_streams. The supplied function of this type is called
    whenever data is required, and the current buffer is empty.

stm: The stream to operate on.

max: a hint as to the maximum number of bytes that the caller
    needs to be ready immediately. Can safely be ignored.

Returns -1 if there is no more data in the stream. Otherwise,
    the function should find its internal state using stm->state,
    refill its buffer, update stm->rp and stm->wp to point to the
    start and end of the new data respectively, and then
    "return *stm->rp++".

*/

typedef int (fz_stream_next_fn)(fz_context *ctx, fz_stream *stm, size_t
    max);
```

When the stream is closed, the foo_close function will be called. This should be a function of type fz_stream_close_fn:

```
fz_stream_close_fn: A function type for use when implementing
fz_streams. The supplied function of this type is called
when the stream is closed, to release the stream specific
state information.
state: The stream state to release.
*/
```

In our example, if the state was created by a simple fz_malloc_struct(ctx, foo_state) then foo_close might be as simple as an fz_free(ctx, state). If the internal state of the stream is more complex then the destructor will be

similarly more complex.

These three functions (creation, next and close) are all that is required to define a stream

Optionally, you can also define a seek and/or a meta function, using functions of the following types:

```
/*
    fz_stream_seek_fn: A function type for use when implementing
    fz_streams. The supplied function of this type is called when
    fz_seek is requested, and the arguments are as defined for
    fz_seek.

The stream can find its private state in stm->state.

*/
typedef void (fz_stream_seek_fn)(fz_context *ctx, fz_stream *stm,
    fz_off_t offset, int whence);

/*
    fz_stream_meta_fn: A function type for use when implementing
    fz_streams. The supplied function of this type is called when
    fz_meta is requested, and the arguments are as defined for
    fz_meta.

The stream can find its private state in stm->state.

*/
typedef int (fz_stream_meta_fn)(fz_context *ctx, fz_stream *stm, int
    key, int size, void *ptr);
```

Chapter 11

The Output interface

11.1 Overview

In the same way as fz_streams abstracts input streams, MuPDF uses a reusable class, fz_output, to abstract output streams.

11.2 Creation

The exact function to call to create an output stream depends on the specific stream required, but they generally follow a similar format. Some common examples are:

```
fz_new_output_with_file: Open an output stream that writes to a
FILE *.

file: The file to write to.

close: non-zero if we should close the file when the fz_output
is closed.

*/
fz_output *fz_new_output_with_file_ptr(fz_context *ctx, FILE *file, int
close);

/*

fz_new_output_with_path: Open an output stream that writes to a
given path.

filename: The filename to write to (specified in UTF-8).
```

```
append: non-zero if we should append to the file, rather than
  overwriting it.
*/
fz_output *fz_new_output_with_path(fz_context *, const char *filename,
        int append);

/*
    fz_new_output_with_buffer: Open an output stream that appends
    to a buffer.

    buf: The buffer to append to.
*/
fz_output *fz_new_output_with_buffer(fz_context *ctx, fz_buffer *buf);
```

One of the most common use cases is to get an output stream that goes to stdout or stderr, and we provide convenience functions for exactly this. In addition we allow the streams for stdout and stderr to be replaced by other fz_outputs, thus allowing redirection to be changed simply for any of our existing tools:

```
/*
   fz_stdout: The standard out output stream. By default
   this stream writes to stdout. This may be overridden
   using fz_set_stdout.
fz_output *fz_stdout(fz_context *ctx);
/*
   fz_stderr: The standard error output stream. By default
   this stream writes to stderr. This may be overridden
   using fz_set_stderr.
fz_output *fz_stderr(fz_context *ctx);
   fz_set_stdout: Replace default standard output stream
   with a given stream.
   out: The new stream to use.
void fz_set_stdout(fz_context *ctx, fz_output *out);
   fz_set_stderr: Replace default standard error stream
   with a given stream.
   err: The new stream to use.
void fz_set_stderr(fz_context *ctx, fz_output *err);
```

11.3 Usage

11.3.1 Writing bytes

```
Single bytes can be written to fz_output streams using fz_write_byte:

/*
    fz_write_byte: Write a single byte.
    out: stream to write to.
    x: value to write

*/
void fz_write_byte(fz_context *ctx, fz_output *out, unsigned char x);

Blocks of bytes can be written to fz_output streams using fz_write:

/*
    fz_write: Write data to output. Designed to parallel fwrite.
    out: Output stream to write to.
    data: Pointer to data to write.

size: Length of data to write.

*/
void fz_write(fz_context *ctx, fz_output *out, const void *data, size_t size);
```

11.3.2 Writing objects

We have convenience functions for outputting 16 and 32bit integers in both big and little endian forms:

```
/*
    fz_write_int32_be: Write a big-endian 32-bit binary integer.
*/
void fz_write_int32_be(fz_context *ctx, fz_output *out, int x);
/*
    fz_write_int32_le: Write a little-endian 32-bit binary integer.
*/
void fz_write_int32_le(fz_context *ctx, fz_output *out, int x);
/*
    fz_write_int16_be: Write a big-endian 16-bit binary integer.
```

11.3.3 Writing strings

To output printable strings, we have the simple fputc, fputs and fputrune equivalents:

```
fz_putc: fputc equivalent for output streams.
#define fz_putc(C,0,B) fz_write_byte(C, 0, B)
   fz_puts: fputs equivalent for output streams.
#define fz_puts(C,0,S) fz_write(C, 0, (S), strlen(S))
   fz_putrune: fputrune equivalent for output streams.
#define fz_putrune(C,O,R) fz_write_rune(C, O, R)
We also provide a family of enhanced output functions, patterned after fprintf:
   fz_vsnprintf: Our customised vsnprintf routine.
   Takes %c, %d, %o, %s, %u, %x, as usual.
   Modifiers are not supported except for zero-padding
   ints (e.g. %02d, %03o, %04x, etc).
   \%f and \%g both output in "as short as possible hopefully lossless
   non-exponent" form, see fz_ftoa for specifics.
   %C outputs a utf8 encoded int.
   %M outputs a fz_matrix*.
   %R outputs a fz_rect*.
```

```
%P outputs a fz_point*.
    %q and %( output escaped strings in C/PDF syntax.
    %11{d,u,x} indicates that the values are 64bit.
    %z{d,u,x} indicates that the value is a size_t.
    %Z{d,u,x} indicates that the value is a fz_off_t.
*/
size_t fz_vsnprintf(char *buffer, size_t space, const char *fmt, va_list args);

/*
    fz_snprintf: The non va_list equivalent of fz_vsnprintf.
*/
size_t fz_snprintf(char *buffer, size_t space, const char *fmt, ...);

/*
    fz_printf: fprintf equivalent for output streams. See fz_snprintf.
*/
void fz_printf(fz_context *ctx, fz_output *out, const char *fmt, ...);

/*
    fz_vprintf: vfprintf equivalent for output streams. See fz_vsnprintf.
*/
void fz_vprintf(fz_context *ctx, fz_output *out, const char *fmt, va_list ap);
```

11.3.4 Seeking

As with fz_streams, fz_outputs normally move linearly, but in special cases, can be seekable.

```
/*
    fz_seek_output: Seek to the specified file position. See fseek
    for arguments.

Throw an error on unseekable outputs.
*/
void fz_seek_output(fz_context *ctx, fz_output *out, fz_off_t off, int
    whence);
```

Unlike fz_streams, which support fz_tell in all cases, fz_outputs can only fz_tell_output if they are seekable:

```
/*
    fz_tell_output: Return the current file position. Throw an error
    on unseekable outputs.
*/
fz_off_t fz_tell_output(fz_context *ctx, fz_output *out);
```

11.4 Implementing a fz_output

The above, relatively rich, set of functions are implemented on a fairly simple basic structure.

To implement your own fz_output, simply define a creation function of the form:

```
fz_output *fz_new_output_foo(fz_context *ctx, <more parameters here>)
{
    fz_output *out = fz_new_output(ctx, <state>, foo_write, foo_close);
    <optionally set out->seek = foo_seek>
     <optionally set out->tell = foo_tell>
    return out;
}
```

This has parallels with the implementation of fz_streams, but is not quite identical.

If <code>jstate</code>; needs no destruction, then we can use NULL in place of <code>foo_close</code>. Otherwise <code>foo_close</code> should be a function of type:

```
/*
    fz_output_close_fn: A function type for use when implementing
    fz_outputs. The supplied function of this type is called
    when the output stream is closed, to release the stream specific
    state information.

    state: The output stream state to release.
*/
typedef void (fz_output_close_fn)(fz_context *ctx, void *state);
```

This can be as simple as doing fz_free(ctx, state), or (depending on the complexity of the state structure) can require more involved operations to clean up.

The most important function and the only non-optional one is foo_write. This is a function of type:

```
fz_output_write_fn: A function type for use when implementing fz_outputs. The supplied function of this type is called whenever data is written to the output.

state: The state for the output stream.

data: a pointer to a buffer of data to write.

n: The number of bytes of data to write.
```

```
*/
typedef void (fz_output_write_fn)(fz_context *ctx, void *state, const
    void *data, size_t n);
```

Optionally we can choose to have our output stream support fz_seek_output and fz_tell_output. To do that we must implement foo_seek and foo_tell respectively, and assign them out->seek and out->tell during creation.

```
/*
    fz_output_seek_fn: A function type for use when implementing
    fz_outputs. The supplied function of this type is called when
    fz_seek_output is requested.

    state: The output stream state to seek within.

    offset, whence: as defined for fs_seek_output.

*/

typedef void (fz_output_seek_fn)(fz_context *ctx, void *state, fz_off_t
    offset, int whence);

/*

    fz_output_tell_fn: A function type for use when implementing
    fz_outputs. The supplied function of this type is called when
    fz_tell_output is requested.

    state: The output stream state to report on.

Returns the offset within the output stream.

*/

typedef fz_off_t (fz_output_tell_fn)(fz_context *ctx, void *state);
```

Chapter 12

Rendered Output Formats

12.1 Overview

MuPDFs built in renderer (see /rjwrefDrawDevice) produces in-memory arrays of contone values for areas of document pages. The MuPDF library includes routines to be able to output these areas to a number of different output formats.

Typically these devices all follow a similar pattern, enabling either full page or banded rendering to be performed according to the requirements of the particular application.

For a given format XXX, there tend to be 3 functions defined:

The first function outputs a pixmap to a utf-8 encoded filename as an XXX formatted file. If the pixmap is not in a suitable colorspace/alpha configuration, then an exception will be thrown.

The second function does the same thing, but to a given fz_output rather than to a named file.

The third function returns an fz_band_writer to do the same thing.

12.2 Band Writers

The purpose of the fz_band_writer mechanism is to allow banded rendering; rather than having to allocate a pixmap large enough to hold the entire page at once, we instead render bands across the page and feed those to the fz_band_writer which assembles them into a properly formed XXX format output stream.

Having created a fz_band_writer using one of the creation functions defined in the following sections, the page output starts by calling fz_write_header. This both configures the band writer for the type of data that is being sent, and triggers the output of the file header.

```
fz_write_header: Cause a band writer to write the header for
   a banded image with the given properties/dimensions etc. This
   also configures the bandwriter for the format of the data to be
   passed in future calls.
   w, h: Width and Height of the entire page.
   n: Number of components (including alphas).
   alpha: Number of alpha components.
   xres, yres: X and Y resolutions in dpi.
   pagenum: Page number
   Throws exception if incompatible data format.
void fz_write_header(fz_context *ctx, fz_band_writer *writer, int w, int
    h, int n, int alpha, int xres, int yres, int pagenum);
Next, the caller should render bands of the page in turn, and pass them in to
fz_write_band.
   fz_write_band: Cause a band writer to write the next band
   of data for an image.
   stride: The byte offset from the first byte of the data
   for a pixel to the first byte of the data for the same pixel
   on the row below.
   band_height: The number of lines in this band.
   samples: Pointer to first byte of the data.
```

```
void fz_write_band(fz_context *ctx, fz_band_writer *writer, int stride,
   int band_height, const unsigned char *samples);
```

Once enough data has been sent, the band writer automatically writes any trailer for the file.

At this point, the caller can either call fz_write_header to start a new page, or they can call fz_drop_band_writer to clean up.

```
void fz_drop_band_writer(fz_context *ctx, fz_band_writer *writer);
```

12.3 PNM

The simplest output format supported is that of PNM. The pixmap can be greyscale, or RGB, with or without alpha (though the alpha plane is always ignored on writing).

```
/*
    fz_save_pixmap_as_pnm: Save a pixmap as a PNM image file.
*/
void fz_save_pixmap_as_pnm(fz_context *ctx, fz_pixmap *pixmap, char
    *filename);

void fz_write_pixmap_as_pnm(fz_context *ctx, fz_output *out, fz_pixmap
    *pixmap);

fz_band_writer *fz_new_pnm_band_writer(fz_context *ctx, fz_output *out);
```

12.4 PAM

Related to PNM we have PAM. The pixmap formats here can be greyscale, RGB or CMYK, with or without alpha (and the alpha plane is written to the file). The TUPLTYPE in the image header reflects the color and alpha configuration, though not all readers support all variants.

```
/*
    fz_save_pixmap_as_pam: Save a pixmap as a PAM image file.
*/
void fz_save_pixmap_as_pam(fz_context *ctx, fz_pixmap *pixmap, char
    *filename);

void fz_write_pixmap_as_pam(fz_context *ctx, fz_output *out, fz_pixmap
    *pixmap);
```

```
fz_band_writer *fz_new_pam_band_writer(fz_context *ctx, fz_output *out);
```

12.5 PBM

Bitmaps suitable for output to the PBM format are generated by drawing to greyscale contone (with no alpha), and then halftoning down to monochrome.

```
/*
    fz_save_bitmap_as_pbm: Save a bitmap as a PBM image file.
*/
void fz_save_bitmap_as_pbm(fz_context *ctx, fz_bitmap *bitmap, char
    *filename);

void fz_write_bitmap_as_pbm(fz_context *ctx, fz_output *out, fz_bitmap
    *bitmap);

fz_band_writer *fz_new_pbm_band_writer(fz_context *ctx, fz_output *out);
```

12.6 PKM

Bitmaps suitable for output to the PKM format are generated by drawing to CMYK contone (with no alpha), and then halftoning down to give 1bpc cmyk.

```
/*
    fz_save_bitmap_as_pkm: Save a 4bpp cmyk bitmap as a PAM image file.
*/
void fz_save_bitmap_as_pkm(fz_context *ctx, fz_bitmap *bitmap, char
    *filename);

void fz_write_bitmap_as_pkm(fz_context *ctx, fz_output *out, fz_bitmap
    *bitmap);

fz_band_writer *fz_new_pkm_band_writer(fz_context *ctx, fz_output *out);
```

12.7 PNG

The PNG format will accept either greyscale or RGB pixmaps, with or without alpha. As a special case, alpha only pixmaps are accepted and written as greyscale.

/*

Because PNG is such a useful and widely used format, we have another couple of functions. These take either an fz_image or an fz_pixmap and produce an fz_buffer containing a PNG encoded version. This is very useful when converting between document formats as we can frequently use a PNG version of an image as a replacement for other image formats that may not be supported.

```
/*
    Create a new buffer containing the image/pixmap in PNG format.
*/
fz_buffer *fz_new_buffer_from_image_as_png(fz_context *ctx, fz_image
    *image);
fz_buffer *fz_new_buffer_from_pixmap_as_png(fz_context *ctx, fz_pixmap
    *pixmap);
```

12.8 PWG/CUPS

The PWG format is intended to encapsulate output for printers. As such there are many values that can be set in the headers. To allow for this, we expose these fields as an options structure that can be fed into the output functions.

```
typedef struct fz_pwg_options_s fz_pwg_options;
struct fz_pwg_options_s
{
    /* These are not interpreted as CStrings by the writing code, but
    * are rather copied directly out. */
    char media_class[64];
    char media_color[64];
    char media_type[64];
```

```
char output_type[64];
   unsigned int advance_distance;
   int advance_media;
   int collate;
   int cut_media;
   int duplex;
   int insert_sheet;
   int jog;
   int leading_edge;
   int manual_feed;
   unsigned int media_position;
   unsigned int media_weight;
   int mirror_print;
   int negative_print;
   unsigned int num_copies;
   int orientation;
   int output_face_up;
   unsigned int PageSize[2];
   int separations;
   int tray_switch;
   int tumble;
   int media_type_num;
   int compression;
   unsigned int row_count;
   unsigned int row_feed;
   unsigned int row_step;
   /* These are not interpreted as CStrings by the writing code, but
    * are rather copied directly out. */
   char rendering_intent[64];
   char page_size_name[64];
};
```

No documentation for these fields is given here - for more information see the PWG specification.

There are 2 sets of output functions available for PWG, those that take fz_pixmaps (for contone output) and those that take f_bitmaps (for halftoned output).

PWG files are structured as a header (to identify the format), followed by a stream of pages (images). Those functions that save (or write) a complete file include the file header as part of their output. If the option is used to append to a file, then the header is not added, as we presume we are appending new page information to the end of an existing file.

In circumstances when the header is not output automatically (such as when using the band writer) the header output must be triggered manually, by calling:

```
/*
    Output the file header to a pwg stream, ready for pages to follow it.
*/
void fz_write_pwg_file_header(fz_context *ctx, fz_output *out);
```

12.8.1 Contone

The PWG writer can accept pixmaps in greyscale, RGB and CMYK format, with no alpha planes.

PWG files can be saved to a file using:

```
/*
    fz_save_pixmap_as_pwg: Save a pixmap as a pwg
    filename: The filename to save as (including extension).
    append: If non-zero, then append a new page to existing file.
    pwg: NULL, or a pointer to an options structure (initialised to zero before being filled in, for future expansion).
*/
void fz_save_pixmap_as_pwg(fz_context *ctx, fz_pixmap *pixmap, char *filename, int append, const fz_pwg_options *pwg);
```

The file header will only be sent in the case where we are not appending to an existing file.

Alternatively, pages may be sent to an output stream. Two functions exist to do this. The first always sends a complete PWG file (including header):

```
/*
    Output a pixmap to an output stream as a pwg raster.
*/
void fz_write_pixmap_as_pwg(fz_context *ctx, fz_output *out, const
    fz_pixmap *pixmap, const fz_pwg_options *pwg);
```

The second sends just the page data, and is therefore suitable for sending the second or subsequent pages in a file. Alternatively, the header can be sent manually, and then this function can be used for all the pages in a file.

```
/*
    Output a page to a pwg stream to follow a header, or other pages.
*/
void fz_write_pixmap_as_pwg_page(fz_context *ctx, fz_output *out, const
    fz_pixmap *pixmap, const fz_pwg_options *pwg);
```

Finally, a standard band writer can be used:

```
/*
    fz_new_pwg_band_writer: Generate a new band writer for
    contone PWG format images.
*/
fz_band_writer *fz_new_pwg_band_writer(fz_context *ctx, fz_output *out,
    const fz_pwg_options *pwg);
```

In all cases, a NULL value can be sent for the fz_pwg_options field, in which case default values will be used.

12.8.2 Mono

The monochrome version of the PWG writer parallels the contone one. It can accept monochrome bitmaps only.

PWG files can be saved to a file using:

The file header will only be sent in the case where we are not appending to an existing file.

Alternatively, pages may be sent to an output stream. Two functions exist to do this. The first always sends a complete PWG file (including header):

```
/*
    Output a bitmap to an output stream as a pwg raster.
*/
void fz_write_bitmap_as_pwg(fz_context *ctx, fz_output *out, const
    fz_bitmap *bitmap, const fz_pwg_options *pwg);
```

The second sends just the page data, and is therefore suitable for sending the second or subsequent pages in a file. Alternatively, the header can be sent manually, and then this function can be used for all the pages in a file.

In all cases, a NULL value can be sent for the fz_pwg_options field, in which case default values will be used.

12.9 TGA

The TGA writer can accept pixmaps in greyscale, RGB and BGR formats, with and without alpha.

```
fz_save_pixmap_as_tga: Save a pixmap as a TGA image file.
   Can accept RGB, BGR or Grayscale pixmaps, with or without
void fz_save_pixmap_as_tga(fz_context *ctx, fz_pixmap *pixmap, const
    char *filename);
/*
   Write a pixmap to an output stream in TGA format.
   Can accept RGB, BGR or Grayscale pixmaps, with or without
   alpha.
*/
void fz_write_pixmap_as_tga(fz_context *ctx, fz_output *out, fz_pixmap
    *pixmap);
/*
   fz_new_tga_band_writer: Generate a new band writer for TGA
   format images. Note that image must be generated vertically
   flipped for use with this writer!
   Can accept RGB, BGR or Grayscale pixmaps, with or without
   alpha.
```

```
is_bgr: True, if the image is generated in bgr format.
*/
fz_band_writer *fz_new_tga_band_writer(fz_context *ctx, fz_output *out,
    int is_bgr);
```

12.10 PCL

PCL is not a standard image format, rather it is a page description language for printers. Unfortunately, the exact implementation of PCL varies from printer to printer, so it can be necessary to tweak the output according to the exact intended destination.

Accordingly, we have a pcl_options structure to allow this to happen. To use this, you simply define a pcl_options structure on the stack:

```
pcl_options options = { 0 };
```

Next you populate those options. Typically this is done by requesting a preset from our current defined set.

```
fz_pcl_preset: Retrieve a set of fz_pcl_options suitable for a given
    preset.
    opts: pointer to options structure to populate.
    preset: Preset to fetch. Currently defined presets include:
       ljet4 HP DeskJet
       dj500 HP DeskJet 500
       fs600 Kyocera FS-600
             HP LaserJet, HP LaserJet Plus
       1j
              HP LaserJet IIp, HP LaserJet IId
       1j2
       1j3
              HP LaserJet III
      1j3d HP LaserJet IIId
       1i4
             HP LaserJet 4
       lj4pl HP LaserJet 4 PL
       lj4d HP LaserJet 4d
       1p2563b HP 2563B line printer
       oce9050 Oce 9050 Line printer
   Throws exception on unknown preset.
void fz_pcl_preset(fz_context *ctx, fz_pcl_options *opts, const char
    *preset);
```

These options can then be tweaked further using fz_pcl_option:

```
fz_pcl_option: Set a given PCL option to a given value in the
    supplied options structure.

    opts: The option structure to modify,
    option: The option to change.

val: The value that the option should be set to. Acceptable ranges of
    values depend on the option in question.

Throws an exception on attempt to set an unknown option, or an
    illegal value.

Currently defined options/values are as follows:
```

```
spacing,0
                                  No vertical spacing capability
                                  PCL 3 spacing (<ESC>*p+<n>Y)
        spacing,1
        spacing,2
                                  PCL 4 spacing (<ESC>*b<n>Y)
        spacing,3
                                  PCL 5 spacing (<ESC>*b<n>Y and clear seed
                                  row)
        mode2,0 or 1
                                  Disable/Enable mode 2 graphics compression
        mode2,0 or 1 Disable/Enable mode 2 graphics compression mode3,0 or 1 Disable/Enable mode 3 graphics compression mode3,0 or 1 Disable/Enable mode 3 graphics compression eog_reset,0 or 1 End of graphics (<ESC>*rB) resets all
                                  parameters
        has_duplex,0 or 1
                                  Duplex supported (<ESC>&1<duplex>S)
        has_papersize,0 or 1 Papersize setting supported
                                   (<ESC>&l<sizecode>A)
        has_copies,0 or 1
                                  Number of copies supported
                                   (<ESC>&l<copies>X)
        is_ljet4pjl,0 or 1
                                  Disable/Enable HP 4PJL model-specific output
        is_oce9050,0 or 1
                                  Disable/Enable Oce 9050 model-specific
                                   output
void fz_pcl_option(fz_context *ctx, fz_pcl_options *opts, const char
     *option, int val);
```

12.10.1 Color

Color PCL output can be generated from RGB pixmaps with alpha (though the alpha is ignored) using:

```
void fz_save_pixmap_as_pcl(fz_context *ctx, fz_pixmap *pixmap, char
    *filename, int append, const fz_pcl_options *pcl);
```

```
void fz_write_pixmap_as_pcl(fz_context *ctx, fz_output *out, const
    fz_pixmap *pixmap, const fz_pcl_options *pcl);

fz_band_writer *fz_new_color_pcl_band_writer(fz_context *ctx, fz_output
    *out, const fz_pcl_options *options);
```

This is 24bpp RGB output, relying on the printers ability to dither. Blank lines are skipped, repeated lines are coded efficiently, and other lines are coded using deltas. Nonetheless file sizes can still be large with this output method.

12.10.2 Mono

Monochrome PCL output can be generated from monochrome bitmaps. These are generated by rendering to greyscale (no alpha) pixmaps and dithering down. The functions in question are:

```
fz_band_writer *fz_new_mono_pcl_band_writer(fz_context *ctx, fz_output
    *out, const fz_pcl_options *options);

void fz_write_bitmap_as_pcl(fz_context *ctx, fz_output *out, const
    fz_bitmap *bitmap, const fz_pcl_options *pcl);

void fz_save_bitmap_as_pcl(fz_context *ctx, fz_bitmap *bitmap, char
    *filename, int append, const fz_pcl_options *pcl);
```

12.11 Postscript

Postscript output is currently done as image output rather than high-level objects.

Pixmaps suitable for PS image output are greyscale, RGB or CMYK with no alpha.

```
void fz_write_pixmap_as_ps(fz_context *ctx, fz_output *out, const
    fz_pixmap *pixmap);

void fz_save_pixmap_as_ps(fz_context *ctx, fz_pixmap *pixmap, char
    *filename, int append);

fz_band_writer *fz_new_ps_band_writer(fz_context *ctx, fz_output *out);
```

Postscript requires file level headers and trailers, over and above that produced by the band writer itself. These can be generated using the following functions:

```
void fz_write_ps_file_header(fz_context *ctx, fz_output *out);
```

```
void fz_write_ps_file_trailer(fz_context *ctx, fz_output *out, int
    pages);
```

Chapter 13

The Image interface

13.1 Overview

Images are ubiquitous in document formats, and come in a huge variety of formats, ranging from full colour to monochrome, compressed to uncompressed, large to small. The ability to efficiently represent and decode 2d arrays of pixels is vital.

MuPDF represents images using an abstract type, fz_image. This takes the form of a base class, upon which different implementations can be built. All fz_images are reference counted, using the standard fz_keep and fz_drop conventions:

```
/*
    fz_drop_image: Drop a reference to an image.
    image: The image to drop a reference to.
*/
void fz_drop_image(fz_context *ctx, fz_image *image);
/*
    fz_keep_image: Increment the reference count of an image.
    image: The image to take a reference to.
    Returns a pointer to the image.
*/
fz_image *fz_keep_image(fz_context *ctx, fz_image *image);
```

The key operation required is to be able to request a decoded version of a subarea of that image (yielding a fz-pixmap), suitable for rendering at a given

```
size:
   fz_get_pixmap_from_image: Called to get a handle to a pixmap from an
       image.
   image: The image to retrieve a pixmap from.
   subarea: The subarea of the image that we actually care about (or
   to indicate the whole image).
   trans: Optional, unless subarea is given. If given, then on entry
   the transform that will be applied to the complete image. It should
   updated on exit to the transform to apply to the given subarea of the
   image. This is used to calculate the desired width/height for
       subsampling.
   w: If non-NULL, a pointer to an int to be updated on exit to the
   width (in pixels) that the scaled output will cover.
   h: If non-NULL, a pointer to an int to be updated on exit to the
   height (in pixels) that the scaled output will cover.
   Returns a non NULL pixmap pointer. May throw exceptions.
*/
fz_pixmap *fz_get_pixmap_from_image(fz_context *ctx, fz_image *image,
    const fz_irect *subarea, fz_matrix *trans, int *w, int *h);
```

Many images have a resolution encoded within them. This may or may not be honoured in the way they are positioned on the page, and it will certainly not be honoured when zooming is taken into account, but for some operations it is useful to be able to request it.

```
/*
    fz_image_resolution: Request the natural resolution
    of an image.

    xres, yres: Pointers to ints to be updated with the
    natural resolution of an image (or a sensible default
    if not encoded).
*/
void fz_image_resolution(fz_image *image, int *xres, int *yres);
```

If no resolution is specified within the image, sensible defaults are returned.

A key ability of fz_images is that they are automatically cached in the fz_store

when decoded - repeated requests for pixmaps from the same image will (not necessarily) require the image to be decoded again and again.

13.2 Standard Image Types

13.2.1 Compressed

The most common type of fz_image is fz_compressed_image - that is, an image based upon a fz_buffer of data in a standard compressed format, such as JPEG, PNG, TIFF, and others.

With such images, the data is held in an fz_compressed_buffer:

```
typedef struct fz_compressed_buffer_s
{
    fz_compression_params params;
    fz_buffer *buffer;
} fz_compressed_buffer;
```

The data is held in the buffer field, and the details of the compression used are given in the params field, of type fz_compression_params:

```
struct fz_compression_params_s
   int type;
   union {
           int color_transform; /* Use -1 for unset */
       } jpeg;
       struct {
           int smask_in_data;
       } jpx;
       struct {
          int columns;
          int rows;
           int k;
           int end_of_line;
           int encoded_byte_align;
           int end_of_block;
           int black_is_1;
           int damaged_rows_before_error;
       } fax;
       struct
           int columns;
           int colors;
           int predictor;
```

```
int bpc;
       }
       flate;
       struct
           int columns;
           int colors;
           int predictor;
           int bpc;
           int early_change;
       } lzw;
   } u;
};
The choice of which of the union clauses is used is made by the type field:
enum
{
   FZ_IMAGE_UNKNOWN = O,
   /* Uncompressed samples */
   FZ_IMAGE_RAW,
   /* Compressed samples */
   FZ_IMAGE_FAX,
   FZ_IMAGE_FLATE,
   FZ_IMAGE_LZW,
   FZ_IMAGE_RLD,
   /* Full image formats */
   FZ_IMAGE_BMP,
   FZ_IMAGE_GIF,
   FZ_IMAGE_JPEG,
   FZ_IMAGE_JPX,
   FZ_IMAGE_JXR,
   FZ_IMAGE_PNG,
   FZ_IMAGE_PNM,
   FZ_IMAGE_TIFF,
};
To determine if an fz_image is a compressed image, call:
/*
   fz_compressed_image_buffer: Retrieve the underlying compressed
   data for an image.
   Returns a pointer to the underlying data buffer for an image,
   or NULL if this image is not based upon a compressed data
   buffer.
```

```
This is not a reference counted structure, so no reference is returned. Lifespan is limited to that of the image itself.

*/
fz_compressed_buffer *fz_compressed_image_buffer(fz_context *ctx, fz_image *image);
```

The easiest way to tell if an image is a compressed image is to request its underlying buffer. If it returns NULL, you know it is not this sort of image.

13.2.2 Decoded

The next most common type of image is based upon a decoded fz_pixmap. These are generally only used if the pixmap takes less storage than the compressed data would.

```
/*
    fz_pixmap_image_tile: Retried the underlying fz_pixmap
    for an image.

Returns a pointer to the underlying fz_pixmap for an image,
    or NULL if this image is not based upon an fz_pixmap.

No reference is returned. Lifespan is limited to that of
    the image itself. If required, use fz_keep_pixmap to take
    a reference to keep it longer.

*/
fz_pixmap *fz_pixmap_image_tile(fz_context *ctx, fz_pixmap_image *cimg);
```

The easiest way to tell if an image is a decoded image is to request its underlying tile. If it returns NULL, you know it is not this sort of image.

13.2.3 Display List

The final standard sort of image in MuPDF (though more types may of course be added in future) is that based upon a display list.

we use this to easily embed one file format within another. For example, epub files frequently contain SVG images for title pages. We open the SVG image as a separate document, run it to a display list, and close the document. We can then create an image from the display list, and use this in the HTML flow of the epub document.

These images maintain the properties of the original (vector-based) document in that they remain scalable even after conversion to an image.

13.3 Creating Images

To create an image from a standard type, simply call the appropriate function. For example, if you have an fz_buffer with the source data:

```
/*
    fz_new_image_from_buffer: Create a new image from a
    buffer of data, inferring its type from the format
    of the data.
*/
fz_image *fz_new_image_from_buffer(fz_context *ctx, fz_buffer *buffer);

If the data is in a file, use:
/*
    fz_image_from_file: Create a new image from the contents
    of a file, inferring its type from the format of the
    data.
*/
fz_image *fz_new_image_from_file(fz_context *ctx, const char *path);
```

This loads the data into memory, and calls fz_new_image_from_buffer internally.

If the data cannot be recognised from its header, and more information is required, then the data can be formed in an fz_compressed_buffer, and an image created with:

```
#
fz_new_image_from_compressed_buffer: Create an image based on
the data in the supplied compressed buffer.

w,h: Width and height of the created image.

bpc: Bits per component.

colorspace: The colorspace (determines the number of components,
and any color conversions required while decoding).

xres, yres: The X and Y resolutions respectively.

interpolate: 1 if interpolation should be used when decoding
this image, 0 otherwise.

imagemask: 1 if this is an imagemask (i.e. transparent), 0
otherwise.

decode: NULL, or a pointer to to a decode array. The default
decode array is [0 1] (repeated n times, for n color components).
```

```
colorkey: NULL, or a pointer to a colorkey array. The default
   colorkey array is [0 255] (repeatd n times, for n color
   components).
   buffer: Buffer of compressed data and compression parameters.
   Ownership of this reference is passed in.
   mask: NULL, or another image to use as a mask for this one.
   Supplying a masked image as a mask to another image is
   illegal!
*/
fz_image *fz_new_image_from_compressed_buffer(fz_context *ctx, int w,
    int h, int bpc, fz_colorspace *colorspace, int xres, int yres, int
    interpolate, int imagemask, float *decode, int *colorkey,
    fz_compressed_buffer *buffer, fz_image *mask);
Finally, if we have a decoded fz_pixmap, we can form a new image from it:
   fz_new_image_from_pixmap: Create an image from the given
   pixmap.
   pixmap: The pixmap to base the image upon. A new reference
   to this is taken.
   mask: NULL, or another image to use as a mask for this one.
   A new reference is taken to this image. Supplying a masked
   image as a mask to another image is illegal!
*/
fz_image *fz_new_image_from_pixmap(fz_context *ctx, fz_pixmap *pixmap,
    fz_image *mask);
```

13.4 Implementing an Image Type

Support for a new type of image, can be implemented fairly simply, by defining a structure derived from an fz_image, perhaps:

```
typedef struct
{
    fz_image super;
    <foo specific fields>
} foo_image;
```

Then we'd define a new image creation function, fz_new_image_from_foo, of the form:

```
fz_image *fz_new_image_from_foo(fz_context *ctx, <foo specific</pre>
    parameters>) {
   foo_image *foo = fz_new_image(ctx, ..., foo_image, foo_get,
        foo_size, foo_drop);
   if (!foo)
       return NULL;
   <initialise foo specific fields from foo specific parameters>
   return &foo->super;
}
The key call here is the call to fz_new_image. This is a macro which wraps a
call to fz_new_image_of_size:
   fz_new_image_of_size: Internal function to make a new fz_image
   structure for a derived class.
   w,h: Width and height of the created image.
   bpc: Bits per component.
   colorspace: The colorspace (determines the number of components,
   and any color conversions required while decoding).
   xres, yres: The X and Y resolutions respectively.
   interpolate: 1 if interpolation should be used when decoding
   this image, 0 otherwise.
   imagemask: 1 if this is an imagemask (i.e. transparent), 0
   otherwise.
   decode: NULL, or a pointer to to a decode array. The default
   decode array is [0 1] (repeated n times, for n color components).
   colorkey: NULL, or a pointer to a colorkey array. The default
   colorkey array is [0\ 255] (repeatd n times, for n color
   components).
   mask: NULL, or another image to use as a mask for this one.
   A new reference is taken to this image. Supplying a masked
   image as a mask to another image is illegal!
   size: The size of the required allocated structure (the size of
   the derived structure).
   get: The function to be called to obtain a decoded pixmap.
```

```
get_size: The function to be called to return the storage size
    used by this image.

drop: The function to be called to dispose of this image once
    the last reference is dropped.

Returns a pointer to an allocated structure of the required size,
    with the first sizeof(fz_image) bytes initialised as appropriate
    given the supplied parameters, and the other bytes set to zero.

*/
fz_image *fz_new_image_of_size(fz_context *ctx, int w, int h, int bpc,
    fz_colorspace *colorspace, int xres, int yres, int interpolate, int
    imagemask, float *decode, int *colorkey, fz_image *mask, int size,
    fz_image_get_pixmap_fn *get, fz_image_get_size_fn *get_size,
    fz_drop_image_fn *drop);

#define fz_new_image(CTX,W,H,B,CS,X,Y,I,IM,D,C,M,T,G,S,Z) \
((T*)Memento_label(fz_new_image_of_size(CTX,W,H,B,CS,X,Y,I,IM,D,C,M,sizeof(T),G,S,Z),#T))
```

The macro takes identical parameters to the function other than passing the structure type in place of the structure type saved, and performing a typecast to simplify the typical enclosing code.

Both function and macro take pointers to 3 functions that need to be defined for the new format. Firstly, foo_get is of the following type:

```
/*
   fz_get_pixmap_fn: Function type to get a decoded pixmap
   for an image.
```

im: The image to decode.

subarea: NULL, or the subarea of the image required. Expressed in terms of a rectangle in the original width/height of the image. If non NULL, this should be updated by the function to the actual subarea decoded - which must include the requested area!

 $\ensuremath{\mathbf{w}},\ \ensuremath{\mathbf{h}}\ \ensuremath{\mathbf{:}}$ The actual width and height that the whole image would need to be decoded to.

l2factor: On entry, the log 2 subsample factor required. If possible the decode process can take care of (all or some) of this subsampling, and must then update the value so the caller knows what remains to be done.

Returns a reference to a decoded pixmap that satisfies the requirements of the request.

```
*/
typedef fz_pixmap *(fz_image_get_pixmap_fn)(fz_context *ctx, fz_image
    *im, fz_irect *subarea, int w, int h, int *12factor);

Secondly, foo_get_size will be of type:

/*
    fz_image_get_size_fn: Function type to get the given storage
    size for an image.

    Returns the size in bytes used for a given image.

*/
typedef size_t (fz_image_get_size_fn)(fz_context *, fz_image *);

Finally, foo_drop will be of type:

/*
    fz_drop_image_fn: Function type to destroy an images data
    when it's reference count reaches zero.

*/
typedef void (fz_drop_image_fn)(fz_context *ctx, fz_image *image);
```

The actual deallocation of the fz_image block and its associated resources will be done on return from this function. The fz_drop_image_fn is responsible just for deallocating its implementation specific resources (i.e. the contents of foo_image rather than fz_image).

13.5 Image Caching

While caching of decoded images happens automatically within MuPDF, it is perhaps worth saying a small amount about it.

Whenever a decoded image is requested, MuPDF searches in the store (see chapter 5 Memory Management and The Store) to see if a suitable pixmap exists there already. If one is found, the store remembers that is has been reused, and returned immediately - no decoding is done.

If no suitable pixmap is found, MuPDF calculates how large the image would be on a rendered page. By comparing this size to the native size of the image, it calculates a log 2 subsampling factor to use. That is, it attempts to avoid decoding the image at full size, when one 1/2 (or 1/4 etc) of the width/height would do.

A log 2 subsampling is used because a) some compression formats such as JPEG can achieve this as part of their decompression run, and b) it is easy to rapidly shrink decompressed pixmaps in this way.

The decoded and subsampled image is then placed into the store so that it will (hopefully) be found the next time a decode of the image is requested.

Chapter 14

The Document Handler interface

14.1 Overview

MuPDF is written as an extensible framework for handling different document types. Each different document format provides an fz_document_handler structure that provides the required callbacks to recognise and open files of its supported type. For example:

```
extern fz_document_handler pdf_document_handler;
extern fz_document_handler xps_document_handler;
extern fz_document_handler svg_document_handler;
...
```

At startup, the calling program must register the required document handlers. It can either register them each individually, by repeatedly calling fz_register_document_handler:

```
/*
    fz_register_document_handler: Register a handler
    for a document type.

    handler: The handler to register.
*/
void fz_register_document_handler(fz_context *ctx, const
    fz_document_handler *handler);
```

For example:

```
fz_register_document_handler(ctx, &pdf_document_handler);
fz_register_document_handler(ctx, &xps_document_handler);
fz_register_document_handler(ctx, &svg_document_handler);
```

or, it can use a convenience function to register all the standard handlers enabled in a given build:

```
/*
    fz_register_document_handler: Register handlers
    for all the standard document types supported in
    this build.
*/
void fz_register_document_handlers(fz_context *ctx);
```

14.2 Implementing a Document Handler

14.2.1 Recognize and Open

To implement a new document handler, a new fz_document_handler structure is required. There are 3 components to such a structure, all function pointers:

```
typedef struct fz_document_handler_s
{
    fz_document_recognize_fn *recognize;
    fz_document_open_fn *open;
    fz_document_open_with_stream_fn *open_with_stream;
} fz_document_handler;
```

The first is a function to recognize a document from a magic string, typically a mimetype or a filename:

```
/*
    fz_document_recognize_fn: Recognize a document type from
    a magic string.

magic: string to recognise - typically a filename or mime
    type.

Returns a number between 0 (not recognized) and 100
    (fully recognized) based on how certain the recognizer
    is that this is of the required type.

*/
typedef int (fz_document_recognize_fn)(fz_context *ctx, const char
    *magic);
```

The second is a function to open a document from a filename:

```
/*
    fz_document_open_fn: Function type to open a document from a
    file.
    filename: file to open

    Pointer to opened document. Throws exception in case of error.
*/
typedef fz_document *(fz_document_open_fn)(fz_context *ctx, const char
    *filename);
```

This function can permissibly be NULL, as it can be synthesized automatically from the third entry, a function to open a document from a stream:

```
/*
    fz_document_open_with_stream_fn: Function type to open a
    document from a file.

    stream: fz_stream to read document data from. Must be
    seekable for formats that require it.

Pointer to opened document. Throws exception in case of error.
*/
typedef fz_document *(fz_document_open_with_stream_fn)(fz_context *ctx,
    fz_stream *stream);
```

To create an fz_document use the fz_new_document macro. For a document of type foo, typically a foo_document structure would be defined as below:

```
typedef struct
{
    fz_document super;
    <foo specific fields>
} foo_document;
```

This would then be created using a call to fz_new_document, such as:

```
foo_document *foo = fz_new_document(ctx, foo_document);
```

This returns an empty document structure with **super** populated with default values, and the foo specific fields initialized to 0. The document handler then needs to fill in the document level functions.

14.2.2 Document Level Functions

The fz_document structure contains a list of functions used to implement the document level calls:

```
typedef struct fz_document_s
   int refs;
   fz_document_drop_fn *drop_document;
   fz_document_needs_password_fn *needs_password;
   fz_document_authenticate_password_fn *authenticate_password;
   fz_document_has_permission_fn *has_permission;
   fz_document_load_outline_fn *load_outline;
   fz_document_layout_fn *layout;
   fz_document_make_bookmark_fn *make_bookmark;
   fz_document_lookup_bookmark_fn *lookup_bookmark;
   fz_document_resolve_link_fn *resolve_link;
   fz_document_count_pages_fn *count_pages;
   fz_document_load_page_fn *load_page;
   fz_document_lookup_metadata_fn *lookup_metadata;
   int did_layout;
   int is_reflowable;
} fz_document;
```

Implementations must fill in the drop-document field, with a pointer to a function called to free any resources help by the document when the reference count drops to 0. In the unlikely event that your implementation has no resources, this field can be left NULL.

```
/*
    fz_document_drop_fn: Called when the reference count for
    the fz_document drops to 0. The implementation should
    release any resources held by the document. The actual
    document pointer will be freed by the caller.
*/
typedef void (fz_document_drop_fn)(fz_context *ctx, fz_document *doc);
```

If your document handler is capable of handling password protected documents, then you must fill in the needs_password field with a pointer to a function called to enquire whether a given document needs a password:

```
/*
    fz_document_needs_password_fn: Type for a function to be
    called to enquire whether the document needs a password
    or not. See fz_needs_password for more information.
*/
typedef int (fz_document_needs_password_fn)(fz_context *ctx, fz_document
    *doc);
```

If your document handler is capable of handling password protected documents, then you must fill in the authenticate_password field with a pointer to a function called to attempt to authenticate a password:

```
/*
    fz_document_authenticate_password_fn: Type for a function to be
    called to attempt to authenticate a password. See
    fz_authenticate_password for more information.
*/
typedef int (fz_document_authenticate_password_fn)(fz_context *ctx,
    fz_document *doc, const char *password);
```

Certain document types encode permissions within them to say what users are allowed to do with them (printing, extracting etc). If your document handler's format has this concept, then you must fill in the has_permission field with a pointer to a function called to attempt to query such permissions:

```
/*
    fz_document_has_permission_fn: Type for a function to be
    called to see if a document grants a certain permission. See
    fz_document_has_permission for more information.
*/
typedef int (fz_document_has_permission_fn)(fz_context *ctx, fz_document
    *doc, fz_permission permission);
```

Certain document types can optionally include outline (table of contents) information within them. If your document handler's format has this concept, then you must fill in the <code>load_outline</code> field with a pointer to a function called to attempt to load such information if it is there:

If your document format requires a layout pass before it can be viewed, then you must fill in the layout field with a pointer to a function called to perform such a layout:

```
/*
    fz_document_layout_fn: Type for a function to be called to lay
    out a document. See fz_layout_document for more information.
*/
typedef void (fz_document_layout_fn)(fz_context *ctx, fz_document *doc,
    float w, float h, float em);
```

If your document requires a layout pass, you should provide functions to both make and resolve bookmarks to enable reader positions to be kept over layout changes. Accordingly the make_bookmark and lookup_bookmark fields should be filled out:

```
/*
    fz_document_make_bookmark_fn: Type for a function to make
    a bookmark. See fz_make_bookmark for more information.
*/
typedef fz_bookmark (fz_document_make_bookmark_fn)(fz_context *ctx,
    fz_document *doc, int page);

/*
    fz_document_lookup_bookmark_fn: Type for a function to lookup
    a bookmark. See fz_lookup_bookmark for more information.
*/
typedef int (fz_document_lookup_bookmark_fn)(fz_context *ctx,
    fz_document *doc, fz_bookmark mark);
```

Some document formats can encode internal links that point to another page in the document. If your document supports this concept, then you must fill in the resolve_link field with a pointer to a function called to resolve a textual link to a page number, and location on that page:

```
/*
    fz_document_resolve_link_fn: Type for a function to be called to
    resolve an internal link to a page number. See fz_resolve_link
    for more information.
*/
typedef int (fz_document_resolve_link_fn)(fz_context *ctx, fz_document
    *doc, const char *uri, float *xp, float *yp);
```

All document formats must fill in the count_pages field with a pointer to a function called to return the number of pages in a document:

```
/*
    fz_document_count_pages_fn: Type for a function to be called to
    count the number of pages in a document. See fz_count_pages for
    more information.
*/
typedef int (fz_document_count_pages_fn)(fz_context *ctx, fz_document
    *doc);
```

Different document formats encode different types of metadata. We therefore have an extensible function to allow such data to be queried. If your document handler wishes to support this, then the <code>lookup_metadata</code> field must be filled in with a pointer to a function to perform such lookups:

```
/*
    fz_document_lookup_metadata_fn: Type for a function to query
    a documents metadata. See fz_lookup_metadata for more
    information.
*/
typedef int (fz_document_lookup_metadata_fn)(fz_context *ctx,
    fz_document *doc, const char *key, char *buf, int size);
```

All document formats must fill in the load_page field with a pointer to a function called to return a reference to a fz_page structure:

```
/*
    fz_document_load_page_fn: Type for a function to load a given
    page from a document. See fz_load_page for more information.
*/
typedef fz_page *(fz_document_load_page_fn)(fz_context *ctx, fz_document
    *doc, int number);
```

To create a fz_page use the fz_new_page macro. For a document of type foo, typically a foo_page structure would be defined as below:

```
typedef struct
{
   fz_page super;
   <foo specific fields>
} foo_page;
```

This would then be created using a call to fz_new_page, such as:

```
foo_page *foo = fz_new_page(ctx, foo_page);
```

This returns an empty document structure with super populated with default values, and the foo specific fields initialized to 0. The document handler implementation then needs to fill in the page level functions.

14.2.3 Page Level Functions

The fz_page structure contains a list of functions used to implement the page level calls:

```
typedef struct fz_page_s
{
   int refs;
   fz_page_drop_page_fn *drop_page;
   fz_page_bound_page_fn *bound_page;
   fz_page_run_page_contents_fn *run_page_contents;
   fz_page_load_links_fn *load_links;
```

```
fz_page_first_annot_fn *first_annot;
fz_page_page_presentation_fn *page_presentation;
fz_page_control_separation_fn *control_separation;
fz_page_separation_disabled_fn *separation_disabled;
fz_page_count_separations_fn *count_separations;
fz_page_get_separation_fn *get_separation;
} fz_page;
```

The fz_page (and hence derived foo_page) structures are reference counted. The refs field is used to keep the reference count in. All the reference counting is handled by the core library, and all that is required of the implementation is that it should supply a drop_page function that will be called when the reference count reaches zero. This is of type:

```
/*
    fz_page_drop_page_fn: Type for a function to release all the
    resources held by a page. Called automatically when the
    reference count for that page reaches zero.
*/
typedef void (fz_page_drop_page_fn)(fz_context *ctx, fz_page *page);
```

Implementations must fill in the bound_page field with the address of a function to return the pages bounding box, of type:

```
/*
    fz_page_bound_page_fn: Type for a function to return the
    bounding box of a page. See fz_bound_page for more
    information.
*/
typedef fz_rect *(fz_page_bound_page_fn)(fz_context *ctx, fz_page *page,
    fz_rect *);
```

Implementations must fill in the run_page_contents field with the address of a function to interpret the contents of a page, of type:

```
/*
    fz_page_run_page_contents_fn: Type for a function to run the
    contents of a page. See fz_run_page_contents for more
    information.
*/
typedef void (fz_page_run_page_contents_fn)(fz_context *ctx, fz_page
    *page, fz_device *dev, const fz_matrix *transform, fz_cookie
    *cookie);
```

If a document format supports internal or external hyperlinks, then its implementation must fill in the load_links field with the address of a function to load the links from a page, of type:

```
/*
    fz_page_load_links_fn: Type for a function to load the links
    from a page. See fz_load_links for more information.
*/
typedef fz_link *(fz_page_load_links_fn)(fz_context *ctx, fz_page *page);
```

If a document format supports annotations, then its implementation must fill in the first_annot field with the address of a function to load the annotations from a page, of type:

```
/*
    fz_page_first_annot_fn: Type for a function to load the
    annotations from a page. See fz_first_annot for more
    information.
*/
typedef fz_annot *(fz_page_first_annot_fn)(fz_context *ctx, fz_page
    *page);
```

Some document formats can encode information that specifies how pages should be presented to the user as a slideshow - how long they should be displayed, and which transition to use when moving to the next page etc. In implementations of document handlers for such formats, they should fill in the page_presentation field with the address of a function to obtain this information, of type:

```
/*
    fz_page_page_presentation_fn: Type for a function to
    obtain the details of how this page should be presented when
    in presentation mode. See fz_page_presentation for more
    information.
*/
typedef fz_transition *(fz_page_page_presentation_fn)(fz_context *ctx,
    fz_page *page, fz_transition *transition, float *duration);
```

Some document formats can encapsulate multiple color separations. In order to allow proofing of such formats, MuPDF allows such separations to be enumerated and enabled/disabled. In document handlers for such document formats, the control_separation, separation_disabled, count_separations and get_separation fields should be filled in with functions of the following types respectively:

```
/*
    fz_page_control_separation: Type for a function to enable/
    disable separations on a page. See fz_control_separation for
    more information.
*/
typedef void (fz_page_control_separation_fn)(fz_context *ctx, fz_page
    *page, int separation, int disable);
```

```
/*
   fz_page_separation_disabled_fn: Type for a function to detect
   whether a given separation is enabled or disabled on a page.
   See fz_separation_disabled for more information.
*/
typedef int (fz_page_separation_disabled_fn)(fz_context *ctx, fz_page
    *page, int separation);
/*
   fz_page_count_separations_fn: Type for a function to count
   the number of separations on a page. See fz_count_separations
   for more information.
*/
typedef int (fz_page_count_separations_fn)(fz_context *ctx, fz_page
   fz_page_get_separation_fn: Type for a function to retrieve
   details of a separation on a page. See fz_get_separation
   for more information.
typedef const char *(fz_page_get_separation_fn)(fz_context *ctx, fz_page
    *page, int separation, uint32_t *rgb, uint32_t *cmyk);
```

14.3 Standard Document Handlers

MuPDF contains a range of document handlers for different formats. Which of these are built/enabled by default depends on configuration options in the include/mupdf/fitz/config.h file. See chapter 18 Build configuration for more information.

14.3.1 PDF

Support for PDF (Portable Document Format) is provided by pdf_document_handler. All current versions at the time of writing (i.e up to and including PDF 1.7) are supported.

MuPDF contains functionality to allow deeper access to the contents and structure of a PDF file than is exposed through the standard fz_prefixed functions, by using pdf_prefixed functions.

The library provides a pdf_specifics function to safely promote a fz_document pointer to a pdf_document pointer. This will return NULL if the document is not a PDF, indicating that the pdf_functions cannot be used.

14.3.2 XPS

Support for XPS (Open XML Paper Specification) is provided by xps_document_handler. All current versions at the time of writing are supported.

14.3.3 EPUB

Support for EPub v2 is provided by epub_document_handler. Tables are not currently supported, but is planned. Support for v3 is not planned.

The same document handler supports the FB2 (Fiction Book 2) electronic book format.

14.3.4 HTML

Support for basic HTML + simple CSS is provided by htdoc_document_handler. Tables are not currently supported, but is planned.

14.3.5 SVG

Support for SVG (Scalable Vector Graphics) is provided by svg_document_handler. Support is incomplete, but sufficient for many files.

14.3.6 Image

Support for a range of common image types (including PNG, JPEG, TIFF, JPEG2000, BMP and GIF) is provided by image_document_handler.

14.3.7 CBZ

Support for CBZ (Comic Book Archive) format is provided by cbz_document_handler. This supports files in .zip or .tar format.

Chapter 15

The Document Writer interface

15.1 Usage

As well as opening existing documents, MuPDF contains functions to allow the easy creation of new documents. The most general form of this functionality takes the form of the fz_document_writer interface.

A document writer is obtained by calling a generation function. The most general purpose one is:

```
/*
    fz_new_document_writer: Create a new fz_document_writer, for a
    file of the given type.

path: The document name to write (or NULL for default)

format: Which format to write (currently cbz, pdf, pam, pbm,
    pgm, pkm, png, ppm, pnm, svg, tga)

options: NULL, or pointer to comma separated string to control
    file generation.

*/
fz_document_writer *fz_new_document_writer(fz_context *ctx, const char
    *path, const char *format, const char *options);
```

Alternatively, direct calls to generate specific document writers can be used, such as:

```
fz_document_writer *fz_new_cbz_writer(fz_context *ctx, const char *path,
```

```
const char *options);
fz_document_writer *fz_new_pdf_writer(fz_context *ctx, const char *path,
    const char *options);
fz_document_writer *fz_new_svg_writer(fz_context *ctx, const char *path,
    const char *options);
fz_document_writer *fz_new_png_pixmap_writer(fz_context *ctx, const char
    *path, const char *options);
fz_document_writer *fz_new_tga_pixmap_writer(fz_context *ctx, const char
    *path, const char *options);
fz_document_writer *fz_new_pam_pixmap_writer(fz_context *ctx, const char
    *path, const char *options);
fz_document_writer *fz_new_pnm_pixmap_writer(fz_context *ctx, const char
    *path, const char *options);
fz_document_writer *fz_new_pgm_pixmap_writer(fz_context *ctx, const char
    *path, const char *options);
fz_document_writer *fz_new_ppm_pixmap_writer(fz_context *ctx, const char
    *path, const char *options);
fz_document_writer *fz_new_pbm_pixmap_writer(fz_context *ctx, const char
    *path, const char *options);
fz_document_writer *fz_new_pkm_pixmap_writer(fz_context *ctx, const char
    *path, const char *options);
```

Once a fz_document_writer has been created, pages can be written to the document one at a time. The process is started by calling fz_begin_page:

```
/*
    fz_begin_page: Called to start the process of writing a page to
    a document.

mediabox: page size rectangle in points.

Returns a fz_device to write page contents to.
*/
fz_device *fz_begin_page(fz_context *ctx, fz_document_writer *wri, const
    fz_rect *mediabox);
```

This function returns a fz_device pointer that should be used to write the page contents to. This can be done by making a sequence of normal device calls (see chapter 7 The Device interface) to paint the page with its content. One of the most common ways of doing this is by calling fz_run_page_contents on another open document. This therefore offers a quick mechanism for converting documents from one format to another.

Once the page contents have all been written, the page is finalized by calling fz_end_page:

```
/*
   fz_end_page: Called to end the process of writing a page to a
   document.
```

```
*/
void fz_end_page(fz_context *ctx, fz_document_writer *wri);
```

At this point, many formats will allow more pages to be written, simply by repeating the fz_begin_page, output, fz_end_page loop.

When all the pages have been written, the produced document can be finalized by calling fz_close_document_writer:

```
/*
    fz_close_document_writer: Called to end the process of writing
    pages to a document.

This writes any file level trailers required. After this
    completes successfully the file is up to date and complete.
*/
void fz_close_document_writer(fz_context *ctx, fz_document_writer *wri);
```

Finally, the document writer itself can be freed in the usual fashion by calling fz_drop_document_writer:

```
/*
    fz_drop_document_writer: Called to discard a fz_document_writer.
    This may be called at any time during the process to release all
    the resources owned by the writer.

Calling drop without having previously called drop may leave
    the file in an inconsistent state.
*/
void fz_drop_document_writer(fz_context *ctx, fz_document_writer *wri);
```

15.2 Implementation

Support for a new type of document writer requires a new structure, derived from fz_document_writer:

```
typedef struct
{
    fz_document_writer_begin_page_fn *begin_page;
    fz_document_writer_end_page_fn *end_page;
    fz_document_writer_close_writer_fn *close_writer;
    fz_document_writer_drop_writer_fn *drop_writer;
    fz_device *dev;
} fz_document_writer;
```

For instance:

```
typedef struct
   fz_document_writer super;
   <foo specific fields>
} foo_document_writer;
A generator function should be defined to return such an instance, perhaps:
fz_document_writer *fz_new_foo_document_writer(fz_context *ctx, const
    char *path, <foo specific params>) {
   foo_document_writer *foo = fz_new_derived_document_writer(ctx,
        foo_document_writer, foo_begin_page, foo_end_page, foo_close,
        foo_drop);
   <initialise foo specific fields>
   return &foo->super;
}
This uses a friendly macro that allocates a structure of the required size, ini-
tialises the function pointers as required, and zeroes the extra values in the
structure.
   fz_new_document_writer_of_size: Internal function to allocate a
   block for a derived document_writer structure, with the base
   structure's function pointers populated correctly, and the extra
   space zero initialised.
fz_document_writer *fz_new_document_writer_of_size(fz_context *ctx,
    size_t size, fz_document_writer_begin_page_fn *begin_page,
   fz_document_writer_end_page_fn *end_page,
        fz_document_writer_close_writer_fn *close,
        fz_document_writer_drop_writer_fn *drop);
#define
    fz_new_derived_document_writer(CTX, TYPE, BEGIN_PAGE, END_PAGE, CLOSE, DROP)
   ((TYPE
        *)Memento_label(fz_new_document_writer_of_size(CTX,sizeof(TYPE),BEGIN_PAGE,END_PAGE,CLOSE,DROF
The actual work for the document writer is done in the functions that are pas-
sed to fz_new_derived_document_writer. In the example above these were
```

foo_begin_page, foo_end_page, foo_close, and foo_drop. These have the fol-

fz_document_writer_begin_page_fn: Function type to start

the process of writing a page to a document.

lowing 4 types respectively.

```
mediabox: page size rectangle in points.
   Returns a fz_device to write page contents to.
*/
typedef fz_device *(fz_document_writer_begin_page_fn)(fz_context *ctx,
    fz_document_writer *wri, const fz_rect *mediabox);
/*
   fz_document_writer_end_page_fn: Function type to end the
   process of writing a page to a document.
   dev: The device created by the begin_page function.
typedef void (fz_document_writer_end_page_fn)(fz_context *ctx,
    fz_document_writer *wri, fz_device *dev);
   fz_document_writer_close_writer_fn: Function type to end
   the process of writing pages to a document.
   This writes any file level trailers required. After this
   completes successfully the file is up to date and complete.
typedef void (fz_document_writer_close_writer_fn)(fz_context *ctx,
    fz_document_writer *wri);
   fz_document_writer_drop_writer_fn: Function type to discard
   an fz_document_writer. This may be called at any time during
   the process to release all the resources owned by the writer.
   Calling drop without having previously called close may leave
   the file in an inconsistent state.
typedef void (fz_document_writer_drop_writer_fn)(fz_context *ctx,
    fz_document_writer *wri);
```

Once defined, if this is intended to be a generally useful document writer, it should probably be hooked into fz_new_document_writer, where it can be selected by appropriate format and options strings.

Chapter 16

Progressive Mode

16.1 Overview

When used in the normal way, MuPDF requires the entirety of a file to be present before it can be opened. For some applications, this can be a significant restriction - for instance, when downloading a PDF file over a slow internet link, being able to view just the first page or two may be enough to know whether it is the correct file or not.

Normal PDF files require the end of the file to be present before file reading can begin, as this is where the 'trailer' lives (effectively the index for the entire file). In an effort to allow early display of the first page, Adobe (the originators of the PDF format) introduced the concept of a 'linearized' PDF file. This is a PDF file that, while constructed in accordance with the original specification, also has some extra information contained within the file to allow fast access to the first page. This information is known as the 'hint stream'. In addition, extra constraints are placed upon the ordering of data within the file in an effort to ensure that the first page will download quickly.

Unfortunately, Linearized PDF files are far from a panacea. The specification is overly-complex, unclear and consequently poorly supported in both readers and writers of the format. Even when implemented correctly, it is of limited use for pages other than the first one.

MuPDF therefore attempts to solve the problem using a combination of mechanisms, known together as "progressive mode". When run in this mode, MuPDF can not only take advantage of the linearization information (if present) in a file, but is also capable of directing the actual download mechanism used by a file. By controlling the order in which sections of a file are fetched, any page required can be viewed before the whole fetch is complete.

For optimum performance a file should be both linearized and be available over a byte-range supporting link, but benefits can still be had with either one of these alone.

Coupled with the ability to render pages ignoring (and detecting) errors, this means that 'rough renderings' of pages can be given even before all the content (such as images and fonts) for a page have been downloaded.

16.2 Implementation

MuPDF has made various extensions to its mechanisms for handling progressive loading. They rely on some special properties built into a type of fz_stream known as a 'progressive' stream.

16.2.1 Progressive Streams

At its lowest level MuPDF reads file data from a fz_stream, using the fz_open_document_with_stream call. The alternative entrypoint fz_open_document is implemented by calling this.

The PDF interpreter uses the fz_lookup_metadata call to check for its stream being progressive or not. Any non-progressive stream will be read as normal, with the system assuming that the entire file is present immediately.

If it is found to be progressive, another fz_lookup_metadata call is made to find out what the length of the stream will be once the entire file is fetched. An HTTP fetcher can know this by consulting the Content-Length header before any data has been fetched.

With this information MuPDF can decide whether a file is linearized or not. (Technically, knowing the length enables us to check with the length value given in a linearized object - if these differ, the assumption is that an incremental save has taken place, thus the file is no longer linearized.)

Other than supporting the required metadata responses, the key thing that marks a stream as being progressive, is that it will not block when attempting to read data it does not have. Instead, it will throw a FZ_ERROR_TRYLATER error. This particular error code will be interpreted by the caller as an indication that it should retry the parsing of the current objects at a later time.

When a MuPDF call is made on a progressive stream, such as fz_open_document_with_stream, or fz_load_page, the caller should be prepared to handle a FZ_ERROR_TRYLATER error as meaning that more data is required before it can continue. No indication is directly given as to exactly how much more data is required, but as the caller will be implementing the progressive

fz_stream that it has passed into MuPDF to start with, it can reasonably be expected to figure out an estimate for itself.

With these mechanisms in place, a caller can repeatedly try to render each page in turn until it gets a successful result.

16.2.2 Rough renderings

Once a page has been loaded, if its contents are to be 'run' as normal (using e.g. fz_run_page) any error (such as failing to read a font, or an image, or even a content stream belonging to the page) will result in a rendering that aborts with an FZ_ERROR_TRYLATER error. The caller can catch this and display a placeholder instead.

If each pages data was entirely self-contained and sent in sequence this would perhaps be acceptable, with each page appearing one after the other. Unfortunately, the linearization procedure as laid down by Adobe does NOT do this: objects shared between multiple pages (other than the first) are not sent with the pages themselves, but rather AFTER all the pages have been sent.

This means that a document that has a title page, then contents that share a font used on pages 2 onwards, will not be able to correctly display page 2 until after the font has arrived in the file, which will not be until all the page data has been sent.

To mitigate against this, MuPDF provides a way whereby callers can indicate that they are prepared to accept an 'incomplete' rendering of the file (perhaps with missing images, or with substitute fonts).

Callers prepared to tolerate such renderings should set the 'incomplete_ok' flag in the cookie, then call fz_run_page etc as normal. If a FZ_ERROR_TRYLATER error is thrown at any point during the page rendering, the error will be swallowed, the 'incomplete' field in the cookie will become non-zero and rendering will continue. When control returns to the caller the caller can check the value of the 'incomplete' field and know that the rendering it received is not authoritative.

16.2.3 Directed downloads

If the caller has control over the fetch of the file (be it http or some other protocol), then it is possible to use byte range requests to fetch the document 'out of order'. This enables non-linearized files to be progressively displayed as they download, and fetches complete renderings of pages earlier than would otherwise be the case. This process requires no changes within MuPDF itself, but rather in the way the progressive stream learns from the attempts MuPDF makes to fetch data.

Consider for example, an attempt to fetch a hypothetical file from a server.

- The initial http request for the document is sent with a "Range:" header to pull down the first (say) 4k of the file.
- As soon as we get the header in from this initial request, we can respond
 to meta stream operations to give the length, and whether byte requests
 are accepted.
 - If the header indicates that byte ranges are acceptable the stream proceeds to go into a loop fetching chunks of the file at a time (not necessarily in-order). Otherwise the server will ignore the Range: header, and just serve the whole file.
 - If the header indicates a content-length, the stream returns that.
- MuPDF can then decide how to proceed based upon these flags and whether the file is linearized or not. (If the file contains a linearized object, and the content length matches, then the file is considered to be linear, otherwise it is not).

If the file is linear:

- We proceed to read objects out of the file as it downloads. This will
 provide us the first page and all its resources. It will also enable us
 to read the hint streams (if present).
- Once we have read the hint streams, we unpack (and sanity check) them to give us a map of where in the file each object is predicted to live, and which objects are required for each page. If any of these values are out of range, we treat the file as if there were no hint streams.
- If we have hints, any attempt to load a subsequent page will cause MuPDF to attempt to read exactly the objects required. This will cause a sequence of seeks in the fz_stream followed by reads. If the stream does not have the data to satisfy that request yet, the stream code should remember the location that was fetched (and fetch that block in the background so that future retries will succeed) and should raise an FZ_ERROR_TRYLATER error.
 - [Typically therefore when we jump to a page in a linear file on a byte request capable link, we will quickly see a rough rendering, which will improve fairly fast as images and fonts arrive.]
- Regardless of whether we have hints or byte requests, on every fz_load_page call MuPDF will attempt to process more of the stream (that is assumed to be being downloaded in the background). As linearized files are guaranteed to have pages in order, pages will gradually become available. In the absence of byte requests and hints however, we have no way of getting resources early, so the renderings for these pages will remain incomplete until much more of the file has arrived.

[Typically therefore when we jump to a page in a linear file on a non byte request capable link, we will see a rough rendering for that page as soon as data arrives for it (which will typically take much longer than would be the case with byte range capable downloads), and that will improve much more slowly as images and fonts may not appear until almost the whole file has arrived.]

 When the whole file has arrived, then we will attempt to read the outlines for the file.

For a non-linearized PDF on a byte request capable stream:

- MuPDF will immediately seek to the end of the file to attempt to read the trailer. This will fail with a FZ_ERROR_TRYLATER due to the data not being here yet, but the stream code should remember that this data is required and it should be prioritized in the background fetch process.
- Repeated attempts to open the stream should eventually succeed therefore. As MuPDF jumps through the file trying to read first the xrefs, then the page tree objects, then the page contents themselves etc, the background fetching process will be driven by the attempts to read the file in the foreground.

[Typically therefore the opening of a non-linearized file will be slower than a linearized one, as the xrefs/page trees for a non-linear file can be 20%+ of the file data. Once past this initial point however, pages and data can be pulled from the file almost as fast as with a linearized file.]

For a non-linearized PDF on a non-byte request capable stream:

— MuPDF will immediately seek to the end of the file to attempt to read the trailer. This will fail with a FZ_ERROR_TRYLATER due to the data not being here yet. Subsequent retries will continue to fail until the whole file has arrived, whereupon the whole file will be instantly available.

[This is the worst case situation - nothing at all can be displayed until the entire file has downloaded.]

16.2.4 Example implementation

An example implementation of a fetcher process can be found in curl-stream.c. This implements a fz_stream using the popular 'curl' http fetching library.

The structure of this process broadly behaves as follows:

We consider the file as an (initially empty) buffer which we are filling by
making requests. In order to ensure that we make maximum use of our download link, we ensure that whenever one request finishes, we immediately

launch another. Further, to avoid the overheads for the request/response headers being too large, we may want to divide the file into 'chunks', perhaps 4 or 32k in size.

- We have a receiver thread that sits there in a loop requesting chunks to fill this buffer. In the absence of any other impetus the receiver should request the next chunk of data from the file that it does not yet have, following the last fill point. Initially we start the fill point at the beginning of the file, but this will move around based on the requests made of the progressive stream.
- Whenever MuPDF attempts to read from the stream, we check to see if we have data for this area of the file already. If we do, we can return it. If not, we remember this as the next 'fill point' for our receiver process and throw a FZ_ERROR_TRYLATER error.
- The caller process is responsible for implementing the fetcher, hence it can know when more data has arrived. This can trigger retries of renderings intelligently, thus avoiding retrying renders when the incoming data is stalled.

Chapter 17

Fonts

17.1 Overview

Fonts are represented in MuPDF by the abstract fz_font type. This reference counted structure, encapsulates the basic information about a font, specifically:

Glyph list Each font consists of a list of glyphs.

- Glyph data How to draw each glyph. In traditional fonts this information is known as the 'Outline data' (or 'Outlines'), but some font types (such as Type 3 fonts from PDF) can encapsulate other data, such as images and colors too.
- Unicode map Most (but not all) fonts contain information that enables glyphs to be mapped to/from the Unicode code points they represent. Without such information, it can be impossible to meaningfully extract text information from a document (such as for cut and paste).
- **Font BBox** All fonts include information for a bounding box that covers all the glyphs within a font. Sadly this can frequently be inaccurate or incorrect, so should be treated with distrust.
- **Glyph advances** All fonts contain simple Glyph advance information how far to move the text cursor after having drawn a given glyph. This information ensures that successive characters are properly spaced w.r.t. each other.
- Kerning data Most fonts contain simple kerning data; this allows for the glyph advance between any 2 glyphs to be adjusted based upon particular glyph values. The classic example of kerning is noting that the spacing between A and the left hand edge of its following letter is typically different between AV and AN.

Shape data Some fonts allow for the automatic 'shaping' of glyph sequences. The trivial example of this in western fonts is that the letters 'f' and 'i' can be combined into a single ligature glyph 'fi'. For many non Latin scripts (especially Indic and south east Asian scripts), this procedure happens to a far greater extent. This can be as simple as the incorporation of diacritical marks, or as complex as the complete rearrangement or replacement of glyph sequences to give different appearances on the final rendered page. This process is know as 'font shaping' and the data required to perform this is font specific, and is optionally encapsulated within fonts themselves.

The fz_font does not include information about the particular size that a font is used at on the page, nor the basic colour used to render a font. It is therefore typical to see fz_fonts passed around the system paired with both a size (and/or transformation matrix), a colorspace, and color definition.

MuPDF uses Freetype to handle most of its font rendering. For Type 3 PDF fonts, it renders them itself. Font shaping is done using the HarfBuzz library.

17.2 Inbuilt Fonts

The exact set of fonts built in to any version of MuPDF is configurable (See chapter 18 Build configuration).

For PDF, we build in a basic set of fonts licensed from URW. Originally the PDF specification suggested that 14 standard fonts should be available on all readers, and that any other fonts should be embedded within files. This recommendation has since been updated to suggest that all fonts (or at least the required subset thereof) are embedded in all files. Nonetheless it is still common to find many PDF files that ask for fonts that are not embedded.

In order to cope with the widest range of scripts possible, MuPDF is supplied with (and can optionally include) a selection of the 'Noto' fonts from Google.

If this would take too much space on your target system, an alternative is to use the supplied DroidSansFallback font (also from Google) which is a good trade-off between size and coverage.

MuPDF does not, by default, make use of fonts present on the underlying system (for instance, on Windows, MuPDF will not look for fonts in C:/Windows/). Should you wish to implement this kind of 'system font' loading, however, MuPDF does provide hooks for this to be done. The fz_install_load_system_font_funcs call takes a set of function pointers that can be used for this purpose.

17.3 Implementation

The implementation details of fz_fonts are still in flux, so it would be inappropriate to document them in any more detail at the moment.

Chapter 18

Build configuration

18.1 Overview

By default, MuPDF builds almost the most capable version of itself that it can. This can result in larger library sizes than are actually required for any given application. Some care has been taken in the design of MuPDF to try to allow linkers to intelligently drop sections of the code that are not actually required, but nonetheless it can still be worthwhile tuning builds.

18.2 Configuration file

To simply the task of tuning builds, all the configuration options have been gathered into a single header file, include/mupdf/fitz/config.h.

This file is in two halves; the top half consists of a sequence of pairs of comments, and commented out #defines, the second half consists of #ifdef logic to make sense of the #define values set.

The configuration options available at build time are therefore described by the pairs in the first half of the file.

Each one of these pairs has first a comment that describes what the following configuration options do, and then commented out #defines that sets the configuration options to their defaults.

If an integrator wants to change a build option from the default, they have two options. Firstly, and most simply, they can edit the first half of the file to set the required #defines by uncommenting the relevant line and editing it. Alternatively, they can arrange for these values to be predefined by the compiler, normally by editing the CFLAGS defined in the Makefile. This latter method has

the advantage of not requiring any edits to the source itself, and of allowing different configurations to be built from the same source tree.

The second half of the file should never need to be edited.

18.3 Plotter selection

The first section of the file deals with the plotters that are to be built into MuPDF.

```
/*
Choose which plotters we need.
By default we build the greyscale, RGB and CMYK plotters in, but omit the arbitrary plotters. To avoid building plotters in that aren't needed, define the unwanted FZ_PLOTTERS_... define to 0.
*/
/* #define FZ_PLOTTERS_G 1 */
/* #define FZ_PLOTTERS_RGB 1 */
/* #define FZ_PLOTTERS_CMYK 1 */
/* #define FZ_PLOTTERS_N 0 */
```

The plotter selection built into MuPDF will determine which formats can be rendered too. If, for instance, you are using MuPDF to target a greyscale only device (say, an e-ink screen for a greyscale ebook reader) then there is no need to ever render in color, and the RGB and CMYK options can be disabled.

Similarly, if you know you are targeting screen display, then the greyscale and CMYK plotters can be omitted.

The N plotters are generic plotters capable of coping with any color depth, but are not as optimised for rendering to G, RGB or CMYK as the specific sets of plotters for those depths. You may find that you can trade some speed for space by enabling the N plotters and disabling the other plotters.

If you wish to render to color spaces other than G, RGB or CMYK, you must enable the N plotters.

At least 1 plotter family must be defined in any build. If all the plotters are specifically disabled, then the N plotters will be enabled.

18.4 Document handlers

Support for the different document types supported by MuPDF is given by a set of document handlers (see chapter 14 The Document Handler interface). Each handler type can be enabled or disabled as required:

```
/*
    Choose which document handlers to include.
    By default all but GPRF are enabled. To avoid building unwanted ones, define FZ_ENABLE_... to 0.
*/
/* #define FZ_ENABLE_PDF 1 */
/* #define FZ_ENABLE_XPS 1 */
/* #define FZ_ENABLE_SVG 1 */
/* #define FZ_ENABLE_CBZ 1 */
/* #define FZ_ENABLE_IMG 1 */
/* #define FZ_ENABLE_TIFF 1 */
/* #define FZ_ENABLE_HTML 1 */
/* #define FZ_ENABLE_EPUB 1 */
/* #define FZ_ENABLE_EPUB 1 */
/* #define FZ_ENABLE_GPRF 1 */
```

For instance to omit support for HTML, we would define FZ_ENABLE_HTML to be 0. Note that some document handlers share substantial parts of their code with other ones; for example the HTML and EPub document ages share a large amount of code, so disabling just one of them will not make much difference to the overall code size.

18.5 **JPEG 2000 support**

Some security minded applications choose to disable JPEG2000 decoding. While MuPDF ships with the latest version of the JPEG2000 decoder we use, with all known security patches applied, it is possible to disable this entirely if required.

```
/*
   Choose whether to enable JPEG2000 decoding.
   By default, it is enabled, but due to frequent security
   issues with the third party libraries we support disabling
   it with this flag.
*/
/* #define FZ_ENABLE_JPX 1 */
```

Note that if this is disabled, MuPDF will no longer be able to decode all PDF files. If you are authoring your own PDF files (or you know that they do not make use of JPEG2000, then disabling this will have no effect).

18.6 Javascript

PDF files can make use of Javascript for form data validation. If such interactive features are not required then the inclusion of an (albeit tiny) javascript engine

serves no purpose. Accordingly, it can be disabled by setting ${\tt FZ_ENABLE_JS}$ to 0

```
/*
    Choose whether to enable JavaScript.
    By default JavaScript is enabled both for mutool and PDF
        interactivity.
*/
/* #define FZ_ENABLE_JS 1 */
```

18.7 Fonts

By far the largest impact on MuPDFs size is given by choosing which fonts to include. Accordingly, there are a range of different options:

```
/*
   Choose which fonts to include.
   By default we include the base 14 PDF fonts,
   DroidSansFallback from Android for CJK, and
   Charis SIL from SIL for epub/html.
   Enable the following defines to AVOID including
   unwanted fonts.
/* To avoid all noto fonts except CJK, enable: */
/* #define TOFU */
/* To skip the CJK font, enable: (this implicitly enables TOFU_CJK_EXT
    and TOFU_CJK_LANG) */
/* #define TOFU_CJK */
/* To skip CJK Extension A, enable: (this implicitly enables
    TOFU_CJK_LANG) */
/* #define TOFU_CJK_EXT */
/* To skip CJK language specific fonts, enable: */
/* #define TOFU_CJK_LANG */
/* To skip the Emoji font, enable: */
/* #define TOFU_EMOJI */
/* To skip the ancient/historic scripts, enable: */
/* #define TOFU_HISTORIC */
/* To skip the symbol font, enable: */
/* #define TOFU_SYMBOL */
/* To skip the SIL fonts, enable: */
```

```
/* #define TOFU_SIL */
/* To skip the Base14 fonts, enable: */
/* #define TOFU_BASE14 */
/* (You probably really don't want to do that except for measurement purposes!) */
```

If documents require a font that is not present, systems will try to 'fallback' to alternative ones. When this is not always successful (or indeed possible) unknown glyphs are often rendered as empty boxes, known informally in the typographic world as 'Tofu'.

By default MuPDF includes all the fonts it knows about. The configuration options are therefore a matter of choosing which scripts should instead be rendered as tofu.

Accordingly, to drop support for rendering emoji characters, you'd define ${\tt TOFU_EMOJI}$.

The largest set of fonts are those for the wide range of worldwide scripts given by the Google Noto fonts. These can be omitted by defining TOFU.

Chapter 19

PDF Interpreter Details

19.1 Overview

The PDF document handler is built upon a large corpus of code within MuPDF that deals specifically with the objects, structures and operators found within a document. This code is collectively known as the PDF interpreter.

While it is perfectly possible to use MuPDF to open documents and render pages from a PDF file without understanding anything at all about the PDF interpreter, there are many situations where deeper access to the interpreter can be advantageous.

For example, in order for PDF documents to have their pages rearranged, or files embedded/extracted from them, simple access to the underlying PDF document structure is required.

In fact, the access given to a PDF document structure is such that almost any operation can be coded for.

19.2 PDF Document

The first step in dealing with a PDF document is to get a handle to it. This is done by opening it as normal using fz_open_document to get a fz_document pointer. To 'promote' this to a pdf_document, we use the pdf_specifics call:

```
/*
    pdf_specifics: down-cast a fz_document to a pdf_document.
    Returns NULL if underlying document is not PDF
*/
pdf_document *pdf_specifics(fz_context *ctx, fz_document *doc);
```

If pdf_specifics returns non-NULL, then you know that you are indeed dealing with a PDF format document.

Having a pdf_document pointer allows a series of new APIs to be called (see include/mupdf/pdf/document.h).

In terms of handling a PDF file via its constituent objects, one of the most useful is:

```
pdf_obj *pdf_trailer(fz_context *ctx, pdf_document *doc);
```

This obtains a pointer to a representation of the trailer dictionary object.

19.3 PDF Objects

PDF files are made up of a series of objects. These objects can be in many different types, including dictionaries, streams, numbers, booleans, names, strings etc. For full details, see 'The PDF Reference Manual'.

MuPDF represents all of these as a pdf_obj pointer. Such pointers are reference counted in the usual way:

```
pdf_obj *pdf_keep_obj(fz_context *ctx, pdf_obj *obj);
void pdf_drop_obj(fz_context *ctx, pdf_obj *obj);
```

Given such a pointer, the actual type of the object can be obtained using:

```
int pdf_is_null(fz_context *ctx, pdf_obj *obj);
int pdf_is_bool(fz_context *ctx, pdf_obj *obj);
int pdf_is_int(fz_context *ctx, pdf_obj *obj);
int pdf_is_real(fz_context *ctx, pdf_obj *obj);
int pdf_is_number(fz_context *ctx, pdf_obj *obj);
int pdf_is_name(fz_context *ctx, pdf_obj *obj);
int pdf_is_string(fz_context *ctx, pdf_obj *obj);
int pdf_is_array(fz_context *ctx, pdf_obj *obj);
int pdf_is_dict(fz_context *ctx, pdf_obj *obj);
int pdf_is_indirect(fz_context *ctx, pdf_obj *obj);
int pdf_is_stream(fz_context *ctx, pdf_obj *obj);
```

These all return non-zero if the object is of the tested type, and zero otherwise.

To extract the data from a PDF object, you can use one of the following functions:

```
/* safe, silent failure, no error reporting on type mismatches */
int pdf_to_bool(fz_context *ctx, pdf_obj *obj);
int pdf_to_int(fz_context *ctx, pdf_obj *obj);
fz_off_t pdf_to_offset(fz_context *ctx, pdf_obj *obj);
```

```
float pdf_to_real(fz_context *ctx, pdf_obj *obj);
char *pdf_to_name(fz_context *ctx, pdf_obj *obj);
char *pdf_to_str_buf(fz_context *ctx, pdf_obj *obj);
int pdf_to_str_len(fz_context *ctx, pdf_obj *obj);
```

It is, in fact, safe to call any of these functions on any pdf_obj pointer. If the object is not of the expected type, a 'safe' default will be returned.

19.3.1 Arrays

Array objects consist of lists of other objects, each of which can potentially be of a different type. Accordingly, we have a function to enquire how long a list we have:

```
int pdf_array_len(fz_context *ctx, pdf_obj *array);
```

Armed with this knowledge we can then fetch any object we want from within the array.

```
pdf_obj *pdf_array_get(fz_context *ctx, pdf_obj *array, int i);
```

Ideally i should be between 0 and length-1 (though the function will just return NULL if an out of range element is requested).

Note that the pdf_obj reference returned by this function is merely borrowed. That is to say, if you wish to keep the object pointer around for more than the immediate lifespan of the call, you should manually call pdf_keep_obj to keep it, and later pdf_drop_obj to dispose of it.

An object can be inserted into an array at a given index, using:

```
void pdf_array_insert(fz_context *ctx, pdf_obj *array, pdf_obj *obj, int
   index);
```

Any objects after this point are shuffled up the array. Alternatively an object can be put into an array at a given point, overwriting any object that is there already:

```
void pdf_array_put(fz_context *ctx, pdf_obj *array, int i, pdf_obj *obj);
```

If the array needs to be extended it will be, and any intervening objects will be created as 'null'. Alternatively objects can be appended to an array using:

```
void pdf_array_push(fz_context *ctx, pdf_obj *array, pdf_obj *obj);
```

In all these cases, the array will take new references to the object passed in that is, after the call, both the array and the caller will hold references to the object. In cases where the object to be inserted is a 'borrowed' reference, this is ideal.

In other cases, where the ownership of the object reference should be passed down into the array, we have alternative formulations of those functions:

```
void pdf_array_insert_drop(fz_context *ctx, pdf_obj *array, pdf_obj
    *obj, int index);
void pdf_array_put_drop(fz_context *ctx, pdf_obj *array, int i, pdf_obj
    *obj);
void pdf_array_push_drop(fz_context *ctx, pdf_obj *array, pdf_obj *obj);
```

These functions are so named because they are equivalent to first inserting/putting/pushing the object, and then dropping it, with the nice side effect that any errors encountered during the push still result in the object being correctly dropped, often saving the caller from having to wrap the call in an fz_try/fz_catch clause.

19.4 PDF Operator Processors

Graphical content within a PDF file is given as streams of PDF "operators". These operators describe marking operations on a conceptual page. In order to display a PDF file the interpreter needs to run through these operators processing each in turn.

In addition, certain manipulations of PDF operations (like redaction, sanitisation and appending, for example) are best done by operating directly on these operators streams. The alternative scheme, of first converting the operators to graphical objects, then resynthesising an operator stream from that leads to problems with round trip conversions, and the potential loss of structure.

For this reason, the PDF interpreter within MuPDF is structured around an extensible class of pdf_processors. A pdf_processor is a set of functions, one for each operator. The interpreter runs through the operators and handles them by calling the appropriate functions.

By changing the pdf_processor in use, we can therefore change what the effect of interpreting the page is.

MuPDF contains three different pdf_processor implementations, though the system is deliberately open ended, and more can be supplied by any user of the library. Some can even be chained together in powerful ways.

19.4.1 Run processor

The first, and most commonly used processor is the pdf_run_processor. This processor has the effect of interpreting the incoming operators and turning them into device calls (i.e. graphical objects rendered on a page).

When using the standard fz_run_page (and similar) function(s) this is the pdf_processor that is used automatically. It can still be useful to create these manually, especially when coupling them with a pdf_filter_processor (or similar).

Such processors can be created using:

```
/*
    pdf_new_run_processor: Create a new "run" processor. This maps
    from PDF operators to fz_device level calls.

dev: The device to which the resulting device calls are to be
    sent.

ctm: The initial transformation matrix to use.

usage: A NULL terminated string that describes the 'usage' of
    this interpretation. Typically 'View', though 'Print' is also
    defined within the PDF reference manual, and others are possible.

gstate: The initial graphics state.

nested: The nested depth of this interpreter. This should be
    0 for an initial call, and will be incremented in nested calls
    due to Type 3 fonts.

*/
pdf_processor *pdf_new_run_processor(fz_context *ctx, fz_device *dev,
    const fz_matrix *ctm, const char *usage, pdf_gstate *gstate, int
    nested);
```

The component parts of this processor are generally functions named pdf_run_..., and frequently call back into the main pdf interpreter (to handle nested content streams as found in XObjects etc).

19.4.2 Filter processor

The pdf_filter_processor is an example of a processor that allows chaining. PDF operators are fed into the processor, which then 'filters' them and passes them out to another processor.

```
/*
   pdf_new_filter_processor: Create a filter processor. This
```

filters the PDF operators it is fed, and passes them down (with some changes) to the child filter.

The changes made by the filter are:

- * No operations are allowed to change the top level gstate. Additional q/\mathbb{Q} operators are inserted to prevent this.
- * Repeated/unnecessary colour operators are removed (so, for example, "0 0 0 rg 0 1 rg 0.5 g" would be sanitised to "0.5 g")

The intention of these changes is to provide a simpler, but equivalent stream, repairing problems with mismatched operators, maintaining structure (such as BMC, EMC calls) and leaving the graphics state in an known (default) state so that subsequent operations (such as synthesising new operators to be appended to the stream) are easier.

The net graphical effect of the filtered operator stream should be identical to the incoming operator stream.

chain: The child processor to which the filtered operators will be fed.

old_res: The incoming resource dictionary.

new_res: An (initially empty) resource dictionary that will be populated by copying entries from the old dictionary to the new one as they are used. At the end therefore, this contains exactly those resource objects actually required.

```
pdf_processor *pdf_new_filter_processor(fz_context *ctx, pdf_processor
    *chain, pdf_obj *old_res, pdf_obj *new_res);
```

Similar filtering processors could be written for other tasks, such as discarding all the text from a page, changing all occurrences of a particular font for another, or converting all the objects on a page to a given colorspace.

The component parts of this processor are generally functions named pdf_filter_....

19.4.3 Buffer processor

The fz_buffer_processor is designed to produce an fz_buffer from an input stream of operators. This is frequently found coupled with a

fz_filter_processor, to gather up the filtered version of the operator stream ready for reinsertion into the document.

```
/*
    pdf_new_buffer_processor: Create a buffer processor. This
    collects the incoming PDF operator stream into an fz_buffer.

buffer: The (possibly empty) buffer to which operators will be
    appended.

ahxencode: If 0, then image streams will be send as binary,
    otherwise they will be asciihexencoded.

*/
pdf_processor *pdf_new_buffer_processor(fz_context *ctx, fz_buffer
    *buffer, int ahxencode);
```

This is built using a fz_output_processor.

19.4.4 Output processor

The fz_output_processor is designed to produce an output stream from an input stream of operators. This is frequently found coupled with a fz_filter_processor, to gather up the filtered version of the operator stream ready for reinsertion into the document.

```
/*
    pdf_new_output_processor: Create an output processor. This
    sends the incoming PDF operator stream to an fz_output stream.

out: The output stream to which operators will be sent.

ahxencode: If 0, then image streams will be send as binary,
    otherwise they will be asciihexencoded.

*/
pdf_processor *pdf_new_output_processor(fz_context *ctx, fz_output *out,
    int ahxencode);
```

The component parts of this processor are generally functions named $\mathtt{pdf_out_...}$

19.5 Copying objects between PDF documents

PDF objects vary in complexity from simple values (booleans, integers, floats, names, etc) to more complex entities (arrays, dictionaries, streams, indirect references etc). While the simplest object types are independent of any particular

document, the more complex types are implicitly bound to the document in which they appear.

Most of the time this is all taken care of automatically by the MuPDF core, but special care must be taken when trying to copy objects from one PDF file to another.

19.5.1 The problem

To illustrate this, imagine that you have 2 PDF documents open, docA and docB. Imagine that we want to lookup an object from docA, and insert into docB. A naive code fragment to do this might be:

This may actually work in limited cases, such as:

```
1 0 obj
<<
    /Type /Catalog
    /Pages 3 0 R
    /Metadata 9 0 R
    /Example true
>>
endobj
...
trailer
<<
    /Root 1 0 R
>>
```

The value of Root/Example is read as true, which can safely be written into another file.

This can easily fall down though, as can be seen in more complex cases:

```
2 0 obj
/Complex
endobj
1 0 obj
<<
/Type /Catalog
/Pages 3 0 R
```

```
/Metadata 9 0 R
/Example [ (More) 2 0 R ]
>>
endobj
...
trailer
<<
    /Root 1 0 R
>>
```

In this case the value of Root/Example is read as an array of 2 elements; the first element being the string "More", and the second being a reference to object 2 in the file.

If this was to be written directly into the new file, we'd still have an array of 2 elements, with the first element being the string "More". The second would refer to whatever object 2 in the new file happens to be.

The solution to this requires us to walk the directed (possibly cyclic) graph of child objects within the object to be copied from one file to another, and to 'deep copy' the contents.

19.5.2 Grafting objects

This solution is implemented within MuPDF as:

```
A \texttt{pdf\_graft\_map} is a mechanism for allowing multiple objects from one file to be 'grafted' into another, without unnecessary duplication of data.

/*

pdf_graft_object: Return a deep copied object equivalent to the supplied object, suitable for use within the given document.

dst: The document in which the returned object is to be used.

obj: The object deep copy.

Note: If grafting multiple objects, you should use a pdf_graft_map to avoid potential duplication of target objects.

*/
pdf_obj *pdf_graft_object(fz_context *ctx, pdf_document *dst, pdf_obj *obj);
```

This takes an object in one document, and returns an equivalent object that can safely be written into document dst. Any indirect references within the original object will have been copied across as new objects within dst as a side effect of this call.

The 'safe' version of the code given above would therefore be:

19.5.3 A further problem

Even this is not perfect. Consider the example:

```
2 0 obj
/Complex
endobj
1 0 obj
<<
    /Type /Catalog
   /Pages 3 0 R
   /Metadata 9 0 R
   /Example [ (More) 2 0 R ]
   /Example2 [ (Even more) 2 0 R ]
>>
endobj
...
trailer
<<
    /Root 1 0 R
>>
```

Suppose we want to copy both Root/Example and Root/Example2 between files. If we read the first of these, and write it, it will cause object 2 to be copied to the new file (as a new object, 99 say). When we read the second one, and write that, it will cause object 2 to be copied into the second file again (as object 100 perhaps).

In the example above, with the object consisting of a single name this duplication may not matter, but when you consider that objects might be dictionaries with lots of contents, or even streams with many megabytes of data attached, the problem becomes clear.

The solution to this is to use a pdf_graft_map.

19.5.4 Graft maps

A pdf_graft_map is a mapping from one pdf_document to another that ensures objects in the source document are only ever copied into the target document at most once.

```
pdf_new_graft_map: Prepare a graft map object to allow objects
   to be deep copied from one document to the given one, avoiding
   problems with duplicated child objects.
   dst: The document to copy objects to.
   Note: all the source objects must come from the same document.
*/
pdf_graft_map *pdf_new_graft_map(fz_context *ctx, pdf_document *dst);
   pdf_drop_graft_map: Drop a graft map.
void pdf_drop_graft_map(fz_context *ctx, pdf_graft_map *map);
   pdf_graft_mapped_object: Return a deep copied object equivalent
   to the supplied object, suitable for use within the target
   document of the map.
   map: A map targeted at the document in which the returned
   object is to be used.
   obj: The object deep copy.
   Note: Copying multiple objects via the same graft map ensures
   that any shared child are not duplicated more than once.
pdf_obj *pdf_graft_mapped_object(fz_context *ctx, pdf_graft_map *map,
    pdf_obj *obj);
A 'safe' version of the example given earlier that copies both Root/Example and
Root/Example2 would therefore be:
pdf_graft_map *map = pdf_new_graft_map(ctx, docB);
pdf_dict_putp_drop(ctx,
                   pdf_trailer(ctx, docB),
                   "Root/Example",
                   pdf_graft_mapped_object(
                                    ctx, map,
                                    pdf_dict_getp(ctx,
```

XPS Interpreter Details

20.1 Overview

The XPS document handler differs from the PDF document handler in that its sole interface is that exposed through the fz_document class.

XPS files are zip format archives with a specific layout of files. As well as opening xps (and .oxps) files (archives) directly, MuPDF will also open unpacked files by pointing fz_open_document at the "rels/.rels" file in the unpacked directory tree.

EPub/HTML Interpreter Details

The Epub and HTML document handlers are based upon the same layout code. With the exception of a few global configuration settings, their sole interfaces are those exposed through the fz_document class.

21.1 CSS rules

The layout follows simple CSS rules. On opening both Epub and HTML documents CSS rules are read from a series of locations in defined order.

Firstly, an inbuilt set of CSS (see html_default_css) is read for all files with the exception of those identified as FictionBook 2 format which have their own special case rules (see fb2_default_css).

Next, the CSS rules from the document itself are read. If you would rather avoid this, it can be suppressed using:

```
/*
    fz_set_use_document_css: Toggle whether to respect document styles
    in HTML and EPUB.
*/
void fz_set_use_document_css(fz_context *ctx, int use);
```

Finally a set of 'user' CSS is read. This defaults to empty, but can be supplied using:

/*

Thus the user CSS is the last to be read and can potentially override all the settings made by the defaults and document CSS.

21.2 Shaped text

The text read from the document is held as Unicode, and displayed using the built in fonts. By default these are the Google Noto fonts, which are in Open-Type format. One of the features of Open-Type fonts is the ability to offer excellent typographical output for a wide range of scripts due to the inbuilt automated tables to control font shaping.

Font shaping allows a font to choose a different set of output glyphs (with highly customised positioning) based on the context within which an input Unicode character (or series of characters) are used.

Some languages use this to add diacritical marks (in particular Vietnamese). Others (such as Arabic) may use it to ensure that characters join smoothly. Still others (such as Indic languages) completely change the appearance of groups of input characters by combining them into single shapes that represent multiple characters at once.

The complex rules that control this are encoded as tables within the OpenType format fonts. The interpretation and application of these tables/rules is handled for us using the HarfBuzz library.

21.3 Bidirectional text

While Western languages are written left to right, others are written (broadly) right to left. Even in right to left languages, specific regions of text (such as numbers) are written left to right. The behaviour of 'enclosing' operators brackets adds additional complexity.

The rules governing exactly how layout should proceed when faced with a combination of left to right and right to left text are complex to say the least, but fortunately an algorithm has been published by the Unicode consortium to specify exactly how layout should proceed in any given circumstance (as 'Technical Recommendation 9').

MuPDF contains an implementation of this algorithm derived from the example code provided with this recommendation.

SVG Interpreter Details

The SVG interpreter offers very little API other than that exposed through the fz_document interface.

The sole extras are defined to facilitate the use of SVGs as illustrations within EPub files.

```
/*
    Parse an SVG document into a display-list.
*/
fz_display_list *fz_new_display_list_from_svg(fz_context *ctx, fz_buffer
    *buf, float *w, float *h);

/*
    Create a scalable image from an SVG document.
*/
fz_image *fz_new_image_from_svg(fz_context *ctx, fz_buffer *buf);
```

These enable the HTML agent to easily create an fz_image out of an SVG. This fz_image has the property that it remains scalable, and hence will not appear pixellated if the document is reflowed to different dimensions.

MuTool

23.1 Overview

Mutool is a collection of useful command line utilities rolled into a single executable.

As explained earlier MuPDF is a C library that encapsulates all the smarts required to open/render/manipulate document files of a range of a formats. This means that most utilities using it are reduced to very thin shells that just call down to the library.

When you consider the additional factor of the size of the resources built into MuPDF (fonts, CMAPs etc), this means it makes a lot of sense to build a single executable with multiple utilities sharing a single copy of the library.

If you run mutool at the command line with no arguments, a list of the possible options will be displayed:

\$ mutool

```
usage: mutool <command> [options]
       clean -- rewrite pdf file
       convert -- convert document
                -- create pdf document
       create
                -- convert document
       draw
       extract -- extract font and image resources
                -- show information about pdf resources
       info
                -- merge pages from multiple pdf sources into a new pdf
                -- show information about pdf pages
       portfolio -- manipulate PDF portfolios
                -- split large page into many tiles
       poster
       run
                -- run javascript
                -- show internal pdf objects
       show
```

23.2 Clean

The clean utility will produce a cleaned version of an input PDF. It can apply a range of different options, a full list of which can be obtained by running mutool clean with no options:

\$ mutool clean usage: mutool clean [options] input.pdf [output.pdf] [pages] -p garbage collect unused objects -g in addition to -g compact xref table -gg in addition to -gg merge duplicate objects -ggg in addition to $\ensuremath{\operatorname{\text{-}ggg}}$ check streams for duplication -gggg -1 linearize PDF ascii hex encode binary streams -a -d decompress streams -z deflate uncompressed streams -f compress font streams -i compress image streams -s clean content streams pages comma separated list of page numbers and ranges

The arguments here are fairly self explanatory, and usage is best explained with a few examples.

Firstly, and most simply, clean can be used to try to repair broken files. Many PDF files found in the wild are broken - sometimes because of having been corrupted, either by transmission/archiving problems, but a disappointing amount by just having been created by bad PDF writing software. Running a clean pass will attempt to repair the files:

```
mutool clean in.pdf out.pdf
```

Individual pages (or page ranges) can be extracted from a PDF. For example:

```
mutool clean -gggg in.pdf out.pdf 1-10,12
```

That will extract the pages 1 to 10, and page 12 of in.pdf and output it into a new out.pdf. The -gggg options ensure that unused objects will be dropped from the PDF.

An 8 page PDF might be rearranged into booklet form using:

```
mutool clean -gggg in.pdf out.pdf 8,1,7,2,6,3,5,4
```

Finally, a more exotic, but very common example; if someone reports a problem seen on page 4 of a given PDF, the following command will extract that page, and expand the content streams, without decompressing the images or the fonts:

```
mutool clean -difgggg in.pdf out.pdf 4
```

characters

If this file still exhibits the same problem, it is generally far easier to debug through it than the original one was.

23.3 Convert

The convert utility performs a similar task to the draw utility, using a different internal mechanism (the document writer interface). Which is better for any given task is often a matter of taste.

```
$ mutool convert
mutool convert version 1.11
Usage: mutool convert [options] file [pages]
              password
       -p -
       -A -
              number of bits of antialiasing (0 to 8)
       -W -
              page width for EPUB layout
              page height for EPUB layout
       -S -
              font size for EPUB layout
       -U -
              file name of user stylesheet for EPUB layout
       -x
              disable document styles for EPUB layout
              output file name (%d for page number)
       -F -
              output format (default inferred from output file name)
                     png, pnm, pgm, ppm, pam, tga, pbm, pkm,
                     pdf, svg, cbz
       -0 -
              comma separated list of options for output format
       pages comma separated list of page ranges (N=last page)
Common raster format output options:
       rotate=N: rotate rendered pages N degrees counterclockwise
       resolution=N: set both X and Y resolution in pixels per inch
       x-resolution=N: X resolution of rendered pages in pixels per inch
       y-resolution=N: Y resolution of rendered pages in pixels per inch
       width=N: render pages to fit N pixels wide (ignore resolution
       height=N: render pages to fit N pixels tall (ignore resolution
           option)
       colorspace=(gray|rgb|cmyk): render using specified colorspace
       alpha: render pages with alpha channel and transparent background
Structured text output options:
       preserve-ligatures: do not expand all ligatures into constituent
```

```
preserve-whitespace: do not convert all whitespace characters
           into spaces
PDF output options:
       decompress: decompress all streams (except compress-fonts/images)
       compress: compress all streams
       compress-fonts: compress embedded fonts
       compress-images: compress images
       ascii: ASCII hex encode binary streams
       pretty: pretty-print objects with indentation
       linearize: optimize for web browsers
       sanitize: clean up graphics commands in content streams
       garbage: garbage collect unused objects
       or garbage=compact: ... and compact cross reference table
       or garbage=deduplicate: ... and remove duplicate objects
SVG output options:
       text=text: Emit text as <text> elements (inaccurate fonts).
       text=path: Emit text as <path> elements (accurate fonts).
       no-reuse-images: Do not reuse images using <symbol> definitions.
```

23.4 Create

The create tool allows PDFs to generated from simple text files full of pdf operator streams plus formatted comments.

```
$ mutool create
usage: mutool create [-o output.pdf] [-O options] page.txt [page2.txt
    ...]
               name of PDF file to create
       -0 -
            comma separated list of output options
       page.txt content stream with annotations for creating resources
Content stream special commands:
       %%MediaBox LLX LLY URX URY
       %%Rotate Angle
       %%Font Name Filename (or base 14 font name)
       %%Image Name Filename
PDF output options:
       decompress: decompress all streams (except compress-fonts/images)
       compress: compress all streams
       compress-fonts: compress embedded fonts
       compress-images: compress images
       ascii: ASCII hex encode binary streams
       pretty: pretty-print objects with indentation
       linearize: optimize for web browsers
```

```
sanitize: clean up graphics commands in content streams garbage: garbage collect unused objects or garbage=compact: ... and compact cross reference table or garbage=deduplicate: ... and remove duplicate objects
```

23.5 Draw

The draw utility is the most commonly used tool, capable of converting/rendering documents to a range of bitmap and vector formats. It performs a similar task to the convert utility, using a different set of internal mechanisms. Which is better for any given task is often a matter of taste.

```
$ mutool draw
mudraw version 1.11
Usage: mudraw [options] file [pages]
              password
       -p -
              output file name (%d for page number)
       -0 -
       -F -
              output format (default inferred from output file name)
              raster: png, tga, pnm, pam, pbm, pkm, pwg, pcl, ps
              vector: svg, pdf, trace
              text: txt, html, stext
       -s -
              show extra information:
              m - show memory use
              t - show timings
              f - show page features
              5 - show md5 checksum of rendered image
       -R -
              rotate clockwise (default: 0 degrees)
              resolution in dpi (default: 72)
       -r -
              width (in pixels) (maximum width if -r is specified)
              height (in pixels) (maximum height if -r is specified)
       -h -
              fit width and/or height exactly; ignore original aspect
       -f -
       -B -
              maximum band_height (pgm, ppm, pam, png output only)
       -W -
              page width for EPUB layout
       -H -
              page height for EPUB layout
       -s -
              font size for EPUB layout
       −U −
              file name of user stylesheet for EPUB layout
       -X
              disable document styles for EPUB layout
              colorspace (mono, gray, grayalpha, rgb, rgba, cmyk,
       -c -
              cmykalpha)
       -G -
              apply gamma correction
              invert colors
       -T
```

```
number of bits of antialiasing (0 to 8)
-A -/- number of bits of antialiasing (0 to 8) (graphics, text)
      minimum stroked line width (in pixels)
-1 -
-D
      disable use of display list
-i
      ignore errors
-L
      low memory mode (avoid caching, clear objects after each
-P
      parallel interpretation/rendering
-y 1
      List the layer configs to stderr
      Select layer config (by number)
-y -{,-}* Select layer config (by number), and toggle the
         listed entries
pages comma separated list of page numbers and ranges
```

23.6 Extract

The extract utility extracts objects from PDF files. This can be used to extract resources such as fonts, ICC profiles, images etc.

Run without any object numbers listed, it will extract all the resources it can find within the file to your local filesystem. It is best to run this in a clean directory!

Alternatively specific resources can be extracted by specifying the PDF object numbers. These can be obtained by using the info utility.

23.7 Info

The info utility displays various different sets of information on the contents of a PDF file.

```
-P list patterns
-S list shadings
-X list form and postscript xobjects
pages comma separated list of page numbers and ranges
```

23.8 Merge

The merge utility allows a new output PDF to be created by combining pages (or ranges of pages) from a set of input pdfs.

```
$ mutool merge
usage: mutool merge [-o output.pdf] [-O options] input.pdf [pages]
    [input2.pdf] [pages2] ...
                name of PDF file to create
                comma separated list of output options
       input.pdf name of input file from which to copy pages
                 comma separated list of page numbers and ranges
       pages
PDF output options:
       decompress: decompress all streams (except compress-fonts/images)
       compress: compress all streams
       compress-fonts: compress embedded fonts
       compress-images: compress images
       ascii: ASCII hex encode binary streams
       pretty: pretty-print objects with indentation
       linearize: optimize for web browsers
       sanitize: clean up graphics commands in content streams
       garbage: garbage collect unused objects
       or garbage=compact: ... and compact cross reference table
       or garbage=deduplicate: ... and remove duplicate objects
```

23.9 Pages

The pages utility displays information on the different pages (such as Media-Boxes, CropBoxes etc) of a PDF file.

23.10 Portfolio

The portfolio utility is used to create or manipulate PDF portfolios.

For safety, only use ASCII characters in entry names for now.

23.11 Poster

The poster utility is used to subdivide pages within a PDF so that they can be printed to a small format printer and then pasted together to form a poster.

23.12 Run

Unlike the other utilities, invoking run with no arguments will not get you a list of arguments, but will instead start an interpreter waiting for your input. This interpreter expects to be fed Javascript commands to be executed using MuJS.

The PDF bindings present within the Javascript environment allow many powerful operations to be scripted on PDF and other files.

23.13 Show

The show command will display various sections of the PDF file in printable format. This will primarily be of use to people working with the internals of PDF files, but the outline option provides a way to get the outlines (a.k.a. bookmarks) from a PDF file at the command line.

\$ mutool show

usage: mutool show [options] file.pdf [grep] [xref] [trailer] [pagetree] [outline] [object numbers]

- -p password
- output file
- print streams as binary data
- print encoded streams (don't decode)

Platform specifics

- 24.1 Android viewer
- 24.2 Desktop Java
- 24.2.1 Language bindings
- 24.2.2 Viewer
- 24.3 GSView
- 24.4 Javascript
- 24.5 Linux/Windows viewer
- 24.5.1 Non-GL version
- 24.5.2 GLFW version

Appendix A

Naming conventions and style