CMPSC 465 Data Structures and Algorithms Spring 2022

Instructor: Chunhao Wang

Flow network (Textbook, Section 7.2 Kleinberg & Tardos Section 7.1)

We use graphs to model "transportation networks"

We use graphs to model "transportation networks" i.e., networks whose edges allow some sort of traffic, and vertices act as switches

We use graphs to model "transportation networks"


i.e., networks whose edges allow some sort of traffic, and vertices a

i.e., networks whose edges allow some sort of traffic, and vertices act as switches

In this setting, edges have **capacities**, and we assume there is a **source vertex** generating traffic, a **sink vertex**, which absorbs traffic.

We use graphs to model "transportation networks" i.e., networks whose edges allow some sort of traffic, and vertices act as switches

In this setting, edges have **capacities**, and we assume there is a **source vertex** generating traffic, a **sink vertex**, which absorbs traffic.



Definition

A flow network is a directed graph G = (V, E) s.t.

Definition

A flow network is a directed graph G = (V, E) s.t.

1. there is a capacity $c_e \ge 0$ for all $e \in E$

Definition

A flow network is a directed graph G = (V, E) s.t.

- 1. there is a capacity $c_e \geq 0$ for all $e \in E$
- 2. there is a single source $s \in V$

Definition

A flow network is a directed graph G = (V, E) s.t.

- 1. there is a capacity $c_e \ge 0$ for all $e \in E$
- 2. there is a single source $s \in V$
- 3. there is a single sink $t \in V$

Definition

An **s-t flow** is a function $f: E \to \mathbb{R}^{\geq 0}$ satisfying

Definition

An **s-t flow** is a function $f: E \to \mathbb{R}^{\geq 0}$ satisfying

■ Capacity constraint: $\forall e \in E, \ 0 \le f(e) \le c_e$

Definition

An **s-t flow** is a function $f:E o\mathbb{R}^{\geq 0}$ satisfying

- Capacity constraint: $\forall e \in E$, $0 \le f(e) \le c_e$
- Conservation condition: $\forall v \in V \{s, t\}$

$$\sum_{e \text{ into } v} f(e) = \sum_{e \text{ out of } v} f(e)$$

Definition

An **s-t flow** is a function $f: E \to \mathbb{R}^{\geq 0}$ satisfying

- Capacity constraint: $\forall e \in E$, $0 \le f(e) \le c_e$
- Conservation condition: $\forall v \in V \{s, t\}$

$$\sum_{e \text{ into } v} f(e) = \sum_{e \text{ out of } v} f(e)$$

Intuition: f(e) is the amount of flow/traffic carried out by e

Definition

An **s-t flow** is a function $f: E \to \mathbb{R}^{\geq 0}$ satisfying

- Capacity constraint: $\forall e \in E$, $0 \le f(e) \le c_e$
- Conservation condition: $\forall v \in V \{s, t\}$

$$\sum_{e \text{ into } v} f(e) = \sum_{e \text{ out of } v} f(e)$$

Intuition: f(e) is the amount of flow/traffic carried out by e

Definition

The **value** of a flow f is

$$v(f) = \sum_{e \text{ out of } s} f(e)$$

Definition

An **s-t flow** is a function $f: E \to \mathbb{R}^{\geq 0}$ satisfying

- Capacity constraint: $\forall e \in E$, $0 \le f(e) \le c_e$
- Conservation condition: $\forall v \in V \{s, t\}$

$$\sum_{e \text{ into } v} f(e) = \sum_{e \text{ out of } v} f(e)$$

Intuition: f(e) is the amount of flow/traffic carried out by e

Definition

The **value** of a flow f is

$$v(f) = \sum_{e \text{ out of } s} f(e)$$

Intuition: v(f) shows how much traffic can be accommodated

Chunhao Wang

Problem (The Max-Flow problem)

Given a flow network, find a flow of the maximum possible value

Problem (The Max-Flow problem)

Given a flow network, find a flow of the maximum possible value

Natural idea: Find an s-t path and push a flow of value $\min\{c_e: e \text{ along the path}\}$. Then keep doing this

Problem (The Max-Flow problem)


Given a flow network, find a flow of the maximum possible value

Natural idea: Find an s-t path and push a flow of value $\min\{c_e: e \text{ along the path}\}$. Then keep doing this

Problem (The Max-Flow problem)

Given a flow network, find a flow of the maximum possible value


Natural idea: Find an s-t path and push a flow of value $min\{c_e: e \text{ along the path}\}$. Then keep doing this



Problem (The Max-Flow problem)

Given a flow network, find a flow of the maximum possible value


Natural idea: Find an s-t path and push a flow of value $\min\{c_e: e \text{ along the path}\}$. Then keep doing this



Problem (The Max-Flow problem)

Given a flow network, find a flow of the maximum possible value


Natural idea: Find an s-t path and push a flow of value $\min\{c_e: e \text{ along the path}\}$. Then keep doing this



Problem (The Max-Flow problem)

Given a flow network, find a flow of the maximum possible value

Natural idea: Find an s-t path and push a flow of value $\min\{c_e: e \text{ along the path}\}$. Then keep doing this



$$f(s, u) = 20$$

$$f(u, v) = 20$$

$$f(v, t) = 20$$

$$f(s, v) = 0$$


$$f(u, t) = 0$$

Problem (The Max-Flow problem)

Given a flow network, find a flow of the maximum possible value

Natural idea: Find an s-t path and push a flow of value $\min\{c_e: e \text{ along the path}\}$. Then keep doing this

Example:



$$f(s, u) = 20$$

$$f(u, v) = 20$$

$$f(v, t) = 20$$

$$f(s, v) = 0$$

$$f(u, t) = 0$$


v(f) = 20

Problem (The Max-Flow problem)

Given a flow network, find a flow of the maximum possible value

Natural idea: Find an s-t path and push a flow of value $\min\{c_e: e \text{ along the path}\}$. Then keep doing this

Example:



$$f(s, u) = 20$$


$$f(u, v) = 20$$


$$f(v, t) = 20$$


$$f(s, v) = 0$$


$$f(u, t) = 0$$


v(f) = 20. Can we do better?





















$$f(s, u) = 20$$

$$f(u, v) = 10$$

$$f(v, t) = 20$$

$$f(s, v) = 10$$

$$f(u, t) = 10$$



$$f(s, u) = 20$$

 $f(u, v) = 10$
 $f(v, t) = 20$
 $f(s, v) = 10$
 $f(u, t) = 10$

$$v(f) = 30.$$

Residual graph

We use a residual graph to keep track of the "leftover" capacity

Residual graph

We use a residual graph to keep track of the "leftover" capacity Given a flow network G, flow f, construct the **residual graph** G_f as follows

We use a residual graph to keep track of the "leftover" capacity Given a flow network G, flow f, construct the **residual graph** G_f as follows

• the vertex set of G_f is the same as G

- the vertex set of G_f is the same as G
- for each edge e of G with $f(e) < c_e$ (leftover),

- the vertex set of G_f is the same as G
- for each edge e of G with $f(e) < c_e$ (leftover), include e in G_f with capacity $c_e f(e)$ (forward edge)

- the vertex set of G_f is the same as G
- for each edge e of G with $f(e) < c_e$ (leftover), include e in G_f with capacity $c_e f(e)$ (forward edge)
- for each edge e = (u, v) in G with f(e) > 0 (how much we can undo),

- the vertex set of G_f is the same as G
- for each edge e of G with $f(e) < c_e$ (leftover), include e in G_f with capacity $c_e f(e)$ (forward edge)
- for each edge e = (u, v) in G with f(e) > 0 (how much we can undo), include e' = (v, u) in G_f with capacity f(e) (backward edge)

We use a residual graph to keep track of the "leftover" capacity Given a flow network G, flow f, construct the **residual graph** G_f as follows


- the vertex set of G_f is the same as G
- for each edge e of G with $f(e) < c_e$ (leftover), include e in G_f with capacity $c_e f(e)$ (forward edge)
- for each edge e = (u, v) in G with f(e) > 0 (how much we can undo), include e' = (v, u) in G_f with capacity f(e) (backward edge)

Capacity of an edge in the residual graph is called residual capacity

We use a residual graph to keep track of the "leftover" capacity Given a flow network G, flow f, construct the **residual graph** G_f as follows

- the vertex set of G_f is the same as G
- for each edge e of G with $f(e) < c_e$ (leftover), include e in G_f with capacity $c_e f(e)$ (forward edge)
- for each edge e = (u, v) in G with f(e) > 0 (how much we can undo), include e' = (v, u) in G_f with capacity f(e) (backward edge)


Capacity of an edge in the residual graph is called residual capacity



We use a residual graph to keep track of the "leftover" capacity Given a flow network G, flow f, construct the **residual graph** G_f as follows

- the vertex set of G_f is the same as G
- for each edge e of G with $f(e) < c_e$ (leftover), include e in G_f with capacity $c_e f(e)$ (forward edge)
- for each edge e = (u, v) in G with f(e) > 0 (how much we can undo), include e' = (v, u) in G_f with capacity f(e) (backward edge)

Capacity of an edge in the residual graph is called **residual capacity**



We introduce augmenting paths

We introduce augmenting paths Let P be an s-t path in G_f ,

We introduce **augmenting paths**

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

We introduce **augmenting paths**

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

Define bottleneck(P, f) as the minimum residual capacity of edges of P

We introduce **augmenting paths**

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

We introduce augmenting paths

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

Define bottleneck(P, f) as the minimum residual capacity of edges of P **def** Augment(f, P):

Set b = bottleneck(P, f);

We introduce augmenting paths

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

```
Set b = \text{bottleneck}(P, f);
for each e = (u, v) \in P:
```

We introduce augmenting paths

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

```
Set b = \text{bottleneck}(P, f);

for each e = (u, v) \in P:

| if e is a forward edge:
```

We introduce **augmenting paths**

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

```
Set b = \text{bottleneck}(P, f);

for each e = (u, v) \in P:

| if e is a forward edge:

| Increase f(e) by b;
```

We introduce **augmenting paths**

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

We introduce augmenting paths

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

```
Set b = bottleneck(P, f);

for each e = (u, v) \in P:

if e is a forward edge:

Lincrease f(e) by b;

else:

Decrease f(e) by b;
```

We introduce augmenting paths

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

```
Set b = \text{bottleneck}(P, f);

for each e = (u, v) \in P:

if e is a forward edge:

b Increase b by b;

else:

b Decrease b by b;

return b:
```

We introduce **augmenting paths**

Let P be an s-t path in G_f , we can improve our flow by augmenting along P as follows

Define bottleneck(P, f) as the minimum residual capacity of edges of P def Augment(f, P):

```
Set b = bottleneck(P, f);

for each e = (u, v) \in P:

if e is a forward edge:

Let Increase f(e) by b;

else:

Decrease f(e) by b;

return f:
```

Any s-t path in G_f is called an **augmenting path**

def FORD-FULKERSON(G, capacities c):

def FORD-FULKERSON(G, capacities c): Set f(e) = 0 for all $e \in G$;

```
def FORD-FULKERSON(G, capacities c):

Set f(e) = 0 for all e \in G;

while \exists s-t path in the residual graph G_f:
```

```
def FORD-FULKERSON (G, capacities c):

Set f(e) = 0 for all e \in G;

while \exists s-t path in the residual graph G_f:

Let P be a simple s-t path in G_f;
```

```
def FORD-FULKERSON(G, capacities c):

Set f(e) = 0 for all e \in G;

while \exists s-t path in the residual graph G_f:

Let P be a simple s-t path in G_f;

f' = \text{Augment}(f, P);
```

```
def FORD-FULKERSON (G, capacities c):

Set f(e) = 0 for all e \in G;

while \exists s-t path in the residual graph G_f:

Let P be a simple s-t path in G_f;

f' = \text{Augment}(f, P);

G_f = G_{f'};
```

```
def FORD-FULKERSON (G, capacities c):

Set f(e) = 0 for all e \in G;

while \exists s-t path in the residual graph G_f:

Let P be a simple s-t path in G_f;

f' = \text{Augment}(f, P);

G_f = G_{f'};

f = f';
```

```
def FORD-FULKERSON (G, capacities c):

Set f(e) = 0 for all e \in G;

while \exists s-t path in the residual graph G_f:


Let P be a simple s-t path in G_f;

f' = \text{Augment}(f, P);


G_f = G_{f'};

f = f';


return f;
```




e		
$s \to u$		
$s \to v$		
$u \to v$		
$u \to t$		
$v \to t$		



$\underline{}e$	$f_1(e)$	
$s \rightarrow u$	0	
$s \to v$	0	
$u \to v$	0	
$u \to t$	0	
$v \to t$	0	




e	$f_1(e)$	
$s \to u$	0	
$s \rightarrow v$	0	
$u \to v$	0	
$u \to t$	0	
$v \to t$	0	




e	$f_1(e)$	
$s \to u$	0	
$s \to v$	0	
$u \to v$	0	
$u \to t$	0	
$v \to t$	0	


April 12, 2022




e	$f_1(e)$	
$s \to u$	0	
$s \to v$	0	
$u \to v$	0	
$u \to t$	0	
$v \to t$	0	




$\underline{}$	$f_1(e)$	$f_2(e)$	
$s \to u$	0	20	
$s \to v$	0	0	
$u \to v$	0	20	
$u \to t$	0	0	
$v \to t$	0	20	



$\underline{}$	$f_1(e)$	$f_2(e)$	
$s \to u$	0	20	
$s \to v$	0	0	
$u \to v$	0	20	
$u \to t$	0	0	
$v \to t$	0	20	




e	$f_1(e)$	$f_2(e)$	
$s \to u$	0	20	
$s \to v$	0	0	
$u \to v$	0	20	
$u \to t$	0	0	
$v \to t$	0	20	




e	$f_1(e)$	$f_2(e)$	
$s \to u$	0	20	
$s \to v$	0	0	
$u \to v$	0	20	
$u \to t$	0	0	
$v \to t$	0	20	


April 12, 2022




e		$f_1(e)$	$f_2(e)$	$f_3(e)$
$s \rightarrow$	u	0	20	20
s -	$\rightarrow v$	0	0	10
u -	$\rightarrow v$	0	20	10
u -	$\rightarrow t$	0	0	10
v –	$\rightarrow t$	0	20	20

April 12, 2022









 G_f


$$P:s$$
$$b:20$$


$$\begin{array}{l} P:s\to v\to u\to t\\ b:10 \end{array}$$

e	$f_1(e)$	$f_2(e)$	$f_3(e)$
$s \to u$	0	20	20
$s \to v$	0	0	10
$u \to v$	0	20	10
$u \to t$	0	0	10
$v \to t$	0	20	20










 G_f

$$P: s \to u \to v \to t$$
$$b: 20$$

$$P: s \to v \to u \to t$$
$$b: 10$$

e	$f_1(e)$	$f_2(e)$	$f_3(e)$
$s \to u$	0	20	20
$s \to v$	0	0	10
$u \to v$	0	20	10
$u \to t$	0	0	10
$v \to t$	0	20	20



No more s-t path