

**\_rzilient**

# VPN Portal

# Customer Guide

---

Complete guide for administrators and team members — setup, access, management and capacity.

ADMIN GUIDE

USER GUIDE

WireGuard VPN

Capacity: 252/instance

May 2026 · v1.1 · rzilient.tech

# // contents

---

## **Part I — For Administrators**

1. What is the VPN Portal?
2. Accessing the Admin Panel
3. Managing Peers
4. Adding Peers Manually
5. Monitoring Traffic
6. Capacity and Scaling
7. Updating the Portal

## **Part II — For Team Members**

8. Getting Access
9. Logging In — Google SSO
10. Logging In — Magic Link
11. Generating Your Credentials
12. Installing WireGuard
13. Connecting to the VPN
14. Troubleshooting

## 1. What is the VPN Portal?

The rzilient VPN Portal is a self-serve WireGuard VPN credential system. Your team members log in with their work email and generate their own WireGuard credentials — no IT intervention required.

| Feature            | Description                                                                       |
|--------------------|-----------------------------------------------------------------------------------|
| Google SSO         | Team members log in with their @yourdomain.com Google account                     |
| Magic Link         | Passwordless email login for non-Google accounts — 1 hour expiry                  |
| Self-serve         | Each user generates their own WireGuard key pair and downloads their config       |
| Admin panel        | Full peer management with live traffic stats, search, sort and CSV export         |
| One-click update   | Portal updates itself from the admin panel — no SSH or technical knowledge needed |
| 252 users/instance | Each VPN instance supports up to 252 team members — add instances to scale        |

## 2. Accessing the Admin Panel

The admin panel uses session-based login — your admin token acts as a password. The token never appears in the URL or browser history.

- 1 Navigate to the login page**  
Open <https://vpn.yourdomain.rzilient.tech/admin/login>
- 2 Enter your admin token**  
Type your ADMIN\_TOKEN in the password field and click "access admin panel"
- 3 Session stored**  
A secure cookie is set — valid for 24 hours. No token in URL.
- 4 Logout when done**  
Click "logout" in the top navigation to clear your session

### Note

The admin token is set via the ADMIN\_TOKEN environment variable. Contact your rzilient account manager to reset it.

### 3. Managing Peers

The peers table shows all team members who have generated VPN credentials, with their email, VPN IP, status, live traffic and last seen time.

| Action      | Button        | What it does                                                             |
|-------------|---------------|--------------------------------------------------------------------------|
| Block       | ■ block       | Removes peer from WireGuard — cannot connect but credentials are kept    |
| Unblock     | ↑ unblock     | Re-adds peer to WireGuard — they can connect again immediately           |
| Revoke      | ✕ revoke      | Permanently deletes peer and credentials — they must generate new ones   |
| Copy config | ■ config      | Copies the WireGuard .conf to clipboard — useful for manual device setup |
| Export CSV  | ↓ export csv  | Downloads all peers with traffic stats as a CSV file                     |
| Search      | // filter...  | Filter by email, name or VPN IP in real time                             |
| Sort        | Column header | Click any column header to sort ascending or descending                  |

### 4. Adding Peers Manually

You can provision credentials directly from the admin panel without requiring the user to log in — useful for devices or service accounts.

#### 1 Scroll to "// add peer"

The form is above the peers table on the admin panel

#### 2 Enter email and name

Type the work email and full name, then click "+ add peer"

#### 3 Share the config securely

Find the peer in the table, click "■ config" and share the .conf file

## 5. Monitoring Traffic

The admin panel shows live WireGuard traffic stats, refreshed every 30 seconds.

| Indicator     | Meaning                                                           |
|---------------|-------------------------------------------------------------------|
| ● Green dot   | Peer is online — last WireGuard handshake less than 3 minutes ago |
| ● Grey dot    | Peer is offline — no recent handshake                             |
| ↓ RX          | Total data received by this peer since the VPN started            |
| ↑ TX          | Total data sent by this peer since the VPN started                |
| Last seen     | Time since last handshake — e.g. "2m ago", "1h ago"               |
| Total RX / TX | Combined traffic across all peers shown in the header stat cards  |

## 6. Capacity and Scaling

Each VPN instance runs on a dedicated server with a private /24 subnet. Understanding the capacity model helps you plan for growth.

|                        |                       |                       |
|------------------------|-----------------------|-----------------------|
| 252                    | 1                     | ∞                     |
| max users per instance | WireGuard IP per user | instances per company |

### How it works

- Each instance uses a /24 subnet (e.g. 10.8.0.0/24)
- IPs .2 through .253 are assigned to peers — 252 total
- IP .1 is reserved for the VPN server itself
- Each user gets a permanent, unique VPN IP that does not change

### Scaling beyond 252 users

If a customer needs more than 252 users, rzilient provisions a second VPN instance on a new /24 subnet (e.g. 10.9.0.0/24). Each instance has its own portal URL. Subnets are assigned sequentially and globally — no two instances share a subnet.

| Instance   | Subnet      | Portal URL                | Capacity  |
|------------|-------------|---------------------------|-----------|
| Instance 1 | 10.8.0.0/24 | vpn-company.rzilient.tech | 252 users |

|                   |             |                           |           |
|-------------------|-------------|---------------------------|-----------|
| <b>Instance 2</b> | 10.9.0.0/24 | vpn2-company.rzilent.tech | 252 users |
| <b>Instance N</b> | 10.N.0.0/24 | vpnN-company.rzilent.tech | 252 users |

**Tip**

Contact your rzilent account manager to provision additional instances. Each instance is independently managed and billed.

## 7. Updating the Portal

When a new version is available, a badge in the top navigation shows "↑ update available". Updates take ~30 seconds and preserve all peer data.

### 1 Check the version badge

The badge shows your current SHA. When an update is available it turns lime green.

### 2 Click "update now"

A confirmation dialog appears. Confirm to start the update.

### 3 Wait ~30 seconds

The portal pulls the new image and restarts. Briefly unavailable.

### 4 Refresh and verify

Refresh the page. The badge shows the new version SHA.

#### Note

All peer data and WireGuard credentials are stored outside the container and are not affected by updates or restarts.

## 8. Getting Access

To connect to your company VPN you need two things: a portal login and WireGuard installed on your device.

| Requirement   | Details                                                                                                          |
|---------------|------------------------------------------------------------------------------------------------------------------|
| Work email    | A @yourdomain.com email registered by your admin                                                                 |
| Portal URL    | Provided by your IT admin — e.g. <a href="https://vpn-company.rzilent.tech">https://vpn-company.rzilent.tech</a> |
| WireGuard app | Free on all platforms — see Section 12 for installation instructions                                             |

## 9. Logging In — Google SSO

If your company uses Google Workspace, log in instantly with your Google account.

- 1 Open the portal URL**  
Navigate to your VPN portal URL in your browser
- 2 Click "continue with Google"**  
You will be redirected to the Google login page
- 3 Select your work account**  
Choose your @yourdomain.com account — personal accounts will be rejected
- 4 You are logged in**  
You will be redirected to the portal home page automatically

## 10. Logging In — Magic Link

If you do not use Google Workspace, or prefer passwordless login, use a magic link sent to your work email.

**1 Open the portal URL**

Navigate to your VPN portal URL — you will land on the login page

**2 Enter your work email**

Type your email and click "send magic link"

**3 Check your inbox**

You will receive an email with a login link — valid for 1 hour

**4 Click the link**

Click "Log in to VPN portal" — you will be logged in automatically

**Note**

The magic link is single-use and expires after 1 hour. If it expires, simply request a new one from the portal login page.

## 11. Generating Your Credentials

Once logged in, if you have not generated credentials yet, you will see a "Generate credentials" button on the home page.

### 1 Click "Generate credentials"

The portal creates a WireGuard key pair and assigns you a permanent VPN IP

### 2 Download your config

Click "Download config" to save your rzilient-vpn.conf file to your device

### 3 Scan the QR code (mobile)

On mobile, tap "Show QR code" and scan it in the WireGuard app instead

### 4 Keep your config safe

Your .conf file contains your private key — do not share it or store it publicly

#### Important

You only need to generate credentials once. Your VPN IP is permanent and will not change. If you lose your config, contact your admin to revoke and regenerate.

## 12. Installing WireGuard

WireGuard is free and available on all major platforms.

| Platform              | Download                                                          | How to install                         |
|-----------------------|-------------------------------------------------------------------|----------------------------------------|
| macOS                 | <a href="#">Mac App Store</a>                                     | Search "WireGuard" and install         |
| Windows               | <a href="https://wireguard.com/install">wireguard.com/install</a> | Download the .msi installer and run it |
| iOS                   | <a href="#">App Store</a>                                         | Search "WireGuard" and install         |
| Android               | <a href="#">Google Play Store</a>                                 | Search "WireGuard" and install         |
| Linux (Ubuntu/Debian) | <a href="#">apt package</a>                                       | sudo apt install wireguard             |
| Linux (Arch/CachyOS)  | <a href="#">pacman</a>                                            | sudo pacman -S wireguard-tools         |

## 13. Connecting to the VPN

---

### Desktop — macOS, Windows, Linux

- 1 Open WireGuard**  
Launch the WireGuard application on your computer
- 2 Import your config**  
Click "Import tunnel(s) from file" and select your rzilient-vpn.conf
- 3 Activate the tunnel**  
Click "Activate" — status shows "Active" when connected
- 4 Verify connection**  
Your VPN IP (e.g. 10.8.0.x) should now be active

### Mobile — iOS and Android

- 1 Open WireGuard**  
Launch the WireGuard app on your phone
- 2 Tap the + button**  
Select "Create from QR code"
- 3 Scan the QR code**  
Open the VPN portal on a computer, show the QR code, and scan it
- 4 Activate the tunnel**  
Toggle the tunnel on and allow VPN permission when prompted

## 14. Troubleshooting

### ● Cannot log in with Google

Cause: Using a personal account, or email domain not authorised

**Fix:** Use your work @yourdomain.com account. Contact your admin if your domain is not listed on the portal.

### ● Magic link email not received

Cause: Spam filter blocking the email, or typo in email address

**Fix:** Check your spam / junk folder first. Request a new link and double-check your email address.

### ● "This link has expired or is invalid"

Cause: The magic link is older than 1 hour, or already used

**Fix:** Magic links are single-use and expire after 1 hour. Request a new one from the portal.

### ● WireGuard shows "Active" but no internet

Cause: DNS or routing misconfiguration in the .conf file

**Fix:** Toggle the tunnel off and back on. Ensure AllowedIPs = 0.0.0.0/0 in your config.

### ● Cannot connect at all (tunnel not activating)

Cause: Firewall blocking UDP ports, or network restrictions

**Fix:** Ask your network admin to allow UDP 51820. The portal also supports UDP 443 as a fallback.

### ● "No IPs available" on generate

Cause: The VPN instance has reached 252 peers

**Fix:** Contact your admin — a second VPN instance needs to be provisioned.

### ● Config file lost

Cause: File was deleted or device was reset

**Fix:** Contact your admin. They will revoke your old credentials and you can generate new ones.

### ● Tunnel connects but keeps dropping

Cause: Network instability on your end

**Fix:** PersistentKeepalive = 25 is already set. Try switching networks (WiFi to mobile data or vice versa).

### ● QR code not scanning on mobile

Cause: Screen brightness or angle

**Fix:** Increase screen brightness on the computer showing the QR code, or download the .conf and transfer it manually.

### Need help?

Contact your rzilient account manager or email [support@rzilient.tech](mailto:support@rzilient.tech). Include your portal URL and the error message you are seeing.