



NANYANG
TECHNOLOGICAL
UNIVERSITY
SINGAPORE

IE2110

Signals and Systems

Part I

Overview

with Instructor:

A/P Teh Kah Chan

Outline of Signals & Systems - Part 1

1. Signals and Systems

- 1.1 Classification of Signals
- 1.2 Elementary and Singularity Signals
- 1.3 Operations on Signals
- 1.4 Properties of Systems

2. Linear Time-Invariant (LTI) Systems

- 2.1 Continuous-Time and Discrete-Time LTI Systems
- 2.2 Convolution
- 2.3 LTI System Properties
- 2.4 Correlation Functions

Signals and Systems Overview




Figure 1: A typical signal and system example



NANYANG
TECHNOLOGICAL
UNIVERSITY
SINGAPORE

IE2110

Signals and Systems

Part I

1.1 Classification of Signals I

with Instructor:

A/P Teh Kah Chan




1.1 Classification of Signals

- 1) **Continuous-Time vs Discrete-Time Signal**
- 2) **Continuous-Value vs Discrete-Value Signal**
- 3) **Deterministic vs Random Signal**
- 4) Even vs Odd Signal
- 5) Periodic vs Aperiodic Signal
- 6) Energy-Type vs Power-Type Signal

1) Continuous-Time vs Discrete-Time Signal

- Continuous-Time (CT) Signal: A signal $x(t)$ that is specified for all value of time t
- Discrete-Time (DT) Signal: A signal $y[n]$ that is specified only for integer value of n

Graph of Continuous-Time Signal



Graph of Discrete-Time Signal





Figure 2: Continuous-Time vs Discrete-Time signal

1) Continuous-Time vs Discrete-Time Signal

Example 1:

Try sketching the waveforms of the CT signal $x(t) = t$ and DT signal $x[n] = n$, respectively.

Graph of CT signal



Graph of DT signal





Figure 3: Example of CT and DT signals

2) Continuous-Value vs. Discrete-Value Signal

- Continuous-Value Signal: A signal $x(t)$ whose amplitude can take on any value
- Discrete-Value Signal: A signal $y(t)$ whose amplitude can take on only a finite number of values

Graph of Continuous-Value Signal



Graph of Discrete-Value Signal





Figure 4: Continuous-Value vs Discrete-Value signal

2) Continuous-Value vs. Discrete-Value Signal

Example 2:

Try sketching the waveforms of the continuous-value signal $x(t) = A \sin(2\pi f_0 t)$ and discrete-value signal $y[n] = (-1)^n$ respectively.

Graph of Continuous-Value Signal



Graph of Discrete-Value Signal





Figure 5: Example of Continuous-Value vs Discrete-Value signals

3) Deterministic vs Random Signal

- Deterministic Signal: A signal $x(t)$ that can be mathematically modeled explicitly as a function of time, i.e., $x(t) = A \sin(2\pi f_0 t)$
- Random Signal: A signal $y(t)$ that is known only in terms of probabilistic description, i.e., noise

Graph of Deterministic Signal



Graph of Random Signal



Figure 6: Deterministic vs Random signal



Classification of Signals Summary 1

- Overview of Signals and Systems
- 1.1 Classification of Signals
 - 1) Continuous-Time vs Discrete-Time Signal
 - 2) Continuous-Value vs Discrete-Value Signal
 - 3) Deterministic vs Random Signal



You have reached the end of this lesson, you have 3 more types to learn!

Please proceed with the next activity.




NANYANG
TECHNOLOGICAL
UNIVERSITY
SINGAPORE

IE2110 Signals and Systems Part I

1.1 Classification of Signals II

with Instructor:

A/P Teh Kah Chan



Outline of Signals & Systems - Part 1

1. Signals and Systems
 - 1.1 Classification of Signals 
 - 1.2 Elementary and Singularity Signals
 - 1.3 Operations on Signals
 - 1.4 Properties of Systems
2. Linear Time-Invariant (LTI) Systems
 - 2.1 Discrete-Time and Continuous-Time LTI Systems
 - 2.2 Convolution
 - 2.3 LTI System Properties
 - 2.4 Correlation Functions


1.1 Classification of Signals

- 1) Continuous-Time vs Discrete-Time Signal ✓
- 2) Continuous-Value vs Discrete-Value Signal ✓
- 3) Deterministic vs Random Signal ✓
- 4) **Even vs Odd Signal**
- 5) **Periodic vs Aperiodic Signal**
- 6) **Energy-Type vs Power-Type Signal**

4) Even vs Odd Signal

- Even Signal: A signal $x_e(t)$ that satisfies the condition $x_e(t) = x_e(-t)$
- Odd Signal: A signal $x_o(t)$ that satisfies the condition $x_o(t) = -x_o(-t)$

Graph of Even Signal



Graph of Odd Signal




Figure 7: Even vs Odd signal

4) Even vs Odd Signal

- Any deterministic signal $x(t)$ can be decomposed into sum of an even and odd signal

$$x(t) = x_e(t) + x_o(t)$$

where

$$x_e(t) = \frac{1}{2} \{x(t) + x(-t)\}$$

and

$$x_o(t) = \frac{1}{2} \{x(t) - x(-t)\}$$

4) Even vs Odd Signal

- The product of two **even** signals is an **even** signal
- The product of two **odd** signals is an **even** signal
- The product of an **even** signal and an **odd** signal is an **odd** signal
- Note that

$$\int_{-T_0}^{T_0} x_e(t) dt = 2 \int_0^{T_0} x_e(t) dt$$

and

$$\int_{-T_0}^{T_0} x_o(t) dt = 0$$

4) Even vs Odd Signal

Example 3:

Show that the signal $x(t) = A \sin(2\pi f_0 t)$ is an odd signal

Since

$$\begin{aligned}x(-t) &= A \sin\{2\pi f_0(-t)\} \\&= -A \sin(2\pi f_0 t) \\&= -x(t)\end{aligned}$$

hence, $x(t)$ is an odd signal.




Figure 8: An odd signal example

4) Even vs Odd Signal

Example 4:

Find the even and odd components of the signal $x(t) = \cos(t) + \sin(t) \cos(t)$.

The even component of $x(t)$ is

$$\begin{aligned}x_e(t) &= \frac{1}{2} \{x(t) + x(-t)\} \\&= \frac{1}{2} \{\cos(t) + \sin(t) \cos(t) + \cos(-t) + \sin(-t) \cos(-t)\} \\&= \cos(t)\end{aligned}$$

The odd component of $x(t)$ is

$$\begin{aligned}x_o(t) &= \frac{1}{2} \{x(t) - x(-t)\} \\&= \frac{1}{2} \{\cos(t) + \sin(t) \cos(t) - \cos(-t) - \sin(-t) \cos(-t)\} \\&= \sin(t) \cos(t)\end{aligned}$$

4) Even vs Odd Signal

Example 5: Evaluate $\int_{-T_0}^{T_0} x(t) dt$ where $x(t) = t^3 \cos^3(10t)$.

Since

$$\begin{aligned}x(-t) &= (-t)^3 \cos^3\{10(-t)\} \\&= -t^3 \cos^3(10t) \\&= -x(t)\end{aligned}$$

hence, $x(t)$ is an odd signal. Thus,

$$\int_{-T_0}^{T_0} x(t) dt = 0$$

5) Periodic vs Aperiodic Signal

- Periodic Signal: A signal $x(t)$ with a constant period $0 < T_0 < \infty$ that

$$x(t) = x(t+T_0), -\infty < t < \infty$$

For a discrete-time signal, the constant period is an integer $0 < K_0 < \infty$ that

$$x[n] = x[n+K_0], -\infty < n < \infty$$

- Aperiodic Signal: A signal $y(t)$ or $y[n]$ that does not satisfy the above equation

5) Periodic vs Aperiodic Signal




Figure 9: Periodic vs Aperiodic signal

6) Energy-Type vs Power-Type Signal

- Energy-Type Signal
 - A signal $x(t)$ or $x[n]$ that has finite energy, i.e., $0 < E_x < \infty$, where

CT signal: $E_x = \int_{-\infty}^{\infty} |x(t)|^2 dt$

DT signal: $E_x = \sum_{n=-\infty}^{\infty} |x[n]|^2$

6) Energy-Type vs Power-Type Signal

- Power-Type Signal
 - A signal $x(t)$ or $x[n]$ that has finite power, i.e., $0 < P_x < \infty$, where

CT signal:
$$P_x = \lim_{T \rightarrow \infty} \frac{1}{T} \int_{-T/2}^{T/2} |x(t)|^2 dt$$

DT signal:
$$P_x = \lim_{K \rightarrow \infty} \frac{1}{2K + 1} \sum_{n=-K}^K |x[n]|^2$$

6) Energy-Type vs Power-Type Signal

Note that if $x(t)$ or $x[n]$ is a periodic signal with period T_0 or K_0 , respectively, then

CT signal:
$$P_x = \frac{1}{T_0} \int_{t_1}^{t_1+T_0} |x(t)|^2 dt$$

DT signal:
$$P_x = \frac{1}{K_0} \sum_{n=k}^{k+K_0-1} |x[n]|^2$$

with any real value of t_1 and any integer value of k .

6) Energy-Type vs Power-Type Signal

Example 6: Determine the energy and power of the periodic signal $x(t) = A \cos(2\pi f_0 t)$

$$E_x = \int_{-\infty}^{\infty} |x(t)|^2 dt$$

$$\begin{aligned} &= \int_{-\infty}^{\infty} |A \cos(2\pi f_0 t)|^2 dt \\ &= \infty \end{aligned}$$

$$P_x = \lim_{T \rightarrow \infty} \frac{1}{T} \int_{-T/2}^{T/2} |x(t)|^2 dt$$

$$= \frac{1}{T_0} \int_{-T_0/2}^{T_0/2} |x(t)|^2 dt$$

$$= \frac{1}{T_0} \int_{-T_0/2}^{T_0/2} |A \cos(2\pi f_0 t)|^2 dt$$

$$= \frac{A^2}{2}$$

Hence, $x(t)$ is a power-type signal.

In general, power-type signals are periodic signals.



Classification of Signals Summary 2

- Classification of Signals

4) Even vs Odd Signal

$$x(t) = x_e(t) + x_o(t)$$

$$x_e(t) = \{x(t) + x(-t)\} / 2$$

$$x_o(t) = \{x(t) - x(-t)\} / 2$$

5) Periodic vs Aperiodic Signal

6) Energy-Type vs Power-Type Signal

$$\text{CT Signals : } E_x = \int_{-\infty}^{\infty} |x(t)|^2 dt$$

$$P_x = \lim_{T \rightarrow \infty} \frac{1}{T} \int_{-T/2}^{T/2} |x(t)|^2 dt = \frac{1}{T_0} \int_{t_1}^{t_1+T_0} |x(t)|^2 dt$$

$$\text{DT Signals : } E_x = \sum_{n=-\infty}^{\infty} |x[n]|^2$$

$$P_x = \lim_{K \rightarrow \infty} \frac{1}{2K+1} \sum_{n=-K}^K |x[n]|^2 = \frac{1}{K_0} \sum_{n=k}^{k+K_0-1} |x[n]|^2$$



Classification of Signals Summary 2

1.1 Classification of Signals

- 1) Continuous-Time vs Discrete-Time Signal
- 2) Continuous-Value vs Discrete-Value Signal
- 3) Deterministic vs Random Signal
- 4) Even vs Odd Signal
- 5) Periodic vs Aperiodic Signal
- 6) Energy-Type vs Power-Type Signal



You have reached the end of module 1.1.

Made some mental notes on each classification of signals?

Try it and proceed with the next activity!




NANYANG
TECHNOLOGICAL
UNIVERSITY
SINGAPORE

IE2110

Signals and Systems

Part 1

with Instructor:
A/P Teh Kah Chan



Outline of Signals & Systems - Part 1

1. Signals and Systems
 - 1.1 Classification of Signals  Recap through further examples
 - 1.2 Elementary and Singularity Signals
 - 1.3 Operations on Signals
 - 1.4 Properties of Systems
2. Linear Time-Invariant (LTI) Systems
 - 2.1 Discrete-Time and Continuous-Time LTI Systems
 - 2.2 Convolution
 - 2.3 LTI System Properties
 - 2.4 Correlation Functions

Recap: 1.1 Classification of Signals

Example 7:

Determine the energy and power of the signal $y(t) = \exp(-|t|)$.

$$\begin{aligned} E_y &= \int_{-\infty}^{\infty} |y(t)|^2 dt & P_y &= \lim_{T \rightarrow \infty} \frac{1}{T} \int_{-T/2}^{T/2} |y(t)|^2 dt \\ &= \int_{-\infty}^{\infty} |\exp(-|t|)|^2 dt & &= \lim_{T \rightarrow \infty} \frac{1}{T} \times E_y \\ &= 2 \times \int_0^{\infty} \exp(-2t) dt & &= 0 \\ &= 1 \end{aligned}$$

Hence, $y(t)$ is an energy-type signal. In general, energy-type signals are aperiodic signals.

Recap: 1.1 Classification of Signals

Example 8:

Determine the energy and power of the discrete-time periodic signal
 $x[n] = A \sin(2\pi n/4)$.

$$\begin{aligned} E_x &= \sum_{n=-\infty}^{\infty} |x[n]|^2 \\ &= \sum_{n=-\infty}^{\infty} \left| A \sin\left(\frac{2\pi n}{4}\right) \right|^2 \\ &= \infty \end{aligned}$$

$$\begin{aligned} P_x &= \frac{1}{K_0} \sum_{n=k}^{k+K_0-1} |x[n]|^2 \\ &= \frac{1}{4} \sum_{n=0}^3 \left| A \sin\left(\frac{2\pi n}{4}\right) \right|^2 \\ &= \frac{A^2}{4} \times [0^2 + 1^2 + 0^2 + (-1)^2] \\ &= \frac{A^2}{2} \end{aligned}$$

Hence, $x[n]$ is a power-type signal.

Recap: 1.1 Classification of Signals

Example 9:

A simplified transmitter model of a digital communication system is shown below (Figure 10). Determine the classifications of each signal.





Figure 10: Transmitter model of a digital communication system

Recap: 1.1 Classification of Signals

Example 9:




- $x(t)$ is a continuous-time, continuous-value, deterministic, even, periodic, and power-type signal
- $x[n] = x(nT_s)$ is a discrete-time, discrete-value, deterministic, even, periodic, and power-type signal
- $\hat{x}[n]$ is a discrete-time, discrete-value, deterministic, even, periodic, and power-type signal
- $w[n]$ is a discrete-time, continuous-value, random, and aperiodic signal
- $y[n]$ is a discrete-time, continuous-value, random, and aperiodic signal


Recap: 1.1 Classification of Signals

Example 9:


$x(t)$ is a continuous-time, continuous-value, deterministic, even, periodic, and power-type signal



$x[n] = x(nT_s)$ is a discrete-time, discrete-value, deterministic, even, periodic, and power-type signal



$\hat{x}[n]$ is a discrete-time, discrete-value, deterministic, even, periodic, and power-type signal



$y[n]$ is a discrete-time, continuous-value, random, and aperiodic signal

$w[n]$ is a discrete-time, continuous-value, random, and aperiodic signal

Figure 10: Transmitter model of a digital communication system

Recap: 1.1 Classification of Signals

Example 9:




Figure 11: Classification of Signals