

Hive setup

Opsætning af hive til brug i BagData 2, under wsl

Søren Magnusson
programmeringsspecialet, datateknikker

2026-09-01

Indholdsfortegnelse

0.1 Download Hive	1
0.2 udpak	1
0.3 Redier hive-miljø i .bashrc	1
0.4 Kopier hive konfigurationsfil	2
0.5 Gør Hive til proxy for hadoop	2
0.6 Genstart hadoop	2
0.7 Opret mapper og set rettigheder INDE i HDFS	2
0.8 Opdater hives mappe indstillinger i hive-site.xml	2

0.1 Download Hive

I en browser, søg efter "hive download". Naviger frem til den nyeste, find de binære filer.
Netop nu er version 4.2.1 den seneste.

Download med wget

```
wget https://dlcdn.apache.org/hive/hive-q.q.q/apache-hive-q.q.q-bin.tar.gz
```

0.2 udpak

```
tar xvfz apache-hive-q.q.q-bin.tar.gz -C BigData
```

0.3 Redier hive-miljø i .bashrc

```
export HIVE_HOME="/home/[user]/BigData/apache-hive-q.q.q-bin"
export PATH=$PATH:$HIVE_HOME/bin
export HADOOP_CONF_DIR=$HADOOP_HOME/etc/Hadoop
```

Bemærk [user] er *din* user, q.q.q er den version du har downloaded. **Husk:** source .bashrc

0.4 Kopier hive konfigurationsfil

```
cp BigData/apache-hive-4.2.1-bin/conf/hive-default.xml.template BigData/  
apache-hive-4.2.1-bin/conf/hive-site.xml
```

q.q.q bla bla

0.5 Gør Hive til proxy for hadoop

Rediger \$HadoopHome/etc/Hadoop/core-site.xml

Tilføj:

```
<property>  
  <name>hadoop.proxyuser.[user].groups</name>  
  <value>*</value>  
</property>  
<property>  
  <name>hadoop.proxyuser.[user].hosts</name>  
  <value>*</value>  
</property>  
<property>  
  <name>hadoop.proxyuser.server.hosts</name>  
  <value>*</value>  
</property>  
<property>  
  <name>hadoop.proxyuser.server.groups</name>  
  <value>*</value>  
</property>
```

0.6 Genstart hadoop

```
$HADOOP_HOME/sbin/stop-all.sh  
$HADOOP_HOME/sbin/start-all.sh
```

0.7 Opret mapper og set rettigheder INDE i HDFS

```
hdfs dfs -mkdir /tmp  
hdfs dfs -mkdir /user  
hdfs dfs -mkdir /user/hive  
hdfs dfs -mkdir /user/hive/warehouse
```

```
hdfs dfs -chmod g+w /tmp  
hdfs dfs -chmod g+w /user/hive/warehouse
```

0.8 Opdater hives mappe indstillinger i hive-site.xml

Rediger \$HIVE_HOME/conf/hive-site.xml Find disse properties og opdater deres værdier:

```
<property>
  <name>hive.metastore.warehouse.dir</name>
  <value>/user/hive/warehouse</value>
</property>
<property>
  <name>hive.downloaded.resources.dir</name>
  <value>/tmp/${user.name}_resources</value>
  <description></description>
</property>
<property>
  <name>hive.exec.local.scratchdir</name>
  <value>/tmp/${user.name}</value>
  <description>Local scratch space for Hive jobs</description>
</property>
```