Search this site...

HOME JAVA PHP Python Ruby Perl HTML CSS Javascript MySQL C++ UNIX MORE...

REFERENCES | FORUM | ABOUT | CC

Assemb Programming Language

Assembly Tutorial

Assembly - Home

Assembly Introduction

Environment Setup

Assembly Basic Syntax

Assembly Memory Segments

Assembly Registers

Assembly System Calls

Addressing Modes

Assembly Variables

Assembly Constants

Arithmetic Instructions

Logical Instructions

Assembly Conditions

Assembly Loops

Assembly Numbers

Assembly Strings

Assembly Arrays

Assembly Procedures

Assembly Recursion

Assembly Macros

Assembly File Management

Assembly Memory Management

Assembly Useful Resources

Assembly Quick Guide

Assembly Useful Resources

Selected Reading

Developer's Best Practices

Effective Resume Writing

Computer Glossary

Who is Who

Addressing Modes and the MOV Instruction

Advertisements







Previous Page

Next Page

Most assembly language instructions require operands to be processed. An operand address provides the location, where the data to be processed is stored. Some instructions do not require an operand, whereas some other instructions may require one, two or three operands.

When an instruction requires two operands, the first operand is generally the destination, which contains data in a register or memory location and the second operand is the source. Source contains either the data to be delivered (immediate addressing) or the address (in register or memory) of the data. Generally, the source data remains unaltered after the operation.

The three basic modes of addressing are:

Register addressing

Immediate addressing

Memory addressing

Register Addressing

In this addressing mode, a register contains the operand. Depending upon the instruction, the register may be the first operand, the second operand or both.

For example,

```
MOV DX, TAX RATE
                   ; Register in first operand
MOV COUNT, CX
                   ; Register in second operand
MOV EAX, EBX
                   ; Both the operands are in registers
```

As processing data between registers does not involve memory, it provides fastest processing of data.

Immediate Addressing

An immediate operand has a constant value or an expression. When an instruction with two operands uses immediate addressing, the first operand may be a register or memory location, and the second operand is an immediate constant. The first operand defines the length of the data

For example.

```
BYTE_VALUE DB 150
                      ; A byte value is defined
WORD VALUE DW 300
                      ; A word value is defined
    BYTE_VALUE, 65
ADD
                       ; An immediate operand 65 is added
MOV AX, 45H
                       ; Immediate constant 45H is transferred to AX
```

Direct Memory Addressing

When operands are specified in memory addressing mode, direct access to main memory, usually to the data segment, is required. This way of addressing results in slower processing of data. To locate the exact location of data in memory, we need the segment start address, which is typically found in the DS register and an offset value. This offset value is also called effective address.

In direct addressing mode, the offset value is specified directly as part of the instruction, usually indicated by the variable name. The assembler calculates the offset value and maintains a symbol table, which stores the offset values of all the variables used in the program.

In direct memory addressing, one of the operands refers to a memory location and the other operand references a register.

For example,

```
ΔDD
        BYTE_VALUE, DL ; Adds the register in the memory location
MOV
        BX, WORD_VALUE
                       ; Operand from the memory is added to register
```

Modern Baby Names Online Photo Editing Advertisements •·Toradex Bring your ideas to reality! Get free Kit of worth

250 USD & win

annual prize money

Register now >

Sponsors

Altıum 🔷 Ciiva AR

1 of 3

Direct-Offset Addressing

This addressing mode uses the arithmetic operators to modify an address. For example, look at the following definitions that define tables of data:

```
BYTE_TABLE DB 14, 15, 22, 45 ; Tables of bytes WORD_TABLE DW 134, 345, 564, 123 ; Tables of words
```

The following operations access data from the tables in the memory into registers:

```
MOV CL, BYTE_TABLE[2] ; Gets the 3rd element of the BYTE_TABLE
MOV CL, BYTE_TABLE + 2 ; Gets the 3rd element of the BYTE_TABLE
MOV CX, WORD_TABLE[3] ; Gets the 4th element of the WORD_TABLE
MOV CX, WORD_TABLE + 3 ; Gets the 4th element of the WORD_TABLE
```

Indirect Memory Addressing

This addressing mode utilizes the computer's ability of Segment:Offset addressing. Generally, the base registers EBX, EBP (or BX, BP) and the index registers (DI, SI), coded within square brackets for memory references, are used for this purpose.

Indirect addressing is generally used for variables containing several elements like, arrays. Starting address of the array is stored in, say, the EBX register.

The following code snippet shows how to access different elements of the variable.

```
MY_TABLE TIMES 10 DW 0 ; Allocates 10 words (2 bytes) each initialized to 0
MOV EBX, [MY_TABLE] ; Effective Address of MY_TABLE in EBX
MOV [EBX], 110 ; MY_TABLE[0] = 110
ADD EBX, 2 ; EBX = EBX +2
MOV [EBX], 123 ; MY_TABLE[1] = 123
```

The MOV Instruction

We have already used the MOV instruction that is used for moving data from one storage space to another. The MOV instruction takes two operands.

SYNTAX:

Syntax of the MOV instruction is:

```
MOV destination, source
```

The MOV instruction may have one of the following five forms:

```
MOV register, register
MOV register, immediate
MOV memory, immediate
MOV register, memory
MOV memory, register
```

Please note that:

Both the operands in MOV operation should be of same size

The value of source operand remains unchanged

The MOV instruction causes ambiguity at times. For example, look at the statements:

```
MOV EBX, [MY_TABLE] ; Effective Address of MY_TABLE in EBX
MOV [EBX], 110 ; MY_TABLE[0] = 110
```

It is not clear whether you want to move a byte equivalent or word equivalent of the number 110. In such cases, it is wise to use a **type specifier**.

Following table shows some of the common type specifiers:

Type Specifier	Bytes addressed
ВҮТЕ	1
WORD	2
DWORD	4
QWORD	8
ТВҮТЕ	10

EXAMPLE:

The following program illustrates some of the concepts discussed above. It stores a name 'Zara Ali' in the data section of the memory, then changes its value to another name 'Nuha Ali' programmatically and

2 of 3 10/1/2013 11:07 PM

```
displays both the names.
section .text
 global _start ;must be decla
_start: ;tell linker entry point
                            ; must be declared for linker (ld)
 ;writing the name 'Zara Ali'
                      edx,9 /message length
ecx, name /message to write
           mov
           mov
                     ebx,1 ;file descriptor (stdout)
eax,4 ;system call number (sys_write)
0x80 ;call kernel
           mov
           mov
                     [name], dword 'Nuha'
                                                       ; Changed the name to Nuha Ali
           mov
 ;writing the name 'Nuha Ali'
                     edx,8
                                     ;message length
           mov
                    edx,8 ;message length
ecx,name ;message to write
ebx,1 ;file descriptor (stdout)
eax,4 ;system call number (sys_write)
0x80 ;call kernel
eax,1 ;system call number (sys_exit)
0x80 ;call kernel
           mov
           mov
           mov
           int
           mov
           int
section .data
name db 'Zara Ali '
When the above code is compiled and executed, it produces the following result:
Zara Ali Nuha Ali
     Previous Page
                                  Print Version
                                                            PDF Version
                                                                                     Next Page
   Advertisements
                                                             D
   Slow computer? Viruses?
   www.ducktoes.com
   We specialize in faster computers. Without
   reformatting or losing data
```

```
ASP.NET | jQuery | AJAX | ANT | iOS | Servlets | log4j | iBATIS | Hibernate | JDBC | Struts | HTML5 | SQL | MySQL | C++ | UNIX
```

Copyright © 2012 by tutorialspoint. All Rights Reserved.

3 of 3