CS162 Operating Systems and Systems Programming Lecture 12


Address Translation

March 5th, 2020 Prof. John Kubiatowicz http://cs162.eecs.Berkeley.edu

Acknowledgments: Lecture slides are from the Operating Systems course taught by John Kubiatowicz at Berkeley, with few minor updates/changes. When slides are obtained from other sources, a reference will be noted on the bottom of that slide, in which case a full list of references is provided on the last slide.

Recall: Starvation vs Deadlock

- Starvation: thread waits indefinitely
 - Example, low-priority thread waiting for resources constantly in use by high-priority threads
- Deadlock: circular waiting for resources
 - Thread A owns Res I and is waiting for Res 2
 Thread B owns Res 2 and is waiting for Res I



- Deadlock ⇒ Starvation but not vice versa
 - Starvation can end (but doesn't have to)
 - Deadlock can't end without external intervention

Recall: Four requirements for Deadlock

Mutual exclusion

- Only one thread at a time can use a resource.

Hold and wait

 Thread holding at least one resource is waiting to acquire additional resources held by other threads

No preemption

 Resources are released only voluntarily by the thread holding the resource, after thread is finished with it

Circular wait

- There exists a set $\{T_1, ..., T_n\}$ of waiting threads
 - » T_1 is waiting for a resource that is held by T_2
 - » T_2 is waiting for a resource that is held by T_3
 - » ...
 - » T_n is waiting for a resource that is held by T_1

Recall: Banker's Algorithm

- Banker's algorithm assumptions:
 - Every thread pre-specifies is maximum need for resources
 - » However, it doesn't have to ask for the all at once... (key advantage)
 - Threads may now request and hold dynamically up to the maximum specified number of each resources
- Simple use of the deadlock detection algorithm
 - For each request for resources from a thread:
 - » Technique: pretend each request is granted, then run deadlock detection algorithm, and grant request if result is deadlock free (conservative!)
 - Keeps system in a "SAFE" state, i.e. there exists a sequence $\{T_1, T_2, ..., T_n\}$ with T_1 requesting all remaining resources, finishing, then T_2 requesting all remaining resources, etc..
- Banker's algorithm prevents deadlocks involving threads and resources by stalling requests that would lead to deadlock
 - Can't fix all issues e.g. thread going into an infinite loop!

Revisit: Deadlock Avoidance using: Banker's Algorithm

- Idea: When a thread requests a resource, OS checks if it would result in deadlock an unsafe state
 - If not, it grants the resource right away
 - If so, it waits for other threads to release resources
- Example:

Thread A x.Acquire(); y.Acquire(); y.Acquire(); x.Acquire(); waits until Thread A y.Release(); x.Release(); y.Release(); y.Release();

Recall: Does Priority Inversion Cause Deadlock?

- Definition: Priority Inversion
 - A low priority task prevents a high-priority task from running
- Does Priority Inversion cause Deadlock?
- Consider typical case (requires 3 threads):
 - 3 threads, T1, T2, T3 in priority order (T3 highest)
 - TI grabs lock, T3 tries to acquire, then sleeps, T2 running
 - Will this make progress?
 - » No, as long as T2 is running
 - » But T2 could stop at any time and the problem would resolve itself...
 - » So, this is not a deadlock (it is a livelock). But is could last a long time...
 - Why is this a priority inversion?
 - » T3 is prevented from running by T2

Priority Donation as a remedy to Priority Inversion


- What is priority donation?
 - When high priority Thread TB is about to sleep while waiting for a lock held by lower priority Thread TA, it may temporarily donate its priority to the holder of the lock if that lock holder has a lower priority
 - » So, Priority(TB) => TA until lock is released
 - So, now, TA runs with high priority until it releases its lock, at which time its priority is restored to its original priority
- How does priority donation help the priority inversion scenario? [TI has lock,T2 running,T3 blocked on lock]
 - Briefly raise T1 to the same priority as T3⇒T1 can run and release lock, allowing T3 to run
 - Does priority donation involve taking lock away from T1?
 - » NO! That would break semantics of the lock and potentially corrupt any information protected by lock!

Next Objective

• Dive deeper into the concepts and mechanisms of memory sharing and address translation

• Enabler of many key aspects of operating systems


- Protection
- Multi-programming
- Isolation
- Memory resource management
- I/O efficiency
- Sharing
- Inter-process communication
- Debugging
- Demand paging
- Today: Translation



Recall: Four Fundamental OS Concepts

- Thread: Execution Context
 - Fully describes program state
 - Program Counter, Registers, Execution Flags, Stack
- Address space (with or w/o translation)
 - Set of memory addresses accessible to program (for read or write)
 - May be distinct from memory space of the physical machine (in which case programs operate in a virtual address space)
- Process: an instance of a running program
 - Protected Address Space + One or more Threads
- Dual mode operation / Protection
 - Only the "system" has the ability to access certain resources
 - Combined with translation, isolates programs from each other and the OS from programs

THE BASICS: Address Space




- What is 2¹⁰ bytes (where a byte is appreviated as "B")?
 - $-2^{10} B = 1024B = 1 KB$ (for memory, 1K = 1024, not 1000)
- How many bits to address each byte of 4KB page?
 - $4KB = 4 \times 1KB = 4 \times 2^{10} = 2^{12}$ ⇒ 12 bits
- How much memory can be addressed with 20 bits? 32 bits? 64 bits?
 - Use 2^k


Address Space, Process Virtual Address Space

- Definition: Set of accessible addresses and the state associated with them
 - $-\frac{2^{32}}{2^{32}} = 4$ billion bytes on a 32-bit machine
- How many 32-bit numbers fit in this address space?
 - -32-bits = 4 bytes, so $2^{32}/4 = 2^{30} = \sim 1$ billion
- What happens when processor reads or writes to an address?
 - Perhaps acts like regular memory
 - Perhaps causes I/O operation
 - » (Memory-mapped I/O)
 - Causes program to abort (segfault)?
 - Communicate with another program


— ...



Recall: Process Address Space: typical structure




Virtualizing Resources



- Physical Reality:
 - **Different** Processes/Threads share the same hardware
 - Need to multiplex CPU (Just finished: scheduling)
 - Need to multiplex use of Memory (starting today)
 - Need to multiplex disk and devices (later in term)
- Why worry about memory sharing?
 - The complete working state of a process and/or kernel is defined by its data in memory (and registers)
 - Consequently, cannot just let different threads of control use the same memory
 - » Physics: two different pieces of data cannot occupy the same locations in memory
 - Probably don't want different threads to even have access to each other's memory if in different processes (protection)


Recall: Single and Multithreaded Processes



- Threads encapsulate concurrency
 - "Active" component of a process
- Address spaces encapsulate protection
 - Keeps buggy program from trashing the system
 - "Passive" component of a process

Recall: Key OS Concept: Address Translation

• Program operates in an address space that is distinct from the physical memory space of the machine



Important Aspects of Memory Multiplexing

Protection:

- Prevent access to private memory of other processes.
 - » Different pages of memory can be given special behavior (Read Only, Invisible to user programs, etc).
 - » Kernel data protected from User programs
 - » Programs protected from themselves


Controlled overlap:

- Separate state of threads should not collide in physical memory.
 Obviously, unexpected overlap causes chaos!
- Conversely, would like the ability to overlap when desired (for communication)


• Translation:

- Ability to translate accesses from one address space (virtual) to a different one (physical)
- When translation exists, processor uses virtual addresses, physical memory uses physical addresses
- Side effects:
 - » Can be used to avoid overlap
 - » Can be used to give uniform view of memory to programs


Recall: Loading



Binding of Instructions and Data to Memory




Second copy of program from previous example



Need address translation!


Second copy of program from previous example



Compile time, Link/Load time, or Execution time?

Multi-step Processing of a Program for Execution

- Preparation of a program for execution involves components at:
 - Compile time (i.e., "gcc")
 - Link/Load time (UNIX "Id" does link)
 - Execution time (e.g., dynamic libs)
- Addresses can be bound to final values anywhere in this path
 - Depends on hardware support
 - Also depends on operating system
- Dynamic Libraries
 - Linking postponed until execution
 - Small piece of code (i.e. the stub), locates appropriate memory-resident library routine
 - Stub replaces itself with the address of the routine, and executes routine



Recall: Uniprogramming

- Uniprogramming (no Translation or Protection)
 - Application always runs at same place in physical memory since only one application at a time
 - Application can access any physical address

Operating System

Application

0×FFFFFFF

Valid 32-bit Addresses

0x0000000



- Application given illusion of dedicated machine by giving it reality of a dedicated machine

Multiprogramming (primitive stage)

- Multiprogramming without Translation or Protection
 - Must somehow prevent address overlap between threads


Operating
System

Application2

0xFFFFFFF

0×00020000


 0×00000000



- Use Loader/Linker: Adjust addresses while program loaded into memory (loads, stores, jumps)
 - » Everything adjusted to memory location of program
 - » Translation done by a linker-loader (relocation)
 - » Common in early days (... till Windows 3.x, 95?)
- With this solution, no protection: bugs in any program can cause other programs to crash or even the OS


Multiprogramming (Version with Protection)

 Can we protect programs from each other without translation?




- Yes: use two special registers BaseAddr and LimitAddr to prevent user from straying outside designated area
 - » Cause error if user tries to access an illegal address
- During switch, kernel loads new base/limit from PCB (Process Control Block)
 - » User not allowed to change base/limit registers

Recall: General Address translation




- Recall: Address Space:
 - All the addresses and state a process can touch
 - Each process and kernel has different address space
- Consequently, two views of memory:
 - View from the CPU (what program sees, virtual memory)
 - View from memory (physical memory)
 - Translation box (Memory Management Unit or MMU) converts between the two views
- Translation ⇒ much easier to implement protection!
 - If task A cannot even gain access to task B's data, no way for A to adversely affect B
- With translation, every program can be linked/loaded into same region of user address space

Recall: Base and Bound (was from CRAY-I)




- Could use base/bounds for dynamic address translation translation happens at execution:
 - Alter address of every load/store by adding "base"
 - Generate error if address bigger than limit
- Gives program the illusion that it is running on its own dedicated machine, with memory starting at 0
 - Program gets continuous region of memory
 - Addresses within program do not have to be relocated when program placed in different region of DRAM

Issues with Simple B&B Method




- Fragmentation problem over time
 - Not every process is same size ⇒ memory becomes fragmented over time
- Missing support for sparse address space
 - Would like to have multiple chunks/program (Code, Data, Stack, Heap, etc)
- Hard to do inter-process sharing
 - Want to share code segments when possible
 - Want to share memory between processes
 - Helped by providing multiple segments per process

More Flexible Segmentation



- Logical View: multiple separate segments
 - Typical: Code, Data, Stack
 - Others: memory sharing, etc
- Each segment is given region of contiguous memory
 - Has a base and limit
 - Can reside anywhere in physical memory


Implementation of Multi-Segment Model



- - Segment number mapped into base/limit pair
 - Base added to offset to generate physical address
 - Error check catches offset out of range
- As many chunks of physical memory as entries
 - Segment addressed by portion of virtual address
 - However, could be included in instruction instead: » x86 Example: mov [es:bx],ax.
- What is "V/N" (valid / not valid)?
 - Can mark segments as invalid; requires check as well

Error


Intel x86 Special Registers



RPL = Requestor Privilege Level
TI = Table Indicator
(0 = GDT, 1 = LDT)
Index = Index into table

Protected Mode segment selector


Typical Segment Register Current Priority is RPL Of Code Segment (CS)



Example: Four Segments (16 bit addresses)




Virtual Address Format




Seg ID #	Base	Limit
0 (code)	0×4000	0×0800
I (data)	0x4800	0×1400
2 (shared)	0×F000	0×1000
3 (stack)	0×0000	0×3000

Physical Address Space

Example: Four Segments (16 bit addresses)



Example: Four Segments (16 bit addresses)



Example of Segment Translation (16bit address)

0x240	main:	la \$	a0, varx
0x244		jal strlen	
•••			
0x360	strlen:	li	<pre>\$v0, 0 ;count</pre>
0x364	loop:	lb	\$t0, (\$a0)
0x368		beq	<pre>\$r0,\$t0, done</pre>
•••		•••	
0x4050	varx	dw	0x314159

Seg ID #	Base	Limit
0 (code)	0×4000	0×0800
I (data)	0×4800	0×1400
2 (shared)	0×F000	0×1000
3 (stack)	0×0000	0×3000

Let's simulate a bit of this code to see what happens ($PC=0\times240$):

I. Fetch 0x0240 (0000 0010 0100 0000). Virtual segment #? 0; Offset? 0x240 Physical address? Base=0x4000, so physical addr=0x4240 Fetch instruction at 0x4240. Get "la \$a0, varx" Move 0x4050 → \$a0, Move PC+4→PC

Example of Segment Translation (16bit address)

0x240	main:	la \$	a0, varx
0x244		jal strlen	
•••		•••	•
0x360	strlen:	li	<pre>\$v0, 0 ;count</pre>
0x364	loop:	1b	\$t0, (\$a0)
0x368		beq	<pre>\$r0,\$t0, done</pre>
•••		•••	
0x4050	varx	dw	0x314159

Seg ID #	Base	Limit
0 (code)	0×4000	0×0800
I (data)	0x4800	0×1400
2 (shared)	0×F000	0×1000
3 (stack)	0×0000	0×3000

Let's simulate a bit of this code to see what happens ($PC=0\times240$):

- I. Fetch 0x0240 (0000 0010 0100 0000). Virtual segment #? 0; Offset? 0x240 Physical address? Base=0x4000, so physical addr=0x4240 Fetch instruction at 0x4240. Get "la \$a0, varx" Move $0x4050 \rightarrow $a0$, Move $PC+4 \rightarrow PC$
- 2. Fetch 0x244. Translated to Physical=0x4244. Get "jal strlen" Move $0x0248 \rightarrow ra (return address!), Move $0x0360 \rightarrow PC$

Example of Segment Translation (16bit address)

0x240 0x244	main:	la \$a0, varx jal strlen	
•••		•••	
0x360	strlen:	li	<pre>\$v0, 0 ;count</pre>
0x364	loop:	lb	\$t0, (\$a0)
0x368		beq	<pre>\$r0,\$t0, done</pre>
		•••	
0x4050	varx	dw	0x314159

Seg ID #	Base	Limit
0 (code)	0×4000	0×0800
I (data)	0x4800	0×1400
2 (shared)	0×F000	0×1000
3 (stack)	0×0000	0×3000

Let's simulate a bit of this code to see what happens ($PC=0\times240$):

- Fetch 0x0240 (0000 0010 0100 0000). Virtual segment #? 0; Offset? 0x240 Physical address? Base=0x4000, so physical addr=0x4240
 Fetch instruction at 0x4240. Get "la \$a0, varx"
 Move 0x4050 → \$a0, Move PC+4→PC
- 2. Fetch 0x244. Translated to Physical=0x4244. Get "jal strlen" Move $0x0248 \rightarrow ra (return address!), Move $0x0360 \rightarrow PC$
- 3. Fetch 0×360 . Translated to Physical= 0×4360 . Get "li \$v0, 0" Move $0\times0000 \rightarrow $v0$, Move PC+4 \rightarrow PC

Example of Segment Translation (16bit address)

0x0240 0x0244	main:	la \$a0, varx jal strlen	
 0x0360	strlen:	li	\$v0, 0 ;count
0x0364	loop:	1b	\$t0, (\$a0)
0x0368		beq	<pre>\$r0,\$t0, done</pre>
•••		•••	
0x4050	varx	dw	0x314159

Seg ID #	Base	Limit
0 (code)	0×4000	0×0800
I (data)	0x4800	0×1400
2 (shared)	0×F000	0×1000
3 (stack)	0×0000	0×3000

Let's simulate a bit of this code to see what happens (PC= 0×0240):

- 1. Fetch 0x0240 (0000 0010 0100 0000). Virtual segment #? 0; Offset? 0x240 Physical address? Base=0x4000, so physical addr=0x4240 Fetch instruction at 0x4240. Get "la \$a0, varx" Move $0x4050 \rightarrow $a0$, Move PC+4 \rightarrow PC
- 2. Fetch 0x0244. Translated to Physical=0x4244. Get "jal strlen" Move $0x0248 \rightarrow ra (return address!), Move $0x0360 \rightarrow PC$
- 3. Fetch 0x0360. Translated to Physical=0x4360. Get "li \$v0, 0" Move $0x0000 \rightarrow $v0$, Move PC+4 \rightarrow PC
- 4. Fetch 0x0364. Translated to Physical=0x4364. Get "lb \$t0, (\$a0)" Since \$a0 is 0x4050, try to load byte from 0x4050


 Translate 0x4050 (0100 0000 0101 0000). Virtual segment #? 1; Offset? 0x50 Physical address? Base=0x4800, Physical addr = 0x4850,

 Load Byte from 0x4850→\$t0, Move PC+4→PC

Observations about Segmentation

- Virtual address space has holes
 - Segmentation efficient for sparse address spaces
 - A correct program should never address gaps (except as mentioned in moment)
 - » If it does, trap to kernel and dump core
- When it is OK to address outside valid range?
 - This is how the stack and heap are allowed to grow
 - For instance, stack takes fault, system automatically increases size of stack
- Need protection mode in segment table
 - For example, code segment would be read-only
 - Data and stack would be read-write (stores allowed)
 - Shared segment could be read-only or read-write
- What must be saved/restored on context switch?
 - Segment table stored in CPU, not in memory (small)
 - Might store all of process' memory onto disk when switched (called ''swapping'')

What if not all segments fit into memory?




- Extreme form of Context Switch: Swapping
 - In order to make room for next process, some or all of the previous process is moved to disk
 - » Likely need to send out complete segments
 - This greatly increases the cost of context-switching
- What might be a desirable alternative?
 - Some way to keep only active portions of a process in memory at any one time
 - Need finer granularity control over physical memory

Problems with Segmentation

- Must fit variable-sized chunks into physical memory
- May move processes multiple times to fit everything
- Limited options for swapping to disk
- Fragmentation: wasted space
 - External: free gaps between allocated chunks
 - Internal: don't need all memory within allocated chunks

Recall: General Address Translation




Physical Address Space

Paging: Physical Memory in Fixed Size Chunks

- Solution to fragmentation from segments?
 - Allocate physical memory in fixed size chunks ("pages")
 - Every chunk of physical memory is equivalent
 - » Can use simple vector of bits to handle allocation: 00110001110001101 ... 110010
 - » Each bit represents page of physical memory $1 \Rightarrow \text{allocated}, 0 \Rightarrow \text{free}$

- Should pages be as big as our previous segments?
 - No: Can lead to lots of internal fragmentation
 - » Typically have small pages (TK-16K)
 - Consequently: need multiple pages/segment

How to Implement Simple Paging?




- Page Table (One per process)
 Resides in physical memory


 - Contains physical page and permission for each virtual page
 » Permissions include: Valid bits, Read, Write, etc
- Virtual address mapping
 - Offset from Virtual address copied to Physical Address
 - » Example: 10 bit offset \Rightarrow 1024-byte pages
 - Virtual page # is all remaining bits
 - » Example for 32-bits: 32-10 = 22 bits, i.e. 4 million entries
 - » Physical page # copied from table into physical address
 - Check Page Table bounds and permissions

Simple Page Table Example

Example (4 byte pages)




What about Sharing?



Where is page sharing used?

- The "kernel region" of every process has the same page table entries
 - The process cannot access it at user level
 - But on U->K switch, kernel code can access it AS WELL AS the region for THIS user
 - » What does the kernel need to do to access other user processes?
- Different processes running same binary!
 - Execute-only, but do not need to duplicate code segments
- User-level system libraries (execute only)
- Shared-memory segments between different processes
 - Can actually share objects directly between processes
 - » Must map page into same place in address space!
 - This is a limited form of the sharing that threads have within a single process


Example: Memory Layout for Linux 32-bit (Pre-Meltdown patch!)




http://static.duartes.org/img/blogPosts/linuxFlexibleAddressSpaceLayout.png

Some simple security measures

- Address Space Randomization
 - Position-Independent Code => can place user code region anywhere in the address space
 - » Random start address makes much harder for attacker to cause jump to code that it seeks to take over
 - Stack & Heap can start anywhere, so randomize placement
- Kernel address space isolation
 - Don't map whole kernel space into each process, switch to kernel page table
 - Meltdown⇒map none of kernel into user mode!




Summary: Paging




3/5/20

Summary: Paging



Summary: Paging



How big do things get?


- 32-bit address space => 2³² bytes (4 GB)
 - Note: "b" = bit, and "B" = byte
 - And for memory:

- Typical page size: 4 KB
 - how many bits of the address is that? (remember $2^{10} = 1024$)
 - Ans 4KB = $4 \times 2^{10} = 2^{12} \Rightarrow 12$ bits of the address
- So how big is the simple page table for each process?
 - $-2^{32}/2^{12} = 2^{20}$ (that's about a million entries) x 4 bytes each => 4 MB
 - When 32-bit machines got started (vax 11/780, intel 80386), 16 MB was a LOT of memory
- How big is a simple page table on a 64-bit processor (x86_64)?
 - -264/212 = 252(that's 4.5×10^{15} or 4.5 exa-entries)×8 bytes each = 36×10^{15} bytes or 36 exa-bytes!!!! This is a ridiculous amount of memory!
 - This is really a lot of space for only the page table!!!
- Mostly, the address space is sparse, i.e. has holes in it that are not mapped to physical memory
 - So, most of this space is taken up by page tables mapped to nothing


Page Table Discussion

- What needs to be switched on a context switch?
 - Page table pointer and limit
- What provides protection here?
 - Translation (per process) and dual-mode!
 - Can't let process alter its own page table!
- Analysis
 - Pros
 - » Simple memory allocation
 - » Easy to share
 - Con: What if address space is sparse?
 - » E.g., on UNIX, code starts at 0, stack starts at $(2^{3} 1)$
 - » With IK pages, need 2 million page table entries!
 - Con: What if table really big?
 - » Not all pages used all the time ⇒ would be nice to have working set of page table in memory
- Simple Page table is way too big!
 - Does it all need to be in memory?
 - How about multi-level paging?
 - or combining paging and segmentation


Fix for sparse address space:
The two-level page table



Summary: Two-Level Paging




Summary: Two-Level Paging




Multi-level Translation: Segments + Pages

- What about a tree of tables?
 - Lowest level page table ⇒ memory still allocated with bitmap
 - Higher levels often segmented
- Could have any number of levels. Example (top segment):



- What must be saved/restored on context switch?
 - Contents of top-level segment registers (for this example)
 - Pointer to top-level table (page table)

What about Sharing (Complete Segment)?



Multi-level Translation Analysis

• Pros:

- Only need to allocate as many page table entries as we need for application
 - » In other wards, sparse address spaces are easy
- Easy memory allocation
- Easy Sharing
 - » Share at segment or page level (need additional reference counting)

• Cons:

- One pointer per page (typically 4K 16K pages today)
- Page tables need to be contiguous
 - » However, previous example keeps tables to exactly one page in size
- Two (or more, if >2 levels) lookups per reference
 - » Seems very expensive!

Summary

Segment Mapping

- Segment registers within processor
- Segment ID associated with each access
 - » Often comes from portion of virtual address
 - » Can come from bits in instruction instead (x86)
- Each segment contains base and limit information
 - » Offset (rest of address) adjusted by adding base

Page Tables

- Memory divided into fixed-sized chunks of memory
- Virtual page number from virtual address mapped through page table to physical page number
- Offset of virtual address same as physical address
- Large page tables can be placed into virtual memory
- Multi-Level Tables
 - Virtual address mapped to series of tables
 - Permit sparse population of address space