System Events

This appendix lists and describes the system events recognized by Content Server. You can use an Audit method to register any of these events for auditing. You can also use a Register method to register to receive an Inbox notification for any of these events.

API Events

Table B–1, page B–457 lists the events arising from API methods. (Events arising from methods that are specific to workflows are listed separately in Table B–2, page B–460.)

Table B-1. Events Arising From API Methods

| Event | Target Object Type | Event Description | Trigger |
|--------------------|--------------------|-----------------------------|--|
| dm_all (or all) | 0 or omitted | All | All auditable events in Docbase |
| | dm_sysobject | | Any event on any Sysobject or the specified Sysobject |
| dm_adddigsignature | dm_sysobject | Add Digital Signature | Execution of the Adddigsignature method. |
| | | | Note: Adddigsignature methods are always audited. It is not possible to unregister this event. |
| dm_addesignature | dm_sysobject | Add Electronic Signature | Execution of the Addesignature method. |
| | | | Addesignature methods are always audited and the entries are always signed by Content Server.It is not possible to modify this behavior. |
| dm_addrendition | dm_sysobject | Add Rendition | Addition of a rendition to an object. |

| Event | Target Object Type | Event Description | Trigger |
|-----------------|---|---------------------------------|--|
| dm_addnote | dm_sysobject dm_process | Add Note | Addition of a note to a SysObject. |
| | um_process | | When the target object is a process object, the SysObject is in a workflow package. |
| dm_appendpart | dm_sysobject | Apend to Virtual Document | Addition of a component to a virtual document |
| dm_archive | dm_sysobject | Archive Objects | Execution of an Archive method |
| dm_assemble | dm_sysobject | Assemble Virtual Document | Execution of Assemble method |
| dm_assume | dm_user | Assume User | Execution of Assume method |
| dm_audit | all object types | Audit Event | Execution of Audit method. |
| | | | Note: Audit methods are always audited. It isn't possible to unregister this event. |
| dm_authenticate | dm_user | Authenticate User | Execution of Authenticate method |
| dm_branch | dm_sysobject | Branch Version | Execution of Branch method |
| dm_checkin | dm_sysobject | Checkin Object | Execution of Checkin method |
| dm_checkout | dm_sysobject | Checkout Object | Execution of Checkout method |
| dm_connect | dm_user | Logon | Execution of Connect method |
| dm_destroy | dm_sysobject dm_acl dm_user dm_group | Destroy Object | Execution of Destroy method |
| dm_disassemble | dm_sysobject | Disassemble Virtual Document | Execution of Disassemble method |
| dm_disconnect | dm_user | Logoff | Execution of Disconnect method |
| dm_fetch | dm_sysobject | Fetch Object | Execution of Fetch method |
| dm_freeze | dm_sysobject | Freeze Object | Execution of Freeze method |
| dm_getfile | dm_sysobject | View/Export | Occurs when a document is viewed or exported or when the following methods are executed: Getcontent and Getpath. |
| dm_getlogin | dm_user | Get Login | Execution of Getlogin method |
| dm_insertpart | dm_sysobject | Insert into Virtual Document | Execution of an Insertpart method |
| dm_install | dm_policy dm_process dm_activity | Install | Execution of an Install method |
| dm_invalidate | dm_process dm_activity | Invalidate | Execution of an Invalidate method |

| Event | Target Object Type | Event Description | Trigger |
|-------------------------|---|------------------------------|---|
| dm_kill | not applicable | Kill Session | Execution of a Kill method |
| | | | Note: You cannot audit a Kill method that flushes the cache. |
| dm_link | dm_sysobject | Link To | Execution of a Link method |
| dm_lock | dm_sysobject | Lock Object | Execution of a Lock method |
| dm_logon_failure | dm_user | Logon Failure | User attempts to Connect using invalid credentials. |
| dm_mark | dm_sysobject | Add Version Label | Execution of a Mark method |
| dm_prune | dm_sysobject | Prune Versions | Execution of a Prune method |
| dm_purgeaudit | dm_audittrail dm_audittrail_acl dm_audittrail_group | Purge Audit | Execution of a Destroy method or PURGE_AUDIT administration method to remove audit trail entries |
| | | | Purging an audittrail entry is always auditing. It is not possible to unaudit this event. |
| dm_removecontent | dm_sysobject | Remove Content | Execution of a Removecontent method |
| dm_removenote | dm_sysobject dm_process | Remove Note | Execution of a Removenote method |
| dm_removepart | dm_sysobject | Remove from Virtual Document | Execution of a Removepart method |
| dm_removerendi- tion | dm_sysobject | Remove Rendition | Execution of a Removerendition method |
| dm_restore | dm_sysobject | Restore Object | Execution of a Restore method |
| dm_save | dm_sysobject dm_acl | Save Object | Execution of a Save method. |
| | dm_group dm_user | | Note: For new objects, Content Server stores the value Create in the audit trail attribute string_1. For existing objects, the value in the attribute is Save. |
| dm_saveasnew | dm_sysobject dm_acl | Copy Object | Execution of a Saveasnew method |
| dm_setfile | dm_sysobject | Set Content | Execution of the following methods: |
| | | | Appendcontent Appendfile Bindfile Insertfile Insertcontent Setcontent Setpath |
| dm_setoutput | dm_process | Setoutput | Execution of a Setoutput method. |
| dm_signoff | dm_sysobject | Signoff | Execution of Signoff method |
| | | | Note: Signoff methods are always audited. It isn't possible to unregister this event. |

| Event | Target Object Type | Event Description | Trigger |
|---------------|--|-------------------------------|--|
| dm_unaudit | all object types | Unaudit Event | Execution of an Unaudit method |
| | | | Note: Unaudit methods are always audited. It isn't possible to unregister this event. |
| dm_unfreeze | dm_sysobject | Unfreeze Object | Execution of an Unfreeze method |
| dm_uninstall | dm_policy dm_process dm_activity | Uninstall | Execution of an Uninstall method |
| dm_unlink | dm_sysobject | Unlink From | Execution of an Unlink method |
| dm_unlock | dm_sysobject | Cancel Checkout | Execution of an Unlock method |
| dm_unmark | dm_sysobject | Remove Version Label | Execution of an Unmark method |
| dm_updatepart | dm_sysobject | Update in Virtual Document | Execution of an Updatepart method |
| dm_validate | dm_policy dm_process dm_activity | Validate | Execution of a Validate method |

Workflow Events

Table B–2, page B–460 lists the events specific to workflows. Note that several API events listed in the previous table are also applicable to workflows.

Table B-2. Workflow Events

| Event | Target Object Type | Event Description | Trigger |
|----------------------|------------------------------|---|---|
| dm_all_workflow | dm_process (or not included) | All Workflow Events | All events on workflows generated from the specified process object or all events in the Docbase |
| | | | Note: This does not include dm_validate, dm_install, dm_invalidate, and dm_uninstall events. |
| dm_abortworkflow | dm_process | Abort Workflow | Aborting a workflow |
| dm_addpackage | dm_process | Add Workflow Package | Execution of an Addpackage method |
| dm_autotransactivity | dm_process | Automatic Workflow Activity Transition | An automatic activity transition occurs |

| Event | Target Object Type | Event Description | Trigger |
|-------------------------------------|--------------------|---|--|
| dm_changedactivity instancestate | dm_process | Change Workflow Activity to Failed State | An automatic activity changes state because the error handling flag is set to zero and the work item returns a non-zero value. |
| dm_changepriority- workitem | dm_process | Change Workitem Priority | The priority value of a work item is changed at runtime. |
| dm_changestateactivity | dm_process | Change Workflow Activity State | An activity instance changes state to a state other than failed or changes state due to an automatic transition. |
| dm_changestateprocess | dm_process | Change Workflow Template State | A process definition changes state |
| dm_changestatework-flow | dm_process | Change Workflow State | A workflow changes state by a method other than a Save, Execute, or Abort. |
| dm_changeworkflow supervisor | dm_process | Change Workflow Supervisor | Execution of a Setsupervisor method |
| dm_completedworkitem | dm_process | Complete Workitem | Execution of a Complete method |
| dm_createworkflow | dm_process | Create Workflow | A workflow is created. |
| dm_delegatedworkitem | dm_process | Delegate Workitem | A work item is delegated. |
| dm_finishworkflow | dm_process | Finish Workflow | A workflow is terminated. |
| dm_portselect | dm_process | Select Workflow Port | Selection of output ports by a user or Content Server upon completion of an activity. |
| | | | Note: This event is not triggered if the activity has a transition type of prescribed. |
| dm_removepackage | dm_process | Remove Workflow Package | A package is removed from a workflow |
| dm_repeatworkitem | dm_process | Repeat Workflow Work Item | A work item is repeated. |
| dm_selectedworkitem | dm_process | Select Workitem | A work item is acquired. |
| dm_startworkflow | dm_process | Start Workflow | A workflow is started. |
| dm_startedworkitem | dm_process | Start Workitem | A work item is generated. |

Lifecycle Events

Table B-3, page B-462 lists the events specific to lifecyles.

Table B-3. Lifecycle Events

| Event | Target Object Type | Event Description | Trigger |
|---------------|--------------------|--------------------------------|---|
| dm_bp_attach | dm_sysobject | Attach Lifecycle | Attaching a lifecycle to an object |
| dm_bp_demote | dm_sysobject | Demote from Lifecycle State | Demoting an object from a lifecycle state |
| dm_bp_promote | dm_sysobject | Promote to Lifecycle State | Promoting an object to a lifecycle state |
| dm_bp_resume | dm_syobject | Resume Lifecycle | Resuming an object's suspended lifecycle |
| dm_bp_suspend | dm_sysobject | Suspend Lifecycle | Suspending an object's lifecycle |