10/4/10


How to approach a system called Don't start thinking about writing code.

Do think about the purpose of a system call . Safe" mechanism by which user programs are able to access kernel-protected resources

Lock class & Condition are Kernel resources

Lock & Condition system calls are just interfaces to Lock & Condition Kernel objects

Example: Acquire
V
Task: Provide access to a Lock
object
Task: Provide access to a Lock object Locks are specific to , a process
a process
The Kernel must have a
real Lock object - created
The Kernel must have a real Lock object - created upon request by a user
` /
· ·
program CreateLock syscall
Program CreateLock syscall Locks must be retrievable for Acquire, Release, Destroy Lock syscalls
Program CreateLock syscall Locks must be retrievable for Acquire, Release, Destroy Lock syscalls
Program CreateLock syscall Locks must be retrievable for Acquire, Release, Destroy Lock syscalls
program CreateLock syscall



resource identifier

Let's use an array (kernel)

to store recreated Locks & CVs

of for each - I for Locks

I for CVr

My Kernel return value is the

index position in the array of

the new object

Because of my choice of an arroy, I have to track of where the next index position is for the next new resource · How do I know when I run out of space in my arroy · Use a simple counter.

• Every time a Create syscall
is requested I increment the counter · Be sure to check for a full array The tables & counters are shared by all threads issuing system . Need a lock - used by the Kernel- to protect these shared kernel resources

The array Cannot be an array of Locks/Conditions

• We cannot enforce the process-specific rule

Need some piece of data in the arroy so the Kernel can enforce the process rule If you have a unique PID in your process

· Or ... Addr Space pointer

For now...


struct Lock Entry {

Lock * lock;

Addr Space * owner Process;

3;

Lock Entry lock Table [MAX-LOCKS];




A new issue: If we don't remember

a Destroy Lock has been
requested, the user
program would be forced
to issue - worst casemultiple Destroy Locks
to delete a lock,
new
struct Lock Entry?
Lock+ lock;

Addr Space + owner Process;

bool to Be Deleted = false;

3;



int Create Condition (char +) int len,

void Wait (int cond#, int lock#)

"Signal (int cond#, int lock#)


"Broadcost (int cond#, int lock#)

void Destroy Condition (int cond#);

syscall.h has: * void Halt(); Function declaration To the compiler: There is a function called Halt In my user program, I can #include "syscall.h" int main () & Halt(); I return 0; 1) compile > object file

2 Link => links all object files wany other libraries to make an executable There is C(C++ function called Halt() - it is just a ustub"

The connection is in start.s.
There is assembler code that "converts" the stub function into a jump to Nachas Kerne



Acquire
lock Table Lock -> Acquire(); validations
Lock+ lock = lockTable Lindex]? is To Bellsed = true; is In Use
Dothe Tock-> Acquire(); Tock Table Luck-> Release();

Need a status variable that a lock is going to be used

Scenario: A lock is not in use,
But the thread next
in the Ready Q has
an Acquire about to
be executed

The thread in the CPU has requested a Destroy Lock

* before after validation this thread is context

switched out

This cannot be allowed to happen

Destroy Lock

lock Table Lock > Acquire(); ?

- volidation

context ->

switch delete" the entry

lock Table Lock > Release();