Nvidia-smi
sudo apt update
sudo apt install -y nvidia-driver-525 nvidia-utils-525
sudo reboot

IF not already cuda instttalled
wget
https://developer.download.nvidia.com/compute/cuda/11.7.0/local_installers/cuda_11.7.0_515.43.04_linux.run
sudo sh cuda_11.7.0_515.43.04_linux.run

nvcc --version

If nott docker iinnnssttalled

sudo apt update
sudo apt install -y apt-transport-https ca-certificates curl software-properties-common
curl -fsSL https://download.docker.com/linux/ubuntu/gpg | sudo apt-key add -
sudo add-apt-repository "deb [arch=amd64] https://download.docker.com/linux/ubuntu $(lsb_release -cs) stable"
sudo apt update
sudo apt install -y docker-ce

Enable Docker to use NVIDIA GPUs:

distribution=$(. /etc/os-release;echo IDVERSION_ID)
curl -s -L https://nvidia.github.io/nvidia-docker/gpgkey | sudo apt-key add -
curl -s -L https://nvidia.github.io/nvidia-docker/$distribution/nvidia-docker.list | sudo tee /etc/apt/sources.list.d/nvidia-docker.list
sudo apt update
sudo apt install -y nvidia-docker2
sudo systemctl restart docker

Install NVIDIA TAO Toolkit Launcher

```
sudo apt install -y python3-pip python3-venv
python3 -m venv tao_env
source tao_env/bin/activate
```

```
pip install --upgrade pip
pip install nvidia-tao==5.5.1

tao info --verbose
```

docker login nvcr.io

Use wget to download version 5.3.0 (compatible with TAO 5.5):

```
wget --content-disposition
https://api.ngc.nvidia.com/v2/resources/nvidia/tao/tao-getting-started/versions/5.3.0/zip -O
getting_started_v5.3.0.zip
unzip -u getting_started_v5.3.0.zip -d ./getting_started_v5.3.0
cd getting_started_v5.3.0
```

```
pip install -r notebooks/tao_launcher_starter_kit/deps/requirements-pip.txt
```

```
mkdir -p ~/tao-experiments
cat << EOF > ~/.tao_mounts.json
{
    "Mounts": [
        {
            "source": "$HOME/tao-experiments",
            "destination": "/workspace/tao-experiments"
        },
        {
            "source": "$PWD/getting_started_v5.3.0/notebooks",
            "destination": "/workspace/notebooks"
        }
    ]
```

```
}
EOF



export KEY="your_ngc_api_key"
export LOCAL_EXPERIMENT_DIR=~/tao-experiments
export SAMPLES_DIR=$PWD/getting_started_v5.3.0
export USER_EXPERIMENT_DIR=/workspace/tao-experiments
export DATA_DIR=/workspace/tao-experiments/data
export SPECS_DIR=/workspace/notebooks/pose_classification/specs




mkdir -p $LOCAL_EXPERIMENT_DIR/pretrained_model

pip install nvidia-ngc
ngc registry model download-version nvidia/tao/poseclassificationnet:trainable_v1.0 --dest
$LOCAL_EXPERIMENT_DIR/pretrained_model



Troubleshoot
ngc config set

mkdir -p $LOCAL_EXPERIMENT_DIR/data

tao pose_classification train -e $SPECS_DIR/pose_classification_train.yaml \
                        -k $KEY \
                        -r $USER_EXPERIMENT_DIR/models/exp_unpruned \
                        --gpus 1
```