
Chapter 2: Processes

Chapter 2: Processes

- Process Concept
- Process States
- Process Control Block (PCB)
- Process Scheduling
- Operations on Processes
- Interprocess Communication
- Examples of IPC Systems
- Communication in Client-Server Systems




Introduction

- A process is a **program in execution**.
- It includes:
 - Program code (text section)
 - Data (variables, heap, stack)
 - Current activity (program counter, CPU registers).
- Example: Running *MS Word* → Program on disk becomes a *process* in memory.

Concept of a Process

- Difference between program and process:
 - Program = passive (on disk).
 - Process = active (running in memory).
- A single program can have multiple processes.
- Example: Opening 3 Chrome windows → 3 processes of Chrome.


Process in Memory



Process States

- **New:** Process is being created.
- Ready: Waiting for CPU.
- Running: Currently executing.
- Waiting: Waiting for I/O or event.
- Terminated: Finished execution.
- Example: While downloading a file, the browser may switch between Running (CPU active) and Waiting (I/O pending).

Diagram of Process State



Concurrent Processes

- Multiple processes running at the same time (time-shared).
- The CPU switches rapidly between them → illusion of parallelism.
- Example: Listening to music while typing a Word document and downloading a file .
- In multi-core systems: true parallelism possible.

Process Control Block (PCB)

Information associated with each process (also called **task control block**)

- Process state running, waiting, etc
- Program counter location of instruction to next execute
- CPU registers contents of all process-centric registers
- CPU scheduling information- priorities, scheduling queue pointers
- Memory-management information memory allocated to the process
- Accounting information CPU used, clock time elapsed since start, time limits
- I/O status information I/O devices allocated to process, list of open files

process state

process number

program counter


registers

memory limits

list of open files




CPU Switch From Process to Process



Process Scheduling

- Maximize CPU use, quickly switch processes onto CPU for time sharing
- Process scheduler selects among available processes for next execution on CPU
- Maintains scheduling queues of processes
 - Job queue set of all processes in the system
 - Ready queue set of all processes residing in main memory, ready and waiting to execute
 - Device queues set of processes waiting for an I/O device
 - Processes migrate among the various queues

Representation of Process Scheduling




Queueing diagram represents queues,

represents queues resources, flows

Schedulers

- Short-term scheduler (or CPU scheduler) selects which process should be executed next and allocates CPU
 - Short-term scheduler is invoked frequently (milliseconds) ⇒ (must be fast)
- Long-term scheduler (or job scheduler) selects which processes should be brought into the ready queue
 - Long-term scheduler is invoked infrequently (seconds, minutes) ⇒ (may be slow)
 - The long-term scheduler controls the degree of multiprogramming
- Processes can be described as either:
 - I/O-bound process spends more time doing I/O than computations, many short CPU bursts
 - CPU-bound process spends more time doing computations; few very long CPU bursts

Addition of Medium Term Scheduling



- Medium-term scheduler can be added if degree of multiple programming needs to decrease
 - Remove process from memory, store on disk, bring back in from disk to continue execution: swapping


Context Switch

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- Context-switch time is overhead; the system does no useful work while switching
- Time dependent on hardware support
 - Some hardware provides multiple sets of registers per CPU
 multiple contexts loaded at once

Process Creation

- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- Generally, process identified and managed via a process identifier (pid)
- Resource sharing options
 - Parent and children share all resources
 - Children share subset of parent's resources
 - Parent and child share no resources
- Execution options
 - Parent and children execute concurrently
 - Parent waits until children terminate

Process Creation (Cont.)



- Address space
 - Child duplicate of parent
 - Child has a program loaded into it
- UNIX examples
 - fork() system call creates new process
 - exec() system call used after a fork() to replace the process' memory space with a new program

Process Termination

- Process executes last statement and asks the operating system to delete it (exit)
 - Returns status data from child to parent (via wait())
 - Process' resources are deallocated by operating system
- Parent may terminate the execution of children processes (abort)
 - Child has exceeded allocated resources
 - Task assigned to child is no longer required
 - The parent is exiting and the operating systems does not allow a child to continue if its parent terminates

Interprocess Communication


- Processes within a system may be independent or cooperating
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
 - Information sharing
 - Computation speedup
 - Modularity
 - Convenience
- Cooperating processes need interprocess communication (IPC)
- Two models of IPC
 - Shared memory
 - Message passing

Cooperating Processes


- Independent process cannot affect or be affected by the execution of another process
- Cooperating process can affect or be affected by the execution of another process
- Advantages of process cooperation
 - Information sharing
 - Computation speed-up
 - Modularity
 - Convenience

Communications Models

(a) Shared memory



(b) Message passing.



Producer-Consumer Problem

- Paradigm for cooperating processes, producer process produces information that is consumed by a consumer process
 - unbounded-buffer places no practical limit on the size of the buffer
 - bounded-buffer assumes that there is a fixed buffer size

Bounded-Buffer – Shared-Memory Solution

Shared data

```
#define BUFFER_SIZE 10

typedef struct {
    . . .
} item;

item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```

Solution is correct, but can only use BUFFER_SIZE-1 elements

Bounded-Buffer – Producer

```
item next_produced;
while (true) {
    /* produce an item in next produced */
    while (((in + 1) % BUFFER_SIZE) == out)
        ; /* do nothing */
    buffer[in] = next_produced;
    in = (in + 1) % BUFFER_SIZE;
}
```

Bounded Buffer – Consumer

```
item next_consumed;
while (true) {
    while (in == out)
        ; /* do nothing */
    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;

    /* consume the item in next consumed */
}
```

Interprocess Communication – Message Passing

- Mechanism for processes to communicate and to synchronize their actions
- Message system processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
 - **send**(*message*) message size fixed or variable
 - receive(message)
- If processes P and Q wish to communicate, they need to:
 - Establish a communication link between them
 - Exchange messages via send/receive
- Implementation of communication link
 - Physical (e.g., shared memory, hardware bus)
 - Logical (e.g., logical properties(Synchronous or asynchronous))


Direct Communication

- Processes must name each other explicitly:
 - send (P, message) send a message to process P
 - receive(Q, message) receive a message from process Q
- Properties of communication link
 - Links are established automatically
 - A link is associated with exactly one pair of communicating processes
 - Between each pair there exists exactly one link
 - The link may be unidirectional, but is usually bi-directional

Communications in Client-Server Systems


- Sockets
- Remote Procedure Calls
- Pipes
- Remote Method Invocation (Java)

Sockets




 A socket is defined as an endpoint for communication

Remote Procedure Calls



 Remote procedure call (RPC) abstracts procedure calls between processes on networked systems.

Execution of RPC



End of Chapter 2