




King Fahd University of Petroleum and Minerals
College of Computer Sciences and Engineering
Computer Engineering Department
COE 301: Computer Architecture

LAB 09: Floating-Point

Saleh AlSaleh



Agenda

- IEEE754 Standard
- Coprocessor 1
- Floating Point Instructions
- Floating Point Conditional Instructions
- Registers Convention
- Live Examples
- Tasks

IEEE 754 Standard

- S = Sign Bit (0 positive, 1 negative)
- E = Exponent Bits (8 Single, 11 Double Precision)
- F = Fraction Bits (23 Single, 52 Double Precision)
- Bias (127 Single, 1023 Double)
- Normalized Value = $\pm (1.F)_2 \times 2^{E-\text{Bias}}$

S	Exponent	Fraction
---	----------	----------

Coprocessor 1

- Coprocessor 1 has 32 floating-point registers (32 bit each).
- These registers are numbered as \$f0-\$f31.
- Each register can hold one single-precision floating-point number.
- The double-precision number uses two registers and is stored in an even-odd pair of registers, but we only refer to the even-numbered register.
- There are 8 condition flags, numbered from 0 to 7 used by floating-point compare and branch instructions

Floating Point Instruction

Instruction	Description
lwc1 or l.s	Load a word from memory to a single-precision floating-point register
ldc1 or l.d	Load a double word from memory to a double-precision register
swc1 or s.s	Store a single-precision floating-point register in memory
sdc1 or s.d	Store a double-precision floating-point register in memory
add.s, add.d	Floating Point Addition (Single, Double)
sub.s, sub.d	Floating Point Subtraction (Single, Double)
mul.s, mul.d	Floating Point Multiplication (Single, Double)
div.s, div.d	Floating Point Division (Single, Double)
sqrt.s, sqrt.d	Floating Point Square Root (Single, Double)
abs.s, abs.d	Floating Point Absolute Value (Single, Double)
neg.s, neg.d	Floating Point Negative Value (Single, Double)

Floating Point Instruction (continued)

Instruction	Description
mov.s, mov.d	Copy floating point value from one register to another (Single, Double)
cvt.s.w	Convert from word (integer) to single precision floating point
cvt.s.d	Convert from double precision to single precision floating point
cvt.d.w	Convert from word (integer) to double precision floating point
cvt.d.s	Convert from single precision to double precision floating point
cvt.w.s	Convert from single precision to word (integer)
cvt.w.d	Convert from double precision to word (integer)
ceil.w.s, ceil.w.d	Integer ceiling (Single, Double)
floor.w.s, floor.w.d	Integer floor(Single, Double)
trunc.w.s, trunc.w.d	Truncate (Single, Double)

Floating Point Conditional Instructions

Instruction	Example	Description
c.eq.s, c.eq.d	c.eq.s \$f0, \$f1 c.eq.d 3, \$f2, \$f4	If ($\$f0 == \$f1$), set flag 0 to true, else false If ($\$f2 == \$f4$), set flag 3 to true, else false
c.lt.s, c.lt.d	c.lt.s \$f0, \$f1 c.lt.d 4, \$f2, \$f4	If ($\$f0 < \$f1$), set flag 0 to true, else false If ($\$f2 < \$f4$), set flag 4 to true, else false
c.le.s, c.le.d	c.le.s \$f0, \$f1 c.le.d 5, \$f2, \$f4	If ($\$f0 <= \$f1$), set flag 0 to true, else false If ($\$f2 <= \$f4$), set flag 5 to true, else false
bc1t	bc1t loop bc1t 6, while	Branch to loop if condition flag 0 is true Branch to while if condition flag 6 is true
bc1f	bc1t loop bc1t 7, while	Branch to loop if condition flag 0 is false Branch to while if condition flag 7 is false

Register Convention

Registers	Usage
\$f0 - \$f3	Floating-point procedure results
\$f4 - \$f11	Temporary floating-point registers, NOT preserved across procedure calls
\$f12 - \$f15	Floating-point parameters, NOT preserved across procedure calls. Additional floating-point parameters should be pushed on the stack.
\$f16 - \$f19	More temporary registers, NOT preserved across procedure calls.
\$f20 - \$f31	Saved floating-point registers. Should be preserved across procedure calls.

Live Examples