# Provider 程序安装手册

# 最低要求

一定要有公网 IP

要求 7x24 小时开机,可用性达不到 97%将不能获得奖励

至少 100G 以上可用空间

下行带宽 10Mbps 以上,上行带宽 4Mbps 以上,如何测速请查阅附录

系统推荐使用 linux 等类 Unix 操作系统(比如 Linux、Unix、Openwrt、freenas...)

## 如何运行 provider

- 1,注册必填参数
- -availability string

保证可用性大于 97%, 举例: 98%, 99%, 99.9%

-billEmail string

账单邮箱地址

-downBandwidth uint

下载带宽, 单位: Mbps, 举例: 100, 20

-mainStoragePath string

主要存储路径

-mainStorageVolume string

主要存储容量大小,单位 TB 或 GB,举例: 2TB 或 500GB

-upBandwidth uint

上传带宽, 单位: Mbps, 举例: 100, 20, 8, 4

-walletAddress string

输入 Samos 钱包地址用于接收奖励

#### 运行方式如下:

./nebula-provider register -availability 99% -billEmail youremailaddress@domain.com -downBandwidth 100 -upBandwidth 20 -walletAddress yourwalletaddress -mainStoragePath /your/storage/path/for/provider -mainStorageVolume 800GB

示例:

./nebula-provider register -availability 99% -billEmail youremailaddress@domain.com -downBandwidth 100 -upBandwidth 20 -walletAddress te3iJRP9XNb4hbavxt4ckjBhy9PHo5a9LM -mainStoragePath /media/win\_d/tmp/main-storage -mainStorageVolume 800GB

如果提示:

Register failed, ping 11.22.33.44:6666 failed, You may not have a public network ip, error message:...

说明无法连接您的 provider 端口,可能是路由器不支持 upnp,或者您没有公网 ip

如果成功您将会看到以下信息输出:

Register success, please recieve verify code email to verify bill email and backup your config file: /xxx/yyy/config.json

请备份这个配置文件

2, 邮箱验证

请查阅邮箱复制验证码,然后执行以下命令验证邮箱:

./nebula-provider verifyEmail -verifyCode verifyCodeCopyFromEmail

如果成功您将会看到以下信息输出:

verifyEmail success, you can start daemon now.

3, 启动服务

完成邮箱验证后,注册过程成功完成,您可以运行以下命令运行 provider 服务:

./nebula-provider daemon

在 Linux 等类 Unix 操作系统上,建议以 nohup 模式后台运行

## 高级模式

所有使用参数:

usage: ./nebula-provider <command> [<args>]

The most commonly used commands are:

register [-configDir config-dir] [-trackerServer tracker-server-and-port] [-collectorServer collector-server-and-port] [-listen listen-address-and-port] [-host outer-host] [-dynamicDomain dynamic-domain] [-port outer-port] -walletAddress wallet-address -billEmail bill-email -downBandwidth down-bandwidth -upBandwidth up-bandwidth -availability availability-percentage -mainStoragePath storage-path -mainStorageVolume storage-volume -extraStorage extra-storage-string

-availability string

保证可用性大于 97%, 举例: 98%, 99%, 99.9%

-billEmail string

账单邮箱地址

-configDir string

配置文件夹 (default "/home/samos/.samos-nebula-provider")

-downBandwidth uint

下载带宽,单位: Mbps, 举例: 100, 20

#### -dynamicDomain string

动态域名, 举例: mydomain.xicp.net

#### -extraStorage string

附加存储,格式:路径1:容量1,路径2:容量2,路径不可以包含逗号,举例:/mnt/sde1:1TB,/mnt/sdf1:800GB,/mnt/sdg1:500GB

### -host string

外网或动态域名, 举例: 123.123.123.123

#### -listen string

监听地址和端口, 举例: 111.111.111.111:6666 or :6666 (default ":6666")

#### -mainStoragePath string

主存储路径

#### -mainStorageVolume string

主存储容量大小, 单位 TB 或 GB, 举例: 2TB or 500GB

#### -port uint

外网端口, 举例:6666 (default 6666)

#### -trackerServer string

tracker 服务器地址, 举例: tracker.store.samos.io:6677 (default "tracker.store.samos.io:6677")

#### -upBandwidth uint

上传带宽, 单位: Mbps, 举例: 100, 20, 8, 4

#### -walletAddress string

输入 Samos 钱包地址用于接收奖励

# verifyEmail [-configDir config-dir] [-trackerServer tracker-server-and-port] -verifyCode verify-code

#### -configDir string

```
配置文件夹 (default "/home/samos/.samos-nebula-provider")
-trackerServer string
  tracker 服务器地址, 举例: tracker.store.samos.io:6677 (default
"tracker.store.samos.io:6677")
-verifyCode string
   邮箱验证码
resendVerifyCode [-configDir config-dir] [-trackerServer tracker-server-and-port]
-configDir string
   配置文件夹 (default "/home/samos/.samos-nebula-provider")
-trackerServer string
  tracker 服务器地址, 举例: tracker.store.samos.io:6677 (default
"tracker.store.samos.io:6677")
daemon [-configDir config-dir] [-trackerServer tracker-server-and-port] [-listen
listen-address-and-port] [-disableAutoRefreshIp]
-collectorServer string
  collector 服务器地址, 举例: collector.store.samos.io:6688 (default
"collector.store.samos.io:6688")
-configDir string
   配置文件夹 (default "/home/samos/.samos-nebula-provider")
-disableAutoRefreshIp
  禁用自动刷新 IP
-listen string
  监听地址和端口, 举例: 111.111.111.111:6666 or :6666 (default ":6666")
```

tracker 服务器地址, 举例: tracker.store.samos.io:6677 (default

-trackerServer string

"tracker.store.samos.io:6677")

# addStorage [-configDir config-dir] [-trackerServer tracker-server-and-port] -path storage-path -volume storage-volume

-configDir string

配置文件夹 (default "/home/samos/.samos-nebula-provider")

-path string

添加存储路径

-trackerServer string

tracker 服务器地址, 举例: tracker.store.samos.io:6677 (default "tracker.store.samos.io:6677")

-volume string

添加存储容量大小,单位: TB 或 GB, 举例: 2TB 或 500GB

## 附录

如何测网速,建议使用 speedtest

linux 等类 unix 操作系统: https://github.com/sivel/speedtest-cli

windows 及 macOS: http://www.speedtest.net/apps/desktop

(Windows or macOS)

### 北京联通的宽带如何配置

北京联通接入,例子:

1,命令行启动

#./nebula-provider register -availability 99% -billEmail info@samos.io -downBandwidth 100 -upBandwidth 10 -walletAddress 27JWhwCxgTnNF4vDCFZeURuNpWvDBiq8yuo -mainStoragePath /data1/ -mainStorageVolume 1600GB

use upnp port mapping failed: 未发现网关设备

use upnp get outer ip failed: 未发现网关设备

not specify host and dynamic domain, will use: 123.119.189.51

ping failed, error: rpc error: code = DeadlineExceeded desc = context deadline exceeded

说明公网没有打开

2, 在北京联通提供的光猫后台

高级 NAT 设置中,把公网 IP 映射到内网的矿机

3, 再次命令.

```
/nebula-provider register -availability 99% -billEmail info@samos.io
-downBandwidth 100 -upBandwidth 10 -walletAddress
27JWhwCxgTnNF4vDCFZeURuNpWvDBiq8yuo -mainStoragePath /data1/
-mainStorageVolume 1600GB
use upnp port mapping failed: 未发现网关设备
use upnp get outer ip failed: 未发现网关设备
not specify host and dynamic domain, will use: 123.119.189.51
Register success, please recieve verify code email to verify bill email and backup your
config file: /root/.samos-nebula-provider/config.json
提示生成了配置文件
4,查看配置文件(View configuration file)
more /root/.samos-nebula-provider/config.json
{
"NodeId": "80edb92c94a618059a5fa237c2042df7a1079d29",
"WalletAddress": "27JWhwCxgTnNF4vDCFZeURuNpWvDBiq8yuo",
"BillEmail": "info@samos.io",
5, 验证 email
./nebula-provider verifyEmail -verifyCode r7fe7x68
verifyEmail success, you can start daemon now.
6,启动
# nohup ./nebula-provider daemon &
```