Microeconomic Theory — ECON 323 503 Chapter 7: Costs

Vikram Manjunath

Texas A&M University

November 11, 2014

1. Measuring costs: must account for both explicit and *implicit* cots.

- 1. Measuring costs: must account for both explicit and *implicit* cots.
- 2. Short-run costs: minimize costs by picking the right amount of the variable inputs for give fixed inputs.

- 1. Measuring costs: must account for both explicit and *implicit* cots.
- 2. Short-run costs: minimize costs by picking the right amount of the variable inputs for give fixed inputs.
- 3. Long-run costs: minimize cots by choosing the right amount of every input.

- 1. Measuring costs: must account for both explicit and *implicit* cots.
- 2. Short-run costs: minimize costs by picking the right amount of the variable inputs for give fixed inputs.
- 3. Long-run costs: minimize cots by choosing the right amount of every input.
- 4. Lower costs in the long-run: more flexibility means lower costs.

- 1. Measuring costs: must account for both explicit and *implicit* cots.
- 2. Short-run costs: minimize costs by picking the right amount of the variable inputs for give fixed inputs.
- 3. Long-run costs: minimize cots by choosing the right amount of every input.
- 4. Lower costs in the long-run: more flexibility means lower costs.
- 5. Cost of producing multiple goods.

Measuring costs

► Explicit costs: wages paid for labor, price of raw material, etc.

Measuring costs

- ► Explicit costs: wages paid for labor, price of raw material, etc.
- ▶ Implicit costs: the opportunities foregone when using resources.

What's it cost for you to be here in this room?

What's it cost for you to be here in this room?

You paid tuition. So is that all it costs you?

What's it cost for you to be here in this room?

You paid tuition. So is that all it costs you?

You're also giving up opportunities do other things.

What's it cost for you to be here in this room?

You paid tuition. So is that all it costs you?

You're also giving up opportunities do other things.

The value of those other opportunities is your "opportunity cost" of being here today.

You start a firm and own it.

You start a firm and own it.

You get all of the profits.

You start a firm and own it.

You get all of the profits.

You pay yourself \$1,000 as a salary.

You start a firm and own it.

You get all of the profits.

You pay yourself \$1,000 as a salary.

However, you could make \$11,000 working for another firm.

You start a firm and own it.

You get all of the profits.

You pay yourself \$1,000 as a salary.

However, you could make \$11,000 working for another firm.

Your opportunity cost of working for yourself is \$11,000.

You start a firm and own it.

You get all of the profits.

You pay yourself \$1,000 as a salary.

However, you could make \$11,000 working for another firm.

Your opportunity cost of working for yourself is \$11,000.

That's the value that you'd get from the best alternative use of your time.

You start a firm and own it.

You get all of the profits.

You pay yourself \$1,000 as a salary.

However, you could make \$11,000 working for another firm.

Your opportunity cost of working for yourself is \$11,000.

That's the value that you'd get from the best alternative use of your time.

So your cost of employing yourself isn't the \$1,000 you pay yourself, but the \$11,000 you're forgoing.

Decisions made apply to certain timeframes. So costs need to be measured over those timeframes.

Decisions made apply to certain timeframes. So costs need to be measured over those timeframes.

Two problems in measuring the cost of durable goods (capital).

Decisions made apply to certain timeframes. So costs need to be measured over those timeframes.

Two problems in measuring the cost of durable goods (capital).

1. How do you spread the cost over time?

Decisions made apply to certain timeframes. So costs need to be measured over those timeframes.

Two problems in measuring the cost of durable goods (capital).

- 1. How do you spread the cost over time?
- 2. How do you deal with changes in the value of capital?

A pick-up truck costs your firm \$20,000 to buy and \$400 a month to rent.

A pick-up truck costs your firm \$20,000 to buy and \$400 a month to rent.

What is the monthly cost of using this pickup truck?

A pick-up truck costs your firm \$20,000 to buy and \$400 a month to rent.

What is the monthly cost of using this pickup truck?

If you rent it: \$400. If the rental rate changes over time, that's fine too. The opportunity cost of the truck is just what you pay to rent it.

A pick-up truck costs your firm \$20,000 to buy and \$400 a month to rent.

What is the monthly cost of using this pickup truck?

If you rent it: \$400. If the rental rate changes over time, that's fine too. The opportunity cost of the truck is just what you pay to rent it.

If you buy it: This is a bit more complicated.

A pick-up truck costs your firm \$20,000 to buy and \$400 a month to rent.

What is the monthly cost of using this pickup truck?

If you rent it: \$400. If the rental rate changes over time, that's fine too. The opportunity cost of the truck is just what you pay to rent it.

If you buy it: This is a bit more complicated.

You could consider it a \$20,000 cost for the first month but is it free afterwards?

A pick-up truck costs your firm \$20,000 to buy and \$400 a month to rent.

What is the monthly cost of using this pickup truck?

If you rent it: \$400. If the rental rate changes over time, that's fine too. The opportunity cost of the truck is just what you pay to rent it.

If you buy it: This is a bit more complicated.

You could consider it a \$20,000 cost for the first month but is it free afterwards?

No. There's an opportunity cost: you could rent out the truck or even sell it rather than using it.

Suppose you sell it after the first year for \$17,000.

Suppose you sell it after the first year for \$17,000.

What was your opportunity cost of the truck? Is it 20,000 - 17,000 = 3,000?

Suppose you sell it after the first year for \$17,000.

What was your opportunity cost of the truck? Is it 20,000 - 17,000 = 3,000?

No, you have to think about what you could have done with the money if you hadn't paid for the truck. If your bank gives you (5%) interest, you'd have gotten back \$21,000 if you just deposited the money.

Suppose you sell it after the first year for \$17,000.

What was your opportunity cost of the truck? Is it 20,000 - 17,000 = 3,000?

No, you have to think about what you could have done with the money if you hadn't paid for the truck. If your bank gives you (5%) interest, you'd have gotten back \$21,000 if you just deposited the money.

That \$1,000 is part of the opportunity cost of the truck, bringing its total opportunity cost to \$4,000.

If you're running a business in a building that you own, is your cost for office space zero?

If you're running a business in a building that you own, is your cost for office space zero?

No. You have to account for what others might have paid you for the space if you rented it to them rather than using it yourself.

If you're running a business in a building that you own, is your cost for office space zero?

No. You have to account for what others might have paid you for the space if you rented it to them rather than using it yourself.

You're forgoing that additional income from the resources that you have. That's an opportunity cost.

Sunk costs

 $A\ past\ expenditure\ that\ cannot\ be\ recovered.$

Sunk costs

A past expenditure that cannot be recovered.

These <u>must not</u> be considered in making decisions.

Sunk costs

A past expenditure that cannot be recovered.

These <u>must not</u> be considered in making decisions.

An example: expenditure on specialized/custom equipment that you can't sell to anyone.

You buy a piece of land for \$300,000.

You buy a piece of land for \$300,000.

It's market value now falls to \$200,000.

You buy a piece of land for \$300,000.

It's market value now falls to \$200,000.

The money that you lost on the land is a *sunk cost* (\$300,000 - \$200,000 = \$100,000).

You buy a piece of land for \$300,000.

It's market value now falls to \$200,000.

The money that you lost on the land is a *sunk cost* (\$300,000 - \$200,000 = \$100,000).

You can choose to build a factory on it. With the factory on it, the land is worth \$240,000 to you. Should you build the factory?

You buy a piece of land for \$300,000.

It's market value now falls to \$200,000.

The money that you lost on the land is a *sunk cost* (\$300,000 - \$200,000 = \$100,000).

You can choose to build a factory on it. With the factory on it, the land is worth \$240,000 to you. Should you build the factory?

Yes. By building the factory you end up with something worth \$40,000 = \$240,000 - \$200,000 more.

You buy a piece of land for \$300,000.

It's market value now falls to \$200,000.

The money that you lost on the land is a *sunk cost* (\$300,000 - \$200,000 = \$100,000).

You can choose to build a factory on it. With the factory on it, the land is worth \$240,000 to you. Should you build the factory?

Yes. By building the factory you end up with something worth \$40,000 = \$240,000 - \$200,000 more.

If you considered the original cost (which you've already paid), you'd come to the conclusion that if you build the factory, you'd have a loss of \$60,000.

Short-run costs

If you rent a space for your business, you have to pay that amount every month. You could decide not to do any business at all and avoid it (so it's not a sunk cost), but if you do any business at all you have to pay rent. This is your *fixed cost*, F. How much business you do doesn't affect it.

Short-run costs

If you rent a space for your business, you have to pay that amount every month. You could decide not to do any business at all and avoid it (so it's not a sunk cost), but if you do any business at all you have to pay rent. This is your *fixed cost*, F. How much business you do doesn't affect it.

The cost of inputs that you can use in varying quantities (labor and material) depending on your output is your *variable cost*, VC(q).

Short-run costs

If you rent a space for your business, you have to pay that amount every month. You could decide not to do any business at all and avoid it (so it's not a sunk cost), but if you do any business at all you have to pay rent. This is your *fixed cost*, F. How much business you do doesn't affect it.

The cost of inputs that you can use in varying quantities (labor and material) depending on your output is your *variable cost*, VC(q).

Your cost, C(q) is the sum of these two:

$$C(q) = VC(q) + F.$$

Marginal cost

If you're producing q units already, what's the extra cost of producing one more unit?

Marginal cost =
$$MC(q) = \frac{dC(q)}{dq}$$
.

Marginal cost

If you're producing q units already, what's the extra cost of producing one more unit?

Marginal cost =
$$MC(q) = \frac{dC(q)}{dq}$$
.

Since F is a constant, $MC(q) = \frac{VC(q)}{dq}$.

1. Average Fixed Cost: $AFC(q) = \frac{F}{q}$. This shrinks as q grows large.

- 1. Average Fixed Cost: $AFC(q) = \frac{F}{q}$. This shrinks as q grows large.
- 2. Average Variable Cost: $AVC(q) = \frac{VC(q)}{q}$. Since VC(q) may rise or fall with q, this AVC(Q) may rise or fall as well.

- 1. Average Fixed Cost: $AFC(q) = \frac{F}{q}$. This shrinks as q grows large.
- 2. Average Variable Cost: $AVC(q) = \frac{VC(q)}{q}$. Since VC(q) may rise or fall with q, this AVC(Q) may rise or fall as well.
- 3. Average Cost: $AC(a) = \frac{C(q)}{q}$.

$$AC(q) = \frac{C(q)}{q} = \frac{VC(q)}{q} + \frac{F}{q} = AVC(q) + AFC(q).$$

- 1. Average Fixed Cost: $AFC(q) = \frac{F}{q}$. This shrinks as q grows large.
- 2. Average Variable Cost: $AVC(q) = \frac{VC(q)}{q}$. Since VC(q) may rise or fall with q, this AVC(Q) may rise or fall as well.
- 3. Average Cost: $AC(a) = \frac{C(q)}{q}$.

$$AC(q) = \frac{C(q)}{q} = \frac{VC(q)}{q} + \frac{F}{q} = AVC(q) + AFC(q).$$

AC(q) is what you need to know if you're making a profit or not.

$$C(q) = 100q - 4q^2 + 0.2q^3 + 450$$

What are F and VC(q)?

$$C(q) = 100q - 4q^2 + 0.2q^3 + 450$$

What are F and VC(q)?

$$F = 450$$

$$C(q) = 100q - 4q^2 + 0.2q^3 + 450$$

What are F and VC(q)?

$$F=450$$

$$VC(q) = 100q - 4q^2 + 0.2q^3$$

Marginal cost?

$$MC(q) = \frac{dC(q)}{dq}$$

$$= \frac{d(100q - 4q^2 + 0.2q^3 + 450)}{dq}$$

$$= 100 - 8q + 0.6q^2$$

Marginal cost?

$$MC(q) = \frac{dC(q)}{dq}$$

$$= \frac{d(100q - 4q^2 + 0.2q^3 + 450)}{dq}$$

$$= 100 - 8q + 0.6q^2$$

Average variable cost?

$$AVC(q) = \frac{VC(q)}{q}$$

$$= \frac{100q - 4q^2 + 0.2q^3}{q}$$

$$= 100 - 4q + 0.2q^2$$

 $\label{eq:average fixed cost} Average \ fixed \ cost?$

$$AFC(q) = \frac{450}{q}$$

Average fixed cost?

$$AFC(q) = \frac{450}{q}$$


Average cost?


$$AC(q) = \frac{C(q)}{q}$$

$$= \frac{100q - 4q^2 + 0.2q^3 + 450}{q}$$


$$= 100 - 4q + 0.2q^2 + \frac{450}{q}$$

$$= AVC(q) + AFC(q).$$







F doesn't vary with quantity while VC is a curve parallel to C (the vertical distance between points on VC and C) is F.




Average cost is the slope of a line from 0 to a point on C.




Average cost is minimized at q = 15.



Similarly, AVC is minimized at q = 10.



At each q, both C and VC have the same slope = MC.



AFC is decreasing in q.

Production functions + prices of inputs \longrightarrow cost curves

Production functions + prices of inputs \longrightarrow cost curves

If your only variable cost is labor and you use L units of it to produce q units of output, VC(q) = wL where w is the wage.

Production functions + prices of inputs \longrightarrow cost curves

If your only variable cost is labor and you use L units of it to produce q units of output, VC(q)=wL where w is the wage.

Suppose that $q = f(L, \overline{K}) = g(L)$.

Production functions + prices of inputs \longrightarrow cost curves

If your only variable cost is labor and you use L units of it to produce q units of output, VC(q) = wL where w is the wage.

Suppose that $q = f(L, \overline{K}) = g(L)$.

So L units of input gives us g(L) units of output.

Production functions and the shape of cost curves

Production functions + prices of inputs \longrightarrow cost curves

If your only variable cost is labor and you use L units of it to produce q units of output, VC(q) = wL where w is the wage.

Suppose that $q = f(L, \overline{K}) = g(L)$.

So L units of input gives us g(L) units of output.

It takes $g^{-1}(q)$ units of input to produce q units of output.

Production functions and the shape of cost curves

Production functions + prices of inputs \longrightarrow cost curves

If your only variable cost is labor and you use L units of it to produce q units of output, VC(q) = wL where w is the wage.

Suppose that $q = f(L, \overline{K}) = g(L)$.

So L units of input gives us g(L) units of output.

It takes $g^{-1}(q)$ units of input to produce q units of output.

So $VC(q) = wg^{-1}(q)$.

Production functions and the shape of cost curves

Production functions + prices of inputs \longrightarrow cost curves

If your only variable cost is labor and you use L units of it to produce q units of output, VC(q) = wL where w is the wage.

Suppose that
$$q = f(L, \overline{K}) = g(L)$$
.

So L units of input gives us g(L) units of output.

It takes $g^{-1}(q)$ units of input to produce q units of output.

So
$$VC(q) = wg^{-1}(q)$$
.

Derive MC and AVC from g.

Shape of MC curve

$$MC(q) = \frac{dVC(q)}{dq} = \frac{dwg^{-1}(q)}{dq} = w\frac{1}{\frac{dg}{dq}} = w\frac{1}{MP_L}.$$

Shape of MC curve

$$MC(q) = \frac{dVC(q)}{dq} = \frac{dwg^{-1}(q)}{dq} = w\frac{1}{\frac{dg}{dq}} = w\frac{1}{MP_L}.$$

Diminishing $MP_L \Rightarrow MP_L$ eventually decreases $\Rightarrow MC$ eventually increases.

Shape of AC curve

$$AC(q) = \frac{VC(q)}{q} = \frac{wg^{-1}(q)}{q} = \frac{w}{\frac{q}{q^{-1}(q)}} = \frac{w}{\frac{q}{L}} = \frac{1}{AP_L}$$

Shape of AC curve

$$AC(q) = \frac{VC(q)}{q} = \frac{wg^{-1}(q)}{q} = \frac{w}{\frac{q}{q^{-1}(q)}} = \frac{w}{\frac{q}{L}} = \frac{1}{AP_L}$$

We saw that AP_L rises the falls so AC falls then rises.

Specific tax of \$10 affects variable cost, but not fixed cost.

Specific tax of \$10 affects variable cost, but not fixed cost.

So AFC remains the same while AVC is shifted upwards by \$10.

Specific tax of \$10 affects variable cost, but not fixed cost.


So AFC remains the same while AVC is shifted upwards by \$10.

Similarly, MC is shifted upwards by \$10.

Specific tax of \$10 affects variable cost, but not fixed cost.

So AFC remains the same while AVC is shifted upwards by \$10.

Similarly, MC is shifted upwards by \$10.



Recall: all inputs can be varied.

Recall: all inputs can be varied.

Assume F = 0 since all inputs can be varied. (Really, some inputs are "avoidable" fixed costs, like rent: you can stop renting a business if you choose not to operate).

Recall: all inputs can be varied.

Assume F = 0 since all inputs can be varied. (Really, some inputs are "avoidable" fixed costs, like rent: you can stop renting a business if you choose not to operate).

So

$$C(q) = VC(q)$$

Recall: all inputs can be varied.

Assume F = 0 since all inputs can be varied. (Really, some inputs are "avoidable" fixed costs, like rent: you can stop renting a business if you choose not to operate).

So

$$C(q) = VC(q)$$

Long run cost is never higher than short run costs. Why?

Recall: all inputs can be varied.

Assume F=0 since all inputs can be varied. (Really, some inputs are "avoidable" fixed costs, like rent: you can stop renting a business if you choose not to operate).

So

$$C(q) = VC(q)$$

Long run cost is never higher than short run costs. Why?

In the long run, you'd never be stuck with the wrong amount of inputs that are fixed in the short run. You've got more flexibility.

Input choice

Recall: An isoquant is a curve through all combinations of inputs that can be used to efficiently produce a particular amount of output.

Input choice

Recall: An isoquant is a curve through all combinations of inputs that can be used to efficiently produce a particular amount of output.

Isocost lines are all of the pairs of inputs that cost the same.

Input choice

Recall: An isoquant is a curve through all combinations of inputs that can be used to efficiently produce a particular amount of output.

Isocost lines are all of the pairs of inputs that cost the same.

Somewhat like a budget line.

w — wage r — rental rate

w — wage r — rental rate

All pairs (L, K) that cost \overline{C} :

$$\overline{C} = wL + rK$$

w — wage r — rental rate

All pairs (L, K) that cost \overline{C} :

$$\overline{C} = wL + rK$$

To plot this, you can re-write it as

$$K = \frac{\overline{C}}{r} - \frac{w}{r}L.$$

w — wage r — rental rate

All pairs (L, K) that cost \overline{C} :


$$\overline{C} = wL + rK$$

To plot this, you can re-write it as

$$K = \frac{\overline{C}}{r} - \frac{w}{r}L.$$

Slope is $-\frac{w}{r}$ and vertical intercept is $\overline{C}r$ and horizontal intercept is $\overline{C}w$.

w = \$5 and r = \$8.



Higher isocost lines correspond to higher costs.

What is the cheapest way to produce a given level of output?

What is the cheapest way to produce a given level of output?

Three ways to find out:

What is the cheapest way to produce a given level of output?

Three ways to find out:

1. Lowest-isocost rule: pick inputs where the lowest isocost line touches the isoquant.

What is the cheapest way to produce a given level of output?

Three ways to find out:

- 1. Lowest-isocost rule: pick inputs where the lowest isocost line touches the isoquant.
- 2. Tangency rule: pick inputs where an isoquant is tangent to the isoquant.

What is the cheapest way to produce a given level of output?

Three ways to find out:

- 1. Lowest-isocost rule: pick inputs where the lowest isocost line touches the isoquant.
- 2. Tangency rule: pick inputs where an isoquant is tangent to the isoquant.
- 3. Last-dollar rule: The last dollar spent one input should give you as much extra output as the last dollar spend on any other input.


What is the cheapest way to produce a given level of output?

Three ways to find out:

- 1. Lowest-isocost rule: pick inputs where the lowest isocost line touches the isoquant.
- 2. Tangency rule: pick inputs where an isoquant is tangent to the isoquant.
- 3. Last-dollar rule: The last dollar spent one input should give you as much extra output as the last dollar spend on any other input.

All equivalent.

Lowest-isocost rule



But this implies tangency of isocost line and isoquant.

Recall: slope of isoquant is MRTS.

Recall: slope of isoquant is MRTS.

Slope of isocost line is $-\frac{w}{r}$.

Recall: slope of isoquant is MRTS.

Slope of isocost line is $-\frac{w}{r}$.

So

$$MRTS = -\frac{w}{r}.$$

Recall: slope of isoquant is MRTS.

Slope of isocost line is $-\frac{w}{r}$.

So

$$MRTS = -\frac{w}{r}.$$

Or

$$\frac{MP_L}{MP_K} = \frac{w}{r}.$$

Recall: slope of isoquant is MRTS.

Slope of isocost line is $-\frac{w}{r}$.

So

$$MRTS = -\frac{w}{r}.$$

Or

$$\frac{MP_L}{MP_K} = \frac{w}{r}.$$

Rearranging this:

$$\frac{MP_L}{w} = \frac{MP_K}{r}.$$

Tangency rule

Recall: slope of isoquant is MRTS.

Slope of isocost line is $-\frac{w}{r}$.

So

$$MRTS = -\frac{w}{r}.$$

Or

$$\frac{MP_L}{MP_K} = \frac{w}{r}.$$

Rearranging this:

$$\frac{MP_L}{w} = \frac{MP_K}{r}.$$

That's the last-dollar rule.

Example

Production function:

$$q = 1.52L^{0.6}K^{0.4}$$

What is the lowest cost of producing 100 units if w = \$24 and r = \$8?

Example

Production function:

$$q = 1.52L^{0.6}K^{0.4}$$

What is the lowest cost of producing 100 units if w = \$24 and r = \$8?

Tangency rule says "slope of isoquant = slope of isocost."

Example

Production function:

$$q = 1.52L^{0.6}K^{0.4}$$

What is the lowest cost of producing 100 units if w = \$24 and r = \$8?

Tangency rule says "slope of isoquant = slope of isocost."

$$MRTS = -\frac{w}{r}.$$

$$MRTS = -\frac{MP_L}{MP_K}.$$

$$MRTS = -\frac{MP_L}{MP_K}.$$

$$MP_L = 0.6(1.52L^{-0.4}K^{0.4}) = 0.6(1.52L^{0.6}K^{0.4})L^{-1} = \frac{0.6q}{L}.$$

$$MRTS = -\frac{MP_L}{MP_K}.$$

$$MP_L = 0.6(1.52L^{-0.4}K^{0.4}) = 0.6(1.52L^{0.6}K^{0.4})L^{-1} = \frac{0.6q}{L}.$$

$$MP_K = 0.4(1.52L^{0.6}K^{-0.6}) = 0.4(1.52L^{0.6}K^{0.4})K^{-1} = \frac{0.4q}{K}.$$

$$MRTS = -\frac{MP_L}{MP_K}.$$

$$MP_L = 0.6(1.52L^{-0.4}K^{0.4}) = 0.6(1.52L^{0.6}K^{0.4})L^{-1} = \frac{0.6q}{L}.$$

$$MP_K = 0.4(1.52L^{0.6}K^{-0.6}) = 0.4(1.52L^{0.6}K^{0.4})K^{-1} = \frac{0.4q}{K}.$$

$$MRTS = -\frac{MP_L}{MP_K} = -\frac{\frac{0.0q}{L}}{\frac{0.4q}{V}} = -\frac{0.6K}{0.4L} = -1.5\frac{K}{L}.$$

$$-1.5\frac{K}{L} = -\frac{24}{8} = -3$$

$$-1.5\frac{K}{L} = -\frac{24}{8} = -3$$
$$\frac{K}{L} = \frac{3}{1.5} = 2.$$

$$-1.5\frac{K}{L} = -\frac{24}{8} = -3$$
$$\frac{K}{L} = \frac{3}{1.5} = 2.$$

$$K=2L.$$

$$-1.5\frac{K}{L} = -\frac{24}{8} = -3$$
$$\frac{K}{L} = \frac{3}{1.5} = 2.$$

$$K = 2L$$
.

Need one more equation to solve for K and L!

You started wanting to produce 100 units:

 $1.52L^{0.6}K^{0.4} = 100.$

You started wanting to produce 100 units:

$$1.52L^{0.6}K^{0.4} = 100.$$

Since
$$K = 2L$$
,

$$1.52L^{0.6}(2L)^{0.4} = 100$$

You started wanting to produce 100 units:

$$1.52L^{0.6}K^{0.4} = 100.$$

Since
$$K = 2L$$
,

$$1.52L^{0.6}(2L)^{0.4} = 100$$

$$1.52 \times 2^{0.4}L = 100$$

You started wanting to produce 100 units:

$$1.52L^{0.6}K^{0.4} = 100.$$

Since
$$K = 2L$$
,

$$1.52L^{0.6}(2L)^{0.4} = 100$$

$$1.52 \times 2^{0.4}L = 100$$

$$L = \frac{100}{1.52 \times 2^{0.4}} \approx 50$$

You started wanting to produce 100 units:

$$1.52L^{0.6}K^{0.4} = 100.$$

Since
$$K = 2L$$
,

$$1.52L^{0.6}(2L)^{0.4} = 100$$

$$1.52 \times 2^{0.4}L = 100$$

$$L = \frac{100}{1.52 \times 2^{0.4}} \approx 50$$

So K = 2L = 100.

You started wanting to produce 100 units:

$$1.52L^{0.6}K^{0.4} = 100.$$

Since
$$K = 2L$$
,

$$1.52L^{0.6}(2L)^{0.4} = 100$$

$$1.52 \times 2^{0.4}L = 100$$

$$L = \frac{100}{1.52 \times 2^{0.4}} \approx 50$$

So
$$K = 2L = 100$$
.

Cost of producing 100 units is:

$$wL + rK = 50 \times \$24 + 100 \times \$8 = \$2,000.$$

Suppose that $w = \$24 \rightarrow w' = \8 .

Suppose that $w = \$24 \rightarrow w' = \8 .

Isocost slope:
$$-\frac{w}{r} = -\frac{24}{8} = -3 \rightarrow -\frac{w'}{r} = -\frac{8}{8} = -1$$
.

Suppose that $w = \$24 \rightarrow w' = \8 .

Isocost slope:
$$-\frac{w}{r} = -\frac{24}{8} = -3 \rightarrow -\frac{w'}{r} = -\frac{8}{8} = -1$$
.

New optimal way to produce 100 units is L=77 and K=52. (This comes from setting $MRTS=-1.5\frac{K}{L}=-1$ so that $K=\frac{2}{3}L$.)

Suppose that $w = \$24 \rightarrow w' = \8 .

Isocost slope:
$$-\frac{w}{r} = -\frac{24}{8} = -3 \rightarrow -\frac{w'}{r} = -\frac{8}{8} = -1$$
.

New optimal way to produce 100 units is L=77 and K=52. (This comes from setting $MRTS=-1.5\frac{K}{L}=-1$ so that $K=\frac{2}{3}L$.)

New cost of producing 100 units is \$1,032.

Suppose that $w = \$24 \rightarrow w' = \8 .

Isocost slope:
$$-\frac{w}{r} = -\frac{24}{8} = -3 \rightarrow -\frac{w'}{r} = -\frac{8}{8} = -1$$
.

New optimal way to produce 100 units is L=77 and K=52. (This comes from setting $MRTS=-1.5\frac{K}{L}=-1$ so that $K=\frac{2}{3}L$.)

New cost of producing 100 units is \$1,032.

Notice that the firm substituted labor for capital as it became relatively cheaper.

Does a firm typically use more of an input as it becomes relatively cheaper?

Does a firm typically use more of an input as it becomes relatively cheaper?

Yes. Recall the tangency rule: $\frac{w}{r} = \frac{MP_L}{MP_K}$.

Does a firm typically use more of an input as it becomes relatively cheaper?

Yes. Recall the tangency rule: $\frac{w}{r} = \frac{MP_L}{MP_K}$.

In our example: $\frac{MP_L}{MP_K} = 1.5 \frac{K}{L}$.

Does a firm typically use more of an input as it becomes relatively cheaper?

Yes. Recall the tangency rule: $\frac{w}{r} = \frac{MP_L}{MP_K}$.

In our example: $\frac{MP_L}{MP_K} = 1.5 \frac{K}{L}$.

While minimizing costs: $1.5\frac{K}{L} = \frac{w}{r}$ or $\frac{K}{L} = w \frac{1}{1.5r}$.

Does a firm typically use more of an input as it becomes relatively cheaper?

Yes. Recall the tangency rule: $\frac{w}{r} = \frac{MP_L}{MP_K}$.

In our example: $\frac{MP_L}{MP_K} = 1.5 \frac{K}{L}$.

While minimizing costs: $1.5\frac{K}{L} = \frac{w}{r}$ or $\frac{K}{L} = w \frac{1}{1.5r}$.

Differentiating both sides with respect to w,

$$\frac{d\left(\frac{K}{L}\right)}{dw} = \frac{1}{1.5r} > 0.$$

Does a firm typically use more of an input as it becomes relatively cheaper?

Yes. Recall the tangency rule: $\frac{w}{r} = \frac{MP_L}{MP_K}$.

In our example: $\frac{MP_L}{MP_K} = 1.5 \frac{K}{L}$.

While minimizing costs: $1.5\frac{K}{L} = \frac{w}{r}$ or $\frac{K}{L} = w \frac{1}{1.5r}$.

Differentiating both sides with respect to w,

$$\frac{d\left(\frac{K}{L}\right)}{dw} = \frac{1}{1.5r} > 0.$$

So, holding r fixed, small increases in w lead to an increase of the capital-labor ratio $\left(\frac{K}{L}\right)$.

Expansion path: curve through the cost minimizing inputs for different levels of output.

Expansion path: curve through the cost minimizing inputs for different levels of output.

Back to our example with $q = 1.52L^{0.6}K^{0.4}$, w = \$24, and r = \$8.

Expansion path: curve through the cost minimizing inputs for different levels of output.

Back to our example with $q = 1.52L^{0.6}K^{0.4}$, w = \$24, and r = \$8.

Cost of producing 100 units=\$2,000.

Expansion path: curve through the cost minimizing inputs for different levels of output.

Back to our example with $q=1.52L^{0.6}K^{0.4},\ w=\$24,$ and r=\$8.

Cost of producing 100 units=\$2,000.

Cost of producing 200 units = \$4,000.

Expansion path: curve through the cost minimizing inputs for different levels of output.


Back to our example with $q = 1.52L^{0.6}K^{0.4}$, w = \$24, and r = \$8.

Cost of producing 100 units=\$2,000.

Cost of producing 200 units = \$4,000.

And so on.

Expansion path



Cost curve

What does it cost to produce q units?

What does it cost to produce q units?


Remember, that at these prices, K = q = 2L.

What does it cost to produce q units?

Remember, that at these prices, K = q = 2L.

So

$$C(q) = wL + rK = w\frac{q}{2} + rq = \left(\frac{w}{2} + r\right)q = \left(\frac{24}{2} + 8\right)q = 20q.$$



A word of caution:

A word of caution:

The production function that we just saw was easy.

A word of caution:

The production function that we just saw was easy.

Why?

A word of caution:

The production function that we just saw was easy.

Why?

Because it is "homogenous of degree one": For each x,

$$q = xf(L, K) = f(xL, xK).$$

A word of caution:

The production function that we just saw was easy.

Why?

Because it is "homogenous of degree one": For each x,

$$q = xf(L, K) = f(xL, xK).$$

It's still easy as long as the production function is "homogenous of degree γ " for some γ :

$$q = x^{\gamma} f(L, K) = f(xL, xK).$$

A word of caution:

The production function that we just saw was easy.

Why?

Because it is "homogenous of degree one": For each x,

$$q = xf(L, K) = f(xL, xK).$$

It's still easy as long as the production function is "homogenous of degree γ " for some γ :

$$q = x^{\gamma} f(L, K) = f(xL, xK).$$

This means that it has the same "returns to scale" for all levels of output.

Just like short-run:

▶ MC and AC both depend on C.

Just like short-run:

- ▶ MC and AC both depend on C.
- ▶ If AC is U-shaped, MC cuts it at the minimum.

Just like short-run:

- ▶ MC and AC both depend on C.
- ▶ If AC is U-shaped, MC cuts it at the minimum.

Short-run: AC is U-shaped due to fixed costs and diminishing marginal returns.

Just like short-run:

- ▶ MC and AC both depend on C.
- ▶ If AC is U-shaped, MC cuts it at the minimum.

Short-run: AC is U-shaped due to fixed costs and diminishing marginal returns.

Long-run: No fixed cost and no diminishing marginal return (since all inputs can be varied). AC shape is mostly dependent on returns to scale.

Just like short-run:

- ▶ MC and AC both depend on C.
- ▶ If AC is U-shaped, MC cuts it at the minimum.

Short-run: AC is U-shaped due to fixed costs and diminishing marginal returns.

Long-run: No fixed cost and no diminishing marginal return (since all inputs can be varied). AC shape is mostly dependent on returns to scale.

If returns to scale are increasing at first and then decreasing as quantity increases, AC is U-shaped.

For a U-shaped AC:

1. low levels of output where AC is decreasing: economies of scale.

For a U-shaped AC:

- 1. low levels of output where AC is decreasing: economies of scale.
- 2. intermediate levels of output where AC is flat: no economies of scale.

For a U-shaped AC:

- 1. low levels of output where AC is decreasing: economies of scale.
- 2. intermediate levels of output where AC is flat: no economies of scale.
- 3. high levels of output where AC is increasing: diseconomies of scale.

For a U-shaped AC:

- 1. low levels of output where AC is decreasing: economies of scale.
- 2. intermediate levels of output where AC is flat: no economies of scale.
- 3. high levels of output where AC is increasing: diseconomies of scale.

Competitive industries: firms have U-shaped AC curves.

For a U-shaped AC:

- 1. low levels of output where AC is decreasing: economies of scale.
- 2. intermediate levels of output where AC is flat: no economies of scale.
- 3. high levels of output where AC is increasing: diseconomies of scale.

Competitive industries: firms have U-shaped AC curves.

Non-competitive industries: firms have either U or L-shaped AC curves.

You can vary your capital usage effectively only in the long run.

You can vary your capital usage effectively only in the long run.

Suppose there are three different plant sizes you can choose from: small, medium, and large.

You can vary your capital usage effectively only in the long run.

Suppose there are three different plant sizes you can choose from: small, medium, and large.

Suppose the three short-run average costs of producing q units are: $SRAC^{s}(q)$, $SRAC^{m}(q)$, and $SRAC^{l}(q)$.

You can vary your capital usage effectively only in the long run.

Suppose there are three different plant sizes you can choose from: small, medium, and large.

Suppose the three short-run average costs of producing q units are: $SRAC^{s}(q), SRAC^{m}(q)$, and $SRAC^{l}(q)$.

If you can simultaneously pick labor and capital, what is the (long-run) cost of producing q units?


You can vary your capital usage effectively only in the long run.

Suppose there are three different plant sizes you can choose from: small, medium, and large.


Suppose the three short-run average costs of producing q units are: $SRAC^{s}(q)$, $SRAC^{m}(q)$, and $SRAC^{l}(q)$.

If you can simultaneously pick labor and capital, what is the (long-run) cost of producing q units?

$$LRAC(q) = \min\{SRAC^{s}(q), SRAC^{m}(q), SRAC^{l}(q)\}.$$



Long-run AC is the least of the short-run ACs.



If the choice of K isn't only whole numbers, LRAC is smooth.

Laser printer: \$100 + 4¢ per page.

Laser printer: \$100 + 40 per page.

Inkjet printer: \$30 + 7¢ per page.

Laser printer: \$100 + 4¢ per page.

Inkjet printer: \$30 + 7¢ per page.

Cost functions:

$$AC^{\text{Laser}}(q) = \frac{100}{q} + 0.04$$
$$AC^{\text{Inkjet}}(q) = \frac{30}{q} + 0.07$$

Laser printer: \$100 + 4c per page.

Inkjet printer: \$30 + 7¢ per page.

Cost functions:

$$AC^{\text{Laser}}(q) = \frac{100}{q} + 0.04$$
$$AC^{\text{Inkjet}}(q) = \frac{30}{q} + 0.07$$

Which one should you buy?

Laser printer: \$100 + 4¢ per page.

Inkjet printer: \$30 + 7¢ per page.

Cost functions:


$$AC^{\text{Laser}}(q) = \frac{100}{q} + 0.04$$

$$AC^{\text{Inkjet}}(q) = \frac{30}{q} + 0.07$$


Which one should you buy?

It depends on q:

$$LRAC(q) = \begin{cases} \frac{100}{q} + 0.04 & \text{if } q > 2,333 \\ \frac{30}{q} + 0.07 & \text{if } q \le 2,333 \end{cases}$$




Constant returns to scale and long-run AC/MC




 $CRS \Rightarrow MC = AC$ in the long run.

Short-run and long-run expansion paths



Short-run expansion path: horizontal line at fixed K.

Short-run and long-run expansion paths



Long-run expansion path: both inputs are varied.

Learning by doing

Reasons for long-run costs being lower than short-run costs:


1. More flexibility in choosing inputs.

Reasons for long-run costs being lower than short-run costs:


- 1. More flexibility in choosing inputs.
- 2. Technological progress.

Reasons for long-run costs being lower than short-run costs:

- 1. More flexibility in choosing inputs.
- 2. Technological progress.
- 3. Learning by doing: the more your output (cumulatively), the more efficiently you produce it.




Learning curve.



Learning curve.


Despite common usage, a "steep learning curve" means you make quick progress!

Learning by doing: average cost over time



Larger output means:


Learning by doing: average cost over time



Larger output means:

1. lower average cost today because of economies of scale.

Learning by doing: average cost over time



Larger output means:

- 1. lower average cost today because of economies of scale.
- 2. lower average cost tomorrow because of learning by doing.

Economies of scope: It's less expensive to produce goods together than it is separately.

Economies of scope: It's less expensive to produce goods together than it is separately.

Measure of "scope":

$$SC = \frac{C(q_1, 0) + C(0, q_2) - C(q_1, q_2)}{C(q_1, q_2)}.$$

Economies of scope: It's less expensive to produce goods together than it is separately.

Measure of "scope":

$$SC = \frac{C(q_1, 0) + C(0, q_2) - C(q_1, q_2)}{C(q_1, q_2)}.$$

 $C(q_1,0)$ — Cost of producing only good 1.

Economies of scope: It's less expensive to produce goods together than it is separately.

Measure of "scope":

$$SC = \frac{C(q_1, 0) + C(0, q_2) - C(q_1, q_2)}{C(q_1, q_2)}.$$

 $C(q_1,0)$ — Cost of producing only good 1.

 $C(0, q_2)$ — Cost of producing only good 2.

Economies of scope: It's less expensive to produce goods together than it is separately.

Measure of "scope":

$$SC = \frac{C(q_1, 0) + C(0, q_2) - C(q_1, q_2)}{C(q_1, q_2)}.$$

 $C(q_1,0)$ — Cost of producing only good 1.

 $C(0,q_2)$ — Cost of producing only good 2.

 $C(q_1, q_2)$ — Cost of producing both goods together.

Economies of scope: It's less expensive to produce goods together than it is separately.

Measure of "scope":

$$SC = \frac{C(q_1, 0) + C(0, q_2) - C(q_1, q_2)}{C(q_1, q_2)}.$$

 $C(q_1,0)$ — Cost of producing only good 1.

 $C(0,q_2)$ — Cost of producing only good 2.

 $C(q_1, q_2)$ — Cost of producing both goods together.

 $C(q_1,0) + C(0,q_2) - C(q_1,q_2)$ — Saving from joint production.

Economies of scope

If SC = 0 then $C(q_1, 0) + C(0, q_2) = C(q_1, q_2)$: producing the goods separately costs the same as producing them together.

Economies of scope

If SC = 0 then $C(q_1, 0) + C(0, q_2) = C(q_1, q_2)$: producing the goods separately costs the same as producing them together.


If SC < 0 then $C(q_1, 0) + C(0, q_2) < C(q_1, q_2)$: producing the goods separately costs *more* than producing them together. Diseconomies of scope.

Economies of scope

If SC = 0 then $C(q_1, 0) + C(0, q_2) = C(q_1, q_2)$: producing the goods separately costs the same as producing them together.


If SC < 0 then $C(q_1, 0) + C(0, q_2) < C(q_1, q_2)$: producing the goods separately costs *more* than producing them together. Diseconomies of scope.

If SC > 0 then $C(q_1, 0) + C(0, q_2) > C(q_1, q_2)$: producing the goods separately costs *less* than producing them together. *Economies of scope*.




Production possibility set is all of the pairs of output a fixed amount of input yields.


Production possibility frontier is the boundary of this set.



Economies of scope: PPF bowed outwards (from origin).



No economies of scope: PPF straight line.



Diseconomies of scope: PPF bowed inwards.