

Troubleshooting Guide: Enabling Intel Virtualization Technology for GNS3 on Windows

This document provides troubleshooting steps for resolving errors when attempting to enable Intel Virtualization Technology on a Windows machine to run GNS3 for network device emulation. We have tested these steps successfully on HP and Lenovo laptops running Windows 11. However, please note that results may vary depending on the specific laptop model or Windows version.

BIOS Settings


Enable Virtualization technology in the BIOS





Windows Features

Make Sure "Virtual Machine Platform", "Windows Hypervisor Platform", "Windows subsystem for Linux" and "Hyper-V" are disabled



Troubleshooting Steps

If the issue still persists, in some systems, following the steps below may help:


Please read this entire document before proceeding with the troubleshooting steps. Doing so will give you an overview of the expected results and help ensure a smoother process.

These steps involve adjusting settings in the Windows Registry and Group Policy to disable "Device Guard" (virtualization-based security). Please ensure you backup your registry before making any changes, and proceed at your own risk to avoid unintended issues.

For further reference, I've included a link to the Broadcom discussion post with more detailed steps.

https://community.broadcom.com/vmware-cloud-foundation/communities/community-home/digestviewer/viewthread?MessageKey=43004e0d-13e7-41ec-bedd-9ddfde421e1d&CommunityKey=fb707ac3-9412-4fad-b7af-018f5da56d9f


Go through the below response where they've given the solution. I've added some screenshots for the reference




Step1: Disable Hypervisor from command prompt and Restart the machine


Run "bcdedit /set hypervisorlaunchtype off"

Step2: Disable Virtualization based Security in Group Policy



Step3: Registry Update





Step4: Check Hyper V State from powershell as administrator

It should show as disabled.

Get-WindowsOptionalFeature -Online -FeatureName Microsoft-Hyper-V

```
PS C:\WINDOWS\system32> Get-WindowsOptionalFeature -Online -FeatureName Microsoft-Hyper-V

FeatureName : Microsoft-Hyper-V

DisplayName : Hyper-V Platform

Description : Provides the services that you can use to create and manage virtual machines and their resources.

RestartRequired : Possible

State : Disabled

CustomProperties :
```

Final GNS3 Settings

