

OpenVPN Server configuration

This document provides step by step guide to install OpenVPN server on CentOS 9 system. This lab requires 3 VM's . Update all the 3 systems with **sudo yum upadte -y** .


The OpenVPN Server VM requires 2 network cards. One network card in NAT mode and one in host only mode. Set the hostname of this machine as **openvpnserver**.



The Remote client (VPN client) VM will have a single network card and it should be in NAT mode. Set the hostname for this machine as **client1**.




The LAN computer also will have a single network card and it should be in the host only mode.



Create a user by name admin on all the 3 machines and provide that user sudo permissions.

Please set correct time zone on all the three machines.



OpenVPN Server configuration.

Perform the following steps on the VM which has 2 network cards I.e. the OpenVPN Server.

Disable Selinux

sudo vi /etc/selinux/config

```
#
# grubby --update-kernel ALL --remove-args
#
SELINUX=disabled
# SELINUXTYPE= can take one of these three va
# targeted - Targeted processes are prote
# minimum - Modification of targeted poli
# mls - Multi Level Security protection.
```

Save the file.

Give the command to set the current SELINUX status to permissive as the above setting will come in effect only after a system restart.

sudo setenforce 0

Next enable IP forwarding.

```
echo 1 | sudo tee /proc/sys/net/ipv4/ip_forward
```

To mae it permanent, edit /etc/sysctl.conf file and add following line.

sudo vi/etc/sysctl.conf

```
# For more information, see
net.ipv4.ip_forward = 1
```

Install following packages.

sudo dnf install epel-release -y

sudo dnf install openvpn wget tar -y

Then go to the /etc/openvpn directory.

cd /etc/openvpn

Download the EasyRSA package.

sudo wget https://github.com/OpenVPN/easy-rsa/releases/download/v3.0.6/EasyRSA-unix-v3.0.6.tgz

Once the package is downloaded. Untar is using following command.

```
sudo tar xvzf EasyRSA-unix-v3.0.6.tgz
```

Rename the directory to make it easy to access.

sudo mv EasyRSA-v3.0.6 easy-rsa

Go to that directory.

cd easy-rsa

Create a file by name vars.

vi vars

Add following into this file. Make changes if required.

```
set var EASYRSA "$PWD"
set_var EASYRSA_PKI "$EASYRSA/pki"
set var EASYRSA DN "cn only"
set_var EASYRSA_REQ_COUNTRY "IN"
set_var EASYRSA_REQ_PROVINCE "Maharastra"
set var EASYRSA REQ CITY "Pune"
set var EASYRSA REQ ORG "Demo Labs"
set var EASYRSA REQ EMAIL ""
set_var EASYRSA_REQ_OU "Demo Labs CA"
set_var EASYRSA_KEY_SIZE 2048
set_var EASYRSA_ALGO rsa
set_var EASYRSA_CA_EXPIRE 7500
set_var EASYRSA_CERT_EXPIRE 365
set_var EASYRSA_NS_SUPPORT "no"
set_var EASYRSA_NS_COMMENT "Demo Labs"
set_var EASYRSA_EXT_DIR "$EASYRSA/x509-types"
set var EASYRSA SSL CONF "$EASYRSA/openssl-easyrsa.cnf"
set_var EASYRSA_DIGEST "sha256"
```

Save the file.

Next initialize the PKI system.

sudo ./easyrsa init-pki

```
[osboxes@localhost easy-rsa]$ sudo ./easyrsa init-pki
Note: using Easy-RSA configuration from: ./vars
init-pki complete; you may now create a CA or requests.
Your newly created PKI dir is: /etc/openvpn/easy-rsa/pki
```

Netx build CA.

sudo ./easyrsa build-ca

```
[osboxes@localhost easy-rsa]$ sudo ./easyrsa build-ca
Note: using Easy-RSA configuration from: ./vars

Using SSL: openssl OpenSSL 3.2.1 30 Jan 2024 (Library: OpenSSL

Enter New CA Key Passphrase:
Re-Enter New CA Key Passphrase:
Can't load /etc/openvpn/easy-rsa/pki/.rnd into RNG
00AEE8E52F7F0000:error:12000079:random number generator:RAND_lo
106:Filename=/etc/openvpn/easy-rsa/pki/.rnd
Enter PEM pass phrase:
Verifving - Enter PEM pass phrase:
```

Type a password for the CA. Remember this password as it will be required later while signing the certificates.

```
You are about to be asked to enter information that will be incorporated into your certificate request.
What you are about to enter is what is called a Distinguished Name or a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
```

When it prompts for a common name for CA, enter a name. Here the name given is demo-ca.

```
Common Name (eg: your user, host, or server name) [Easy-RSA CA]:demo-ca
```

CA creation complete and you may now import and sign cert requests. Your new CA certificate file for publishing is at: /etc/openvpn/easy-rsa/pki/ca.crt

Now generate the certificate for the openvpnserver.

Sudo ./easyrsa gen-req openvpnserver nopass

Press Enter at the prompt for the hostname as we will use the default openvpnserver.

```
Common Name (eg: your user, host, or server name) [openvpnserver]:

Keypair and certificate request completed. Your files are:

req: /etc/openvpn/easy-rsa/pki/reqs/openvpnserver.req

key: /etc/openvpn/easy-rsa/pki/private/openvpnserver.key
```

Now get the certificate signed from CA.

sudo ./easyrsa sign-req server openvpnserver

Type yesat the above prompt.

Enter the CA password given in the above steps when prompted for the passphrase.

Next

sudo ./easyrsa gen-dh

```
[osboxes@localhost easy-rsa]$ sudo ./easyrsa gen-dh

Note: using Easy-RSA configuration from: ./vars

Using SSL: openssl OpenSSL 3.2.1 30 Jan 2024 (Library: OpenSSL 3.2.1 30 Jan 2024)

Generating DH parameters, 2048 bit long safe prime
```

The server certificates are generated . Copy them to the server directory as OpenVPN server requires these files in that directory.

```
sudo cp pki/ca.crt /etc/openvpn/server
sudo cp pki/dh.pem /etc/openvpn/server
sudo cp pki/private/openvpnserver.key /etc/openvpn/server
sudo cp pki/issued/openvpnserver.crt /etc/openvpn/server
```

Generate Client Certificates

```
sudo ./easyrsa gen-req client1 nopass
```

Press Enter at the hostname prompt. Next get the certificate signed from the CA. sudo ./easyrsa sign-req client client1

```
[osboxes@localhost easy-rsa]$ sudo ./easyrsa sign-req client client1
Note: using Easy-RSA configuration from: ./vars
Jsing SSL: openssl OpenSSL 3.2.1 30 Jan 2024 (Library: OpenSSL 3.2.1 30 Jan 2024)
You are about to sign the following certificate.
Please check over the details shown below for accuracy. Note that this request
```

Enter the CA password when prompted for the passphrase.

Copy client certificates to the client directory.

```
sudo cp pki/ca.crt /etc/openvpn/client/
sudo cp pki/issued/client1.crt /etc/openvpn/client
sudo cp pki/private/client1.key /etc/openvpn/client
```

Now create the server.conf file.

sudo vi /etc/openvpn/server/server.conf

Add following to the file.

```
port 1194
proto udp
dev tun
ca /etc/openvpn/server/ca.crt
cert /etc/openvpn/server/openvpnserver.crt
key /etc/openvpn/server/openvpnserver.key
dh /etc/openvpn/server/dh.pem
server 10.8.0.0 255.255.255.0
#push "redirect-gateway def1"
push "route 192.168.237.0 255.255.255.0" ### match this address to your LAN side network address.
#push "dhcp-option DNS 208.67.222.222"
#push "dhcp-option DNS 208.67.220.220"
duplicate-cn
cipher AES-256-CBC
tls-version-min 1.2
tls-cipher TLS-DHE-RSA-WITH-AES-256-GCM-SHA384:TLS-DHE-RSA-WITH-AES-256-CBC-SHA256:TLS-
DHE-RSA-WITH-AES-128-GCM-SHA256:TLS-DHE-RSA-WITH-AES-128-CBC-SHA256
auth SHA512
auth-nocache
keepalive 20 60
persist-key
persist-tun
compress Iz4
daemon
user nobody
group nobody
log-append /var/log/openvpn.log
verb 3
```

Save the file.

Now start and enable the OpenVPN server service.

```
sudo systemcti start openvpn-server@server
sudo systemcti status openvpn-server@server
sudo systemcti enable openvpn-server@server
```

Create client configuration file

sudo vi/etc/openvpn/client/client1.ovpn

Add following to the file.

client dev tun proto udp remote vpn-server-ip 1194 ca ca.crt cert client1.crt key client1.key cipher AES-256-CBC auth SHA512 auth-nocache tls-version-min 1.2 resolv-retry infinite

tls-cipher TLS-DHE-RSA-WITH-AES-256-GCM-SHA384:TLS-DHE-RSA-WITH-AES-256-CBC-SHA256:TLS-

DHE-RSA-WITH-AES-128-GCM-SHA256:TLS-DHE-RSA-WITH-AES-128-CBC-SHA256

compress Iz4

nobind

persist-key

persist-tun

mute-replay-warnings

verb 3

Save the file.

Add following rules to firewalld on the OpenVPN Server

```
sudo firewall-cmd --permanent --add-service=openvpn
sudo firewall-cmd --permanent --zone=trusted --add-service=openvpn
sudo firewall-cmd --permanent --zone=trusted --change-interface=tun0
sudo firewall-cmd --add-masquerade
sudo firewall-cmd --permanent --add-masquerade
```

sudo firewall-cmd --permanent --direct --passthrough ipv4 -t nat -A POSTROUTING -s 10.8.0.0/24 -o ens160 - j MASQUERADE

sudo firewall-cmd --reload

From the Server copy client configuration files to the VPN (Remote) client machine.

sudo scp /etc/openvpn/client/* admin@vpn-client-ip:/home/admin

Replace vpn-client-ip with the actual IP address of the VPN client in the above command.

Now go to the VPN client machine. Login as admin user.

Install following packages.

sudo dnf install epel-release -y sudo dnf install openvpn -y

Once the packages are installed copy the files copied from the VPN server as below.

```
sudo cp /home/admin/ca.crt /etc/openvpn/client
sudo cp /home/admin/client1.crt /etc/openvpn/client
sudo cp /home/admin/client1.key /etc/openvpn/client
```

Now change the IP address of this machine to 192.168.100.10. This is required as the LAB is performed in VMWare or VirtualBox. Also change the OpenVPN Server $\mathbf{1}^{\text{st}}$ network card (NAT) to 192.168.100.1

From VPN client you should be able to ping to 192.168.100.1. However you should not be able to ping to the internal LAN machine (3rd VM) IP address.

Edit the client1.ovpn file. Put the server IP address 192.168.100.1 in the remote field as shown below.

```
client
dev tun
proto udp
remote 192.168.100.1 1194
ca ca.crt
cert client1.crt
```

Now start the VPN connection with command,

sudo openvpn --config client1.ovpn

On successful connection you will get following messages.

```
2024-05-17 00:16:01 net_route_v4_best_gw result: via 0.0.0.0 dev
2024-05-17 00:16:01 ROUTE_GATEWAY 0.0.0.0
2024-05-17 00:16:01 TUN/TAP device tun0 opened
2024-05-17 00:16:01 net_iface_mtu_set: mtu 1500 for tun0
2024-05-17 00:16:01 net_iface_up: set tun0 up
2024-05-17 00:16:01 net_addr_ptp_v4_add: 10.8.0.6 peer 10.8.0.5 dev tun0
2024-05-17 00:16:01 net_route_v4_add: 192.168.44.0/24 via 10.8.0.5 dev [NULL] table 0 metric -1
2024-05-17 00:16:01 net_route_v4_add: 10.8.0.1/32 via 10.8.0.5 dev [NULL] table 0 metric -1
2024-05-17 00:16:01 Initialization Sequence Completed
```

The cursor will keep on blinking. You can not use this terminal now.

Open another terminal check with

ip a

Ping to the LAN computer IP

ssh to the LAN computer IP.

Disconnect the VPN connection by pressing ctrl+C and check the above steps again.