dave the date: dodgie if a retaine may to 20 " Regioter new (https://evento.googie.com/10/)

# Docker

<u>Docker</u> (https://docs.docker.com/install/) uses *containers* to create virtual environments that isolate a TensorFlow installation from the rest of the system. TensorFlow programs are run *within* this virtual environment that can share resources with its host machine (access directories, use the GPU, connect to the Internet, etc.). The <u>TensorFlow Docker images</u> (https://hub.docker.com/r/tensorflow/tensorflow/) are tested for each release.

Docker is the easiest way to enable TensorFlow <u>GPU support</u> (https://www.tensorflow.org/install/gpu) on Linux since only the <u>NVIDIA® GPU driver</u>

(https://github.com/NVIDIA/nvidia-docker/wiki/Frequently-Asked-Questions#how-do-i-install-the-nvidia-driver) is required on the host machine (the NVIDIA® CUDA® Toolkit does not need to be installed).

# TensorFlow Docker requirements

- 1. Install Docker (https://docs.docker.com/install/) on your local host machine.
- 2. For GPU support on Linux, install NVIDIA Docker support (https://github.com/NVIDIA/nvidia-docker).
  - Take note of your Docker version with docker -v. Versions earlier than 19.03 require nvidia-docker2 and the --runtime=nvidia flag. On versions including and after 19.03, you will use the nvidia-container-toolkit package and the --gpus all flag. Both options are documented on the page linked above.

To run the **docker** command without **sudo**, create the **docker** group and add your user. For details, see the <u>post-installation steps</u> (https://docs.docker.com/install/linux/linux-postinstall/)<sub>.</sub>

### Download a TensorFlow Docker image

The official TensorFlow Docker images are located in the <u>tensorflow/tensorflow</u>
(https://hub.docker.com/r/tensorflow/tensorflow/) Docker Hub repository. Image releases <u>are tagged</u>
(https://hub.docker.com/r/tensorflow/tensorflow/tags/) using the following format:

Tag	Description
latest	The latest release of TensorFlow CPU binary image. Default.
nightly	Nightly builds of the TensorFlow image. (Unstable.)
version	Specify the <i>version</i> of the TensorFlow binary image, for example: 2.1.0
devel	Nightly builds of a TensorFlow master development environment. Includes TensorFlow source code.

custom- op	Special experimental image for developing 1F custom ops. More info here (https://github.com/tensorflow/custom-op).
Each bas	e tag has variants that add or change functionality:

Tag Variants	Description
tag-gpu	The specified <i>tag</i> release with GPU support. ( <u>See below</u> (#gpu_support))
tag-jupyter	The specified tag release with Jupyter (includes TensorFlow tutorial notebooks)

You can use multiple variants at once. For example, the following downloads TensorFlow release images to your machine:

```
$ docker pull tensorflow/tensorflow # latest stable release
$ docker pull tensorflow/tensorflow:devel-gpu # nightly dev release w/ GPU support
$ docker pull tensorflow/tensorflow:latest-gpu-jupyter # latest release w/ GPU support and Jup
```

#### Start a TensorFlow Docker container

To start a TensorFlow-configured container, use the following command form:

```
$ docker run [-it] [--rm] [-p hostPort:containerPort] tensorflow/tensorflow[:tag] [command]
```

For details, see the <u>docker run reference</u> (https://docs.docker.com/engine/reference/run/).

## Examples using CPU-only images

Tag

**Description** 

Let's verify the TensorFlow installation using the latest tagged image. Docker downloads a new TensorFlow image the first time it is run:

```
$ docker run -it --rm tensorflow/tensorflow \
   python -c "import tensorflow as tf; print(tf.reduce_sum(tf.random.normal([1000, 1000])))"
```

**ss:** TensorFlow is now installed. Read the <u>tutorials</u> (https://www.tensorflow.org/tutorials) to get started.

Let's demonstrate some more TensorFlow Docker recipes. Start a bash shell session within a TensorFlow-configured container:

```
$ docker run -it tensorflow/tensorflow bash
```

Within the container, you can start a python session and import TensorFlow.

To run a TensorFlow program developed on the *host* machine within a container, mount the host directory and change the container's working directory (-v hostDir:containerDir -w workDir):

```
$ docker run -it --rm -v $PWD:/tmp -w /tmp tensorflow/tensorflow python ./script.py
```

Permission issues can arise when files created within a container are exposed to the host. It's usually best to edit files on the host system.

Start a <u>Jupyter Notebook</u> (https://jupyter.org/) server using TensorFlow's nightly build:

```
$ docker run -it -p 8888:8888 tensorflow/tensorflow:nightly-jupyter
```

Follow the instructions and open the URL in your host web browser: http://127.0.0.1:8888/?token=...

## **GPU** support

Docker is the easiest way to run TensorFlow on a GPU since the *host* machine only requires the <u>NVIDIA® driver</u> (https://github.com/NVIDIA/nvidia-docker/wiki/Frequently-Asked-Questions#how-do-i-install-the-nvidia-driver) (the *NVIDIA®* CUDA® Toolkit is not required).

Install the <u>Nvidia Container Toolkit</u> (https://github.com/NVIDIA/nvidia-docker/blob/master/README.md#quickstart) to add NVIDIA® GPU support to Docker. nvidia-container-runtime is only available for Linux. See the nvidia-container-runtime <u>platform support FAQ</u>

(https://github.com/NVIDIA/nvidia-docker/wiki/Frequently-Asked-Questions#platform-support) for details.

Check if a GPU is available:

```
$ lspci | grep -i nvidia
```

Verify your nvidia-docker installation:

```
$ docker run --gpus all --rm nvidia/cuda nvidia-smi
```

nvidia-docker v2 uses --runtime=nvidia instead of --gpus all. nvidia-docker v1 uses the nvidia-docker alias, rather tha time=nvidia or --gpus all command line flags.

## Examples using GPU-enabled images

Download and run a GPU-enabled TensorFlow image (may take a few minutes):

```
$ docker run --gpus all -it --rm tensorflow/tensorflow:latest-gpu \
   python -c "import tensorflow as tf; print(tf.reduce_sum(tf.random.normal([1000, 1000])))"
```

It can take a while to set up the GPU-enabled image. If repeatedly running GPU-based scripts, you can use docker exec to reuse a container.

Use the latest TensorFlow GPU image to start a bash shell session in the container:

```
$ docker run --gpus all -it tensorflow/tensorflow:latest-gpu bash
```

**ss:** TensorFlow is now installed. Read the <u>tutorials</u> (https://www.tensorflow.org/tutorials) to get started.

Except as otherwise noted, the content of this page is licensed under the <u>Creative Commons Attribution 4.0 License</u> (https://creativecommons.org/licenses/by/4.0/), and code samples are licensed under the <u>Apache 2.0 License</u> (https://www.apache.org/licenses/LICENSE-2.0). For details, see the <u>Google Developers Site Policies</u> (https://developers.google.com/site-policies). Java is a registered trademark of Oracle and/or its affiliates.

Last updated 2021-01-28 UTC.