
BuildCore

USER GUIDE · VERSION 2.48.0

Every module, step by step

Installation, first-day setup, the site, the store, purchasing, billing, equipment, cash and the books of a construction company, in one program.



November 2026 · Construction ERP for contractors in Nepal

Contents

About this guide

1 Part 1. Installation and first day

1.1 What you need
1.2 Which file to use
1.3 Installing on a new computer
1.4 Updating a computer that already has BuildCore
1.5 Where things are
1.6 First start: activating the computer
1.7 Creating the administrator and signing in
1.8 First-day setup checklist
1.9 People, jobs and project access

2 Part 2. Finding your way

2.1 Company Workspace and Project Workspace
2.2 The modules screen and the side menu
2.3 Search, new entries and the command palette
2.4 Working with lists
2.5 Dates: English (AD) and Nepali (BS)
2.6 Keys
2.7 Approvals and statuses
2.8 Help and the AI assistant

3 Part 3. The modules

3.1 Dashboard
3.2 Tools & views
3.3 Site work & DPR
3.4 Commercial & billing
3.5 Store & inventory
3.6 Procurement
3.7 Accounts
3.8 Plant (crusher, batching)
3.9 Assets and Fixed assets (NFRS)
3.10 Resources & rates
3.11 Equipment & machines
3.12 Master data
3.13 Administration

4 Part 4. Running BuildCore

4.1 Working from several places
4.2 Daily and weekly routine
4.3 Monthly routine
4.4 Year end
4.5 Backup and restore
4.6 Switches: features accounts turns on
4.7 Troubleshooting

Appendix A. Automatic accounting entries

Appendix B. Keys at a glance

Appendix C. Jobs and their main rights

Appendix D. Glossary

About this guide

BuildCore is a construction ERP: one program that keeps the site diary, the store, purchasing, billing, equipment, cash and the accounts of a contracting company in one database. This guide is for the people who install it and the people who use it every day. It covers version **2.48.0** and every module in it.

Part	What it covers
Part 1. Installation and first day	Installing, activating, the first administrator, the first-day setup list, people, jobs and project access
Part 2. Finding your way	Workspaces, the modules screen, job menus, search, lists, keys, dates, approvals
Part 3. The modules	Every module in the order of the side menu, with every screen and step-by-step instructions for the work done in it
Part 4. Running BuildCore	Working from several places, the monthly routine, year end, backups, switches, troubleshooting
Appendices	Automatic accounting entries, keys, jobs and rights, glossary

How to read a path. *Store & inventory › Goods received* means: open the module **Store & inventory**, then the screen **Goods received**. A third part, such as *Accounts › Ageing › Payables register*, is a tab on that screen. Keys are written like **Ctrl+K**. The module and screen names are exactly the names in the side menu.

Workspaces. Some screens are only in the Company Workspace (the whole company) and some only in a Project Workspace (one project). The screen tables in Part 3 mark them: **C** = Company Workspace only, **P** = Project Workspace only, **C/P** = both. Chapter 2.1 explains workspaces.

Switches. Some newer features start switched off on a company that was updated from an older version, so nothing changes until accounts decides. They are marked *Switch* in the text, and chapter 4.6 lists every switch, its default and who turns it on.

The pictures show BuildCore 2.48 with a demonstration company, *Himal Builders Pvt. Ltd.*, running a road project (ROAD, Hetauda–Bhimphedi Road Upgrading) and a building project (BLDG, Ward Office Building). Your screens show your own company and projects, and only the modules your job allows.

Part 1. Installation and first day

1.1 What you need

Item	Requirement
Main computer (keeps the data)	64-bit Windows 10 or 11, about 1 GB free for the program, plus room for your data and backups
Other computers	Windows with BuildCore installed, or any computer, tablet or phone with a web browser connected to the main computer
Internet	Not needed. Only for working between office and site (chapter 4.1) or for the optional AI assistant
Administrator rights	Not needed. BuildCore installs for the signed-in Windows user
Licence key	One per computer that runs BuildCore. Browsers that connect to it need none

Choose as the main computer the one that is switched on most, normally the accounts computer at head office. Everyone else connects to it, so there is only ever one set of books. For a large company (several companies, 200+ projects, 80+ people at the same time) BuildCore also runs as a server edition on a cloud machine; your supplier sets it up with the *Server guide*.

1.2 Which file to use

File	Use it when
`BuildCore_Setup_2.35.0.exe`	A computer without BuildCore. It installs BuildCore and brings it to 2.35.0. Then run the 2.48.0 update below.
`UPDATE_BuildCore_Complete_2.48.0.bat`	A computer that already has BuildCore, any version from 1.6 onward. One file that carries every update up to 2.48.0.
`UPDATE_BuildCore_Complete_2.48.0_bat.zip`	The same .bat inside a zip, for browsers and e-mail that refuse a .bat file. Unzip first (right-click › Extract All).
`BuildCore_Update_Complete_2.48.0.zip`	The same update as a folder. Unzip it and double-click `UPDATE_BuildCore.bat` inside.

Every installer and update keeps your data, document numbers and accounts exactly as they are. An update backs up the program files first, test-starts BuildCore on an empty database and on a copy of your data, and puts everything back by itself if anything fails.


1.3 Installing on a new computer

1. Close any open BuildCore window.
2. Double-click `BuildCore_Setup_2.35.0.exe`. Windows may show *Windows protected your PC* because the installer is not code-signed. Click **More info**, then **Run anyway**.
3. Click **Install**. If BuildCore is not on the computer yet, the BuildCore program setup opens: click **Install**, wait, then **Finish**.

4. A black window applies the update and shows each step. When it says *Done*, press any key, then click **Finish**.
5. Now run the 2.48.0 update as in 1.4, so the computer has every feature in this guide.

1.4 Updating a computer that already has BuildCore

1. Close BuildCore on that computer.
2. Double-click `UPDATE_BuildCore_Complete_2.48.0.bat` (unzip it first if you downloaded the zip).
3. The black window shows: finding BuildCore, closing it, backing up the program files, copying, test start on an empty database, test start on a copy of your data. When it says **Done: BuildCore is updated to 2.48.0**, press any key.
4. Open BuildCore as usual. A *What's new* box shows once for each new version.



The update window when it has finished

If BuildCore was installed for all users (in Program Files), Windows asks for permission; click **Yes**. If the update cannot find BuildCore by itself, it asks for the folder that contains `BuildCore.exe`, for example `C:\Users\<you>\AppData\Local\Programs\BuildCore`. A log of every update is written to your Desktop as `BuildCore_update_log.txt`; keep it if you need support.

Update every computer that runs BuildCore, not only the main one. Computers that only use a browser need nothing. If the update says it was **NOT applied**, nothing was changed and BuildCore opens as before; send the log to support.

1.5 Where things are


Item	Location
Program	`%LOCALAPPDATA%\Programs\BuildCore`
Your data	`%LOCALAPPDATA%\BuildCore\data\buildcore.db`
Automatic backups	`%LOCALAPPDATA%\BuildCore\backups`
Program files kept by each update	`…\resources\backend\_backup_<date-time>`

Item	Location
Licence files	`<BuildCore>\licence\`

The **File** menu of the BuildCore window opens the data and backup folders, and **Change data folder...** moves the data to another drive. To uninstall, use Windows Settings › Apps; your data is kept unless you choose to delete it. Never keep the data folder in Google Drive, OneDrive or Dropbox sync: the database can be damaged. Use those for backups only.

1.6 First start: activating the computer

The first time BuildCore opens on a new computer it asks for a licence key.



Activating BuildCore on a computer

1. Click **Copy** next to the request code and send the code to your BuildCore supplier or administrator by e-mail, Viber or phone. The code belongs to this computer only.
2. Paste the licence key you receive (it starts with `BCK1-`) and click **Activate**, or load the key file and click **Load**.


For the administrator who makes keys. Keys are made on the admin computer, the only one that holds the master key file (`.bckey`). Open *Administration › Licence keys › Make a licence key*, type the request code, who it is for, valid until (blank = no end), users allowed (0 = no limit) and the master password, then **Make the key**. Send the key or the `.lic` file back. A key opens only the computer it was made for; if Windows is reinstalled the request code changes and a new key is needed. Keep the original master key file on a pen drive in a safe place.

Forgot the master password? On the admin computer, *Administration › Licence keys › Forgot master password?*: load the `.bckey` file again and choose a new master password (8 characters or more). Keys already issued keep working.

A computer that already had BuildCore data before licensing was added gets 15 days to enter its key and works normally meanwhile. A new installation needs its key at first start. *Administration › Licence keys* shows the status, the days left and the request code at any time.

1.7 Creating the administrator and signing in

On a new data file BuildCore asks for the company name and the first administrator. Enter the company name, your full name, a username and a password of six characters or more, then click **Create administrator**. Write them down: usernames are not case-sensitive, passwords are.



Signing in

After that, everyone signs in with their own username. If there are several companies, choose the company first. Five wrong passwords lock a username for some minutes; an administrator can unlock it in *Administration › Users › Sign-in status*.


1.7.1 Forgot password (works offline)

Click **Forgot password?** on the sign-in screen, type the username and choose one way:

Way	Who	What you need
I have a code	Anyone	Your own recovery code, or a one-time reset code from your administrator
I am the administrator › master key file	Administrator, when nobody else can reset them	The master key file (`.bckey`)
I am the administrator › ask my supplier	Administrator of a customer company	A reset key from the supplier, made for the reset request code shown on screen

Type the new password twice; BuildCore signs you straight in.

- **Make your own recovery code now**: user menu (your initials, top right) › **Password recovery code**. Enter your password; the 20-character code shows once. Copy it or save it as a file and keep it safe. It works once; make a new one after using it.
- **Reset code for someone else**: *Administration › Users › Sign-in status › Reset code* on that person's row. It works once, for 24 hours. The person's old password keeps working until they use it.
- **Supplier reset key**: the supplier opens *Administration › Licence keys › Password reset key* on the admin computer, types the request code and the master password, and sends back the key. It works once, only for that request.



Forgot password: the three ways

Every reset closes that person's other sign-ins and is written to the audit log.

1.8 First-day setup checklist

Work through this list once, as administrator, in this order. Most lists have **Paste from Excel**, so you do not have to type them.

Step	Where
Company name, address, PAN, VAT %, tolerances, PO approval limit, scheduled hours per day for equipment (default 10)	Administration › Settings
People: one per person, with their job and where they work	Administration › Users (chapter 1.9)
Chart of accounts: one account per bank, with role *bank*	Accounts › Chart of accounts
Opening balances (debit +, credit –), including every bank and cash account	Accounts › Chart of accounts, click an account
Tally groups for every account (if you will use the Tally-style screens)	Accounts › Gateway (Tally-style) › Group mapping
TDS rates, checked against the current Income Tax Act	Accounts › TDS rates
Fiscal year periods from Shrawan 1, matched to the BS calendar	Accounts › Periods and Fiscal years
Projects, with contract value, start and end (a main store and an in-transit store are made for each)	Master data › Projects
Project teams	Administration › Project teams
Materials (a category containing *Fuel* for diesel and *Spare* for spare parts)	Master data › Materials
Suppliers, subcontractors and clients	Master data › Vendors & clients

Step	Where
BOQ with locations, and its rate analysis	Commercial & billing › BOQ control › Short codes › Import BOQ with locations; Resources & rates › Rate analysis
Control budget from the rate analysis	Commercial & billing › Control budget › From rate analysis
Opening stock per store	Store & inventory › Opening stock
WBS and activities with planned quantities and dates	Site work & DPR › Schedule & WBS
Labour trades and rates	Master data › Labour trades
Machines with operator, rate cards and maintenance plans	Equipment & machines › Register, Rate cards; Maintenance
Make your recovery code	User menu › Password recovery code

The dashboard's **To complete your figures** list (chapter 3.1) tells you which of these are still missing: contract value, cost estimates, programme dates, first IPC, bank and cash opening balances.


1.9 People, jobs and project access

Every person signs in as themselves. Two things decide what they see:

- **Job**: which modules show and what they may do (see, enter, approve).
- **Where**: *Head office, all projects*, or *These projects* (one or more sites).

1.9.1 Adding a person

1. Open *Administration › Users* and click **New person**.
2. Type the name, username and password.
3. Choose the **Job**. One line under it says what the job is for and which modules it shows.
4. Under **Where does this person work?** choose *Head office — all projects*, or *These projects* and tick the projects (use the search box when there are many). Saving *These projects* with nothing ticked is refused.
5. Click **Save**.



Administration › Users: one screen for people, job and where they work

A person on *These projects* works only in the Project Workspace of those projects, whatever their job. A head-office person sees every project. The administrator is never narrowed.


1.9.2 Jobs and the modules each one shows

Job	Modules shown (besides Dashboard and Tools & views)
Administrator, Director, Viewer, Project manager	All
Company accountant	Accounts, Commercial, Procurement, Assets, Fixed assets, Master data
Finance manager	Accounts, Commercial, Procurement, Assets, Fixed assets
Project accountant	Accounts, Procurement
Storekeeper	Store & inventory, Procurement
Procurement officer	Procurement, Store & inventory, Master data
Site engineer	Site work & DPR, Store & inventory, Equipment
Quantity surveyor	Commercial, Site work & DPR
Site supervisor	Site work & DPR, Equipment
Equipment manager	Equipment, Plant, Assets

Show all my screens, at the bottom of the side menu, brings back every module the person is allowed to open; press it again to go back. Hiding a module never removes a right.

1.9.3 Project teams

Administration › Project teams (also a button on *Master data › Projects*): pick a project to see who is placed on it, then **Add person**, **Remove**, or **Copy team from…** another project. Copying only adds people. Head-office people are listed apart because they already see every project.



Project teams: copy a team from another project

1.9.4 Check access

The panel at the top of *Users* lists people who can open every project only because nothing was ticked (an older setting), and people placed on projects that are no longer active. Open each one, choose their projects or Head office, and the line goes away. Do this once after updating from a version before 2.44.

1.9.5 Jobs & permissions

Administration › Jobs & permissions lists the jobs, what each is for, its menu and how many people have it. Click a job to:

- tick the modules its menu shows;
- set rights per area in three columns: **See** (view, export), **Enter** (create, edit, submit) and **Approve** (approve, post).

To make your own job, copy one and change it. Every change is in the audit log. Appendix C gives the main rights of each built-in job.

Part 2. Finding your way


2.1 Company Workspace and Project Workspace

After signing in, each person lands where their work is:

- People with company-wide work (accounts, management, central store) land in the **Company Workspace**: the whole company, all projects.
- People placed on one project go straight into that project's **Project Workspace**.
- People with several projects, or with both kinds of work, choose on a simple screen.

The coloured badge at the top always says where you are: blue for the company, green for a project with its code and name (a long name is shortened; hover to read it all). Click the badge to switch to another place you may work. In a project workspace the project box is locked to that project, and every list, report and file download shows only that project.

Some screens exist only in one workspace. Site documents such as the DPR, requisitions, goods received, measurements and IPCs belong to a project, so they are in the Project Workspace. Company books such as the trial balance, the chart of accounts and fixed assets are in the Company Workspace. The screen tables in Part 3 show which.



The modules screen in the Company Workspace

2.2 The modules screen and the side menu

The modules screen shows one card per module with the number of screens in it, your open work (*My work*) and a **Quick entry** row such as *+ Daily progress (DPR)*, *+ Material issue* and *+ Requisition*. **Ctrl+M** brings you back to it from anywhere. Click a card or press its number (1–9) to open a module. The side menu then lists that module's screens; **‹ All modules** returns to the full list. The breadcrumb above each page (Modules › module › screen) also takes you back.

The modules, in order, are: **Dashboard, Tools & views, Site work & DPR, Commercial & billing, Store & inventory, Procurement, Accounts, Plant (crusher, batching), Assets, Fixed assets (NFRS), Resources & rates, Equipment & machines, Master data** and **Administration**. You only see the modules your job shows (chapter 1.9).

2.3 Search, new entries and the command palette

- **Search anything...** (top bar, **Ctrl+K**) is one box for every screen you may open, every *+ New* entry, commands and records. It looks inside documents too: *cement* finds the goods receipts, issues and orders with cement on a line, and a BOQ short code such as *HW-M25* finds that BOQ line. Typing `>` shows commands only.
- **Alt+G** or **Ctrl+G** goes to any screen or record by part of its name or number.
- **+ New** creates any document your job allows: DPR, issue, GRN, requisition, purchase request, logsheet, measurement, IPC, variation, payment, voucher, issue/snag, RFI, inspection, meeting minutes, drawing and more.
- Click the **star** next to a screen title to pin it; pinned screens stay at the top of the menu and the palette.
- **Continue** on the modules screen lists the screens you used last.

2.4 Working with lists

Every list works the same way:

- Click a column heading to sort; again to reverse; a third time to go back.
- **Columns** chooses which columns show. **Copy** puts the rows (or the ticked rows) on the clipboard ready to paste into Excel. **Export CSV** saves a file headed with the company, project, period and who printed it.
- A strip of totals runs across the top. Click a line for its detail, and any number in the detail to open the document behind it.
- With the keyboard: ↑ ↓ move, **Enter** opens, **Space** ticks a row, **Ctrl+Space** ticks all. **Alt+F12** filters on conditions, **Ctrl+F12** picks values to show, **Alt+R** hides rows and **Alt+U** / **Alt+S** bring them back. **Alt+P** prints and **Alt+E** exports.

Pickers (a material on a receipt, a supplier, a machine, a BOQ item) drop down the whole list and narrow as you type, whole words in any order. If what you need is not there, press **Alt+C** or choose **+ Create new...** to make it without leaving the line.

Short forms. Long forms show the main fields first and keep the rest under **More details**. Turn this on or off with the *Short forms* tick on My work.

2.5 Dates: English (AD) and Nepali (BS)

The date switch in the top bar shows dates in English (AD), Nepali (BS) or both. **F12** (Configure) sets it for the whole program. Dates can be typed in either calendar. With Nepali dates, month boxes become Nepali months (for example *Kartik 2083*, English dates 18 Oct – 16 Nov 2026). The fiscal year runs from Shrawan 1; the year selector in the top bar sets the dates of reports and lists. **F2** changes the from/to dates of the screen you are on, and **F3** changes the project.

2.6 Keys

BuildCore uses the keys Tally uses. Press **F1** for Help (the assistant, the full key list and your own shortcuts) or **Ctrl+/** for the key list.

Key	Action	Key	Action
Ctrl+K	Search and commands	F2	Change report dates
Ctrl+M	Modules screen	F3	Change project

Key	Action	Key	Action
Alt+N	New record on this screen	F4 / F5 / F6 / F7	Contra / Payment / Receipt / Journal
Ctrl+A	Save (accept) the open form	F8 / F9	Sales (client invoice) / Purchase bill
Esc	Close without saving	Ctrl+F8 / Ctrl+F9	Credit note / Debit note
Alt+C	Create the master you are on	F10 then a letter	New site document (D = DPR, I = IPC, M = measurement, V = variation, E = event, Q = purchase request, U = return, L = logsheet)
Alt+2	Duplicate the open voucher	Alt+F9 / Alt+F4	Goods received / Purchase order
Ctrl+P / Ctrl+E	Print / Export CSV	Alt+F8 / Alt+F5 / Alt+F7 / Alt+F6	Material issue / Requisition / Transfer / Measurement
Ctrl+B	Hide the side menu	Alt+F11	Machine logsheets
Ctrl+N	Calculator (Ctrl+Enter puts the result in the box)	Ctrl+F7	Stock count
Alt+F3	Switch company	Alt+F10 / Ctrl+F10	Production run / Fixed assets
Ctrl+Shift+L	Appearance (light, dark, colours)	F11 / F12	Company features / Configure

My shortcuts (F1 › My shortcuts): choose a key, for example Ctrl+Alt+G, and what it does: open a screen, start a new entry, run a command, or type a saved text such as a standard narration. Shortcuts are saved with your user, so they work on any computer.

2.7 Approvals and statuses

Documents move through statuses such as **Draft › Submitted › Checked › Approved › Posted**. The person who writes a document cannot approve it. Posted documents are never deleted: **Cancel** reverses the stock and the voucher with a dated entry, so the history stays complete. The **Approvals list** (*Tools & views*), the badge on **Action centre** and **My work** show what is waiting for you, and the bell (🔔) shows mentions and escalations.

Operational costs raised at site (DPR labour and machines, subcontract and hire bills and similar) wait in the **Accounts posting queue** until accounts checks and posts them (chapter 3.7).

2.8 Help and the AI assistant

- **F1** opens Help. Without AI it searches this guide's topics. With the AI switched on (*Administration › AI assistant settings*), it answers questions, can **Explain this screen**, and can look up live figures your job may see.
- **Copilot** (*Tools & views › Copilot*, Company Workspace) writes reports from a question in your own words and drafts letters, notices and progress reports (chapter 3.2).
- The AI is optional and off unless an administrator turns it on. With the cloud AI, document text and questions are sent to the AI provider; switch it off for confidential companies.

Part 3. The modules


Each chapter starts with a table of every screen in the module (C = Company Workspace only, P = Project Workspace only, C/P = both), then explains the work done there step by step.

3.1 Dashboard

The Dashboard module turns BuildCore's figures into what needs doing today: for the whole company, for one project and for each person.

Screen	Where	What it is for
Company overview	C	Company figures in one page: projects, cash, receivables, payables, budget table
Dashboard	C	The home dashboard: headline tiles, Needs attention, This month, portfolio health, cash outlook, risk
Project overview	P	The same in one project
Action centre	C/P	Everything waiting for action, with the financial alerts and My financial view tabs
Risk register	C/P	Risks with likelihood × impact (5 × 5), owner and response
Project control room	C/P	One project in depth: progress, cost, cash, quality, issues
Portfolio	C	All projects at a glance, with the Financial command centre and Report builder tabs
Project comparison	C	Projects side by side
Decision centre	C	Portfolio radar, client payment grades, bid decision, bid capacity, price adjustment, subcontractor scores, benchmarks
House & small job estimate	C	A first estimate for a house or small job in a minute
My work	C/P	Your own inbox: tasks, issues, RFIs, actions, approvals
Inbox & mentions	C/P	Mentions, replies, letters given to you, reviews and transmittals

3.1.1 The home dashboard



Dashboard (2.48): tiles, Needs attention and This month


Headline tiles. Work in hand, forecast profit and margin, cash today and its lowest month, client money overdue with measured work not yet billed, and portfolio SPI and CPI, each with a trend. Each tile says what to do when it cannot show a figure:

- **Work in hand** shows *Check contract value* with the BOQ total and a link when a project's BOQ total and contract value differ by more than 1% (*BOQ ≠ contract*). Correct either the project's contract value or its BOQ.
- **Forecast profit** counts only BOQ items that have a cost estimate. It says how much BOQ has no estimate yet (margin marked *(part)*), or *Needs cost estimates* with a link to the control budget when none has one. It never shows a 100% margin from missing costs.
- **SPI · CPI** needs a programme with dates and a cost budget; the tile says so until they exist.

To complete your figures. A list of each missing step with its link: contract value, cost estimates, programme dates, first IPC, bank and cash opening balances. Until SPI and CPI exist, it takes the place of the empty portfolio health chart.

Needs attention. One list ranked by urgency and money at stake. Each line says why it is there and opens the screen that fixes it. Labels are **Important**, **This week**, **Review** and **For info**. Filter by Cost, Cash, Time, Contract, Supply, Equipment or Risk.


- *Contract notices follow a rule.* A notice is listed only for an event that is the employer's, neutral or concurrent, and whose notice is not yet marked sent. Due within 7 days: *This week: send the contract notice*. Date passed: one *Review* line per project, *check it was sent*. Your own delays (equipment breakdown, material or labour shortage) are never listed as notices; the card counts them and links to *Delays by responsibility*.
- *Repeats are grouped* into one line with a count (notices per project, material orders per project, 3+ overdue suppliers, 3+ client collections, 3+ risks). Click a grouped line to see each item.



Needs attention: grouped lines with clear labels

This month. The Nepali month by default, with an English month button:

- *Site work*: work reported in DPRs valued at BOQ rates and compared with last month, DPR days, man-days, machine hours.
- *Machines and delays*: machine time working, idle and in breakdown; delay hours split by who carries them; main causes; machines down now.
- *Money*: cash and bank today; billed (IPC), received and paid this month; receivable and payable with how much is overdue; cost booked.
- *Supply and approvals*: stock value, materials below reorder level, POs awaiting delivery, goods received, items waiting for approval, entries waiting for accounts to post.
- *One row per project*: work reported, DPR days, workers per day, machine hours, breakdown hours, delay hours, cost booked, last DPR.



This month panel (Nepali month)

Portfolio health places every project on time against cost; **Cash outlook** shows twelve months against your minimum balance; **Risk** shows the 5 × 5 heat map. **Print report** makes a one-page summary for a board or client meeting. Money figures show only to jobs with commercial or accounts rights.

Switch `gl_on` (on for every company): turning it off in settings brings back the 2.47 dashboard exactly. `gl_month` = bs or ad picks the default month.

3.1.2 Action centre, My work and Inbox

- **Action centre** lists everything waiting for action across the projects you can see: approvals, notices, overdue items. Its **Financial alerts** tab is explained below; **My financial view** is the Financial command centre for your own job and projects.
- **My work** lists what is waiting for *you*: tasks, issues to fix or check, RFIs to answer or close, meeting actions, submittals due, claim steps due within 14 days, serious incidents. Late items come first. The modules screen shows the same count.
- **Inbox & mentions** lists @mentions, replies, letters given to you, reviews and transmittals.

3.1.3 Project control room, Project overview and Project comparison

Project control room shows one project in depth: progress against plan (S-curve), the one project position (cost, value, forecast, chapter 3.4), cash, quality, safety, open issues and the next actions. **Project overview** is the project's own dashboard in the Project Workspace. **Project comparison** lines projects up side by side.

3.1.4 Portfolio and the Financial command centre

Dashboard › Portfolio › Financial command centre puts the company's money on one page: cash today, reserve, restricted funds, available to spend and the lowest week with the 13-week chart; the funding gap; receivables; payables due; IPCs by stage; each project's revenue, cost, final cost, profit and funding need; major purchase commitments; loans; priority alerts; and the actions assigned to each person. Choose the view (director, finance, accounts, project manager, procurement, stores, site); your job picks one for you. Every heading opens the records behind it. A figure that cannot be worked out reads *Not available*, never zero. The project table's note gives each project's contract value from Contracts beside the BOQ revenue.



Financial command centre

3.1.5 Financial alerts

Dashboard › Action centre › Financial alerts raises sixteen kinds of alert from the records: forecast cash below the reserve; negative projected cash; payroll, tax or a loan instalment due; client payment overdue; IPC waiting for submission or certification; measured work not claimed; supplier payments due; an order above the budget left; material shortage for scheduled work; slow stock; idle equipment; cost overrun; margin falling; variations not approved; cash differing from the saved forecast; and a project with no DPR for two days.

Each alert shows how it was worked out, the next action, links to the records, the owner, a target date and its history.

1. The owner clicks **Acknowledge**, then **Working on it**, and finally **Resolve** with a note. **Comment** adds a note; **Escalate** sends it up.
2. Managers (directors, finance managers, project managers) can **Assign**, **Dismiss** with a reason for up to 90 days, and **Reopen**.
3. When the target date has passed by the escalation days, the alert moves one step up (for example finance manager to director) and the next person is told in the bell.
4. When the condition goes away the alert is cleared, never deleted, and it opens again if the condition returns.

Alert rules (finance managers and directors with every project) switch kinds on and off and set limits, owners, target and escalation days.

3.1.6 Risk register

Record each risk with its cause, likelihood and impact (1–5 each), owner, response and due date. The register shows the 5 × 5 heat map and the risks with no response. Risks also feed *Needs attention*.

3.1.7 Decision centre

Dashboard › Decision centre answers the questions that decide whether a contractor makes money, from your own records:

- **Portfolio radar**: every running project scored 0–100 (Critical, At risk, Watch, Healthy) with reasons: progress against time gone, days without a DPR or an IPC, certified bills unpaid, mobilisation advance not recovered, open NCRs, lost-time injuries, guarantees and insurance running out. Act on Critical and At risk first.

- **Client payments**: each client's real days to certify and to pay, graded A to E, what is outstanding and what a late payment costs. *Use this client's real days in the cash forecast* puts them into the project's cash terms.
- **Bid decision**: go / no-go (bid capacity, licence class, work in hand, health of the jobs in hand, client's payment record, cash needed) and a bid price simulator using competitors' past bids (*Commercial & billing › Bids & markup*), for the "closest to the average" or lowest-bid award rule. Check the rule and the 70% floor in each bid document.
- **Bid capacity**: A × N × M − B from your turnover by fiscal year and the work still to do.
- **Price adjustment**: the contract's escalation formula, price indices by month, the adjustment for every IPC, and a claim in Events & claims.
- **Sub-contractors**: man-days, bills, payments, safety and the SSF, bank and insurance of their workers, scored.
- **Benchmarks**: the delay causes that take most hours, weather lost by month, productivity against standard, and building cost per sq ft from your own jobs.
- **Company profile**: the kind of company decides which screens the menus show; *Show all screens* shows everything.

3.1.8 House & small job estimate

Enter the floor area per storey, the number of storeys and the quality. BuildCore gives a first estimate: cement, steel, bricks, sand and aggregate from rules of thumb per sq ft (changeable), priced from your rate book; labour, finishing and services as shares; and a stage payment plan for the client. **Make it a project** creates the project with one BOQ line per stage, so the house is billed by stage.

3.2 Tools & views

Screen	Where	What it is for
KPI dashboard	C/P	Store, supply, finance and contract measures; click a figure to open its screen
Live activity	C/P	What is being entered now, by whom
Company health	C/P	About twenty measures in green, amber and red
Project league	C/P	Projects worst first
Approvals list	C/P	Every document waiting for your approval
Help, AI assistant & keys	C/P	Help topics, the assistant, key list and your shortcuts (F1)
Copilot (AI reports & writing)	C	Reports from a question in your words; letters, notices and report text
Report generator	C/P	Build any report from 42 data sources
Classic dashboard	C	The pre-2.18 dashboard
Today	P	Today's work for the project, with your site buttons
Site mode	P	Large buttons for a phone or tablet at site

3.2.1 Report generator


Tools & views › Report generator (the same tool opens from *Portfolio › Report builder*) builds a report from any of 42 sources:

- **Site progress**: DPR work lines, DPR days, DPR labour lines, DPR machine lines, DPR delays.
- **Store**: stock movements, stock on hand with reorder flag, goods received, material issued, material requests.
- **Procurement**: PO lines (with what is still to come), commitments.

- **Accounts**: purchase bills and client invoices, their lines, payments and receipts, vouchers, ledger lines.
- **Cash and finance**: 13-week forecast, receivables, IPCs, payables, project financial health, alerts.
- **Equipment**: machine days, equipment register (with expiry dates), resource costs.
- **Commercial**: BOQ items and progress, measurements, variations, subcontract work orders and bills, events and claims.
- **Quality, safety, tasks**, **master data** and (administrators) the **audit log**.

To make a report:

1. Choose the **source**, then the **period** (English presets, this or last Nepali month, a chosen Nepali month, Nepali fiscal year or quarter) and **which date** the period applies to, for example a bill's due date.
2. Choose the **projects** (in a Project Workspace it covers the open project unless you choose others).
3. Tick the **columns**, put them in order with ↑ ↓ and type your own headings. Dates can show as week, month, year, Nepali date, Nepali month, fiscal year or quarter, in English, Nepali or both.
4. Add **calculated columns** (a + b, a − b, a × b, a ÷ b, a as % of b, days between two dates).
5. Add **filters** (equals, between, starts with, does not contain…; the value box offers a pick-list).
6. Choose up to **three group levels**, *only one line per group* for a summary, the **sort** and the first N rows (for example top 10).
7. Click **Run**, then **Print / PDF**, **Excel** or **CSV**. **Save** keeps it for you; finance managers can share it with everyone.



Report generator: machine hours by Nepali month


Seventeen ready-made reports (such as *Stock movements by material*, *Machine hours by month*, *DPR labour by trade*, *BOQ progress and billing*, *Bills by due date*) can be opened, changed and saved under a new name. A report only contains the projects and figures your job may see. The screen shows the first 5,000 lines; Excel and CSV take up to 50,000. Filters work together (all must match).

3.2.2 Copilot (AI)

When the AI is on: **Ask for a report**: type what you want, for example *cement issued per site last month*. Copilot writes the query, BuildCore runs it and shows a table (and a chart). It only reads, and only what your job may see. *Change it…* refines it; *Save as my report* keeps it (saved reports run even with the AI off). **Write**: choose a letter, notice (delay, claim, variation, extension of time), monthly report text or minutes, the contract and the language (English or Nepali), and say what it should say. Facts it does not have come as [placeholders]. Edit, then download as Word, print or copy.

3.2.3 Site mode and Today

Site mode shows big buttons for the work done at site: DPR, requisition, material issue, goods received, return, transfer, stock count, purchase request, local purchase bill, equipment log, breakdown, production run, test request, events, tasks, measurement, or any other screen. **Choose what is here** picks the buttons; an administrator can save the choice for everybody. **Today** shows the same buttons with today's work for the project.



Site mode on a phone

3.2.4 KPI dashboard, Company health and Project league

- **KPI dashboard**: stock accuracy, stock-outs, turnover and days on hand, dead and slow stock, issue and GRN time, requisition fulfilment, on-time delivery, rejections, wastage, budget variance, return to store, finance and contract measures.
- **Company health**: about twenty measures in green, amber and red (margin, cash cover, overdue receivables, closes done, data checks...).
- **Project league**: projects ranked worst first on the same measures.

3.3 Site work & DPR

Everything that happens on site: the daily progress report, the programme, quality, safety, drawings, documents and the delays that may become claims.


Screen	Where	What it is for
Daily progress (DPR)	P	The Universal DPR: daily reports, acceptance, issues, reports, progress to cash, set-up
Schedule & WBS	P	WBS, activities, links, calendars, critical path, baselines, S-curve
Quality & NCR	P	Test requests, results, non-conformance reports, QA holds

Screen	Where	What it is for
Documents & photos	P	Project files and site photos
Drawings	P	Drawing register, revisions, issues pinned on the sheet
Issues & punch list	P	Quality, safety, snags, design problems, defects
RFIs	P	Requests for information to the engineer or designer
Inspections	P	Check lists with Pass / Fail / N/A
Meetings	P	Minutes, decisions and actions
Quality dashboard	P	Issues opened and closed, inspection results, RFI answer times
Client progress report	P	A plain report for the client written from the period's records
Tasks	P	Tasks with owner and due date
Events & claims	P	Delays, hindrances, notices and claims
Workers & safety	P	Workers' records, incidents and safety figures
Document control	C/P	Document numbers, revisions, reviews
Transmittals	C/P	What revision went to whom, with cover sheet
Document library	C/P	One searchable library of every file
Discussions	C/P	Team discussions with @mentions
Project directory & lists	C/P	Outside people and distribution lists
Delays by responsibility	C/P	Delay hours by who carries them

3.3.1 The Daily progress report (DPR)

The DPR is the main site screen: *Site work & DPR › Daily progress (DPR)*, or **F10** then **D**. It is a **Universal DPR**: one report that fits a building, a road, a hydropower plant, a railway, a bridge, a water scheme, a transmission line or an EPC job. There is one DPR per project, date and shift. The screen has these tabs:

Tab	What it is for
Daily reports, View & print	The DPR list and printing
Smart DPR register	Every DPR with its status, main work front, rows accepted, man-hours, machine hours, issues and photos
Progress & acceptance	Scope, planned, reported and accepted quantities per BOQ item, and DPRs waiting for acceptance
Issue register	Problems reported on DPRs; one issue across many days
DPR reports	Fifteen reports with print and Excel
Progress to cash	Each BOQ item from planned to cash received (chapter 3.4)
Work fronts & set-up	Packages, work fronts, templates, sections and progress basis
Templates & fields	The DPR templates and their fields




The smart DPR register

Writing a DPR (smart form)

Click **New DPR (smart form)** in the register. The form opens in steps; only what applies to the project shows, and **Show all sections** reveals the rest.

1. **Basics & summary**: date, shift, main work front and weather, then the executive summary: work carried out, key achievements, critical activities, major problems, instructions received and decisions required. *Fill "work carried out" from the work rows* writes the first box for you.
2. **Work done**: one row per activity and BOQ item (pick it by its short code, for example *CH0-5-GSB*), with location and chainage, planned and reported quantity. Each row shows the approved scope, the cumulative reported, the accepted quantity, the balance and the %. A cumulative beyond scope is marked *over scope*. If today is below plan, give the reason.
3. **Manpower & equipment**: labour by trade (own or subcontractor), copied from the previous DPR, so change only what differs. Machines fill themselves (see below).
4. **Problems**: pick a continuing issue to add today's hours to it, or type a new problem with its category, work front, hours lost, impact, action and the decision required. A delay line with *make an event* ticked becomes an event in Events & claims.
5. **Project sections**: the fields of the project's own template, for example layers and cut/fill for a road, or component, tunnel face, geology and support for hydropower.
6. **Quality** and **Safety & environment**: inspection requests, tests, toolbox talks and incidents.
7. **Photos & next day**: photos and the plan for tomorrow.
8. **History**: every step with who and when, and the saved revisions.




A new DPR: basics and executive summary

Materials are not typed again: the store issues for that date are read from the store ledger. The form keeps unsaved work on the computer and restores it if the window closes. Anyone who prefers the older ten-tab form clicks **Full form (classic)**; the administrator can make it the default in DPR settings.

Machine lines fill themselves

On a new DPR:

1. **Machines are listed automatically**: the previous DPR’s machine lines first (with their activity and output), then every other active machine deployed on the project.
2. **Opening = previous closing.** Each machine opens at its last closing reading before this date and shift, from DPRs of any project (the meter belongs to the machine). A night shift opens at the same day’s day-shift closing. You can type over an opening, for example after a meter was replaced.
3. **Operator** comes from *Equipment & machines › Register › Operator*. A name you type is never overwritten.
4. **Working hours = closing – opening**, shown as soon as you type the closing. A closing below the opening is warned. For km machines, type the hours.
5. **Closing = opening?** BuildCore asks **Idle (10 h)** or **Breakdown (10 h)**. Working hours become 0 and the standard day goes into Idle h or Down h. The 10 hours come from *Administration › Settings › Scheduled hours per day (equipment)*.
6. **On saving**, machines that still have no working, idle or breakdown hours are listed in one box. For each choose Idle, Breakdown, or *Not working here today: leave it out* (or use *All idle*, *All breakdown*, *Leave out all with no reading*).
7. **Output / attachment**: each machine line has an output box (default Bucket with its unit), for example *Bucket 4 h · 28 m3; Hydraulic rock breaker 2 h · 4 m3*. This feeds the monthly logsheet and the machine’s hours & output summary.



Machine lines with opening from the previous closing

Statuses: from draft to locked

A DPR moves **Draft › Submitted › Checked › Approved › Locked**.

- **Submit** sends it for checking; the project manager checks and approves it.
- **Return for correction** sends it back with a comment. **Reject** needs a reason; **Revise** takes a rejected DPR back to draft.
- Approving keeps a numbered revision. Reopening an approved DPR (administrator) needs a reason and keeps the version before.
- A locked DPR cannot change; an approver can unlock it with a reason. DPR settings can lock approved DPRs after a number of days.

When a DPR is approved, BuildCore updates in the same second: the BOQ executed quantity; activity and WBS progress and earned value; own labour cost on the project, BOQ item and activity; internal machine charges at the rate card; the machine's logsheet day; a work-order task for breakdown hours; an event for delays marked so; and a pending quality test where the activity needs one. Re-approving never counts twice, and a revised DPR keeps its link to its events and logsheet days.

Reported and accepted quantities

The site enters what it did today (reported). After the DPR is submitted, the QS or engineer clicks **Accept quantities** and records what is accepted. A blank box means not yet accepted; a figure different from the site's needs a note. Each row shows the approved scope (contract quantity plus approved variations), the previous accepted cumulative, the new cumulative and the balance. Going beyond scope needs an approver and a reason. Accepting posts nothing to the accounts.



Accept quantities

The **Progress & acceptance** tab shows per BOQ item the scope, planned to date, reported and accepted in the period and cumulative, and lists DPRs waiting for acceptance. **Progress basis**: progress, earned value and the CVR use reported quantities; in *Work fronts & set-up* a project can switch to accepted quantities from a date (earlier DPRs keep reported figures).

Issue register

A problem typed on a DPR becomes an issue in the same register as *Issues & punch list*. The next day it is picked as a continuing issue, so a problem that lasts a week is one issue with seven days. The tab shows first day reported, days on DPRs, total hours lost, the decision required and from whom, the person responsible, the due date and whether it matters for a claim. *Claim relevant only* filters to those.

Work fronts, templates and fields

Work fronts & set-up (needs the DPR set-up right):

- Packages and work fronts, for example *Package 1: Ch 0–4 km* with *Front A* and *Front B*. Every work, labour and machine row is tagged with its front, so reports can be filtered by front without counting a machine twice.
- Templates in force: Basic plus the project's type. New DPRs use the current published versions.
- Standard sections to show or hide, the progress basis and the tolerance above scope.

Templates & fields lists the nine built-in templates: Basic, Buildings, Roads, Hydropower, Railways, Bridges, Water and sewerage, Transmission lines and substations, and EPC. To add your own fields: copy a template, add sections, fields (23 types such as number, date, dropdown, chainage, BOQ item, photograph), repeating tables or extra columns on work rows, and **Publish**. DPRs already written keep the version they were filled with.

DPR reports and printing

DPR reports has fifteen reports: daily, weekly and monthly summaries; activity-wise and work-front-wise progress; planned against actual; manpower and equipment; material consumption; quality; safety and environment; the delay and issue register; hours lost by cause; photographic progress; and any custom table. Filter by dates, status and front, group and sort, then print or export. **Save layout** keeps your choice.


Print on one DPR, or **Print ticked** in the register, prints the full report: header, summary, quantities with scope, accepted, cumulative and balance, manpower, equipment, problems, delays, the project's sections, next-day plan and signatures. For a PDF choose *Microsoft Print to PDF* in the Windows print window.

3.3.2 Schedule & WBS

WBS elements and activities with planned quantities and dates, links, calendars, the critical path, baselines and the S-curve.

1. Add WBS elements, then activities with quantity, unit, BOQ item and planned dates, or use **Import from Excel / CSV** to load an existing programme.
2. Add links (finish-to-start and others) and calendars.
3. Click **Calculate** to work out dates, critical path and float. Save a **baseline** before work starts.

Progress comes from approved DPRs, so the forecast finish moves when the work moves. An activity that needs a test stays on QA hold until the test passes. The programme with dates is what gives the dashboard its SPI.



Schedule & WBS

3.3.3 Quality, issues, RFIs, inspections and meetings

- **Quality & NCR**: raise a test request (or let an approved DPR raise it), record the result; a failed test raises an NCR with cause, action and close-out.
- **Issues & punch list**: quality problems, safety observations, snags, design problems and warranty defects. Say what is wrong, where, who fixes it and by when; add photos. The fixer marks *Being fixed* and *Fixed – ready to check*; the checker closes it. Late items are red.
- **RFIs**: subject, question, drawing, who must answer and by when. Record the answer and any cost or time impact; **Make an event** turns an answer that changes cost or time into an event. Print an RFI to send it.
- **Inspections**: pick a form (concrete pour card, excavation safety, scaffold, weekly safety walk, masonry and plaster, house handover) or make your own, one check per line. Tap Pass / Fail / N/A; every Fail becomes an issue.
- **Meetings**: start a site progress, client or safety meeting; open actions from the last meeting of the same kind carry forward. An action given to a BuildCore user becomes a task in their My work. Print the minutes.
- **Quality dashboard**: issues opened and closed by week, who has open issues, inspection results and RFI answer times.
- **Client progress report**: a plain report for the client or house owner written from the DPRs, photos, issues and bills of the period. Change the words, then print or copy.
- **Tasks**: tasks with owner, due date and status; they appear in the owner's My work.

3.3.4 Drawings, document control and transmittals

Drawings: add each drawing with number, title, discipline, revision and the PDF or image. Adding the same number with a new revision supersedes the old one, and its open issues move to the new sheet. Click a drawing to view it (zoom, pages); **Add issue on the sheet** then click the spot to pin an issue.


Document control keeps document numbers made from a pattern such as `{P}-{DISC}-{TYPE}-{SEQ}` (RD-12-STR-DRG-0001), revisions with files, and reviews: send to one or more people; each answers A approved, B approved with comments, C revise and resubmit, or D rejected, and the worst answer is the result. **Transmittals** record which revision went to whom and why, with a printable cover sheet and the acknowledgement date.

There is **one drawing register**: a drawing added or revised in *Drawings* adds the same revision to its Document control card, and a revision added in Document control becomes the current sheet in Drawings.

3.3.5 Document library

Site work & DPR › Document library is one searchable library over every file BuildCore holds (DPR photos, letter scans, document revisions, attachments) plus documents you add. Each keeps its project and a link back to its record.

1. **Add documents** one by one or a whole folder. If the top folder is named after a project code, the files go into that project. A duplicate is dropped and the existing document is named.
2. BuildCore **reads the words inside** PDF, Word, Excel, PowerPoint, OpenDocument, RTF, DXF, e-mail and text files, with a progress bar. Scanned PDFs without a text layer show *no text found*.
3. **Search**: all the words, `"exact phrase"`, the start of a word (`penst`), `OR`, and `-word` to leave out. Filter by project, category, file type, where attached, dates, tag, old revisions and removed. Sort by best match, date, name or size.
4. **Categories** (Drawings, Bills & Payments, Minutes of Meeting, Correspondence…) are detected from file and folder names; edit them, and **Detect again** moves documents out of *Other*.
5. **Upload new revision** replaces the file and keeps the earlier one. Bulk actions: move to a project, set category, add tags, read again, remove from library (nothing is deleted; it can be brought back), Export CSV.
6. **Linked to records** (tab): tie a document to a voucher, bill, payment, GRN, PO, IPC, measurement, claim or contract by its number. One document can support several records.



Document library search with highlighted words

3.3.6 Discussions and the project directory

Discussions: talk about a problem or decision where the team can see it; write `@username` to call someone in. **Discuss** buttons on letters and documents open a discussion on that record. **Project directory & lists**: outside people (client engineer, consultant, suppliers) and distribution lists used for copies.

3.3.7 Events & claims and Delays by responsibility

Events & claims records delays, hindrances, notices and claims, each with its cause, responsibility, notice deadline, delay days, cost and status. Delays from the DPR create events automatically (when *make an event* is ticked). When a delay line is removed from a DPR, its event is removed if nobody worked on it; if someone did (notice sent, status changed, EOT, claim or cost entered, files, comments), the event stays and is listed for review. A claim followed in the Claims register (chapter 3.4) keeps its event up to date.

Delays by responsibility shows delay hours by who carries them: employer, neutral, concurrent, or your own (equipment breakdown, material or labour shortage). Only the first three can need a contract notice.

3.3.8 Workers & safety

- **Workers**: trade, subcontractor, SSF number, bank account, accident insurance (Labour Act: at least Rs 7 lakh) and skill certificate; missing items are marked. Paste many from Excel.
- **Incidents**: near miss, first aid, medical, lost-time injury, fatality, property and environmental, with cause, days lost, actions and insurance claim. A lost-time injury makes an investigation task.
- **Safety figures**: man-hours from DPR labour, LTIFR, TRIR, severity, days since the last lost-time injury, causes and open actions.

3.3.9 Who may do what on the DPR

Job	DPR	DPR set-up
Director	view, approve, export	view
Project manager	view, create, edit, submit, approve, export	view, edit
Site engineer	view, create, edit, submit, export	
Site supervisor	view, create, edit, submit	
Quantity surveyor	view, edit, export; accepts quantities	
Finance manager, project accountant	view, export	
Others	view	

Change these in *Administration › Jobs & permissions*. Accepting quantities needs commercial edit (the QS) or DPR approve.

3.4 Commercial & billing


The contract side of every project: the BOQ, what is measured and billed, variations, contracts and claims, and the cost control that links engineering and accounts so both sign the same figures every month.

Screen	Where	What it is for
BOQ control	P	Each BOQ item with contract, revised, executed, measured, billed, certified; summary by item; short codes
Measurements	P	Measured quantities checked by the QS
IPC billing	P	Interim payment certificates, billing pipeline and collections
Variations	P	New or changed items with decision and budget effect
Contract administration	P	What the contract needs now
Correspondence register	P	Letters in and out with register numbers

Screen	Where	What it is for
Notices & time bars	P	Notice clocks per clause
Cost codes	C/P	Each project's cost code list and coding start
Contracts & letters	C/P	Register of client, subcontract, supply, hire and consultant contracts; one contract register
Subcontract work orders	C/P	Labour supply, item-rate and back-to-back work orders and their bills
Execution plan	C/P	How each part of the project is done
Claims register	C/P	Contract conditions, claims, timelines, letters
Bonds, guarantees & insurance	C/P	Securities and insurance with expiry
Contract documents (AI)	C/P	Contract and specification documents, abstract and search
Cost & earned value	C/P	BAC, EV, PV, CPI, SPI
Project cost & exposure	C/P	Cost to date and commitments
Control budget	C/P	Original and current budget per cost code
CVR and forecast	C/P	Value against cost; project position; cost to complete & profit
Project close	C/P	The monthly close checklist
Close status board	C/P	Where every project's close stands
CVR, all projects	C/P	CVR and profit after overhead and financing for every project
Bids & markup	C	Bids, competitors' prices and markup

3.4.1 BOQ control

Each BOQ item with its contract, revised, executed, measured, billed and certified quantities and amounts, and its rate analysis (material, labour, equipment and overhead per unit). The rate analysis is what makes budgets, earned value and cost variance work.




BOQ control

BOQ by location and short codes

A BOQ can repeat the same item in several locations, for example *M25 concrete* 45 m³ in Headworks and 15 m³ in the Settling basin. BuildCore keeps one BOQ line per item and location (so the DPR, store, bills and cost all stay location-specific), and adds:

- **A short code** for every line = location + item, for example **HW-M25**, **SB-M25**, **CH0-5-GSB**, **BLKA-RBAR-FE500**. Location codes are made from the project's BOQ components (HW, SB, HRT, PH for hydropower; chainage for roads; block and floor for buildings; abutment and pier for bridges...). Item keys come from the description (M25, RBAR-FE500, EXC-SOIL, GSB, WMM, DBM, BRICK, PLAS-12MM...).
- **Summary by item** (tab): one row per item with one column per location, total quantity, the overall quantity stated in the BOQ, rate (or range), amount, executed, progress, measured, billed, certified, balance, actual cost and forecast profit. Below it, the BOQ amount by location. Checks at the top warn when an overall line is counted twice, when the stated overall differs from the locations (**Use the location total**), and when the same item is priced differently by location.
- **Short codes** (tab): every line with its code, location and item; click a line to type a code, file it under another item or mark it *overall*.



Summary by item: M25 by location

Every BOQ picker then shows `HW-M25 · 2.1 Providing and laying M25…`: DPR, requisitions, purchase requests, POs, issues, measurements, IPC lines, budgets, variations, invoice lines, quality tests and activities. Typing *HW-M25* or just *M25* filters to it. Search (Ctrl+K) finds a line by its short code.

To import a BOQ with locations:

1. *BOQ control › Short codes › Import BOQ with locations*.
2. Paste from Excel the columns `code | description | unit | qty | rate | location | short_code` (location and short code may be blank). A row with only a description is a location heading (HEADWORKS, Ch 0+000 – 5+000, Block A…).
3. Check the **preview**: each row's action, its short code and the summary after import. Duplicate codes and negative quantities are refused.
4. Click **Import**. Nothing is saved before this.

Add standard locations adds the usual locations for hydropower, road, building, bridge, irrigation/water or transmission line projects. **Rebuild automatic codes** recomputes every automatic code; codes you typed stay.

Switch `bx_on`: off on a company updated from before 2.47. The Short codes tab shows the codes and summary it would give without saving anything; a Commercial approver turns it on there (codes for every project are made at that moment). New companies start with it on. The format (`{LOC}-{ITEM}` , `{ITEM}-{LOC}` , `{LOC}/{ITEM}` , `{LOC}.{ITEM}`) is set on the same tab.


3.4.2 Measurements

Commercial & billing › Measurements › New measurement (Alt+F6) pre-fills the executed quantities not yet measured. The QS checks them; a measurement cannot exceed the work done without an override. Approve it to make it available for billing.

3.4.3 IPC billing

1. *IPC billing › New IPC* (**F10** then **I**) pre-fills the verified measurements not yet billed, with previous, current and cumulative quantities per BOQ item.
2. Check advance recovery, retention, VAT, TDS and other deductions. Billing beyond the revised quantity waits for an approved variation.

3. **Submit** the IPC to the client.
4. **Certify** records what the consultant allowed and posts the client invoice with VAT, TDS, retention and advance recovery.



IPC billing

Billing pipeline & collections (tab): every IPC shows its stage (prepared, submitted, under review, certified with payment due, overdue, partly paid, paid) with the date submitted, certification due (submission plus the project's certification days), certified, payment due and expected payment. The cards on top show work done but not measured and measured work not yet billed, at BOQ rates. Click an IPC to record the person responsible, the next action and date, the consultant's comments, the expected payment date and the reason for any delay; each change goes into the IPC's history.

3.4.4 Variations

Record new or changed items with quantity, rate, reason, decision and budget effect. An approved variation raises the revised quantity, so billing can go beyond the original. Idle claims are listed beside them. A variation can create a new BOQ item (it gets its short code when saved).

3.4.5 Contracts, letters, notices and bonds

- **Contracts & letters**: the register of subcontracts, supply, hire, client and consultant contracts. Each has its letters, reports, deliveries, milestones, notices and payments with due dates; repeating ones get their next date when marked done. Bond and insurance expiry and the contract end date raise warnings 30 days ahead. Templates add the usual deliverables for each kind of contract.
- **Contract administration**: what the contract needs now: letters waiting for reply, notice clocks running, bonds and insurance to extend, events without a notice, variations waiting, transmittals awaiting reply.
- **Correspondence register**: log every incoming letter (their reference, received date, who must act, reply-by date) and write outgoing letters with a register number (RD-12-OUT/2083-84/0001). **Reply** links the answer to the letter. Drafts are ready for a notice of claim, extension of time request, request for instruction, notice of variation, payment reminder and acknowledgement.
- **Notices & time bars**: start a clock when something happens: choose the clause and the date you became aware; BuildCore shows the last day for the notice and the detailed claim. The outgoing letter stops the clock.
- **Bonds, guarantees & insurance**: performance security, advance payment and retention guarantees, bid security, CAR, third-party, workers and vehicle insurance with amount, bank or insurer and expiry. Expiry within 45 days is

flagged and shows in My work; every extension, reduction and release is kept.

One contract register

Contracts & letters › One contract register (tab) shows each project's contract value, start, end, retention % and advance % beside its client contract(s), and whether they agree.

1. Click **Make client contract from the project** (or for every project) where a project has no client contract yet.
2. Check the figures, then **Confirm and switch on** (commercial or accounts approve).


From then on, saving a client contract writes its value, dates, retention and advance to the project; *Master data › Projects* refuses a different value (*kept in Commercial › Contracts*). CVR, cost to complete and Claims show that value. Bonds and insurance live in *Bonds, guarantees & insurance*, copied once from each contract. Subcontract work orders take retention, advance and dates from their subcontract. *Switch*: off on updated companies until confirmed; on for new companies.

3.4.6 Claims register

Commercial & billing › Claims register manages contract claims with the contract's own procedure.

1. **Contract & conditions**: choose the form (FIDIC 1999 Red / Yellow / Silver, MDB 2010, FIDIC 2017 Red / Yellow / Silver, Emerald 2019, Gold 2008, Green 2021, PPMO NCB, PPMO small works, other). Set-up is prefilled from the project; enter the Contract Data, Particular Conditions periods and clause edits.
2. **New claim**: it adds an event (type claim) to Events & claims, or **follow** an existing event such as a DPR delay.
3. The **timeline** follows the form: under FIDIC 2017, Notice 28 days, Detailed claim 84 days, Engineer's determination 42 + 42 days, NOD, DAAB and arbitration. Each step shows its due date and whether it is barred, late or overdue. Changing a period in the Particular Conditions moves the dates.
4. Inside each claim: strength score with gaps, entitlement clauses, cause and effect, evidence checklist, records, quantum and calculator, dispute route.
5. **Draft** a notice, detailed claim, NOD or arbitration letter; copy, print or save it straight into the Correspondence register.

Other tabs: Overview (deadlines, current completion date with EOT, bonds), Payments (IPC payment clock and late-payment financing charge), Timeline, Start-up checklist, Tender review, Negotiation, Clause library and All contracts (every deadline across the portfolio). Claim steps due within 14 days show in My work.



Claims register: a claim and its timeline

3.4.7 Subcontract work orders and Execution plan

Subcontract work orders: labour supply, item-rate with our material and equipment, or back-to-back. Enter the subcontractor, items, rates, retention and advance, then their bills against measured quantities. Material given to a subcontractor is recovered from their bills; their quantities are checked against the main measurement. **Execution plan** records how each part of the project is done (own labour, labour supply, subcontract).

3.4.8 Contract documents (AI)

Upload the contract, GCC, SCC, specifications (PDF, Word or text), optionally linked to a contract. BuildCore reads the text. With the AI on, **Read with AI** makes a contract abstract: value and dates, advance, retention, bonds, insurance, liquidated damages, price adjustment, payment terms, defects liability, notices, preconditions and technical requirements, each with its clause and page. **Approve**, **Edit** or **Reject** each item; approved items with a date can be added to the contract's schedule. **Ask the document** answers with clause and page; without AI, **Search** finds the words. Always check the clause; it is not legal advice.

3.4.9 Cost control: cost codes, budget, CVR and the monthly close

Cost codes

Commercial & billing › Cost codes: every BOQ item plus preliminaries, site overhead, temporary works, idle by responsibility, defects and unallocated. Set the **coding start** date in *Coding start & pilot*. From that date a DPR cannot be submitted, and a requisition, purchase request, store issue or work order cannot be approved, until each line has a code. A requisition's code is copied to the purchase request and the issue.

Control budget

1. *Control budget › From rate analysis* previews what each item would get, with the cost per unit by type and where it came from.
2. Choose **Fill only items without a line** (keeps lines someone edited) or **Rebuild the whole draft**.
3. The project manager **submits**; the director **approves**, which locks the *Original budget*.

The *Current budget* changes only by approved variation or a reasoned re-plan. The purchase request and PO budget box uses the same check: the control budget when there is one, otherwise the material budget.

CVR and forecast, Project position

CVR and forecast shows value earned against cost per BOQ item with CPI, cost to complete, forecast final cost and forecast margin, live or from a locked close. Click any figure to see what is behind it.

The **Project position** tab gives every project one set of figures, used on every project screen:

- **Cost to date**: posted, waiting in the posting queue, and accrued at the month close. Each own machine's cost is shared over the projects that logged its hours.
- **Value**: certified, measured, billed and earned.
- **Forecast per item**, tried in this order: PM override; actual unit cost once the item is 20% done; control budget; rate analysis; actual cost (*no budget*); *No forecast*. Items with no cost estimate are not counted as profit.


Ledger screens (Profit & loss, Budget vs actual) keep the ledger figure and show the position beside it with one reconciliation line.

Switch: on an updated company, check each project's before and after on the tab and press **Confirm and switch on** (accounts approve). Three more switches are on the same tab: monthly runs by Nepali month, the equipment cost centre (EQUIP) date, and *over-budget PO needs administrator* (chapter 4.6).

Cost to complete & profit

CVR and forecast › Cost to complete & profit adds what is already committed (open PO lines and subcontract work orders) to the forecast. The remaining cost is the larger of forecast cost to complete and open commitments, so an order is counted once. Below gross profit it adds head-office overhead and financing (interest on the project's cash need) to give **profit after overhead & financing**. Unapproved variations and claims are listed as potential, not counted. *Resources*

vs plan & cost compares the man-days and machine hours the rate analysis allows with those worked on the DPRs. *CVR, all projects* shows the same for every project you can see.



Cost to complete and profit

Project close (monthly)

One checklist per project per month:

1. Site cut-off: DPRs, logsheets, issues and returns approved.
2. Quantities done to date confirmed by the QS.
3. Subcontract and hire quantities confirmed.
4. Accounts posting queue cleared to the cut-off.
5. Accruals calculated (*Accounts › Accruals register*).
6. Integrity checks pass, or the director overrides one with a reason.
7. Signed by the QS, the project accountant and the project manager.
8. Locked by the director, which saves the snapshot and locks the month.

Close status board shows where every project's close stands. **Control settings** (Accounts) holds thresholds, cut-off day and rules. *Start with a pilot*: one running project with a clean BOQ and an active QS, set its coding start, import and approve its control budget, and run two monthly closes before bringing in the others.

Cost & earned value, Project cost & exposure, Bids & markup

- **Cost & earned value**: BAC, EV, PV, CPI and SPI from the rate analysis and the programme.
- **Project cost & exposure**: cost to date with commitments and what is still exposed.
- **Bids & markup**: your bids and competitors' prices, used by the Decision centre's bid simulator.

3.5 Store & inventory


Every material movement, from the site's request to the physical count, with stock and the books always agreeing.

Screen	Where	What it is for
Requisitions	P	Site asks the store for material (Alt+F5)

Screen	Where	What it is for
Goods received	P	Receipts against a PO or without one (Alt+F9)
Import GRNs from Excel	P	Many receipts from one sheet
Issues	P	Material given to an activity, BOQ item or machine (Alt+F8)
Returns	P	Usable material back to the store
Stock count	P	Physical count and adjustments (Ctrl+F7)
Material reconciliation	P	Theoretical use against actual issues
Opening stock	P	Stock at the start
Stock on hand	C/P	What is in each store, with value
Store by kind	C/P	Consumables, tools, spare parts; who holds each tool
Stock by segment	C/P	Stock split by projects, trading and company
Material forecast	C/P	What runs out before the next delivery
Transfers	C/P	Stock moved between stores through in-transit (Alt+F7)
Stock card	C/P	Every movement of one material
Stores & locations	C/P	The stores and their locations
Stock by location	C	Stock across all stores
Central store	C	The head-office store

3.5.1 The store chain

1. **Requisition** (Alt+F5): the site asks for material, with the BOQ item (short code) and cost code it is for.
2. If the stock is there, the store **issues** it (Alt+F8) from the requisition. If not, **Raise purchase request for shortfall** turns the rest into a purchase request (chapter 3.6), priced from past purchases.
3. **Goods received** (Alt+F9): choose the PO and the quantities come in, or receive without a PO. Record received and accepted quantity and any rejection. Stock is valued at landed cost including freight.
4. **Returns** bring usable material back; **Transfers** move stock between stores through *in transit*.
5. **Stock count** records the physical count; differences post as gains or losses after approval.



Goods received

Rules that protect you: stock cannot go negative; an issue cannot exceed what the store holds; stock is valued at moving weighted average per store; every movement posts its own voucher (Appendix A). Cancelling a posted document reverses it; nothing is deleted.

3.5.2 Recording a goods receipt step by step

1. *Store & inventory › Goods received › New* (or Alt+F9).
2. Choose the project's store, the supplier and the PO (lines and rates fill from the PO), or leave the PO blank for a direct receipt; the rate then fills from past purchases.
3. Type the challan / bill number, vehicle number and date.
4. Enter the received and accepted quantity per line; rejected quantity and reason if any.
5. Attach the challan scan in the **Papers** panel (required if your company's papers rule for GRNs is on).
6. **Save**, then **Post**. Stock and the GRN clearing account move; the supplier's bill comes later in Procurement.

3.5.3 Import GRNs from Excel


Store & inventory › Import GRNs from Excel (or *Import from Excel* on the Goods received list). Download the sample sheet: one row per material with 15 columns (GRN Date, Project Code, Store, Vendor Name, Vendor PAN/VAT No, Vendor Phone, Vendor Address, Challan/Bill No, Vehicle No, Material Code, Material Name, Unit, Received Qty, Accepted Qty, Rate excl. VAT). Rows with the same date, project, store, vendor and challan become one GRN. A new vendor or material is created. Dates may be AD or BS.

1. Choose a date range if you want only some rows.
2. **Check the sheet** runs everything and undoes it, so you see every problem first.
3. **Import** saves and posts (or leaves drafts). A challan with a bad row is held back whole; a challan already in BuildCore is skipped, so the same sheet can be imported again after adding rows.

3.5.4 Reports

- **Stock on hand** and **Store by kind**: what is in each store; tools show who holds them. Change a material's kind with *Move items to this kind*.
- **Stock card**: every movement of one material with running balance and value.

- **Material forecast**: what runs out before the next delivery, from scheduled use.
- **Material reconciliation**: theoretical consumption from the work done and the norms against actual issues, with the wastage value.
- **Stock by location**, **Stock by segment**, **Central store**: the company-wide views.



Stock on hand

Every stock check in the integrity checks counts entries waiting in the accounts posting queue, so a difference fully explained by waiting entries passes, and each waiting entry is named.

3.6 Procurement

From the purchase request to the supplier's bill, with past prices, budget checks and three-way matching of what arrived, what was billed and what was paid.


Screen	Where	What it is for
Purchase requests	C/P	Requests to buy, with estimated rate from past prices
Quotation comparison	C/P	Quotes side by side; L1 marked
Purchase orders	C/P	POs with approval check and past prices (Alt+F4)
Pending deliveries	C/P	What is still to come and what is late
Purchase bills	C/P	Supplier bills (F9); match receipts, bills & payments
Project & trading purchases	C/P	One bill split between projects, trading and company use
Trading sales	C	Sales from the trading store
Trading stock	C	Stock held for trading

Screen	Where	What it is for
Vendor performance	C	Delivery record, rejections, prices per supplier
Price history	C	Rates paid per material over time

3.6.1 The buying chain

Purchase request › Quotation comparison › Purchase order › Pending deliveries › Goods received › Purchase bill › Payment.

1. **Purchase request** (F10 then Q, or from a requisition shortfall). Pick each material; the rate fills itself from past purchases (below). The budget box shows the control budget left for the cost code.
2. **Quotation comparison**: enter each supplier's quote. The lowest complete quote is marked **L1**; choosing another supplier, or having fewer quotes than the minimum, needs a reason.
3. **Purchase order** (Alt+F4). Orders above the high-value limit need an administrator. Revising a PO keeps its history.
4. **Pending deliveries** shows what is still to come and what is late.
5. Receipts beyond the PO quantity plus tolerance are blocked; bills whose rate differs by more than the tolerance need approval.
6. **Purchase bill** (F9) against goods received, or a direct bill for freight, hire or services.




Purchase orders

3.6.2 Past prices on purchase requests and POs

When you pick a material on a purchase request or PO, BuildCore looks at the posted GRNs for that project:

Past purchases on this project	Rate filled in	*Past prices (latest 3)* column
Always the same price	that price	"always 104.00"
Prices differ	average of the latest three	the three rates, newest first
Never here, bought on other projects	same rule from other projects	marked "(other projects)"
Never bought	the standard rate, as before	blank

The **Past prices** panel under the lines shows the latest three purchases with date, rate, vendor, GRN and project. A rate you type is never changed. *Switch* `pr_price_fill` is on in every company.



Purchase request with past prices

3.6.3 Before approving a PO: stock, budget and cash

Purchase orders › Approval check lists orders waiting for approval. Opening a draft or pending order shows **Before approval**: stock on this project and in all stores, other open orders, scheduled use over 30 days, the budget left after the order (control budget when there is one), the company cash in the week the order is paid (accounts users only), and the latest delivery date the work needs. A company can make an over-budget order need an administrator (switch on the Project position tab).

3.6.4 Match receipts, VAT bills and payments

Material reaches site and the store receives it, but the supplier's VAT bill may name another item, split the price ("sand 800 + other item 200"), or cover less than was paid. BuildCore keeps three truths with three owners and links them:

	Arrived at site	Vendor billed	Paid
Who enters	Storekeeper (site)	Accounts	Accounts
Screen	Goods received	Purchase bills, typed exactly as printed	Payments
Drives	Stock and project cost	Input VAT, VAT register	Bank, cash, vendor balance

Procurement › Purchase bills has three tabs for this:


- **Match receipts, bills & payments**: one row per vendor with received not billed, bills waiting for goods, paid with no VAT bill yet, payable on bills, purchases without VAT bill and different-item links. Open a vendor to see the three tables side by side.
- **Bill vs actual**: every linked bill line, what the bill says beside what really came, with the reason and approver; export to CSV for the auditor.
- **Match settings**: the switch, approval limit and self-approval.

Link a bill to the goods:

1. Type the draft purchase bill exactly as printed.
2. On each printed line click **Link to goods**; BuildCore suggests GRN lines of the same item. Link a part quantity if only part was billed (250 of 300 bags; the other 50 stay *received, not billed*).
3. A line for a different item (for example *other item 20,000* that is really part of the sand price) links to the sand GRN with quantity 0 and the amount, with a reason. It needs approval by someone else (Procurement approve).
4. **Post** the bill. One voucher clears GRN clearing and books input VAT as printed; stock shows the real rate; the VAT register shows the bill as printed.

Purchase without VAT bill: for goods that came and were paid (often in cash) but will never get a VAT bill, pick the GRN lines, give a reason and reference. BuildCore makes a zero-VAT bill against the goods, leaves it out of the VAT register, and after approval sets the money already paid against it.

Reclassify cost (on a bill posted before this feature, Accounts approve): moves an "other item" amount to the right cost account with a reason, without touching the bill or its VAT.



Match: one vendor's receipts, bills and payments

Switch `mt_on` : off on updated companies, on for new ones; turned on in *Match settings* (Accounts approve). Gaps are listed from the day it is turned on. A VAT bill that describes goods not supplied is a tax and audit risk; BuildCore records the truth and lists every such bill. Confirm the treatment with your auditor.

3.6.5 Project & trading purchases

One supplier bill can be split between projects, the trading store and company use: choose *Mixed purchase* as the procurement purpose on the goods receipt and use **Allocate destinations**. One supplier, one bill, one liability and one VAT entry; ten report views show the split and prove it adds back to the books. **Trading sales** sells from the trading store; **Trading stock** shows what is held.

3.6.6 Vendor performance and Price history

Vendor performance shows each supplier's on-time delivery, rejections and prices. **Price history** shows each material's price over time from posted receipts.

3.7 Accounts

One set of books for the whole company. Most vouchers post themselves from the site, store, billing and equipment screens (Appendix A); accounts checks them, pays, collects, reconciles and closes. The Tally-style Gateway is a second way to enter and read the same books.

Screen	Where	What it is for
Gateway (Tally-style)	C/P	Tally-like start screen, keyboard vouchers, Tally reports, controls
Vouchers	C	Manual journals, payments, receipts; voucher list
Accounts posting queue	C/P	Site costs waiting for accounts to post
Accruals register	C/P	Month-end accruals per project
Costs by way of working	C/P	Cost by direct labour, subcontract, own and rented equipment
Payments & receipts	C	Payments, receipts, payment requests, wages, salaries, petty cash, money settings, papers rules
Client invoices	C	Sales invoices from IPCs and others (F8)
Chart of accounts	C	Accounts, roles, opening balances
Trial balance, Account ledger, Day book	C	The books
Profit & loss, Balance sheet	C	Statements by company or project
Party statement, Ageing	C	Parties, receivables, payables, collection actions
VAT books, TDS register, TDS rates	C	Tax records
Bank reconciliation	C	Tick-off and bank statement import
Budget vs actual	C/P	Budget against the ledger
Project cost vs ledger	C	Project position against the ledger
Cash forecast & ratios	C	13-week forecast, funding gap, loans, ratios
Returns (ROA / ROE), Finance by segment	C/P	Return and finance by projects, trading and company
Periods, Fiscal years	C	Month locks, year close, opening balances
Control settings	C/P	Close thresholds, cut-off day and rules
Integrity checks	C	Integrity and financial data checks


3.7.1 Vouchers and keys

Contra **F4**, Payment **F5**, Receipt **F6**, Journal **F7**, Sales **F8**, Purchase **F9**, Credit note **Ctrl+F8**, Debit note **Ctrl+F9**. They open from anywhere. **Ctrl+A** saves, **Alt+2** duplicates, **Alt+C** in a ledger box creates a ledger.

- Manual vouchers wait for a second person to post them (maker and checker).
- Posted vouchers cannot be edited. Cancel or reverse them and enter a new one; with the Tally-style *edit with log* policy, alteration reverses the old voucher and posts the new one under the same number (below).
- Numbering is gapless per fiscal year (PV/2083-84/0006).

3.7.2 The Gateway (Tally-style)

Accounts › Gateway (Tally-style) is a Tally-like start screen over the same books: no voucher is copied and no balance moves.



Gateway (Tally-style)

Keys on the Gateway: V vouchers, K day book, T trial balance, P profit & loss, B balance sheet, M group mapping, Y voucher types, L Edit Log, F11 features. Every key is also clickable in the list on the right.

First set-up (accounts, once):


1. **F11 Features**: turn the Tally screens on (*switch* `tl_on`: off on companies updated from before 2.46, on for new ones) and choose the alteration policy: *reverse only* (the old rule) or *edit with log*.
2. **Group mapping**: BuildCore proposes one of the 28 Tally groups for every account from its role (Cash & Bank → Bank Accounts / Cash-in-Hand, Payables → Sundry Creditors, Direct contract costs → Direct Expenses…). Check the list and confirm it. A P&L account cannot go under a Balance Sheet group. **Contractor pack** adds 11 groups such as Retention Receivable, Retention Payable, Mobilisation Advance and Work in Progress.
3. **Voucher types**: 24 Tally types plus BuildCore's own (Material Receipt (GRN), Supplier Bill, IPC Invoice, Auto – DPR, Auto – Depreciation…). Make your own child types, for example *Site Payment – SMK* under Payment, with numbering: automatic or manual, prefix and suffix with `{FY}` `{MM}` `{YYYY}` `{PROJECT}`, one series or one per project, restart yearly / monthly / never. Example: `SMK/ROAD/2083/84/001`.
4. **Controls**: the audit lock date (no entry on or before it on any screen; only the administrator moves it back), back-date days and alteration days per job.

Parties appear as their own ledgers under Sundry Creditors / Sundry Debtors with their balances. Ledgers can have an alias, bill-wise on/off, credit days and limit, PAN, default TDS section and a note.

Entering a payment Tally-style (F5):

1. Press **F5**. Choose single entry (cash/bank on top) or double entry (By/To); **Ctrl+H** switches.
2. Pick the ledger (the list shows group and balance as you type; Alt+C creates one).
3. For a party, choose bill-wise: **Agst Ref** (pick from the pending bills, including BuildCore purchase bills and client invoices), **New Ref**, **Advance** or **On Account**; choose the TDS section.
4. Set the **cost centre** for each line: project, BOQ item and machine; a line can be split.
5. Type the narration (**Alt+R** repeats the last). The amount in words shows in English and Nepali.

6. **Ctrl+A** to accept. A payment to a party against BuildCore bills goes through the normal BuildCore payment (allocation, TDS, payment-request rule). Everything else is a manual voucher, so the posting queue, maker-checker and period locks still apply.



Payment voucher, Tally style, with bill-wise and cost centres

PgUp / PgDn move to the previous / next voucher, **Alt+X** cancels with a reason, **Alt+P** prints, **Alt+Q** opens the Edit Log, **Esc** quits. Sales and Purchase stay on their BuildCore screens; stock ledgers are refused here because stock moves only through store documents.

Reports in Tally groups: Trial Balance (group tree, party split, opening / debit / credit / closing, drill-down), Profit & Loss (trading account to gross profit, then to net profit), Balance Sheet (horizontal, with Profit & Loss A/c) and Day Book with voucher types. They agree to the paisa with BuildCore's own reports.

Edit Log records every voucher created, posted, altered or cancelled and every ledger, party, group and voucher type change, with user, time, reason and the full record; compare any two versions. **Alteration** under *edit with log*: the old version is reversed on its own date and the new one posted under the same number. It is not allowed for vouchers from other screens (GRN, bill, DPR...), in a closed period or before the lock date, on a bank-reconciled line, or when a bill it made is already partly settled.

3.7.3 Accounts posting queue

Operational costs raised at site (DPR labour and machines, subcontract and hire bills and similar) wait here until accounts checks and posts them. Entries waiting are not in the trial balance yet; their cost shows separately in project figures as *waiting*.

1. Open the queue, filter by project and date.
2. Open an entry to see its source document and voucher lines.
3. **Post** (or post ticked), or **Return** with a note.


3.7.4 Payments & receipts

Payment requests

A request names the party, project, bill or order, amount, due date, proposed date, terms and its obligation: statutory, wages, safety-critical, contractual, operational or normal. It goes through **Verify documents › Verify accounts › Cash**

reviewed › Approve › Pay, each step recorded with the person and time.

- The amount can never be more than the bill's open balance less other open requests; this is checked again at approval and payment.
- The person who asked can never approve it. With strict separation on, one person can do only one step.
- A statutory, wage, safety-critical or contractual payment proposed after its due date needs a reason, and the approver must write a note.
- **Return for correction**, **Reject** (with reason) and **Cancel** are available.
- **Pay now** makes the payment (bank or cash account, mode, reference, TDS). **Link payment already made** connects an existing one. Once its bank line is cleared, the request shows *Reconciled*.



A payment request with its approval trail

Payment plan lists open requests and dues within the chosen days in order of obligation (statutory first, then wages, safety, contracts, operational, normal) against cash and bank less the reserve, with a running total and the shortfall. It is a proposal; nothing is paid from it.

Money settings: *Supplier, subcontractor and hire payments need an approved payment request*. When on, such a payment is refused unless paid from an approved request (receipts, wages, tax deposits and EMIs are not affected; subcontractors and small amounts can be exempted). *Switch*: on for new companies; off on updated companies until accounts turns it on. **Payment-control settings** set the reserve, the tax deposit day, strict separation and the right each step needs.

Duplicate guards: a payment with a cheque or transfer reference already used for the same party, or a supplier bill number already booked for that supplier, is refused with the earlier document's number. An accounts approver can tick *allow duplicate*; the override is logged.

Wages from the DPR

One **wage sheet** per project and month (Nepali month when the company runs by Nepali month):

1. Open *Payments & receipts › Wages*, choose project and month. The sheet lists by trade the head-days, hours, OT hours and wages from approved DPRs (own gangs), attendance by day, and the same total as credited to Wages Payable.
2. Enter deductions: advance recovered, tax and others. Wage advances are paid earlier to the Wage Advances account.
3. **Pay the sheet**: one voucher, Dr Wages Payable / Cr bank and deductions. A sheet is paid once.

Staff salaries

Every active staff member with a monthly rate. Deductions: social security tax 1% (to TDS Payable); with SSF enrolled, employee 11% and employer 20% (to SSF Payable). Cost goes to the person's project or to Salaries – Head Office. Run, check, then pay the run as a separate step.

Petty cash

1. Set up an **imprest** per site with a holder and a float; it gets its own account.
2. Record **slips**: date, amount, what for, BOQ item (or site overhead) and expense account. A slip cannot post until the bill or receipt is attached. It posts to the project's cost.
3. **Replenish** brings the imprest back to its float. Slips waiting to be replenished show in the cash forecast.

Papers rules

Payments & receipts › Papers rules: one switch per record type for *needs its paper before posting*: supplier bill, payment, GRN, IPC certification, and manual vouchers of 1,00,000 or more. Defaults are on for bills, payments and large vouchers in new companies, all off in updated companies. When a rule refuses, the screen opens **Attach the paper**: upload a scan or photo, or pick it from the library, then **Post again**. Bills, invoices, GRNs, POs and vouchers have a **Papers** panel showing their files and linked library documents.

3.7.5 Client invoices

IPC certification posts the client invoice. Other sales (F8) are entered here, with VAT, TDS and retention. Receipts (F6) settle them bill-wise.

3.7.6 Ageing: receivables, collections and payables


Receivables: five buckets shows per project what is owed to you:

1. Work done but not billed.
2. IPCs submitted and awaiting certification (with the part past the certification period).
3. Certified and not yet due.
4. Certified and overdue, aged 1–30, 31–60, 61–90 and over 90 days.
5. Retention held, with what can be claimed now and the release dates.

Buckets 3 and 4 are the open sales invoices and agree with the debtors account. Choose an *As of* date to see any day.

Collection actions turns the buckets into one list of next steps (complete measurements, prepare an IPC, submit it, obtain certification, follow up, escalate, request retention release), each with amount, target date, person responsible and last follow-up. Click a line to record what was done, the next follow-up date and any promised date and amount; promised receipts go straight into the cash forecast.

Payables register lists everything you owe by due date: supplier, subcontractor and hire bills (including those still in the queue), wages payable, VAT and TDS to deposit, and the next loan and equipment-finance instalments. **Request payment** on a line starts a payment request.



Receivables in five buckets

3.7.7 Books, statements and tax

- **Trial balance, Account ledger, Day book, Profit & loss, Balance sheet**, by company or by project. Gateway letters work like Tally (T, B, P, K, L).
- **Party statement**: one party's bills, payments and balance.
- **VAT books** and **TDS register**; **TDS rates** by section. Confirm rates and layouts with your tax adviser.
- **Budget vs actual** and **Project cost vs ledger**: the ledger cost beside the one project position, with the reconciliation (ledger cost − internal machine charges ± machine cost shared by hours + waiting + accrued = project cost).
- **Costs by way of working** and **Finance by segment**: cost and return by direct labour, subcontract, own and rented equipment, and by projects, trading and company. **Returns (ROA / ROE)** by segment.

3.7.8 Bank reconciliation and statement import

The **tick-off** screen clears book entries against the statement by hand. **Statement import** (tab):

1. Import the bank's statement as CSV or Excel. BuildCore finds the date, cheque/reference, withdrawal and deposit columns (or one signed amount).
2. Each line is matched to an uncleared book entry: same amount and same reference first, then same amount within 7 days, nearest first.
3. **Unmatch** or match by hand where needed.
4. **Confirm** clears the matched entries with the statement date. Lines not in the books (bank charges, interest) are listed to enter as vouchers.


3.7.9 Cash forecast & ratios

The 13-week cash forecast

Week 1 is the current week. The grid opens with today's cash and bank and shows week by week the money in and out line by line, the net flow, the closing balance, the reserve and restricted funds, what is available to spend, and a **prudent closing** (only confirmed and likely receipts against every payment). Click any line to see the bills, IPCs, requests or instalments behind it. Amounts show in lakh; untick for full amounts.

Line	Source	Confidence
Promised by the client	promised date and amount in a collection follow-up	confirmed
Certified bills falling due	open sales invoices	confirmed
Overdue receivables with no promise	assumed 30 days from today (changeable)	uncertain
IPCs awaiting certification	certification due date plus payment days	likely
Retention released	its release date	likely
Payment requests	their proposed date	confirmed or likely
Bills, wages, VAT and TDS	the payables register	confirmed
Purchase orders to be delivered	delivery date plus 30 days	likely
Loan and equipment instalments	the loan register	confirmed
Future work billed and its costs	each project's schedule and payment terms	estimate
Head-office overhead	overhead budget or last 12 months' average	estimate
Petty cash to replenish	slips waiting	confirmed
Entered by hand	your own items (loan drawdown, equity, land purchase…)	as you set

Restricted funds records money that cannot be spent between two dates (guarantee margin, escrow). **Scenarios**: client receipts 15, 30 or 45 days late; costs 10% over; or your own. **Save forecast** keeps today's forecast; **Forecast vs actual** later compares it week by week.



13-week cash forecast

Funding gap & financing

Shows the gap week by week on the prudent view, then the eight actions that close it, each with the amount from your records: collect certified receivables; measure and submit IPCs; resolve certification objections and variations; reduce excess stock and early buying; use equipment better; align buying and payment with contract terms; evaluate financing; review projects with negative cash or falling margins. Under **Financing options**, enter an overdraft, term loan, invoice discounting, supplier credit or equity; each is compared with *No financing*. BuildCore does not borrow, post or recommend.

Loan register

One register for every loan. Machine loans from Equipment finance show read-only with their ledger balance. A typed loan can be **linked to its machine**, so it is counted once in the forecast, command centre and funding gap; BuildCore suggests the link when the lender or instalment matches. A typed loan can also be given a ledger account; its ledger balance is shown beside the typed one and a check lists any difference.


3.7.10 Periods, fiscal years and month-end

- **Periods**: lock a month when it is done; nothing can then be dated inside it. Reopening is logged with a reason.
- **Fiscal years**: *Close year* freezes the balances and stock of the year, locks its periods and creates the next year (BuildCore warns about drafts first). Opening balances are the frozen closing balances; profit of earlier years shows as *Profit & loss brought forward*. *Tax summary* gives VAT, TDS and profit by year.
- **Accruals register**: month-end accruals per project, used by the project close.
- **Control settings**: close thresholds, cut-off day and rules.

3.7.11 Integrity checks and financial data checks

Accounts › Integrity checks confirms that the store equals the inventory accounts, GRN clearing equals goods not yet billed, creditors and debtors equal open invoices, and the balance sheet balances. The **Financial data checks** tab runs the read-only checks, including: every voucher balances; opening balances add to zero; debtors and creditors control

agree with open invoices for the company and each project; no supplier bill booked twice; stock = books with the queue explained; asset cost and accumulated depreciation registers = ledger; no machine depreciated twice in a month; no machine hours charged twice; every disposal has a voucher; hire bills not above approved hours; payments without a request; wages payable older than 45 days; petty cash balance; loan balances typed = ledger; records without their paper; goods received and not billed for more than 30 days. Each shows errors or warnings, where to correct it and the items behind it.



Financial data checks

3.8 Plant (crusher, batching)

Screen	Where	What it is for
Plant register	C	Crushers, batching plants and similar
Mix designs	C	What one unit of output consumes
Production runs	P	Raw material out, finished material in at its real cost (Alt+F10)
Plant performance	C	Output, running hours and cost per unit

Recording a production run: choose the plant and the mix design, enter the output quantity and hours. BuildCore issues the raw materials from stock and receives the finished material (aggregate, concrete) at its real cost.

3.9 Assets and Fixed assets (NFRS)

Screen	Where	What it is for
Asset register	C	Everything owned that is not equipment or stock: custodian, location, insurance, condition
Asset depreciation	C	Monthly depreciation of the asset register

Screen	Where	What it is for
Small assets (scaffolding, tools)	C/P	Pools of small assets hired to projects
Capital register	C	The NFRS fixed asset register; machine purchases; link to ledger
Depreciation run	C	Monthly depreciation; *Check: one depreciation*
Equipment costing	C	Allocation of machine cost by logbook hours
Maintenance plan	C	Planned maintenance of fixed assets
Leases (NFRS 16)	C	Right-of-use assets and lease liabilities
Impairment watch	C	Signs of impairment
Tax depreciation	C	Depreciation by tax rules
PPE note	C	The property, plant and equipment note for the accounts
Inventory analysis	C	Stock analysis for the statements

3.9.1 Buying a machine on a purchase bill

1. On a draft purchase bill line, tick **as a new machine** and give its code, name, category, life, depreciation method and residual value. The line's account becomes Plant & Machinery.
2. Post the bill. BuildCore creates the machine in Equipment (owned, value and date from the bill), its Fixed assets row, debits Plant & Machinery once with the machine on the line, and starts its Equipment finance ready for a down payment and loan.

Link to ledger (Capital register tab) shows each machine's register cost against the ledger lines that carry it; link a hand journal that booked a machine without naming it.

3.9.2 One depreciation per machine and month

Whichever screen posts a machine's month first, the other skips it, and both registers carry the same months. *Depreciation run › Check: one depreciation* lists months depreciated twice before this rule; accounts proposes which posting to keep and another accounts approver presses **Approve and post the correction** (one correcting journal; the original vouchers stay). **Bring history across** copies missing months between the registers without posting.

Bringing machines into Fixed assets copies their depreciation so far, method, life, residual and WDV rate from the equipment register. Disposals always post (the fixed asset row is created first if needed).


Monthly runs by Nepali month (*switch* on the Project position tab): equipment depreciation, fixed asset depreciation and allocation, internal hire, hire bills and small-asset hire then take a Nepali month, covering the same days as the month close. Runs already posted stay; running a month again posts nothing.

3.10 Resources & rates

Screen	Where	What it is for
Resource pool	C	Labour, material and equipment resources
Norms library	C	About 1,740 official norms: DoR 2075 roads and bridges, DUDBC buildings, Electrical and Sanitary 2079/80
Rate books	C	Market and district rates

Screen	Where	What it is for
Rate analysis	C	One item in full, with cartage, saved against a BOQ item
Item rates (all norms)	C	Every norm priced with the chosen book, overhead & profit and VAT
Machine hire rates (DoR)	C	Hourly hire rate by the DoR method

- **Norms library**: open a norm to see its labour, material and equipment lines. Norms marked *Check against book* should be compared with the printed page. Shipped norms are locked; **Copy to edit** makes a company version. Percentage lines (tools 3% of labour) use the code L, M, E, LM or LME.
- **Rate books**: *Market reference 2083/84 (Kathmandu)* and the rates printed in the Electrical & sanitary books. Make your own book for your district and copy or enter rates.
- **Item rates**: every norm priced with the book you choose, with overhead & profit (15%) and VAT (13%); flags for missing and estimated rates. Export to Excel.
- **Rate analysis**: one item with cartage leads, saved against a BOQ item. This feeds the control budget, earned value and the forecast.
- **Machine hire rates (DoR)**: ownership + operating + crew per hour by the DoR guideline method; 25 sample machines (enter today's prices first). *Put into rate book* prices the equipment resource; *Make rate card* costs your own machine.



Rate analysis

3.11 Equipment & machines

Owned and hired machines: the register, logsheets from the DPR, maintenance, repairs, hire bills and what each machine earns and costs.

Screen	Where	What it is for
Monthly logsheets	P	One sheet per machine and month, built from the DPR (Alt+F11)


Screen	Where	What it is for
Day-by-day log	P	One machine day at a time
Maintenance	P	Service plan by hours or days and what is due
Work orders	P	Breakdowns and services with repair records
Register	C	Owned and hired machines, operator, outputs, rates; hours & output summary
Rate cards	C	Ownership, fuel, operator, maintenance and overhead per hour
Repairs & history	C	Fleet maintenance and repair history
Hired equipment	C	Hire bills from approved hours
Rental deductions	C/P	Idle and breakdown hours deducted from hire
Equipment cost per hour	C/P	Cost per hour with EMI and down payment; Machine P&L
Own equipment recovery	C/P	What own machines recovered from projects
Equipment business	C/P	Each machine's month: hours, fuel, charged against cost, break-even
Depreciation & hire charges	C	Monthly depreciation and internal hire charges
Performance	C/P	Availability, utilisation, MTTR, MTBF, fuel and cost per hour

3.11.1 Register and the machine's hours & output

Register: every owned and hired machine with code, make, category, operator, outputs / attachments (Bucket, Hydraulic rock breaker…) with their units and norms per hour, rates and depreciation. The **operator** typed here fills the DPR machine lines.

Click a machine: the top of its form shows **Operating hours and output**, and *Open full summary* opens the machine passport on its **Hours & output** tab:

- Project (the machine's current project, any other it worked on, or all projects you may see).
- Totals: operating hours as per the entries, days worked, average hours a day, idle and breakdown hours, fuel. Draft logsheet hours and hours on DPRs not yet approved are shown apart.
- Output by attachment: hours, quantity, output per hour and the norm per hour.
- Month by month (Nepali or English months), with a Total row and Export CSV. Click a month to open its logsheet.




A machine's hours and output by month

3.11.2 Monthly logsheets

Logsheets are made from the DPR: each approved DPR machine line becomes a logsheet day.

1. *Equipment & machines › Monthly logsheets* (Alt+F11). The register lists each machine's sheet for the month with days, hours, idle, breakdown, fuel, hire and *DPR days waiting*.
2. Click a sheet. Each day shows its DPR number, output and quantity. Machine lines on DPRs not yet approved show in italics with their status, in a separate *Hours on DPRs not yet approved* figure; they join the totals when the DPR is approved.
3. Add the paper fields beside each day if you use them (fuel requisition, times, signatures).
4. **Submit**, and have someone else **approve**. An approved sheet does not take in new days; reopen it to take them.

Sheets per Nepali month. With dates in Nepali, an administrator (equipment approve) sees **Keep sheets per Nepali month**. After pressing it, the Month box and *Open a sheet* use Nepali months (Bhadra 2083 = 17 Aug – 16 Sep 2026) and draft English sheets move over; submitted and approved sheets are not touched. **Keep sheets per English month instead** moves drafts back.



Monthly logsheet with output per day

Split by output shows each day's hours by attachment from the DPR (Bucket, breaker...). Hours not split count at the machine's default attachment.

3.11.3 Maintenance, work orders and repairs

- **Maintenance**: the service plan by hours or days; what is due and overdue.
- **Work orders**: breakdowns and services. Breakdown hours on an approved DPR raise a work-order task. *Repair record* adds parts, labour, external cost, workshop, parts replaced and cause.
- **Repairs & history**: the fleet and each machine's full maintenance and repair history; earlier repairs can be entered here.
- **Performance**: availability, utilisation, MTTR, MTBF, fuel per hour and cost per hour.


3.11.4 Hired equipment and rental deductions

Hired equipment makes hire bills from **approved** logsheet hours only; unapproved hours are named on the bill line and not billed. **Rental deductions** take off idle and breakdown hours under the hire terms. The hire bill goes to the posting queue like other site costs.

3.11.5 Cost, recovery and the equipment business

- **Rate cards**: ownership, fuel, operator, maintenance and overhead per hour. DPR machine hours are charged to the project at the rate card.
- **Equipment cost per hour** includes EMI and down payment. Its **Machine P&L** tab shows per machine and month: owning cost, running cost, hours, cost per hour, recovered, and over or under recovered.
- **Own equipment recovery**: what each own machine recovered from projects.
- **Equipment business**: each machine's month: hours, utilisation, fuel against norm, charged against cost, idle cost and break-even, with flags.
- **Depreciation & hire charges**: the monthly depreciation and internal hire run. One depreciation per machine and month: if Fixed assets has posted a machine's month, this run skips it (*posted in Fixed assets*), and the other way round.

Equipment cost centre (*switch*, off by default): from a date accounts sets on the Project position tab, owned-machine costs post to cost centre *EQUIP – Own equipment* with the machine on every line, and the using project keeps only its charge. Each machine's cost is shared over projects by the hours they logged.



Machine P&L


3.12 Master data

Screen	Where	What it is for
Projects	C	Projects with code, client, contract value, dates, type; Project teams button
Materials	C	Materials with unit, category, kind, reorder level, standard rate
Vendors & clients	C	Suppliers, subcontractors and clients with PAN and terms
BOQ items	C/P	BOQ lines with short code column
Labour trades	C	Trades and rates
Staff	C/P	Staff with monthly rate, project and SSF
Daily check lists	C	Check lists used by inspections and the DPR
Extra fields	C	Your own fields on materials, machines, parties, projects, contracts, staff, BOQ items

One master list serves both workspaces. Most lists have **Paste from Excel**.

- **Projects**: creating a project makes its main store and in-transit store. With the one contract register on, the contract value and dates come from *Commercial › Contracts* and are refused here.
- **Materials**: use a category containing *Fuel* for diesel and *Spare* for spare parts, so fuel and repairs post to the right accounts.

- **Extra fields**: an administrator adds fields (text, number, date, choice, yes/no); fill them in the grid. Copilot reports can use them.



Projects

3.13 Administration

Screen	Where	What it is for
Users	C	People, job, where they work, sign-in status, reset codes, Check access
Jobs & permissions	C	Jobs, their menus and See / Enter / Approve rights
Project teams	C/P	Who is placed on each project; Copy team
Companies	C	Several companies, each with its own data
AI assistant settings	C	Switch the AI on or off, choose the provider
Team & devices	C	Who is online, from which computer; end a lost laptop's sign-in
Remote access	C	This computer's short code and connection details
Site packs	C	Make and load packs for sites without internet
Licence keys	C	Licence status, keys, master key, password reset keys
Settings	C	Company details, VAT %, tolerances, limits, hours per day

Screen	Where	What it is for
Backup & restore	C	Backups now, download, restore
Audit log	C	Every save, post, approval and cancellation

Users, Jobs & permissions and Project teams are explained in chapter 1.9, licence keys in 1.6, and forgotten passwords in 1.7.


Companies. Each company has its own data, users, fiscal years and backups. *Companies › New company* can copy the chart of accounts, materials, parties, machines, staff and users from the current company; opening balances start at zero. Switch company with **Alt+F3** or the company chip in the top bar.

Settings. Company name, address and PAN; VAT %; receipt and rate tolerances; PO approval and high-value limits; *Scheduled hours per day (equipment)* (default 10, used for idle and breakdown days); reset-code hours; and the company's other rules.

AI assistant settings. Off by default. Choose Claude (cloud; needs internet only while asking, and an API key) or a local AI on your own network (an OpenAI-compatible server). *Let the assistant look up figures* allows answers with live figures, read only and within each person's rights.

Team & devices shows who is signed in, from which computer, and can end a lost laptop's sign-in.

Audit log lists every save, post, approval, cancellation, team change and password reset with user and time.



Administration › Backup & restore

Part 4. Running BuildCore

4.1 Working from several places

One computer keeps the data; everyone else connects to it. Never run two copies “to be merged later” unless a site truly has no internet.

Everyone in one office. On the main computer choose *Team › Share this computer with the office network*, restart when asked, then *Team › Show address for other computers* (for example `http://192.168.1.20:8750`). On every other computer choose *Team › Connect to BuildCore on another computer* and type that address. A phone or tablet opens the same address in its browser.

Office, site and owner, each with internet. Join them with a private network (VPN) such as Tailscale: install it on the office computer, the site computers and the owner’s laptop or phone, signed in with the same account. Share the office computer as above and connect with its address that starts with `100.`. There is no syncing step because there is only one database. Do not open port 8750 on your router.

Many companies, projects and users. The server edition runs BuildCore on an always-on cloud machine with https and several engines side by side, so one long report does not make anyone wait. It was tested with 80 people at once. Your supplier installs it with the Server guide and moves your desktop company across with one command.

A site with no internet. The site runs its own copy with a short site code (*Administration › Remote access*) and the same project, material, BOQ, activity and machine codes as head office.

1. At site: *Site mode* or *Administration › Site packs*, pick the dates, tick what goes in the pack, **Make the pack file**. Send the `.bcpack` file by pen drive, e-mail or phone. Only finished records go.
2. At head office: *Administration › Site packs › Load a pack › Check the file › Load these records*. DPRs arrive as submitted; issues, receipts, returns, transfers, counts, bills and production runs arrive as drafts for head office to approve and post. Loading the same pack twice adds nothing.

4.2 Daily and weekly routine

Who	Every day	Every week
Site engineer / supervisor	DPR for each shift, with machine readings, labour, problems and photos	Close issues and RFIs; check My work
Storekeeper	Requisitions, issues, goods received with challan scans	Check reorder list and pending deliveries
QS	Accept DPR quantities	Measurements; prepare the IPC
Project manager	Approve DPRs; look at Needs attention	Approve requisitions and POs; review delays and notices
Accountant	Post the queue; enter bills (linked to goods); payments from approved requests	Bank statement import; collection actions; payment plan
Director / finance manager	Dashboard, This month, alerts	Financial command centre; funding gap

4.3 Monthly routine

1. Approve the month's DPRs and logsheets (*Equipment & machines › Monthly logsheets*).
2. Prepare and post hire bills for hired machines (*Hired equipment*), from approved hours.
3. Post depreciation and internal hire charges (*Depreciation & hire charges* or *Fixed assets › Depreciation run*; one per machine and month).
4. Prepare and pay the wage sheets and the salary run (*Accounts › Payments & receipts*); replenish petty cash.
5. Count each store and post the differences (*Store & inventory › Stock count*).
6. Clear the accounts posting queue to the month end.
7. Reconcile every bank (*Accounts › Bank reconciliation › Statement import*).
8. Work through *Match receipts, bills & payments*: goods not billed, no-VAT purchases, links waiting for approval.
9. Print the VAT books and the TDS register; deposit tax on time.
10. Run the project close for each coded project (*Commercial & billing › Project close*).
11. Work through Collection actions and the Payment plan; save the 13-week cash forecast so next month can be compared with what really happened.
12. Clear or assign every open financial alert.
13. Run *Accounts › Integrity checks* and the financial data checks, then lock the month (*Accounts › Periods*), and move the audit lock date if you use the Gateway.

4.4 Year end

1. Finish the last month's routine for Asar and lock it.
2. Run the year's last depreciation and the tax depreciation; print the PPE note.
3. *Accounts › Fiscal years › Close year*: BuildCore warns about drafts and unbalanced items, then freezes balances and stock, locks the periods and creates the next year with its opening balances.
4. An administrator can reopen a closed year if needed; the reopening is logged.

4.5 Backup and restore

- **Automatic**: a backup every day while BuildCore runs, in the backups folder; the last 30 are kept. Updates also back up before changing anything.
- **Manual**: *Administration › Backup & restore › Download a backup now*. Copy it to a USB drive or another computer at least once a week.
- **Restore** from the same screen; the current data is backed up first.
- To move BuildCore to another computer, install it there, activate it, then restore your latest backup.

4.6 Switches: features accounts turns on

Newer features that change figures or rules start **off** on a company updated from an older version, so nothing changes until accounts has looked. New companies start with them on. Every change is recorded with who made it.

Feature	Setting	Updated company	New company	Where to turn it on (right needed)
One project position	`pfp_on`	off	on	Commercial › CVR and forecast › Project position › Confirm and switch on (accounts approve)

Feature	Setting	Updated company	New company	Where to turn it on (right needed)
Monthly runs by Nepali month	`run_months`	English	Nepali	Project position tab › Switch to Nepali months
Equipment cost centre (EQUIP)	`eqcc_from`	off	off	Project position tab: set the date
Over-budget PO needs administrator	`po_budget_block`	off	off	Project position tab
Payments need an approved request	money settings	off	on	Accounts › Payments & receipts › Money settings
Papers before posting (per record type)	papers rules	off	bills, payments, large vouchers on	Accounts › Payments & receipts › Papers rules
One contract register	contract register	off	on	Commercial › Contracts & letters › One contract register
Match receipts, bills & payments	`mt_on`	off	on	Procurement › Purchase bills › Match settings (accounts approve)
Tally-style Gateway	`tl_on`	off, *reverse only*	on, *edit with log*	Accounts › Gateway › F11 Features
BOQ short codes and summary	`bx_on`	off	on	Commercial › BOQ control › Short codes (commercial approve)
Informative dashboard	`gl_on`	on	on	Display only; turning off restores the 2.47 dashboard
Past prices on PR / PO	`pr_price_fill`	on	on	Setting; 0 = old behaviour
Forecast profit only where costed	`fx_uncosted`	exclude	exclude	Setting; *include* = old figures
Job menus	`acc_job_menus`	on	on	Link under the Users list
Nepali-month logsheets	button	English	English	Equipment › Monthly logsheets (equipment approve)

Suggested order on an updated company: (1) enter bank and cash opening balances and contract values; (2) build control budgets from the rate analysis; (3) confirm the project position; (4) turn on the contract register; (5) after a month close, switch the runs to Nepali months; (6) turn on BOQ short codes; (7) turn on match receipts, bills & payments; (8) papers rules and the payment-request rule; (9) the Tally Gateway with group mapping.

4.7 Troubleshooting

What you see	What to do
***Windows protected your PC* when installing**	Click More info › Run anyway. The installer is not code-signed.

What you see	What to do
The browser will not download the .exe or .bat	Download the .zip of the same file, right-click › Extract All, run the file inside.
The update says BuildCore was not found	Type the folder that contains `BuildCore.exe`, or drag that folder onto the .bat.
The update says it was NOT applied	Nothing was changed. Send `BuildCore_update_log.txt` from the Desktop to support.
Activate BuildCore on this computer	Send the request code and enter the key (chapter 1.6).
Forgot your password	Forgot password? on the sign-in screen (chapter 1.7).
***Cannot reach the BuildCore server* on another computer**	The main computer must be on with BuildCore open; check the address and that Windows Firewall allows BuildCore.
A screen looks old after an update	Close BuildCore completely and open it again.
A blank or frozen window	View › Reset the window (keeps your data), or View › Open BuildCore in the web browser.
Your role cannot...	Ask an administrator to change your job's rights, or use *Show all my screens* if the module is only hidden.
Period locked	The date is in a locked month, a closed year or before the audit lock date; ask the accountant.
Papers needed	Attach the scan or link it from the Document library, then post again.
Payment needs an approved payment request	Pay from the approved request in Payment requests.
A posting stops with a message about a missing account role	Give the account its role in *Accounts › Chart of accounts*; BuildCore never skips a posting silently.
Forecast profit says *Not available*	Make the control budget or rate analysis for the project's BOQ items.
Work in hand says *BOQ ≠ contract*	Correct the project's contract value or its BOQ.

For support, send the update log, a photo of the message, and the error log from *Help › Engine and error logs*.

Appendix A. Automatic accounting entries

Event	Debit	Credit
Goods received	Inventory (landed cost incl. freight)	GRN clearing (+ freight clearing)
Purchase bill against GRN	GRN clearing + VAT input (+ rate difference)	Supplier (less retention / advance recovery)
Purchase bill linked to goods (match)	GRN clearing (real value) + VAT input as printed	Supplier
Purchase without VAT bill	GRN clearing	Supplier (then set against the advance paid)
Direct bill (freight, hire, subcontract)	Expense account + VAT input	Supplier
Machine bought on a bill	Plant & Machinery (machine on the line) + VAT input	Supplier
Payment	Supplier (or supplier advance)	Bank + TDS payable
Material issue	Material consumed / fuel / repairs (project, BOQ item, machine)	Inventory
Usable return	Inventory	The same cost account
Transfer to another project	Inventory (receiving project)	Inventory (sending project)
Transit shortage or count loss	Inventory loss	Inventory
Count gain	Inventory	Stock adjustment gain
Client invoice (IPC)	Debtors + TDS receivable + retention receivable + client advance	Contract revenue + VAT output
Client receipt	Bank	Debtors
DPR own labour	Labour cost (project, BOQ item, activity)	Wages payable
Wage sheet paid	Wages payable	Bank + wage advances recovered + deductions
Salary run	Labour cost or Salaries – Head Office (+ employer SSF)	Salaries payable + TDS payable + SSF payable
Petty cash slip	Site expense (project, BOQ item)	Imprest account
Petty cash replenishment	Imprest account	Bank or cash
DPR own machine hours	Equipment cost (project)	Equipment recovery (EQUIP cost centre when on)
Hired equipment bill	Equipment hire + VAT input	Supplier
Depreciation	Depreciation	Accumulated depreciation
Depreciation correction (approved)	Accumulated depreciation	Depreciation
Disposal	Bank / loss on disposal + accumulated depreciation	Plant & Machinery (+ gain)
Trading sale	Customer; trading cost of goods sold	Trading sales + VAT output; inventory
Reclassify cost (match)	The right cost account	The account first used

If an account role is missing, BuildCore stops with a clear message instead of skipping the posting. VAT and TDS rates and the VAT book layout should be confirmed with your tax adviser.

Appendix B. Keys at a glance

Area	Keys
Finding	Ctrl+M modules · Ctrl+K search · Alt+G go to · F1 help · Ctrl+/ key list
Context	F2 dates · F3 project · Alt+F3 company · F11 features · F12 configure
Vouchers	F4 contra · F5 payment · F6 receipt · F7 journal · F8 sales · F9 purchase · Ctrl+F8 credit note · Ctrl+F9 debit note
Site and store	F10 then D / I / M / V / E / Q / U / L · Alt+F4 PO · Alt+F5 requisition · Alt+F6 measurement · Alt+F7 transfer · Alt+F8 issue · Alt+F9 GRN · Ctrl+F7 count · Alt+F10 production run · Alt+F11 logsheets · Ctrl+F10 asset
Forms	Ctrl+A save · Esc close · Alt+C create master · Alt+2 duplicate · Alt+R last narration · Ctrl+H single/double entry · Alt+X cancel voucher · Alt+Q edit log
Lists	↑ ↓ move · Enter open · Space tick · Ctrl+Space tick all · Alt+F12 filter · Ctrl+F12 pick values · Alt+R hide · Alt+U / Alt+S show · Alt+P print · Alt+E export
Gateway	V vouchers · K day book · T trial balance · P profit & loss · B balance sheet · M group mapping · Y voucher types · L edit log
Other	Ctrl+N calculator · Ctrl+B hide side menu · Ctrl+Shift+L appearance

Appendix C. Jobs and their main rights

These are the built-in jobs. An administrator can change any of them in *Administration › Jobs & permissions*, and *Where* (head office or chosen projects) is set on each person.

Job	Main work	Approves
Administrator	Everything; users, settings, backups, licence	Everything; moves the audit lock date
Director	Sees all; company figures	Control budgets, project close lock, payment requests, alert overrides
Project manager	Project figures, DPR, programme, requisitions	DPRs, requisitions, POs, different-item bill links, no-VAT purchases
Site engineer	DPR, requisitions, issues, quality, site documents	—
Site supervisor	DPR, site documents	—
Quantity surveyor	Accepts DPR quantities; measurements, IPCs, variations, cost codes, BOQ	Measurements; signs the close
Storekeeper	Goods received, issues, returns, transfers, counts	—
Procurement officer	Purchase requests, quotations, POs, vendors	—
Equipment manager	Register, logsheets, maintenance, hire	Logsheets
Company accountant / Accountant	Vouchers, bills, payments, bank, VAT and TDS, posting queue	Vouchers made by others; posting queue; payment steps
Finance manager	Cash forecast, funding gap, alerts, payment control, reports	Payment requests; alert rules; shared reports
Project accountant	The project's posting queue, bills, payments and close	Payment steps as set; signs the close
Viewer	Sees what they are allowed to see	—

Company-wide money figures (cash, funding gap, financing, loans) need access to every project, so a person on chosen projects never sees them.

Appendix D. Glossary

Term	Meaning
BOQ	Bill of quantities: the contract items with quantity and rate
Short code	Location + item code for a BOQ line, such as HW-M25
DPR	Daily progress report from site
Reported / accepted quantity	What the site says it did / what the QS or engineer accepts
Work front	A part of the project worked by one team, such as a chainage stretch or a block
IPC	Interim payment certificate: the running bill to the client
GRN	Goods received note
Three-way match	Linking what arrived (GRN), what was billed (VAT bill) and what was paid
Posting queue	Site costs waiting for accounts to post them
CVR	Cost value reconciliation: value earned against cost, per item
Project position	The one set of cost, value and forecast figures used on every project screen
SPI / CPI	Schedule and cost performance index (above 1 is good)
Cost code	The BOQ item or indirect head a cost line belongs to
Close	The monthly sign-off of a project's value and cost
Prudent closing	The cash forecast counting only confirmed and likely receipts
Funding gap	The largest shortfall of available cash in the 13 weeks
Cost to complete	The cost still to be spent to finish the work, with open orders counted once
Payment request	A request to pay a bill, checked and approved step by step before payment
Wage sheet	One project's monthly wages from the approved DPRs
Imprest	A site's petty cash float with its holder
Gateway	The Tally-style start screen over the same books
Audit lock date	No entry on or before this date on any screen
Workspace	Company (whole company) or Project (one project at a time)
Job / Where	What a person does (menus and rights) / which projects they work on
Switch	A setting that turns a newer feature on; off on updated companies until accounts decides