# Accessing GPS information on your Android Phone

(Modified from Original Source at <a href="http://www.devx.com/wireless/Article/39239">http://www.devx.com/wireless/Article/39239</a>)

Using Eclipse, create a new Android project and name it GPS.java.

To use GPS functionality in your Android application, you'll need to add the ACCESS\_FINE\_LOCATION permission to the Android Manifest.xml file:

```
<?xml version="1.0" encoding="utf-8"?>
<manifest xmlns:android="http://schemas.android.com/apk/res/android"</pre>
     package="android.gps"
     android:versionCode="1"
      android:versionName="1.0">
      <uses-permission</pre>
        android:name="android.permission.ACCESS FINE LOCATION" />
    <application android:icon="@drawable/icon" android:label="@string/app name">
        <activity android:name=".androidgps"</pre>
                  android:label="@string/app name">
            <intent-filter>
                <action android:name="android.intent.action.MAIN" />
                <category android:name="android.intent.category.LAUNCHER" />
            </intent-filter>
        </activity>
    </application>
```

#### </manifest>

In Android, location-based services are provided by the LocationManager class located in the android.location package. Using the LocationManager class, your application can obtain periodic updates of the device's geographical locations as well as fire an intent when it enters the proximity of a certain location.

In the GPS.java file, first obtain a reference to the LocationManager class using the getSystemService() method. To be notified whenever there is a change in location, you need to register for a request for changes in locations so that your program can be notified periodically. This is done via the requestLocationUpdates(). This method takes in four parameters:

- provider: The name of the provider with which you register
- minTime: The minimum time interval for notifications, in milliseconds.
- minDistance: The minimum distance interval for notifications, in meters.
- listener: An object whose onLocationChanged() method will be called for each location update.

In this example, you're more interested in what happens when a location changes, so you'll write some <u>code</u>in the onLocationChanged()method.

Specifically, when a location changes you will display a small dialog on the screen showing the new <u>location information</u>: latitude and longitude. You show this dialog using the Toast class. The complete GPS.java now looks like:

```
package android.gps;
import android.app.Activity;
import android.os.Bundle;
```

```
import android.content.Context;
import android.location.Location;
import android.location.LocationListener;
import android.location.LocationManager;
import android.widget.Toast;
public class androidgps extends Activity {
  /** Called when the activity is first created. */
        private LocationManager lm;
  private LocationListener locationListener;
  /** Called when the activity is first created. */
  @Override
  public void onCreate(Bundle savedInstanceState) {
    super.onCreate(savedInstanceState);
    setContentView(R.layout.main);
    //---use the LocationManager class to obtain GPS locations---
    lm = (LocationManager)
       getSystemService(Context.LOCATION SERVICE);
    locationListener = new MyLocationListener();
    lm.requestLocationUpdates(
       LocationManager.GPS PROVIDER,
       0,
       locationListener);
  private class MyLocationListener implements LocationListener
     @Override
    public void onLocationChanged(Location loc) {
       if (loc != null) {
         Toast.makeText(getBaseContext(),
            "Location changed : Lat: " + loc.getLatitude() +
            "Lng: " + loc.getLongitude(),
           Toast.LENGTH SHORT).show();
    @Override
    public void onProviderDisabled(String provider) {
       // TODO Auto-generated method stub
    @Override
    public void onProviderEnabled(String provider) {
       // TODO Auto-generated method stub
    @Override
    public void onStatusChanged(String provider, int status,
       Bundle extras) {
       // TODO Auto-generated method stub
    }}}
```

### Using GPS with Google Maps

(Modified from original source at: http://www.devx.com/wireless/Article/39239/0/page/3 http://www.remwebdevelopment.com/dev/a35/Android-How-To-Set-Up-an-API-Key-for-Google-Maps.html)

Simply displaying the latitude and longitude when a location has changed is not very interesting. A much more interesting thing to do would be to couple the data together with the Google Maps application.

When you create your application choose the Google API (as the target device). If not listed, you need to update Eclipse using the avd update manager (under windows menu item in eclipse).

As you learnt in the previous Section, for Google Maps to work, you need to add the ACCESS FINE LOCATION permission into the Androidmanifest.xml file and then use the Google Maps library.

```
<?xml version="1.0" encoding="utf-8"?>
<manifest xmlns:android="http://schemas.android.com/apk/res/android"</pre>
    package="gps.google">
    <uses-permission</pre>
        android:name="android.permission.INTERNET" />
    <uses-permission</pre>
        android:name="android.permission.ACCESS FINE LOCATION" />
    <application android:icon="@drawable/icon"</pre>
        android:label="@string/app name">
        <uses-library android:name="com.google.android.maps" />
        <activity android:name=".GPS google" android:label="@string/app name">
            <intent-filter>
                <action android:name="android.intent.action.MAIN" />
                <category android:name="android.intent.category.LAUNCHER" />
            </intent-filter>
        </activity>
    </application>
</manifest>
In main.xml, replace the <TextView> element with the <MapView> element:
<?xml version="1.0" encoding="utf-8"?>
    android:orientation="vertical"
    android:layout width="fill parent"
    android:layout height="fill parent"
```

```
<LinearLayout xmlns:android="http://schemas.android.com/apk/res/android"</pre>
<com.google.android.maps.MapView</pre>
    android:id="@+id/mapview1"
    android:layout width="fill parent"
   android:layout height="fill parent"
   android:enabled="true"
    android:clickable="true"
    android:apiKey="apikey" />
</LinearLayout>
```

The google maps api uses an apikey ("apikey" value in main.xml file needs to be replaced with this). This is like a code signing key specific to the computer you are developing on. The steps to generate the apikey are:

- Locate the debug.keystore file on your computer. On windows XP this is located in:
- C:\Documents and Settings\(your account name)\.android
- Copy the debug keystore file to the android tools folder in the location for your SDK on the machine.
- From the tools folder run the command:

keytool -list -alias androiddebugkey -storepass android -keypass android -keystore debug.keystore

- Once you hit the enter key, you'll see something like this (the actual MD5 that we're interested in is the last line):

```
androiddebugkey, Mar 10, 2009, PrivateKeyEntry, Certificate fingerprint (MD5): D1:16:4A:BD:73:73:A4:56:9D:CD:9A:44:A2:6C:11:AC
```

- Now open your browser and go to the following url... <a href="http://code.google.com/intl/ja/android/maps-api-signup.html">http://code.google.com/intl/ja/android/maps-api-signup.html</a>
- Accept the agreement and paste the md5 that the key tool returned to you, in my case it was something like...

```
D1:16:4A:BD:73:73:A4:56:9D:CD:9A:44:A2:6C:11:AC
```

Then press "Generate API Key" and you'll be redirected to a page that has your api key.

Now that you have the api key, you can use it in the main.xml layout file of your MapTest application. Here's what mine looks like:

```
<?xml version="1.0" encoding="utf-8"?>
<LinearLayout xmlns:android="http://schemas.android.com/apk/res/android"
    android:orientation="vertical"
    android:layout_width="fill_parent"
    android:layout_height="fill_parent"
    >

<com.google.android.maps.MapView
    android:id="@+id/mapview1"
    android:layout_width="fill_parent"
    android:layout_height="fill_parent"
    android:enabled="true"
    android:clickable="true"
    android:apiKey="0d7RxErORpPEjtZxhh82FFBsvkaRAXuXk9IAnzw" />

</LinearLayout>
```

Finally, modify the . java file in your project to incorporate Google Maps.

```
package gps.google;
import com.google.android.maps.GeoPoint;
import com.google.android.maps.MapActivity;
import com.google.android.maps.MapController;
import com.google.android.maps.MapView;
```

```
import android.content.Context;
import android.location.Location;
import android.location.LocationListener;
import android.location.LocationManager;
import android.os.Bundle;
import android.widget.Toast;
public class GPS google extends MapActivity
    private LocationManager lm;
    private LocationListener locationListener;
    private MapView mapView;
    private MapController mc;
    /** Called when the activity is first created. */
    @Override
    public void onCreate(Bundle savedInstanceState) {
        super.onCreate(savedInstanceState);
        setContentView(R.layout.main);
        //---use the LocationManager class to obtain GPS locations---
        lm = (LocationManager)
            getSystemService(Context.LOCATION SERVICE);
        locationListener = new MyLocationListener();
        lm.requestLocationUpdates(
            LocationManager. GPS PROVIDER,
            0,
            0,
            locationListener);
        mapView = (MapView) findViewById(R.id.mapview1);
        mc = mapView.getController();
    }
    @Override
    protected boolean isRouteDisplayed() {
        // TODO Auto-generated method stub
        return false;
    private class MyLocationListener implements LocationListener
        @Override
        public void onLocationChanged(Location loc) {
            if (loc != null) {
                Toast.makeText(getBaseContext(),
                    "Location changed : Lat: " + loc.getLatitude() +
                    " Lng: " + loc.getLongitude(),
                    Toast.LENGTH SHORT).show();
                GeoPoint p = new GeoPoint(
                        (int) (loc.getLatitude() * 1E6),
                        (int) (loc.getLongitude() * 1E6));
                mc.animateTo(p);
```

```
mc.setZoom(16);
    mapView.invalidate();
}

@Override
public void onProviderDisabled(String provider) {
    // TODO Auto-generated method stub
}

@Override
public void onProviderEnabled(String provider) {
    // TODO Auto-generated method stub
}

@Override
public void onStatusChanged(String provider, int status,
    Bundle extras) {
    // TODO Auto-generated method stub
}
```

In the above, when a location changes, the latitude and longitude is sent to the Google Maps application, which then displays the map of the current location

# Accessing Accelerometer information on your Android Phone

(Modified from original source at: <a href="http://blog.androgames.net/85/android-accelerometer-tutorial/">http://blog.androgames.net/85/android-accelerometer-tutorial/</a> <a href="http://mobilestrategist.blogspot.com/2010/01/android-accelerometer-and-orientation.html">http://mobilestrategist.blogspot.com/2010/01/android-accelerometer-and-orientation.html</a>)

An instance of the <u>SensorManager</u> is required in order to retrieve informations about the supported sensors. No permission is required to access the sensor service. It is then possible to retrieve the list of available sensors of a certain type. For an accelerometer sensor, the type to use is given by the Sensor.TYPE\_ACCELEROMETER constant. If at least one <u>Sensor</u> exists, it is possible to register a <u>SensorEventListener</u> for a <u>Sensor</u> of the list. It is possible to specify the delivering rate for sensor events. Specified rate must be one of:

```
SensorManager.SENSOR_DELAY_FASTEST: as fast as possible SensorManager.SENSOR_DELAY_GAME: rate suitable for game SensorManager.SENSOR_DELAY_NORMAL: normal rate SensorManager.SENSOR_DELAY_UI: rate suitable for UI Thread
```

You need to first specify all the variables in the main.xml file which form the GUI of your accelerometer application:

```
<?xml version="1.0" encoding="utf-8"?>
<TableLayout xmlns:android="http://schemas.android.com/apk/res/android"
    android:layout width="fill parent"</pre>
```

```
android:layout height="fill parent"
android:stretchColumns="1">
<TableRow>
    <TextView
        android:id="@+id/accelerometer label"
        android:layout column="1"
        android:text="Accelerometer"
        android:textSize="9pt"
        android:padding="3dip" />
</TableRow>
<TableRow>
    <TextView
        android:id="@+id/accel x label"
        android:layout column="1"
        android:text="X:"
        android:textSize="8pt"
        android:padding="3dip" />
    <TextView
        android:id="@+id/accel x value"
        android:gravity="right"
        android:textSize="8pt"
        android:padding="3dip" />
</TableRow>
<TableRow>
    <TextView
        android:id="@+id/accel y label"
        android:layout column="1"
        android:text="Y:"
        android:textSize="8pt"
        android:padding="3dip" />
    <TextView
        android:id="@+id/accel_y_value"
        android:gravity="right"
        android:textSize="8pt"
        android:padding="3dip" />
</TableRow>
<TableRow>
    <TextView
        android:id="@+id/accel z label"
        android:layout column="1"
        android:text="\overline{z}:"
        android:textSize="8pt"
        android:padding="3dip" />
    <TextView
        android:id="@+id/accel_z_value"
        android:gravity="right"
        android:textSize="8pt"
        android:padding="3dip" />
</TableRow>
<View
    android:layout height="2dip"
    android:background="#FF909090" />
```

```
<TextView
            android:id="@+id/orientation label"
            android:layout column="1"
            android:text="Orientation"
            android:textSize="9pt"
            android:padding="3dip" />
    </TableRow>
    <TableRow>
        <TextView
            android:id="@+id/orient x label"
            android:layout column="1"
            android:text="X:"
            android:textSize="8pt"
            android:padding="3dip" />
        <TextView
            android:id="@+id/orient x value"
            android:gravity="right"
            android:textSize="8pt"
            android:padding="3dip" />
    </TableRow>
    <TableRow>
        <TextView
            android:id="@+id/orient y label"
            android:layout column="1"
            android:text="Y:"
            android:textSize="8pt"
            android:padding="3dip" />
        <TextView
            android:id="@+id/orient y value"
            android:gravity="right"
            android:textSize="8pt"
            android:padding="3dip" />
    </TableRow>
    <TableRow>
        <TextView
            android:id="@+id/orient z label"
            android:layout column="1"
            android:text="Z:"
            android:textSize="8pt"
            android:padding="3dip" />
        <TextView
            android:id="@+id/orient z value"
            android:gravity="right"
            android:textSize="8pt"
            android:padding="3dip" />
    </TableRow>
</TableLayout>
```

In the case of a <u>SensorEvent</u> triggered by a <u>Sensor</u> of type Sensor. TYPE\_ACCELEROMETER, the event's values represents the acceleration of the phone given by a vector in a cartesian coordinate system. Landing on a table, the values returned by the SensorEvent for the phone should be:

- 1. 0 m/s2 along x axis
- 2. 0 m/s2 along y axis

# 3. 9,80665 m/s2 along z axis

From an event to another, the coordinates of the acceleration vector are stored to detect sudden acceleration changes and to trigger a shake event when the threshold is reached. Others events could be implemented such as the detection of up and down gestures, circular gestures and lot more.

As usual, it is preferable to register listeners in the onResume() method of the <u>Activity</u> and removed in the onFinish() method of the <u>Activity</u>.

Then add the following code to your activity class before compiling on your android device (note that accelerometer code will only work for a device and not the emulator).

```
package android.accelerometer;
import android.app.Activity;
import android.hardware.Sensor;
import android.hardware.SensorEvent;
import android.hardware.SensorEventListener;
import android.hardware.SensorManager;
import android.os.Bundle;
import android.widget.TextView;
public class accelerometer extends Activity implements SensorEventListener {
// Accelerometer X, Y, and Z values
private TextView accelXValue;
private TextView accelYValue;
private TextView accelZValue;
// Orientation X, Y, and Z values
private TextView orientXValue;
private TextView orientYValue;
private TextView orientZValue;
private SensorManager sensorManager = null;
  /** Called when the activity is first created. */
  @Override
  public void onCreate(Bundle savedInstanceState) {
    super.onCreate(savedInstanceState);
    // Get a reference to a SensorManager
    sensorManager = (SensorManager) getSystemService(SENSOR SERVICE);
    setContentView(R.layout.main);
    // Capture accelerometer related view elements
    accelXValue = (TextView) findViewById(R.id.accel x value);
    accelYValue = (TextView) findViewById(R.id.accel y value);
    accelZValue = (TextView) findViewById(R.id.accel z value);
    // Capture orientation related view elements
    orientXValue = (TextView) findViewById(R.id.orient x value);
    orientYValue = (TextView) findViewById(R.id.orient y value);
    orientZValue = (TextView) findViewById(R.id.orient z value);
    // Initialize accelerometer related view elements
```

```
accelXValue.setText("0.00");
    accelYValue.setText("0.00");
    accelZValue.setText("0.00");
    // Initialize orientation related view elements
    orientXValue.setText("0.00");
    orientYValue.setText("0.00");
    orientZValue.setText("0.00");
  // This method will update the UI on new sensor events
  public void onSensorChanged(SensorEvent sensorEvent) {
  synchronized (this) {
   if (sensorEvent.sensor.getType() == Sensor.TYPE ACCELEROMETER) {
    accelXValue.setText(Float.toString(sensorEvent.values[0]));
    accelYValue.setText(Float.toString(sensorEvent.values[1]));
    accelZValue.setText(Float.toString(sensorEvent.values[2]));
   if (sensorEvent.sensor.getType() == Sensor.TYPE ORIENTATION) {
    orientXValue.setText(Float.toString(sensorEvent.values[0]));
    orientYValue.setText(Float.toString(sensorEvent.values[1]));
    orientZValue.setText(Float.toString(sensorEvent.values[2]));
  // I've chosen to not implement this method
 public void onAccuracyChanged(Sensor arg0, int arg1) {
 // TODO Auto-generated method stub
  @Override
  protected void onResume() {
  super.onResume();
  // Register this class as a listener for the accelerometer sensor
  sensorManager.registerListener(this, sensorManager.getDefaultSensor(Sensor.TYPE ACCELEROMETER),
SensorManager.SENSOR DELAY NORMAL);
  // ... and the orientation sensor
  sensorManager.registerListener(this, sensorManager.getDefaultSensor(Sensor.TYPE ORIENTATION),
SensorManager.SENSOR DELAY NORMAL);
  @Override
  protected void onStop() {
  // Unregister the listener
  sensorManager.unregisterListener(this);
  super.onStop();
```