# CS232 Exam 1 February 25, 2004

Name:	

- This exam has 5 pages, including this cover.
- There are three questions, worth a total of 100 points.
- The last page is a summary of the MIPS instruction set, which you may remove for your convenience.
- No other written references or calculators are allowed.
- Write clearly and show your work. State any assumptions you make.
- You have 50 minutes. Budget your time, and good luck!

Question	Maximum	Your Score	
1	40		
2	45		
3	15		
Total	100		

#### **Question 1: Understanding MIPS programs (40 points)**

nvidia:	li	\$t0,	0	
	li	\$t1,	0	
	li	\$t2,	0x3fffffff	
ibm:	bge	\$t0,	\$a1,	sun
	mul	\$t3,	\$t0,	4
	add	\$t3,	\$a0,	\$t3
	lw	\$t3,	0(\$t3)	
	ble	\$t3,	\$t1,	hp
	move	\$t1,	\$t3	
hp:	bge	\$t3,	\$t2,	intel
	move	\$t2,	\$t3	
intel:	addi	\$t0,	\$t0,	1
	j	ibm		
sun:	SW	\$t1,	0(\$a2)	
	SW	\$t2,	0(\$a3)	
	jr	\$ra		

#### Part (a)

Translate the function nvidia above into a high-level language like C or Java. Your function header should list the types of any arguments and return values. Also, your code should be as concise as possible, without any gotos or pointer arithmetic. We will not deduct points for syntax errors unless they are significant enough to alter the meaning of your code. (30 points)

*The key things to realize are the following:* 

- \$a1 is compared to \$t0, suggesting it's an integer.
- \$t0 is then used to calculate the offset of \$a0, which suggests a0 is an array
- \$t3 is loaded from \$a0, and is compared to \$t2, which suggests it's an integer
- \$t1 and \$t2 are stored to addresses of \$a2 and \$a3; since \$a2 and \$a3 are used directly as addresses, they must be pointers.
- The function does not put anything into \$v0, thus should be **void**.

#### Part (b)

Describe briefly, in English, what this function does. (10 points)

The function traverses an array of length \$a1 finding the maximum and minimum elements and returning them through two pointers.

### **Question 2: Write a recursive MIPS function (45 points)**

In class, we demonstrated a bit\_count function which counted the number of set bits (e.g., 1's) in the two's complement representation of a 32-bit integer. Here is a recursive implementation of the same function that takes 1 argument (the 32-bit integer) and has one return value (the number of set bits).

```
int
recursive_bit_count(int input_word) {
  if (input_word == 0)
    return 0;
  int lowest_bit = input_word & 1;
  return lowest_bit + recursive_bit_count(input_word >> 1);
}
```

Translate recursive\_bit\_count into a **recursive** MIPS assembly language function; iterative versions (*i.e.*, those with loops) will not receive full credit. You will not be graded on the efficiency of your code, but you must follow all MIPS conventions. Comment your code!!!

```
recursive bit count:
                  $a0, $0, done # if (input == 0)
         beq
                  $sp, $sp, 8
                                    #save regs
         sub
                  $t0, $a0, 1
                                     # else and t0 = input&&1
         and
                  $t0, 0($sp)
         SW
                  $ra, 4($sp)
         SW
                  $a0, $a0, 1
                                     \# a0 = a0 >> 1
         srl
                  recursive bit count
                                             # the recursive call
         jal
         lw
                  $t0, 0($sp) # restore caller saved reg
                  $v0, $v0, $t0  # compute the return val
         add
         lw
                  $ra, 4($sp)
                                    # load and restore sp
                  $sp, $sp, 8
         add
         jr
                  $ra
done:
         li
                  $v0, 0
                                    # base case
         jr
                  $ra
```

#### **Question 3: Concepts (15 points)**

Write a short answer to the following questions. For full credit, answers should not be longer than **two** sentences.

Part a) What is abstraction? How does it relate to instruction set architectures (ISAs)? (5 points)

Abstraction separates interface from implementation.

ISAs are an example of abstraction because they describe the interface to hardware, without details of the implementation. This idea enables binary compatibility across generations of hardware.

**Part b)** Explain how a machine knows whether to interpret a group of bits as an integer, a floating point number, or an instruction. (5 points)

As the bits in memory are not tagged with any type information the manner that bits are interpreted is determined by the instruction with which they are accessed. Bits are interpreted as integers when loaded with an integer load (e.g., lw), as a floating point number if loaded with a a floating point load (e.g., l.s) and as instruction if jumped to using a control flow instruction (e.g., j or bne).

Part c) Order the following (single precision) floating point numbers in increasing value from 1 to 4, where 1 is the smallest number (*i.e.*, the most negative) and 4 is the largest number (*i.e.*, the most positive). (5 points)

- - s e f

$$(1 - 2s) * (1 + f) * 2^{e-bias}$$

### **MIPS** instructions

These are some of the most common MIPS instructions and pseudo-instructions, and should be all you need. However, you are free to use *any* valid MIPS instructions or pseudo-instruction in your programs.

Category	Example Instruction		Meaning	
Arithmetic	add	\$t0, \$t1, \$t2	\$t0 = \$t1 + \$t2	
	sub	\$t0, \$t1, \$t2	\$t0 = \$t1 - \$t2	
	addi	\$t0, \$t1, 100	\$t0 = \$t1 + 100	
	mul	\$t0, \$t1, \$t2	$$t0 = $t1 \times $t2$	
	div	\$t0, \$t1, \$t2	\$t0 = \$t1 / \$t2	
Logical	and	\$t0, \$t1, \$t2	\$t0 = \$t1 & \$t2 (Logical AND)	
	or	\$t0, \$t1, \$t2	\$t0 = \$t1   \$t2 (Logical OR)	
	sll	\$t0, \$t1, \$t2	\$t0 = \$t1 << \$t2 (Shift Left Logical)	
	srl	\$t0, \$t1, \$t2	\$t0 = \$t1 >> \$t2 (Shift Right Logical)	
Register Setting	move	\$t0, \$t1	\$t0 = \$t1	
	li	\$t0, 100	\$t0 = 100	
Data Transfer	lw	\$t0, 100(\$t1)	\$t0 = Mem[100 + \$t1] 4 bytes	
	lb	\$t0, 100(\$t1)	\$t0 = Mem[100 + \$t1] 1 byte	
	sw	\$t0, 100(\$t1)	Mem[100 + \$t1] = \$t0 4 bytes	
	sb	\$t0, 100(\$t1)	Mem[100 + \$t1] = \$t0 1 byte	
Branch	beq	\$t0, \$t1, Label	if $(\$t0 = \$t1)$ go to Label	
	bne	\$t0, \$t1, Label	if $(\$t0 \neq \$t1)$ go to Label	
	bge	\$t0, \$t1, Label	if $(\$t0 \geq \$t1)$ go to Label	
	bgt	\$t0, \$t1, Label	if $(\$t0 > \$t1)$ go to Label	
	ble	\$t0, \$t1, Label	if $(\$t0 \leq \$t1)$ go to Label	
	blt	\$t0, \$t1, Label	if $(\$t0 \leq \$t1)$ go to Label	
Set	slt	\$t0, \$t1, \$t2	if (\$t1 < \$t2) then \$t0 = 1 else \$t0 = 0	
	slti	\$t0, \$t1, 100	if (\$t1 < 100) then \$t0 = 1 else \$t0 = 0	
Jump	j	Label	go to Label	
	jr	\$ra	go to address in \$ra	
	jal	Label	\$ra = PC + 4; go to Label	

The second source operand of the arithmetic, logical, and branch instructions may be a constant.

## **Register Conventions**

The *caller* is responsible for saving any of the following registers that it needs, before invoking a function.

\$t0-\$t9 \$a0-\$a3 \$v0-\$v1

The *callee* is responsible for saving and restoring any of the following registers that it uses.

\$s0-\$s7 \$ra

## **Pointers in C:**

Declaration: either char \*char ptr -or- char char array[] for char c

Dereference:  $c = c\_array[i]$  -or-  $c = c\_pointer$ 

Take address of:  $c_pointer = &c$