Office Info Controller

User Manual: Login Page and Dashboard

This manual explains the website screen by screen, in the order you meet them. Each section has the explanation first and the real screenshot of that screen under it.

Section	What it covers	Page
	PART 1 - THE LOGIN PAGE	
1	The top bar: logo, security labels and shortcut buttons	2
2	Choosing your role (CEO, VP, HR, HOD, Team Lead, Employee)	3
3	Signing in: company, email and password	4
4	Two-factor authentication (6-digit code)	5
5	Forgot Password: resetting your password	6
6	Create New Account: registering in the hierarchy	7
7	Platform details below the login card	8
8	Quick reference and common problems for the login page	9
	PART 2 - THE DASHBOARD (AFTER YOU SIGN IN)	
9	The top bar after you sign in	10
10	Dashboard home: banner and the four tabs	11
11	Author control panel: counters and the file inventory	12
12	Upload and send a protected file	14
13	The audit ledger	16
14	Recipient Inbox and Directives (what recipients see)	17
15	Quick reference for the dashboard	18
	PART 3 - AI SCANNER, SOC MONITORING AND PROTOCOL DETAILS	
16	Recipient Inbox at full size and the way into the AI Scanner	19
17	AI Compliance Scanner tab: presets, draft and scorecard	20
18	Running a scan: the passed result and the release button	21
19	Live SOC Monitoring tab: counters, charts and leak defense	22
20	Live viewing sessions and the SIEM telemetry stream	23
21	The top bar when you are signed in as a Team Lead	25
22	Inspect Protocol pop-ups: watermarking and encryption	26
23	Quick reference and common problems for Part 3	27

Still to come. The sandboxed file viewer and the Emergency Kill-Switch.

PART 1 - THE LOGIN PAGE

1. The top bar

The strip across the top of every page. It identifies the product and shows two security labels and four controls.

How to find it

Open the website. The bar is always at the very top and stays there while you move around.

What each item is

Item	What it shows or does
Logo and name	The Office Info Controller logo with a green status dot, the name, version badge **V3.2** and the line "Zero-Leak Corporate Governance".
Zero-Leak Shield: AES-256-GCM	A security label stating that files are encrypted with AES-256-GCM.
FIPS 140-3 HSM: Level 3	A second security label shown in the header. It is a display label of the demo.
Speaker icon and sun icon	Two small round buttons at the right of the labels. They look like a sound toggle and a light/dark theme toggle.
PDF Manual (green button)	A shortcut to the user manual.
Fast Demo Login (blue button)	A one-click shortcut for signing in with a demo account, so you do not have to type credentials during a demonstration.




Figure 1. The top bar of the Office Info Controller website.

Login page at a glance

From top to bottom the page is arranged like this:

Area	Where	Section
Top bar	Very top of the page	1
Role selector and "Signing in as" bar	First thing inside the login card	2
Company, email, password, Forgot Password link	Middle of the login card	3 and 5
Create New Account	Below the sign-in button	6
Platform detail cards and flow explanation	Scroll down below the card	7

2. Choosing your role

The first decision on the login page. Your role decides which privileges and which dashboard you get after signing in.

How to access it

It is at the top of the login card, under the heading **SELECT AUTHORIZED CORPORATE ROLE**.

How to use it

- Click one of the six role buttons: **CEO, VP, HR, HOD, Team Lead, Employee**. The selected button turns bright blue with a glow.
- The bar underneath changes at once to "**Signing in as** {role}" with a green dot, and shows the hierarchy level on the right (for example "Tier 1 (Root Authority)" for the CEO, "Tier 3 (Human Resources)" for HR).
- The label in the top-right corner changes too, for example **CEO Privilege Context** or **HR Privilege Context**.
- Click another button at any time to switch again. You can switch as often as you like before signing in.

The six roles

Role button	Group shown under the name	Typical use
CEO	Executive	Top of the hierarchy; sends directives to everyone
VP	Executive	Senior leadership below the CEO
HR	Management	People and policy communication
HOD	Management	Head of a department
Team Lead	Management	Manages a team and delegates files to team members
Employee	Production	Receives files and submits drafts upward



Figure 2. CEO selected: the "Signing in as CEO" bar, "Hierarchy Level: Tier 1 (Root Authority)" and the "CEO Privilege Context" label.



Figure 3. HR selected: the bar now reads "Signing in as HR" with "Tier 3 (Human Resources)" and "HR Privilege Context".

Tip: choose the role that matches your account. If your account belongs to a different role, the server will tell you which role to select instead.

3. Signing in

Enter your company details and password under the role selector.

How to access it

It is the middle part of the login card, under the heading **Zero-Trust Corporate Gateway** (subtitle: "Sign in with enterprise credentials & 2FA").

The fields

Field	What to enter
Company Name	Your company, for example **Acme Global Corp**.
Official Corporate Email	Your registered company email, for example **ceo.acme@gmail.com**.
Password	Your password. It carries a green **AES-256 secured** tag. Click the **eye icon** at the right end of the box to show or hide what you typed.
Forgot Password?	Blue link above the right end of the password box. Opens the reset window (Section 5).

Steps

- Click your role (Section 2).
- Check the company name, type your email and password.
- Click the wide blue sign-in button under the password box.
- The Two-Factor Authentication window opens (Section 4).




Figure 4. The sign-in form: Company Name, Official Corporate Email, and the Password box with the AES-256 secured tag, the Forgot Password? link and the show/hide eye icon.

Demo tip: in a demonstration the company name and email can be pre-filled for you. Use the **Fast Demo Login** button in the top bar for a quick start.

4. Two-factor authentication (2FA)

A second check after your password, to confirm it is really you.

How to access it

It opens automatically in the middle of the screen after you click the sign-in button with correct details.

What you see

- Title **Two-Factor Authentication**: "Enter the 6-digit code dispatched to your identity".
- A **Demo Simulation Hint** box showing **Code: 123456 (Click to Fill)**. In this demonstration the code is always 123456. Clicking the box fills it in for you.
- A large box for the six digits. Typed digits appear as dots.
- A blue button **Verify OTP & Open Dashboard**.
- An **X** button at the top-right corner to close the window.

Steps

- Click the hint box (or type **123456**).
- Click **Verify OTP & Open Dashboard**.
- A correct code opens the dashboard for your role. A wrong code shows an error and lets you try again.
- To go back and change your details, click the **X**.




Figure 5. The Two-Factor Authentication window with the demo hint (Code: 123456), the six-digit entry box, the verify button and the X close button.

In a real company deployment the code would be sent to your phone or email. The fixed code 123456 exists only so that the demonstration works without any outside service.

5. Forgot Password

Set a new password if you cannot remember the current one.

How to access it

On the login card, click the blue **Forgot Password?** link above the right end of the password box. A window titled **Reset Account Password** ("Recovery code protocol") opens.

The fields

Field	What to enter
Corporate Email	The email of your account, in the form name@company.com.
Reset Security Code (Demo: 999999)	The recovery code. In this demonstration the code is **999999**.
New AES Password	The new password you want to use. Dots hide what you type.

Steps

- Click **Forgot Password?**.
- Type your corporate email.
- Enter the recovery code (999999 in the demo).
- Type your new password.
- Click **Confirm Password Reset**. Close the window with the **X** in the top-right corner, then sign in with the new password.




Figure 6. The Reset Account Password window: Corporate Email, Reset Security Code (Demo: 999999), New AES Password and the Confirm Password Reset button.

Choose a password of at least 8 characters, mixing letters, numbers and symbols.

6. Create New Account

Register yourself in the company hierarchy. Every account is attached to a manager.

How to access it

On the login page click **Create New Account**, below the sign-in button. The card changes to **Register Enterprise Account & Hierarchy** ("Create corporate credentials bound to your department manager").

The fields

Field	What to enter
Official Corporate Email	Your company email, for example new.employee@acme.com.
Assigned Role	Pick your role from the list (the example shows **Employee**).
Reports to (Hierarchy)	Pick the manager you report to. The list shows name, role and email, for example "Sarah Jenkins (CEO) - ceo.acme@gmail.com". This places you under that person in the hierarchy tree.
New Password	At least 8 characters (the hint says "Minimum 8 characters").
Password Strength	Four bars and a word that rate the password as you type.
Re-enter Password	Type the same password again to confirm it.

Steps

- Fill in the email, role and manager.
- Choose a password and watch the strength bars.
- Re-enter the password.
- Click the green **Register Account & Join Hierarchy** button, then sign in with the new account.




Figure 7. The registration form: email, Assigned Role, Reports to (Hierarchy), New Password with the strength meter, Re-enter Password and the green Register button.

Why the manager matters: files can only be sent to people inside your own hierarchy, so your manager choice decides who you can send to and who can send to you.

7. Platform details below the login card

Four protection cards and a short explanation of how files move through the company.

How to access it

Scroll down below the login card on the same page. No sign-in is needed to read it.

The four cards

Card	What it explains
AES-256 Envelope Encryption	Every file gets its own data key, which is itself protected by a master key, so keys are kept apart from the stored files.
Ephemeral Time-Bound Viewing	Files are viewed in temporary memory with precise timers, so access ends when the time ends.
AI Visual & Semantic Verification	Automated checks of the logo, brand colour codes and the accuracy of the numbers in a document.
Forensic Leak Watermarking	Layers over the document that show the viewer's ID, IP address and a timestamp, so any leak can be traced.

Each card has an **Inspect Protocol** link at the bottom for more detail.

The two flows

Flow	Meaning
Downward Flow (Officials to Employees)	Master Asset Governance & Delegated Viewing: leaders and team leads send sealed brand guidelines, benchmarks and logos down to authorized team members with time-limited view access, watermarking and no download.
Upward Flow (Employees to Officials)	AI-Gated Draft Verification & Review: employees submit work to their managers. The AI compliance engine checks every submission (logo, colours, figures such as 94.5%) before the manager reviews it.




Figure 8. The four protection cards and the Downward Flow and Upward Flow panels.

8. Quick reference and common problems

Everything from Part 1 on one page.

Demo values seen on the login page

Item	Value
Company name	Acme Global Corp
Example email (CEO)	ceo.acme@gmail.com
Two-factor code (demo)	123456
Password reset code (demo)	999999
Password for the demo accounts	Shown in the project README. Use Fast Demo Login if unsure.

Sign-in in five steps

- Click your role.
- Check company and email.
- Type the password (eye icon to check it).
- Click the sign-in button, then enter the 6-digit code.
- Click **Verify OTP & Open Dashboard**.

Common problems

Problem	What to do
The role I clicked does not match my account	Select the role your account is registered under, then sign in again.
Wrong password	Click the eye icon to check what you typed. If needed use **Forgot Password?**.
Wrong two-factor code	Use 123456 in the demo, or click the hint box to fill it in.
I closed a window by mistake	Click the same button or link again. Every window has an **X** in the top-right corner.
Reset window does not accept the code	Use the demo code shown in its title, 999999.
I cannot choose my manager when registering	The manager must already have an account. Register the manager first.

Next: Part 2 explains the dashboard you reach after signing in.

PART 2 - THE DASHBOARD

9. The top bar after you sign in

Once you are signed in, the top bar gains the controls you need while working: session timer, notifications, role switcher and your account.

How to find it

It stays at the very top of every dashboard page. Compared with the login page, the **Fast Demo Login** button is gone and four new items appear.

What each item is

Item	What it shows or does
Logo, name, V3.2, security labels	Same as on the login page: the product name and version, the AES-256-GCM label and the FIPS 140-3 HSM label (display labels of the demo).
Session: 00:10:00	A countdown of your session time, starting at 10 minutes. An amber **Test** button sits next to it; it appears to be a demonstration helper for trying the timeout.
Bell with a red number	Your notifications. The red number (2 in the screenshot) is how many are new. Click the bell to read them.
PDF Manual	Shortcut to this manual.
ROLE: CEO, VP, HR, HOD, Team Lead, Employee	The role switcher. The highlighted pill is the role you are using now (CEO in the screenshot).
Name, role tag and email	Who is signed in: **Sarah Jenkins**, tagged **CEO**, email **ceo.acme@gmail.com**.
Red logout icon	The red outlined button at the far right. Click it to sign out.




Figure 9. The top bar after sign-in: session timer with the Test button, notification bell showing 2, PDF Manual, the ROLE switcher with CEO highlighted, the account block for Sarah Jenkins and the logout icon.

Tip: keep an eye on the session timer. When your session time runs out you are signed out and must log in again with a new two-factor code.

10. Dashboard home: banner and the four tabs

The first screen under the top bar. It tells you which role you are using and lets you move between the main work areas.

How to access it

It opens automatically after you enter the two-factor code. Scroll to the top of the page to return to it.

What you see

- **Banner:** the headline "Start Your Energetic Work - Zero-Leak Corporate Governance & AI Brand Compliance" with a short description.
- **Two small tiles** on the right: **Master Standard 94.5% Eff.** (the official efficiency figure that documents are checked against) and **Envelope Shield AES-256** (the encryption in use).
- **Upload & Send Protected File**: the green button at the right of the tab bar. It opens the upload window (Section 12).
- **Command Center panel** under the tabs: a chip showing **Active Role: CEO**, the heading **Master Asset Transmission & Author Control Panel** and a reminder that, as the Author, you can modify files, deploy new versions, expand recipients or trigger the Emergency Kill-Switch. The **Corporate Efficiency 94.5%** tile (Master Brand Benchmark 2026) is on its right.

The four tabs

Tab	What it is for
Author & File Controls	The files you have sent: counters, the file inventory and the audit ledger (Sections 11 and 13). It is the tab shown when you arrive.
Recipient Inbox & Directives	Files and instructions sent to you, which you open in the secure viewer (Section 14).
AI Compliance Scanner	Checks a draft against the company brand rules before it is sent. Covered in Part 3.
Live SOC Monitoring (REAL-TIME)	A live security monitoring view. Covered in Part 3.

To switch tab, click its name. The selected tab is filled blue.




Figure 10. Dashboard home: banner, the two tiles, the four tabs with the green Upload & Send Protected File button, and the Executive Command Center panel with the Corporate Efficiency tile.

11. Author control panel: counters and the file inventory

Everything about the files you have sent, in one place. Anyone who uploads a file becomes its Author and sees this panel for that file.

How to access it

Open the **Author & File Controls** tab and scroll down under the Command Center panel.

The four counters

Counter	What it counts
Authored Files	How many files you uploaded and govern ("Directly governed by you").
Active Buffers	Files that currently have live time-limited view access ("Live client viewtokens").
Revoked / Killed	Files you withdrew with the Emergency Kill-Switch ("Emergency kill-switched").
Dwell Time Reads	Recipient opens that were verified as real reading ("Verified recipient opens").




Figure 11. The four counters (1 authored file, 1 active buffer, 0 killed, 7 verified reads) and the top of the Secured File Transmission Inventory with its column headings and the Transmit New File button.

The file inventory

Secured File Transmission Inventory lists files you authored or that were shared within your corporate chain. Click any row for analytics or author controls. The blue **Transmit New File** button opens the upload window (Section 12). Each row has these columns:

Column	What it shows
Title & Details	The title, the file name, size and the start of its SHA fingerprint. An **URGENT** badge marks urgent files.
Type and Version	The file type (for example .PDF) and the version (v1.0).
AI Compliance	The result of the brand check, for example a green **Compliant**.
Recipients & Seen	How many recipients have seen it ("Seen by 2 of 4") and the latest receipt status (Delivered).
Status / Expiry	A live countdown of the remaining access time (01:52:50) with "Time-bound access".
Author Actions	Five round icon buttons, described below.




Figure 12. One inventory row: Brand Guidelines 2026 Master Specification.pdf, urgent, v1.0, Compliant, Seen by 2 of 4, 01:52:50 left, and the five author action icons.

The five Author Actions

From left to right, identified from the icon shapes (hover over each icon in the app to confirm its label):

Icon	What it is for
Eye	View the file in the secure viewer
Blue download arrow	Download your own original (Authors only; recipients cannot download)
Amber branch	Upload a new version of the file
Bar chart	See analytics: who opened the file and when
Red skull	Emergency Kill-Switch: withdraw the file immediately

12. Upload and send a protected file

The window where you choose a file, choose who may see it and for how long, then encrypt and send it.

How to access it

Click the green **Upload & Send Protected File** button (top right of the dashboard) or the blue **Transmit New File** button in the file inventory. The window **Transmit Encrypted Corporate File** opens ("Strict hierarchy routing - AES-256 Envelope GCM"). Close it any time with the **X** in its top-right corner.

The fields, top to bottom

Field	What to do
File Payload	Click the box or drag and drop a file. Allowed: .doc .docx .xls .xlsx .pdf .jpg .jpeg .mp4, up to 100 MB. The box notes that the real file type and a SHA-256 fingerprint are checked, so renaming a file does not get it past the check.
Document Title	The name recipients will see, for example "Brand Guidelines 2026 Master Directive".
Recipient Email(s)	Type the registered email addresses, separated by commas. They must belong to your hierarchy tree. Under the box, **In your tree** lists the people you are allowed to send to, with their roles.
Access Duration Window	How long recipients can open the file. The screenshot shows "2 Hours (Standard Executive)"; pick another duration from the list if needed.
Transmission Priority	Normal Governance by default. An urgent file gets a red URGENT badge in the inventory.
Allow Recipient Delegation	Tick the box to let recipients forward their view access downward in the tree. Leave it empty to keep the file to the people you named.
Optional Executive Note	A short message for recipients, for example "Mandatory review by 16:00 UTC".
Seal with AES-256 & Transmit	The wide blue button at the bottom. It encrypts the file and sends it to the recipients.

Steps

- Open the window and add the file.
- Type the title and the recipient emails (or read the names under "In your tree").
- Choose the access time and priority; tick delegation only if you want it.
- Add a note if useful, then click **Seal with AES-256 & Transmit**.




Figure 13. The Transmit Encrypted Corporate File window: file box, title, recipients with the In your tree list, access duration, priority, delegation tick box, executive note and the Seal with AES-256 & Transmit button.

Remember: you can only send to people inside your own hierarchy, and recipients can only view the file inside the website until the time you set runs out.

13. The audit ledger

A permanent record of what happened to your files. Each entry is linked to the one before it, so nothing can be changed without it being noticed.

How to access it

Open the **Author & File Controls** tab and scroll to the bottom, under the file inventory. The panel is titled **Immutable Hash-Chained Audit Ledger**.

What you see

- A green chip **CRYPTOGRAPHIC INTEGRITY: SEALED** and the label **SHA-256 Merkle Chain**. "Sealed" means the chain currently checks out.
- A sentence explaining that every transmission, view, dwell duration and kill-switch use is signed and chained to the block before it.

The three buttons

Button	What it does
Verify Log Integrity (green)	Re-checks the whole chain and reports whether any entry was altered.
Simulate Tamper Test (amber)	A demonstration: it deliberately alters an entry so you can watch the check catch it.
Restore Chain (grey)	Puts the ledger back to its correct state after the tamper test.

The columns

Block # (oldest at the bottom), **Timestamp** (UTC), **Actor Email** (who did it), **Action Type**, **Target Payload** (which file) and two fingerprints, **Previous Block Hash** and **Block Hash (SHA-256)**, which link each entry to the one before.




Figure 14. The audit ledger: four blocks from the genesis block to the acknowledgement, with the Verify Log Integrity, Simulate Tamper Test and Restore Chain buttons.

Reading the example

- **#1** 14:00:00, GENESIS_BLOCK - the system starts the chain.
- **#2** 14:00:15, TRANSMIT_FILE - the CEO sends Brand Guidelines 2026 Master Specification.pdf.
- **#3** 14:05:22, SANDBOX_VIEW - the VP opens it in the sandbox viewer.
- **#4** 14:18:45, ACKNOWLEDGE - the VP confirms reading it.
- Each block's *previous block hash* equals the *block hash* of the block below it. Changing one entry would break every link after it.

14. Recipient Inbox and Directives

What a person sees when files and instructions have been sent to them.

How to access it

On the dashboard click the second tab, **Recipient Inbox & Directives**. It turns blue when selected.

Official directives panel

- Chip **OFFICIAL DIRECTIVES & MASTER ASSETS** and the label "Confidential Downward Dispatch".
- Heading **Executive Guidance & Sealed Master Assets** with the rule: all production material must follow the official brand vectors, the primary royal blue (#0066FF) and the mandatory 94.5% Product Efficiency threshold before public distribution.
- Two buttons: **Test Draft in AI Scanner** (check your own draft against these rules) and **Submit Draft to Manager** (send a draft upward).

Assigned Ephemeral Documents

The list of files sent to you. The note under the heading explains that they are streamed in read-only sandbox viewports with forensic watermarking, and that raw downloads and local saves are locked. A **Downloads Disabled** tag repeats this. Each file row shows:

Item	Meaning
Title and details	Q4 Product Efficiency Audit & Financial Model.xlsx, type .XLSX, v1.0; the author (vp.acme@gmail.com), size (840 KB) and delivered date (2026-10-23); and the Author's quoted note.
Your Status	Where you stand: **Seen** with two blue ticks once you have read it. One grey tick means sent and two grey ticks mean delivered.
Expires in	A live countdown (03:45:49) of the access time you have left.
Open Sandboxed Viewer	The blue button that opens the file inside the website.

To read a file: click **Open Sandboxed Viewer**. It opens inside the website with a watermark carrying your identity and has no download button. Read it before the countdown ends; your status changes to Seen once you have read it to the end.




Figure 15. The Recipient Inbox & Directives tab: the directives panel with the AI Scanner and Submit Draft buttons, one assigned document with Your Status Seen, the Expires in countdown and the Open Sandboxed Viewer button, and the page footer.

15. Quick reference for the dashboard

Where to click for the most common jobs.

I want to...	Where to click
Send a file	Green **Upload & Send Protected File** button (top right), or **Transmit New File** in the inventory
See who has read my file	Author & File Controls tab, column **Recipients & Seen** (or the bar-chart icon for details)
See how long a file stays open	Column **Status / Expiry** (Authors) or the **Expires in** label (recipients)
Replace a file with a newer one	Amber branch icon in Author Actions
Withdraw a file at once	Red skull icon in Author Actions (Authors only)
Check the record of what happened	Audit ledger at the bottom of the Author tab, then **Verify Log Integrity**
Read a file sent to me	Recipient Inbox & Directives tab, then **Open Sandboxed Viewer**
Check a draft against the brand rules	**Test Draft in AI Scanner** button or the AI Compliance Scanner tab
Send a draft to my manager	**Submit Draft to Manager** button
Read my notifications	Bell icon in the top bar
Sign out	Red logout icon at the far right of the top bar

Common problems

Problem	What to do
I cannot add a recipient	They must be inside your hierarchy. Choose from the **In your tree** list under the Recipient Email(s) box.
A file will not open any more	Its countdown ran out, or the Author withdrew it. Ask the Author to send it again.
There is no Download button on a file I received	This is intended: recipients can only view files inside the website.
I was signed out	Your session timer reached zero. Sign in again and enter the two-factor code.
The tab I need is not showing	Click its name in the tab bar under the banner.

The page footer

At the bottom of every dashboard page: the copyright line, links to AES-256 Specifications, Forensic Leak Protocol, AI Verification Engine and Download Manual (PDF), and a compliance status label that is display text in this demo (visible at the bottom of Figure 15).

Next: Part 3 (from page 19) covers the AI Compliance Scanner tab, the Live SOC Monitoring tab and the Inspect Protocol pop-ups. The sandboxed viewer and the Emergency Kill-Switch will be added later.

PART 3 - AI SCANNER, SOC MONITORING AND PROTOCOL DETAILS

16. Recipient Inbox at full size

Section 14 introduced this tab. This is the full-width view, with a guide to each area.

How to access it

Click the second tab, **Recipient Inbox & Directives**. It turns blue when selected. Everything described below sits on one screen, under the tab bar.

What you see, top to bottom

Area	What it shows or does
Tab bar	Four tabs: Author & File Controls, **Recipient Inbox & Directives** (selected, blue), AI Compliance Scanner, and Live SOC Monitoring (green dot, REAL-TIME tag). The green **Upload & Send Protected File** button is at the right.
Directives panel	Chip OFFICIAL DIRECTIVES & MASTER ASSETS, the label "Confidential Downward Dispatch" and the heading **Executive Guidance & Sealed Master Assets**. The brand rule highlights two values: royal blue **#0066FF** and **94.5% Product Efficiency**.
Two buttons	**Test Draft in AI Scanner** (blue) opens the AI Compliance Scanner so you can check your own draft before sending it (Sections 17 and 18). **Submit Draft to Manager** sends a draft upward to your manager.
Assigned Ephemeral Documents (1)	The files sent to you; the number in brackets is how many. The **Downloads Disabled** tag says the files are read-only and cannot be saved.
The file row	Q4 Product Efficiency Audit & Financial Model.xlsx (.XLSX, v1.0), author vp.acme@gmail.com, 840 KB, delivered 2026-10-23. At the right: Your Status **Seen**, the countdown **Expires in: 03:45:49** and the blue **Open Sandboxed Viewer** button.




Figure 16. The Recipient Inbox & Directives tab at full width: tab bar, directives panel with the two buttons, the Assigned Ephemeral Documents list with one file, and the page footer.

Remember: the countdown keeps running while the page is open. When it reaches zero the file can no longer be opened and the Author has to send it again.

17. AI Compliance Scanner tab

A sandbox that checks a draft against the company brand rules before a manager reviews it (the Upward Flow in Section 7).

How to access it

Click the third tab, **AI Compliance Scanner**, or click **Test Draft in AI Scanner** in the Recipient Inbox. The screenshot shows the tab as it first opens, before any scan has run. To use it: keep the draft shown or load a sample with a preset, click **Run AI Compliance Scan**, then read the scorecard (Section 18).

What you see

Area	What it shows or does
Banner	Chips AUTONOMOUS VERIFICATION ENGINE V4.2 and NEURAL OCR READY, and the heading **AI Visual, Vector & Semantic Brand Scanner**. Drafts are audited against the Master Logo hashes (SHA-256), the Royal Blue palette (#0066FF) and the 94.5% efficiency figure, which the scanner reads from the image with OCR (text recognition).
Presets	**Preset A (Compliant)** (green) and **Preset B (Non-Compliant)** (red), at the right of the banner. They look like demo helpers that load a ready-made good or bad sample.
Submitted Production Draft	Left card: the file name Corporate_Brand_Card_Compliant.png, a VALIDATED SEED tag, a preview with the Office Info Controller logo and three readings: Target Vector Brand **Official Logo v3.2**, Dominant Primary Hex **#0066FF** and OCR Efficiency Metric **94.5%**. The wide blue **Run AI Compliance Scan** button below starts the check.
Neural Audit Scorecard	Right card. The grey tag **Awaiting Scan** shows that no scan has run. Its three rows are the checks: **Vector Logo Identity** (target Official Brand Logo v3.2, SHA-256 verified), **Primary Chromatic Hex Code** (target Royal Blue #0066FF, colour difference below 0.5 on the Delta E scale) and **OCR Financial & Efficiency Data** (target "94.5% Product Efficiency").

Delta E measures how different two colours look. Below 0.5 means the blue in the draft has to be practically identical to the official royal blue.




Figure 17. The AI Compliance Scanner before a scan: the banner with the two presets, the submitted draft with its three readings, the Run AI Compliance Scan button and the scorecard marked Awaiting Scan.

18. Running a scan: the passed result

What the scanner shows once the scan has finished and the draft is fully compliant.

How to access it

On the AI Compliance Scanner tab, click **Run AI Compliance Scan**. The right-hand card updates; the draft card on the left stays the same.

What changes

Item	Before the scan (Section 17)	After a passed scan
Tag on the Neural Audit Scorecard	Awaiting Scan (grey)	**PASSED (100% COMPLIANT)** (green)
The three check rows	Grey ticks	Green ticks. The targets are the same and the values stay on the right: Official Logo v3.2, #0066FF and 94.5%.
Result panel	None	A green panel under the rows: **100% Brand Compliant - Verification Passed**
Release button	None	A wide green button: **Push to Official Website (Production Release)**

Reading the result

The green panel states that all vectors, chromatic hex values and OCR financial metrics match the Master Guidelines 2026, and that the draft is cryptographically certified for publication. In this example all three checks agree with their targets. When the draft passes, click **Push to Official Website (Production Release)** to release it.




Figure 18. The scanner after a passed scan: the PASSED (100% COMPLIANT) tag, three green ticks, the 100% Brand Compliant panel and the Push to Official Website (Production Release) button.

Not shown yet: what happens after the release button is clicked, and the result for Preset B (Non-Compliant). Section 20 does show one rejection in the security log: a legacy 2023 logo and the colour #FF5722 were rejected by the CI/CD gate.

19. Live SOC Monitoring tab

A live security view: files sent, files open right now and leak attempts stopped.

How to access it

Click the fourth tab, **Live SOC Monitoring** (green dot, REAL-TIME tag). SOC stands for Security Operations Center, the team that watches security events.

What you see

Area	What it shows or does
Banner	DEFCON 1 - LIVE SIEM SURVEILLANCE and a FIPS 140-3 ACTIVE chip (display labels in this demo), the heading **Security Operations Center (SOC) & Cryptographic Telemetry** and a line on what is watched. At the right: **STREAM HEARTBEAT 2,400 events/sec** and a round refresh button.
Hourly chart	**Hourly Encrypted Ingestion & Viewing Velocity**, a 12-hour bar chart (1h to 12h) tagged SHA-256 Validated. The bars rise overall with small dips at 3h, 5h, 7h and 10h; 12h is the tallest. There are no scale numbers, so read the shape.
Leak Defense Intercept Spectrum	Three bars for blocked copy-out attempts: **Clipboard / Screen Capture Neutralized 58%** (red), **Print Spooler Blackhole Invocations 24%** (amber) and **Expired Token Replay Invocations 18%** (blue). They add up to 100%.
Watermark status box	**Forensic Watermarking Operational**: 100% of viewports carry tamper-evident user identity microdots (see Section 22).

The four counter tiles

Tile	Value	In plain words
TOTAL ENCRYPTED TRANSMISSIONS	1420	Encrypted file transmissions so far. The green line says traffic is up 14% this hour (Peak Traffic).
ACTIVE AIR-GAPPED BUFFERS	4	Files open right now in protected viewing memory. Nothing is stored unencrypted on disk.
BLOCKED LEAK INTERCEPTIONS	12	Attempts to copy, capture or print that were stopped ("100% Screenshot & Print Neutralized").
FIPS HSM LATENCY	1.24 ms	How long unlocking a file's key takes (Envelope GCM Decrypt P99): 99 out of 100 unlocks took 1.24 milliseconds or less.



Figure 19. The Live SOC Monitoring tab: banner with the stream heartbeat, the four counter tiles, the hourly bar chart, the Leak Defense Intercept Spectrum and the watermarking status box.

20. Live sessions and the SIEM stream

Who is looking at a protected file right now, and the security events as they happen.

How to access it

Open the Live SOC Monitoring tab and scroll down, below the hourly chart and the Leak Defense Intercept Spectrum. Two panels follow: **Active Air-Gapped Client Viewports (Live Sessions)** and **SIEM Security Telemetry Stream**.

Live sessions

The panel carries a green tag **4 CONCURRENT VIEWERS** and the line "Real-time sockets listening to active clients. Terminate any active session remotely with one click." Each row is one person viewing one file:

Column	What it shows
SESSION TOKEN	The ID of the viewing session (SESS-901 to SESS-904), in blue.
AUTHORIZED VIEWER	Name and role of the person who has the file open.
TARGET PAYLOAD	The file being viewed.
WATERMARK IP	The network address stamped into that viewer's watermark, so a leak can be traced.
DWELL DURATION	How long the file has been open, in green (for example 14m 20s).
SECURITY LEVEL	The green AIR-GAPPED tag: the file is shown only in protected memory.
EMERGENCY ACTION	The red **Terminate & Kill** button. It ends that viewer's session remotely, at once.

Reading the example

- Four viewers are connected, matching the 4 CONCURRENT VIEWERS tag and the ACTIVE AIR-GAPPED BUFFERS tile (4) in Section 19.
- Three sessions show Brand Guidelines 2026.pdf (Sarah Jenkins, CEO; Marcus Vance, HOD; Alex Rivera, Lead). David Chen (VP) is viewing Q4 Efficiency Financials.xlsx.
- Sarah Jenkins has had her file open the longest (14m 20s); Alex Rivera the shortest (1m 05s). SESS-901 and SESS-904 show the same watermark IP, 192.168.1.1.

The SIEM security telemetry stream

SIEM means a system that gathers security events into one list. The label **Live Socket Feeds** sits at the top right. Each line shows a level tag, the time (UTC), a message and an EventID. The newest event is first.

Level	Time (UTC)	Message	EventID
CRITICAL (red)	15:18:22	Direct raw download blocked under Zero-Leak Policy #804-A	554340
WARN (amber)	15:12:04	Legacy 2023 logo vector and #FF5722 rejected by CI/CD gate	182559
INFO (blue)	15:05:41	Ephemeral document encryption key rotated cleanly	929396
WARN (amber)	14:52:19	Right-click inspection attempt intercepted in sandboxed viewer	537744

The screenshot

Figure 20 shows both panels described above: the live sessions table at the top and the SIEM stream below it.




Figure 20. Live sessions and the SIEM telemetry stream: four active viewers, each with a red Terminate & Kill button, and four log entries (CRITICAL, WARN, INFO, WARN).

Levels and the kill button: INFO appears to mark routine events, WARN something rejected or intercepted, and CRITICAL a serious attempt that was blocked. Terminate & Kill acts on one viewing session; to withdraw a whole file the Author uses the red skull icon (Section 11). The screenshot shows no confirmation step, so check in the app whether it asks you to confirm.

21. The top bar as a Team Lead

The same top bar as Section 9, shown for a different role. Use it to check which role you are working in.

How to find it

It stays at the very top of every dashboard page once you are signed in (Section 9). This screenshot was taken in a narrower window, so some labels wrap onto several lines, for example "Zero-Leak Shield: AES-256-GCM".

What is different from Section 9

Item	Section 9 (CEO)	This screenshot (Team Lead)
Name	Sarah Jenkins	Alex Rivera
Role tag	CEO	Team Lead
Email	ceo.acme@gmail.com	lead.acme@gmail.com
Highlighted role pill	CEO	Team Lead
Same in both	Session: 00:10:00 with the amber Test button, the bell showing 2, PDF Manual and the red logout icon.	

All six role pills are always shown; only the highlighted one is the role you are using. A Team Lead is in the Management group and delegates files to team members (Section 2).




Figure 21. The top bar signed in as Alex Rivera, Team Lead: the session timer 00:10:00 with the Test button, the bell showing 2, PDF Manual, the ROLE switcher with Team Lead highlighted, and the account block with the logout icon.

22. Inspect Protocol pop-ups

Two short windows that explain a protection in plain terms. Each asks you to confirm that you have read it.

How to access it

On the login page, click **Inspect Protocol** at the bottom of one of the four protection cards (Section 7). The two windows shown here belong to the cards **Forensic Leak Watermarking** and **AES-256 Envelope Encryption**. The footer links with the same names (Forensic Leak Protocol, AES-256 Specifications) appear to open the same kind of window.

What you see

- A title at the top left and a round **X** button at the top right.
- One or two sentences of specification text under a thin line.
- A wide blue button, **Acknowledge Specification**. Click it, or the X, to close the window.

What each window says

Window	What it says on screen	In plain words
Forensic Leak Watermarking	Multi-layer dynamic SVG overlays injecting viewer email, enterprise IP, and microsecond timestamps across the document canvas.	Every file you view is covered with see-through layers that carry your email, your company network address and the exact time. If a screenshot or photo leaks, it can be traced back to the viewer.
AES-256 Envelope Encryption	Per-file ephemeral data keys sealed under FIPS 140-3 HSM master keys.	Each file is locked with its own short-lived key. That key is itself locked with a master key kept in a secure hardware module, so keys are stored apart from the files (Section 7).




Figure 22. The Forensic Leak Watermarking window, with the X button and the Acknowledge Specification button.




Figure 23. The AES-256 Envelope Encryption window, with the same X and Acknowledge Specification buttons.

23. Quick reference for Part 3

Where to click for the most common jobs in the scanner and the monitoring tab.

Where to click

I want to...	Where to click
Check a draft against the brand rules	AI Compliance Scanner tab, or **Test Draft in AI Scanner** in the Recipient Inbox
Try the scanner with a sample	**Preset A (Compliant)** or **Preset B (Non-Compliant)** in the scanner banner
Start a scan	**Run AI Compliance Scan** under the draft preview
Release a draft that passed	**Push to Official Website (Production Release)**, shown with the PASSED result
See live security activity	Live SOC Monitoring tab (fourth tab)
See who has a file open right now	Live SOC Monitoring tab, scroll down to Active Air-Gapped Client Viewports
End one viewer's session at once	**Terminate & Kill** at the end of that viewer's row
Read recent security events	SIEM Security Telemetry Stream, under the sessions table
Read what a protection means	**Inspect Protocol** on a login-page card, then **Acknowledge Specification**
Check which role I am using	The highlighted pill in the ROLE switcher in the top bar

Common problems

Problem	What to do
The scorecard still says Awaiting Scan	No scan has run yet. Click **Run AI Compliance Scan**.
I cannot see the Push to Official Website button	In the screenshots it appears together with the PASSED (100% COMPLIANT) result and the green panel. Run the scan and check that the draft passes.
The SOC numbers differ from this manual	The tab is real-time, so the figures change. The manual shows one moment.
A pop-up window will not go away	Click **Acknowledge Specification**, or the X in its top-right corner.

Still to come. The sandboxed file viewer and the Emergency Kill-Switch confirmation will be added when their screenshots are available. The only kill control in these screenshots is the Terminate & Kill button (Section 20).