EANCOM IFTMBF D01B

Firm booking message

Version: 1.0

Modified: 04.05.2018

Table of Contents

IF٦	MBF Fir	m booking message ·····	1
	UNB	INTERCHANGE HEADER	3
	UNH	Message header	5
	BGM	Beginning of message	7
	DTM	Date/time/period	8
	Group 3	Segment Group 3	ĝ
	RFF	Reference	10
	DTM	Date/time/period	11
	Group 3	Segment Group 3	12
	RFF	Reference	13
	Group 3	Segment Group 3	14
	RFF	Reference	15
	Group 10	Segment Group 10	16
	NAD	Name and address	17
	Group 10	Segment Group 10	19
	NAD	Name and address	20
	Group 16	Segment Group 16	21
	GID	Goods item details	22
	HAN	Handling instructions	24
	Group 18	Segment Group 18	25
	MEA	Measurements	26
	Group 18	Segment Group 18	27
	MEA	Measurements	28
	Group 19	Segment Group 19	29
	DIM	Dimensions	30
	UNT	Message trailer	31
	UNZ	INTERCHANGE TRAILER	32

IFTMBF Firm booking message

Message Status=2

Definition: A message from a party booking forwarding and/or transport services for a consignment to the party providing those services. The message will contain conditions under which the sender of the messages requires the services to take place.

Not Defined:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Notes</u>	<u>Usage</u>
0010	UNB	INTERCHANGE HEADER	M	1	N0/0010	Must use
Uoodino						
Heading) :					
<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Notes</u>	<u>Usage</u>
0020	UNH	Message header	M	1	N1/0020	Must use
0030	BGM	Beginning of message	M	1	N1/0030	Must use
0040	DTM	Date/time/period	С	9	N1/0040	Must use
<u>0110</u>		Segment Group 3	<u>M</u>	<u>99</u>	N1/0110	Must use
0120	RFF	Reference	М	1	N1/0120	Must use
0130	DTM	Date/time/period	С	9	N1/0130	Must use
<u>0140</u>		Segment Group 3	<u>M</u>	99	N1/0140	Must use
0150	RFF	Reference	М	1	N1/0150	Must use
<u>0170</u>		Segment Group 3	<u>C</u>	99	N1/0170	<u>Used</u>
0180	RFF	Reference	С	1	N1/0180	Used
0250		Segment Group 10	<u>M</u>	99	N1/0250	Must use
0260	NAD	Name and address	М	1	N1/0260	Must use
0310		Segment Group 10	<u>M</u>	99	N1/0310	Must use
0320	NAD	Name and address	M	1	N1/0320	Must use

Detail:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Notes</u>	<u>Usage</u>
<u>0370</u>		Segment Group 16	<u>C</u>	<u>999</u>	N2/0370	Must use
0380	GID	Goods item details	М	1	N2/0380	Must use
0390	HAN	Handling instructions	С	1	N2/0390	Must use
<u>0480</u>		Segment Group 18	<u>M</u>	<u>99</u>	N2/0480	Must use
0490	MEA	Measurements	М	1	N2/0490	Must use
<u>0500</u>		Segment Group 18	<u>M</u>	99	N2/0500	Must use
0510	MEA	Measurements	М	1	N2/0510	Must use
<u>0530</u>		Segment Group 19	<u>C</u>	99	N2/0530	<u>Dependent</u>
0540	DIM	Dimensions	М	1	N2/0540	Must use

Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Notes</u>	<u>Usage</u>
0680	UNT	Message trailer	M	1	N3/0680	Must use

Not Defined:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Notes</u>	<u>Usage</u>
0690	UNZ	INTERCHANGE TRAILER	M	1	N0/0690	Must use

UNB INTERCHANGE HEADER

Pos: 0010 Max: 1
Mandatory
Group: N/A Elements: 6

User Option (Usage): Must use

Function: To start, identify and specify an interchange.

Element Summary:

<u>Ref</u> UNB010	<u>Tag</u> S001	Element Name SYNTAX IDENTIFIER	<u>Status</u> M	<u>Type</u> Comp	Min/Max	<u>Usage</u> Must use
		Description: Identification of the agency level.	y controll	ing the sy	ntax and indic	ation of syntax
UNB010-010	0001	Syntax identifier	М	а	4/4	Must use
		Description: Coded identification of the used in an interchange.	agency	controlling	g a syntax and	syntax level
		CodeList Summary (Total Codes: 6, In Code Name UNOA UN/ECE level A UNOC UN/ECE level C	cluded: 2)		
UNB010-020	0002	Syntax version number	М	n	1/1	Must use
		Description: Version number of the syn	ntax ident	ified in th	e syntax identi	fier (0001).
		CodeList Summary (Total Codes: 3, In Code Name Version 2	cluded: 1)		
UNB020	S002	INTERCHANGE SENDER	М	Comp		Must use
		Description: Identification of the sende	r of the in	iterchang	e.	
UNB020-010	0004	Sender identification	М	an	1/35	Must use
		Description: Name or coded representa	ation of th	ne sendei	r of a data inter	rchange.
UNB020-020	0007	Partner identification code qualifier	М	an	1/4	Must use
		Description: Qualifier referring to the separtners.			the identifiers	of interchanging
		All valid standard codes are used. (To		es: 43)		
UNB030	S003	INTERCHANGE RECIPIENT	M	Comp		Must use
		Description: Identification of the recipie	ent of the	interchar		
UNB030-010	0010	Recipient identification	М	an	1/35	Must use
		Description: Name or coded representa	ation of th	ne recipie	nt of a data int	erchange.
UNB030-020	0007	Partner identification code qualifier	M	an	1/4	Must use
		Description: Qualifier referring to the so partners. All valid standard codes are used. (To			the identifiers	of interchanging

3

<u>Ref</u>	<u>Tag</u>	Element Name	<u>Status</u>	<u>Type</u>	Min/Max	<u>Usage</u>
UNB040	S004	DATE/TIME OF PREPARATION	М	Comp		Must use
		Description: Date/time of preparation of	of the inte	rchange.		
UNB040-010	0017	Date of preparation	М	n	6/6	Must use
		Description: Local date when an interc	hange or	a functio	nal group was	prepared.
UNB040-020	0019	Time of preparation	M	n	4/4	Must use
		Description: Local time of day when a	n intercha	nge or a	functional grou	p was prepared.
UNB050	0020	Interchange control reference	М	an	1/14	Must use
		Description: Unique reference assigne	d by the	sender to	an interchange	e.
UNB100	0032	Communication agreement ID	М	an	1/35	Must use
		Description: Identification by name or interchange takes place.	code of th	e type of	agreement un	der which the

4

Example:

UNB+UNOC:2+<Sender GLN>:14+<Receiver GLN>:14+140407:0427+99++++EANCOM'

UNH Message header

Pos: 0020 Max: 1 Mandatory

Group: N/A Elements: 2

User Option (Usage): Must use

Function: To head, identify and specify a message.

Element Summary:

Ref UNH010	<u>Tag</u> 0062	Element Name Message reference number	<u>Status</u> M	<u>Type</u> an	Min/Max 1/14	<u>Usage</u> Must use		
		Description: Description: Unique message reference assigned by the sender.						
UNH020	S009	MESSAGE IDENTIFIER	М	Comp		Must use		
UNH020-010	0065	Message type	М	an	1/6	Must use		
		Description: Code identifying a type of	message	and ass	igned by its co	ontrolling agency.		
		CodeList Summary (Total Codes: 49, I Code Name IFTMBF Firm booking message	ncluded:	1)				
UNH020-020	0052	Message version number	М	an	1/3	Must use		
		Description: Version number of a mess	sage type					
	CodeList Summary (Total Codes: 2, Included: 1) Code Name D Draft version/UN/EDIFACT Directory							
UNH020-030	0054	Message release number	М	an	1/3	Must use		
		Description: Release number within the	e current	message	type version	number (0052).		
		CodeList Summary (Total Codes: 3, In Code Name 01B Release 2001 - B	cluded: 1)				
UNH020-040	0051	Controlling agency, coded	М	an	1/3	Must use		
		Description: Code to identify the agend publication of the message type.	cy control	ling the s	pecification, n	naintenance and		
		CodeList Summary (Total Codes: 2, In Code Name UN UN/CEFACT	cluded: 1)				
UNH020-050	0057	Association assigned code	С	an	1/6	Must use		
		Description: Indicates that the message Booking message.	e is the E	ANCOM	version 003 o	f the UNSM Firm		
		CodeList Summary (Total Codes: 10, I Code Name EAN003 EAN version control number (I						

Segment Notes:

Example:

UNH+1+IFTMBF:D:01B:UN:EAN003'

Confidential

6

BGM Beginning of message

Pos: 0030 Max: 1 Mandatory Group: N/A Elements: 2

User Option (Usage): Must use

Function: To indicate the type and function of a message and to transmit the identifying number.

Element Summary:

Ref BGM010	<u>Tag</u> C002	Element Name DOCUMENT/MESSAGE NAME	Status C	<u>Type</u> Comp	Min/Max	<u>Usage</u> Must use
BGM010-010	1001	Document name code	С	an	1/3	Must use
		Description: Code specifying the docum	nent nam	ie.		
		CodeList Summary (Total Codes: 137,	Included	: 1)		
		Code Name				
		335 Booking request				
BGM020	C106	DOCUMENT/MESSAGE IDENTIFICATION	С	Comp		Must use
BGM020-010	1004	Document identifier	С	an	1/35	Must use
		Description: Booking number assigned	by the de	ocument :	sender.	

7

Example:

BGM+335+00000333'

DTM Date/time/period

Pos: 0040 Max: 9
Conditional
Group: N/A Elements: 1

User Option (Usage): Must use

Function: To specify date, and/or time, or period.

Element Summary:

Ref DTM010	<u>Tag</u> C507	Element Name DATE/TIME/PERIOD	Status M	<u>Type</u> Comp	Min/Max	<u>Usage</u> Must use
DTM010-010	2005	Date or time or period function code qualifier	M	an	1/3	Must use
		Description: Code qualifying the function	on of a da	ite, time o	or period.	
		CodeList Summary (Total Codes: 194, Code Name Document/message date/time	Included	: 1)		
DTM010-020	2380	Date or time or period value	С	an	1/35	Must use
		Description: The value of a date, a date representation.	e and time	e, a time	or of a period in	a specified
DTM010-030	2379	Date or time or period format code	С	an	1/3	Must use
	Description: Code specifying the representation of a date, time or period.					
		CodeList Summary (Total Codes: 30, I Code Name COMPANY COMPANY (Total Codes: 30, I COMPANY (Total Codes: 30, I	ncluded:	1)		

8

Example:

DTM+137:201601030800:203'

Pos: 0110 Repeat: 99 Mandatory

Group: 3 Elements: N/A

User Option (Usage): Must use

Segment Group Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	Status	<u>Rep</u>	<u>Usage</u>
0120	RFF	Reference	М	1	Must use
0130	DTM	Date/time/period	С	9	Must use

9

RFF Reference

Pos: 0120 Max: 1

Mandatory

Group: 3 Elements: 1

User Option (Usage): Must use **Function:** To specify a reference.

Element Summary:

Ref RFF010	<u>Tag</u> C506	Element Name REFERENCE	<u>Status</u> M	<u>Type</u> Comp	Min/Max	<u>Usage</u> Must use
RFF010-010	1153	Reference code qualifier	М	an	1/3	Must use
		Description: Code qualifying a reference	ce.			
		CodeList Summary (Total Codes: 212, Code Name BN Booking reference number	Included	: 1)		
RFF010-020	1154	Reference identifier	С	an	1/70	Must use

Description: Identifies a reference.

Segment Notes:

This segment is used to specify references relating to the booking.

We recommend that you use the same ID as that which is used in the BGM+351 segment of the DESADV document.

There can only be one Routing Request per ASN.

You must build the Booking Request ID with your vendor code at the beginning followed by a sequential number. (Do not repeat the same ID within 365 days)

Example:

RFF+BN:DES5A7441' Vendor Code: DES5A Sequential Number: 7441

Should align with BGM+351:DES5A7441' from DESADV.

DTM Date/time/period

Pos: 0130 Max: 9
Conditional
Group: 3 Elements: 1

User Option (Usage): Must use

Function: To specify date, and/or time, or period.

Element Summary:

Ref DTM010	<u>Tag</u> C507	Element Name DATE/TIME/PERIOD	<u>Status</u> M	<u>Type</u> Comp	Min/Max	<u>Usage</u> Must use
DTM010-010	2005	Date or time or period function code qualifier	М	an	1/3	Must use
		Description: Code qualifying the function	on of a da	ate, time	or period.	
		CodeList Summary (Total Codes: 194, Code Name Shipment date/time, requested	Included	: 1)		
DTM010-020	2380	Date or time or period value	С	an	1/35	Must use
		Description: The value of a date, a dat representation.	e and tim	e, a time	or of a period ir	n a specified
DTM010-030	2379	Date or time or period format code	С	an	1/3	Must use
		Description: Code specifying the repre	sentation	of a date	e, time or period	
		CodeList Summary (Total Codes: 30, I Code Name	ncluded:	1)		

11

Segment Notes:

This segment must contain the earliest shipment collection date.

CCYYMMDD

Example:

DTM+10:20140408:102'

The earliest shipment collection date is 8th of April 2014.

102

Pos: 0140 Repeat: 99

Mandatory

Group: 3 Elements: N/A

User Option (Usage): Must use

Segment Group Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Usage</u>
0150	RFF	Reference	М	1	Must use

RFF Reference

Pos: 0150 Max: 1 Mandatory

Group: 3 Elements: 1

User Option (Usage): Must use **Function:** To specify a reference.

Element Summary:

<u>Ref</u>	<u>Tag</u>	Element Name	<u>Status</u>	<u>Type</u>	Min/Max	<u>Usage</u>
RFF010	C506	REFERENCE	М	Comp		Must use
RFF010-010	1153	Reference code qualifier	М	an	1/3	Must use
		Description: Code qualifying a reference	ce.			
		CodeList Summary (Total Codes: 212,	Included	: 1)		
		Code Name				
		ON Order number (buyer)				
RFF010-020	1154	Reference identifier	С	an	1/70	Must use
		Description: Identifies a reference.				
RFF010-030	1156	Document line identifier	С	an	1/6	Must use
		Description: To identify a line of a docu	ıment.			

Segment Notes:

Amazon Purchase Order MUST be provided. A Shipment might contain multiple POs. If the shipment contains multiple POs you must use "RFF010-030 - 1156" as a sequential counter.

Example:

RFF+ON:1AA1TEST':1' RFF+ON:2AA2TEST':2' RFF+ON:3AA3TEST':3'

Pos: 0170 Repeat: 99 Conditional

Group: 3 Elements: N/A

User Option (Usage): Used

Segment Group Summary:

<u>Pos</u>	Tag	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Usage</u>
0180	RFF	Reference	С	1	Used

RFF Reference

Pos: 0180 Max: 1 Conditional

Group: 3 Elements: 1

User Option (Usage): Used **Function:** To specify a reference.

Element Summary:

Ref RFF010	<u>Tag</u> C506	Element Name REFERENCE	<u>Status</u> M	<u>Type</u> Comp	Min/Max	<u>Usage</u> Must use
RFF010-010	1153	Reference code qualifier	М	an	1/3	Must use
		Description: Code qualifying a referen	ce.			
		CodeList Summary (Total Codes: 212	, Included	: 1)		
		Code Name				
		BM Bill of lading number				
RFF010-020	1154	Reference identifier	С	an	1/70	Must use

Description: Identifies a reference.

Segment Notes:

You may send in the RFF+BM segment the Bill of Lading number of the shipment.

Example:

RFF+BM:ABCD12332'

Should align with RFF+BM:ABCD12332' from DESADV.

Pos: 0250 Repeat: 99

Mandatory

Group: 10 Elements: N/A

User Option (Usage): Must use

Segment Group Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Usage</u>
0260	NAD	Name and address	M	1	Must use

NAD Name and address

Pos: 0260 Max: 1
Mandatory
Group: 10 Elements: 7

User Option (Usage): Must use

Function: To specify the name/address and their related function, either by C082 only and/or unstructured by C058 or structured by C080 thru 3207.

Element Summary:

Ref NAD010	<u>Tag</u> 3035	Element Name Party function code qualifier	<u>Status</u> M	<u>Type</u> an	Min/Max 1/3	<u>Usage</u> Must use
		Description: Code giving specific mean	ning to a	party.		
		CodeList Summary (Total Codes: 126, Code Name SF Ship from	Included	l: 1)		
NAD020	C082	PARTY IDENTIFICATION DETAILS	С	Comp		Must use
		Description: General explanations				
NAD020-010	3039	Party identifier	М	an	1/35	Must use
		Description: For identification of parties	s it is rec	ommende	ed to use GLN	- Format n13.
NAD020-030	3055	Code list responsible agency code	С	an	1/3	Must use
		Description: Code specifying the agend	cy respor	nsible for	a code list.	
		CodeList Summary (Total Codes: 43, I Code Name 9 EAN (International Article Numbers) 92 Assigned by buyer or buyer's agents.	ering ass			
NAD040	C080	PARTY NAME	С	Comp		Must use
NAD040-010	3036	Party name	М	an	1/35	Must use
		Description: Party Name in clear text.				
NAD050	C059	STREET	С	Comp		Must use
NAD050-010	3042	Street and number or post office box identifier	M	an	1/35	Must use
		Description: Building Name/Number ar	nd Street			
NAD050-020	3042	Street and number or post office box identifier	С	an	1/35	Must use
		Description: Name and/or P.O. Box				
NAD060	3164	City name	С	an	1/35	Must use
		Description: City/Town, clear text.				
NAD080	3251	Postal identification code	С	an	1/17	Must use
		Description: Postal Code				

<u>Ref</u>	<u>Tag</u>	Element Name	<u>Status</u>	<u>Type</u>	Min/Max	<u>Usage</u>
NAD090	3207	Country name code	С	an	1/3	Must use

Description: ISO 3166 two alpha code

Segment Notes:

It is important that the address fields in NAD040 - NAD090 are completely transmitted.

In case you do not have a GLN and need Amazon to generate a Unique Warehouse Code for your location, please consult the "EU EDI ROUTING REQUEST Business Requirements" in the EDI package from Vendor Central ResourceCenter for further information.:

Example:

NAD+SF+<SUPPLIER WAREHOUSE GLN>::9++COMPANY NAME+STREET AND NUMBER OR P.O.BOX+CITY++ZIP CODE+ISOCOUNTRYCODE'

NAD+SF+<AMAZON WAREHOUSE CODE>::92++COMPANY NAME+STREET AND NUMBER OR P.O.BOX+CITY++ZIP CODE+ISOCOUNTRYCODE'

18

Pos: 0310 Repeat: 99

Mandatory

Group: 10 Elements: N/A

User Option (Usage): Must use

Segment Group Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Usage</u>
0320	NAD	Name and address	M	1	Must use

NAD Name and address

Pos: 0320 Max: 1
Mandatory
Group: 10 Elements: 3

User Option (Usage): Must use

Function: To specify the name/address and their related function, either by C082 only and/or unstructured by C058 or structured by C080 thru 3207.

Element Summary:

<u>Ref</u> NAD010	<u>Tag</u> 3035	Element Name Party function code qualifier	<u>Status</u> M	<u>Type</u> an	Min/Max 1/3	<u>Usage</u> Must use
		Description: Code giving specific mean	ning to a p	oarty.		
		CodeList Summary (Total Codes: 126) Code Name ST Ship to	, Included	: 1)		
NAD020	C082	PARTY IDENTIFICATION DETAILS	С	Comp		Must use
		Description: General explanations				
NAD020-010	3039	Party identifier	М	an	1/35	Must use
		Description: For identification of parties	s it is reco	ommende	ed to use GLN	- Format n13.
NAD020-030	3055	Code list responsible agency code	С	an	1/3	Must use
		Description: Code specifying the agen	cy respor	sible for	a code list.	
		CodeList Summary (Total Codes: 43, Code Name 9 EAN (International Article Number)		•		
NAD090	3207	Country name code	С	an	1/3	Must use
		Description: ISO 3166 two alpha code				

Segment Notes:

Please use the GLN Overview from the Vendor Central Resource Center for the values to be used. Address details for the ship-to locations are available in your Vendor Manual in the Vendor Central Resource Center.

Example:

NAD+ST+<ShipTo GLN>::9+++++ISOCOUNTRYCODE'

Pos: 0370 Repeat: 999 Conditional

Group: 16 Elements: N/A

User Option (Usage): Must use

Segment Group Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Usage</u>
0380	GID	Goods item details	M	1	Must use
0390	HAN	Handling instructions	С	1	Must use
0480		Segment Group 18	M	99	Must use
0500		Segment Group 18	M	99	Must use
0530		Segment Group 19	С	99	Dependent

GID Goods item details

Pos: 0380 Max: 1 Mandatory

Group: 16 Elements: 3

User Option (Usage): Must use

Function: To indicate totals of a goods item.

Element Summary:

Ref GID010	<u>Tag</u> 1496	Element Name Goods item number	<u>Status</u> C	Type n	Min/Max 1/5	<u>Usage</u> Must use		
		Description: Application number identif	ying item	s within t	the current co	nsignment.		
GID020	C213	NUMBER AND TYPE OF PACKAGES	С	Comp		Must use		
		Description: General explanations						
GID020-010	7224	Package quantity	С	n	1/8	Must use		
		Description: To specify the number of p	packages	i.				
GID020-020	7065	Package type description code	С	an	1/17	Must use		
		Note: You must use "PX" for non-standard						
		CodeList Summary (Total Codes: 149, Code Name PX Pallet 201 Pallet ISO 1 - 1/1 EURO Pallet (E		·				
GID020-040	3055	Code list responsible agency code	С	an	1/3	Must use		
		Note: Code specifying the agency responsible for a code list.						
		CodeList Summary (Total Codes: 43, Inc. Code Name 9 EAN (International Article Number						
GID030	C213	NUMBER AND TYPE OF PACKAGES	С	Comp		Must use		
		Note: If the carton quantity applies to the the first GID loop.	e total sh	nipment ti	hen only provi	de this value in		
GID030-010	7224	Package quantity	С	n	1/8	Must use		
		Description: To specify the number of p	packages	i.				
GID030-020	7065	Package type description code	С	an	1/17	Must use		
		Description: Code specifying the type of	of packag	e.				
		CodeList Summary (Total Codes: 149, Code Name CT Carton	Included	: 1)				

Segment Notes:

For shipments containing only parcels the value 0 needs to be sent for pallet count as below: GID+1+0+11:CT - The shipment contains 0 pallet and 11 cartons.

Example:

If the shipment contains different pallet types:

1) If the carton quantity applies to each pallet type then you must provide the carton quantity for each pallet type as below:

GID+1+4:201::9+60:CT' - 1st GID Loop: 4 standard pallets containing 60 cartons.

GID+2+1:PX::9+5:CT' - 2nd GID Loop: 1 non-standard pallet containing 5 cartons.

Please note that in case of a non-standard pallet, you have to define the dimensions of the pallet in DIM segment group 19.

2) If the carton quantity applies to the total shipment then only provide it in the first GID Loop as below: GID+1+4:201::9+65:CT' - 1st GID Loop: 4 standard pallets and 65 cartons (which represents the declared carton quantity for entire shipment).

GID+2+1:PX::9' - 2nd GID Loop: 1 non-standard pallet. The carton quantity is not needed as the total count is in the first GID Loop.

HAN Handling instructions

Pos: 0390 Max: 1
Conditional
Group: 16 Elements: 1

User Option (Usage): Must use

Function: To specify handling and where necessary, notify hazards.

Element Summary:

<u>Ref</u> HAN010	<u>Tag</u> C524	Element Name HANDLING INSTRUCTIONS	Status C	<u>Type</u> Comp	Min/Max	<u>Usage</u> Must use
		Description: General explanations				
HAN010-010	4079	Handling instruction description code	С	an	1/3	Must use
	Description: Code specifying a handling instruction.					

CodeList Summary (Total Codes: 40, Included: 1)
Code Name

Code Name
3 Stacked

Segment Notes:

This segment must be sent if stackable pallet(s) are being shipped.

Example:

HAN+3'

The pallet is stackable

Pos: 0480 Repeat: 99

Mandatory

Group: 18 Elements: N/A

User Option (Usage): Must use

Segment Group Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Usage</u>
0490	MEA	Measurements	M	1	Must use

MEA Measurements

Pos: 0490 Max: 1 Mandatory

Group: 18 Elements: 3

User Option (Usage): Must use

Function: To specify physical measurements, including dimension tolerances, weights and counts.

Element Summary:

Ref MEA010	<u>Tag</u> 6311	Element Name Measurement purpose code qualifier	<u>Status</u> M	<u>Type</u> an	Min/Max 1/3	<u>Usage</u> Must use
		Description: Code qualifying the purpo	se of the	measure	ment.	
		CodeList Summary (Total Codes: 38, I Code Name AAE Measurement	ncluded:	1)		
MEA020	C502	MEASUREMENT DETAILS	С	Comp		Must use
MEA020-010	6313	Measured attribute code	С	an	1/3	Must use
		Description: Code specifying the attrib	ute meas	ured.		
		CodeList Summary (Total Codes: 90, I Code Name Gross weight	ncluded:	1)		
MEA030	C174	VALUE/RANGE	С	Comp		Must use
		Note: All other units of measure will be	rejected.			
MEA030-010	6411	Measurement unit code	М	an	1/3	Must use
		Description: Code specifying the unit of	f measur	ement.		
		CodeList Summary (Total Codes: 130, Code Name KGM kilogram	Included	l: 1)		
MEA030-020	6314	Measurement value	С	an	1/18	Must use
		Description: To specify the value of a r	measurer	nent.		

Segment Notes:

If the weight measurement applies to the total shipment (ASN level measurement) then provide this value only in the first GID loop.

Example:

MEA+AAE+G+KGM:1600'

Pos: 0500 Repeat: 99

Mandatory

Group: 18 Elements: N/A

User Option (Usage): Must use

Segment Group Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Usage</u>
0510	MEA	Measurements	М	1	Must use

MEA Measurements

Pos: 0510 Max: 1 Mandatory

Group: 18 Elements: 3

User Option (Usage): Must use

Function: To specify physical measurements, including dimension tolerances, weights and counts.

Element Summary:

Ref MEA010	<u>Tag</u> 6311	Element Name Measurement purpose code qualifier	<u>Status</u> M	<u>Type</u> an	Min/Max 1/3	<u>Usage</u> Must use			
		Description: Code qualifying the purpose of the measurement.							
		CodeList Summary (Total Codes: 38, I Code Name AAE Measurement	ncluded:	1)					
MEA020	C502	MEASUREMENT DETAILS	С	Comp		Must use			
MEA020-010	6313	Measured attribute code	С	an	1/3	Must use			
		Description: Code specifying the attribute measured.							
		CodeList Summary (Total Codes: 90, I Code Name AAW Gross volume	ncluded:	1)					
MEA030	C174	VALUE/RANGE	С	Comp		Must use			
		Note: All other units of measure will be	rejected.						
MEA030-010	6411	Measurement unit code	М	an	1/3	Must use			
		Description: Code specifying the unit of measurement.							
		CodeList Summary (Total Codes: 130, Code Name MTQ cubic meter	Included	l: 1)					
MEA030-020	6314	Measurement value	С	an	1/18	Must use			
		Description: To specify the value of a r	measuren	nent.					

Segment Notes:

If the volume measurement applies to the total shipment (ASN level measurement) then provide this value only in the first GID loop.

Example:

MEA+AAE+AAW+MTQ:5

Pos: 0530 Repeat: 99 Conditional

Group: 19 Elements: N/A

User Option (Usage): Dependent

Segment Group Summary:

<u>Pos</u>	<u>Tag</u>	Segment Name	<u>Status</u>	<u>Rep</u>	<u>Usage</u>
0540	DIM	Dimensions	M	1	Must use

DIM Dimensions

Pos: 0540 Max: 1 Mandatory

Group: 19 Elements: 2

User Option (Usage): Must use **Function:** To specify dimensions.

Element Summary:

Ref DIM010	<u>Tag</u> 6145	Element Name Dimension type code qualifier	<u>Status</u> M	<u>Type</u> an	Min/Max 1/3	<u>Usage</u> Must use			
		Description: Code qualifying the type of	f the dim	ension.					
		CodeList Summary (Total Codes: 12, Inc. Code Name Pallet dimensions (incl.goods)	ncluded:	1)					
DIM020	C211	DIMENSIONS	М	Comp		Must use			
		Note: None other unit of measure than "meter" is accepted.							
DIM020-010	6411	Measurement unit code	М	an	1/3	Must use			
		Description: Code specifying the unit of measurement.							
		CodeList Summary (Total Codes: 130, Code Name MTR meter	Included	l: 1)					
DIM020-020	6168	Length dimension value	С	n	1/15	Must use			
		Description: To specify the value of a le	ength din	nension.					
DIM020-030	6140	Width dimension value	С	n	1/15	Must use			
		Description: To specify the value of a v	vidth dim	ension.					
DIM020-040	6008	Height dimension value	С	n	1/15	Must use			
		Description: To specify the value of a h	neight din	nension.					

Segment Notes:

This segment is mandatory if non-standard pallets are being shipped. You have to define the height, width and depth.

Example:

DIM+4+MTR:4:2:2'

Dimension of a pallet (including goods) using meters as unit measure:

Length: 4 Width: 2 Height: 2

UNT Message trailer

Pos: 0680 Max: 1 Mandatory

Group: N/A Elements: 2

User Option (Usage): Must use

Function: To end and check the completeness of a message.

Element Summary:

	<u>Ref</u>	<u>Tag</u>	Element Name	<u>Status</u>	<u>Type</u>	Min/Max	<u>Usage</u>
	UNT010	0074	Number of segments in a message	М	n	1/10	Must use
			Description: Control count of number of	f segmen	ts in a m	nessage.	
	UNT020	0062	Message reference number	М	an	1/14	Must use
Description: Unique message reference assigned by the sender.							

Segment Notes:

This segment is a mandatory UN/EDIFACT segment. It must always be the last segment in the message.

Example:

UNT+40+1'

UNZ INTERCHANGE TRAILER

Pos: 0690 Max: 1
Mandatory

Group: N/A Elements: 2

User Option (Usage): Must use

Function: To end and check the completeness of an interchange.

Element Summary:

<u>Ref</u>	<u>Tag</u>	Element Name	<u>Status</u>	<u>Type</u>	Min/Max	<u>Usage</u>
UNZ010	0036	Interchange control count	М	n	1/6	Must use
		Description: Count either of the num functional groups in an interchange.	ber of mess	ages or,	if used, of the	number of
UNZ020	0020	Interchange control reference	М	an	1/14	Must use
		Description: Unique reference assign	ned by the s	ender to	an interchand	ıe.

Segment Notes:

UNZ+1+99'