Create Dynamic Table for Structure using Runtime Type Identification (RTTI)

Created by Alexander Adam on Oct 03, 2017

Another variant to class CL_ALV_TABLE_CREATE that was described on the page

Dynamic Internal table

is the use of Runtime Type Identification classes (RTTI classes).

As described in the earlier blog, there are cases where the structure and table type are not known at design time. For example if you want to create a generic method with input parameters of 'type ref to data'. There are multiple descriptor classes provided by SAP Basis:

- CL ABAP TYPEDESCR
- CL ABAP DATADESCR
- CL ABAP STRUCTDESCR
- CL ABAP TABLEDESCR

see also https://help.sap.com/doc/abapdocu 750 index htm/7.50/en-US/abapassign mem area dynamic dobj.htm

Below some coding examples how to use them...

Create a dynamic structure

```
DATA Ir_structdescr TYPE REF TO cl_abap_structdescr.

DATA Ir_structure TYPE REF TO data.

Ir_structdescr ?= cl_abap_typedescr=>describe_by_data_ref( ir_data ).

CREATE DATA Ir_structure TYPE HANDLE Ir_structdescr.

ASSIGN Ir_structure->* TO FIELD-SYMBOL(<fs_structure>).
```

Create a dynamic table of a known structure

```
DATA Ir_table TYPE REF TO data.

DATA Ir_structdescr TYPE REF TO cl_abap_structdescr.

Ir_structdescr ?= cl_abap_typedescr=>describe_by_data_ref( ref #( Is_structure ) ).

DATA Ir_tabledescr TYPE REF TO cl_abap_tabledescr.

Ir_tabledescr ?= cl_abap_tabledescr=>create( p_line_type = Ir_structdescr ).

CREATE DATA Ir_table TYPE HANDLE Ir_tabledescr.

ASSIGN Ir_table->* TO FIELD-SYMBOL(<ft_table>).
```

You can of course add to the first example and create the dynamic table out of the dynamic structure

```
DATA Ir_structdescr TYPE REF TO cl_abap_structdescr. DATA Ir_structure TYPE REF TO data.
```

Ir_structdescr ?= cl_abap_typedescr=>describe_by_data_ref(ir_data).

CREATE DATA Ir_structure TYPE HANDLE Ir_structdescr.

Ir_tabledescr ?= cl_abap_tabledescr=>create(p_line_type = Ir_structdescr).

CREATE DATA Ir_table TYPE HANDLE Ir_tabledescr.

ASSIGN Ir_table->* TO FIELD-SYMBOL(<ft_table>).

Accessing a specific field of dynamic structure

ASSIGN COMPONENT 'key' OF STRUCTURE <fs_structure> TO FIELD-SYMBOL(<lv_key>).

Here 'key' is a data field of the structure.

No labels

Privacy Terms of Use Legal Disclosure Copyright Trademark Cookie Preferences