

SATORI Core — Install/Bootstrap & Public Hooks v1 Spec (v0.2)

Draft Baseline — Aug 2025

Executive Summary

SATORI Core provides the foundation for all SATORI plugins. It ensures a consistent bootstrap process, shared hooks,

and central update/licensing client. It is not a user-facing product but loads silently when any module requires it.

1. Goals

- Ensure every SATORI module can run standalone but seamlessly detect and load Core when needed.
- Provide a smooth, one-click Core installation flow from within WordPress.
- Define public hooks so developers can extend and integrate with SATORI modules safely.
- Act as the shared place for update/licensing client logic.

2. Core Guard

A reusable snippet included in all modules:

```
```php
require_once __DIR__ . '/../..//core/includes/CoreGuard.php';
\Satori\Shared\CoreGuard::guard(__FILE__, '0.2.0');
```
```

Responsibilities:

- Verify Core is installed and active at required minimum version.
- If missing, show an admin notice with one-click “Install/Activate Core” link.
- Handle multisite-awareness and permissions checks.
- Provide AJAX handler for silent install/activation.

3. Public Hooks

Hooks provided by Core for other modules:

- `satori/core/loaded` — Fires when Core is initialized.
- `satori/core/register\_capabilities` — For modules to register new caps.
- `satori/core/register\_settings\_tabs` — For modules to inject tabs in Tools/Settings.
- `satori/core/register\_telemetry` — For telemetry providers (opt-in).
- `satori/core/register\_update\_channels` — For modules to declare update endpoints.

4. Update Service Client

- Contacts ``updates.wordpressed.com.au`` for version checks.
- Implements ``pre_set_site_transient_update_plugins`` filter.
- Validates license keys (for PRO/Enterprise).
- Returns JSON with version, URL, changelog.
- Handles rollbacks and delta updates in roadmap.

5. Security

- Nonces and caps required for all Core actions.
- Sanitization and escaping at every I/O boundary.
- No direct file includes — always autoloaded.
- Secure CoreGuard install/activation with nonces.

6. Developer Contract

- Modules must call CoreGuard on load.
- Modules must declare ``const SATORI_MIN_CORE = 'x.x.x';``.
- All module hooks must use ``satori/{module}/...`` namespace.
- Comments follow boxed SATORI format.

Appendix A — Future Proofing

- Enterprise: SSO, org hierarchy, audit sink hooks (placeholders now).
- Shared UI components (tabs, lists, search).
- Shared Tables/Folders APIs.
- AI-assisted help panel injection point.