so we can use sensitivity $S = {}^{\prime}$ to assess performance (d) fundamental limits $S = \frac{1}{1+PC} = 1 - \frac{PC}{1+PC} = 1 - T$; plog/ $S(\mu)$ /dw is conserved

(a) transfer matrix [AMV2 Cla 6.3, 9.2] [NV7 Cla 4.11]

L) i.e a matrix of transfer functions relating a vector of inputs to a vector of outputs

ogner L71 system in state-space form, $\dot{x} = Ax + Bu$, $x \in \mathbb{R}^{N}$, $u \in \mathbb{R}^{N}$ when that $x(t) = e^{At}x(0) + \int_{0}^{t} e^{A(t-z)}Bu(z)dz$ so $y(t) = Ce^{At}x(0) + C\int_{0}^{t} e^{A(t-z)}Bu(z)dz + Du(t)$

olets see what output is produced by $u(t) = e^{st} \cdot u_0$, $s \in \mathbb{C}$, $u_0 \in \mathbb{R}^p$ $y(t) = Ce^{At}x(0) + Cf^{e}A(t-\tau)B[e^{s\tau}u]d\tau + De^{st}u$ $= C \int_{a}^{b} e^{A(t-z)} e^{sz} dz Bu_{o}$ $=e^{At} \cdot e^{-A\tau} \cdot e^{sT\tau} \leftarrow e^{s\tau} \cdot I = e^{sT\tau}$ $y(t) = Ce^{At}x(0) + Ce^{At} [\int_{0}^{t} e^{(sI-A)z} dz] \cdot B \cdot u_0 + De^{st} \cdot u_0$ -> evaluate this integral bint: find expression whose derivative is the integrand $e^{(sI-A)\tau}$ - recall that $\frac{d}{d\tau}e^{(sI-A)\tau} = (sI-A)e^{(sI-A)\tau}$ $-so \frac{d}{d\tau} \left[(sI-A)^{-1} e^{(sI-A)\tau} \right] = e^{(sI-A)\tau}$ wheris this matrix invertible?


(a) det(sI-A) ≠0 (a) s € \(\lambda(A)\), i.e. s is if an eigenvalue of A oso $\int_{0}^{t} e^{(sT-A)\tau} d\tau = \left[(sT-A)^{-1} e^{(sT-A)\tau} \right]_{\tau=0}^{\tau=t}$ $= (sI-A)^{-1} \left[e^{(sI-A)t} - e^{(sI-A)t} \right]$ $= e^{-At} \cdot e^{sIt} = e^{At} \cdot e^{st}$ =u(t)Mence

$$y(t) = Ce^{At}(x(o) - (sI - A)^{-1}Bu_o) + [C(sI - A)^{-1}B + D]e^{st}u_o$$

$$+ assuming A stable: transient response steady-state response$$

$$= > e^{At} > 0 \text{ as } t > \infty \qquad \rightarrow 0 \text{ as } t > \infty \qquad Gyn(s) \in \mathbb{R}^{oxp}$$

takeaway: given
$$\dot{x} = Ax + Bu$$
 get $Gyu(s) = ((sI-A)^{'}B+D)$
 $y = Cx + Du$ transfer matrix
(i.e. matrix of transfer functions)



guadrotor imputs
$$u = \begin{bmatrix} F_a \\ F_b \end{bmatrix}$$
 cutputs: $\begin{bmatrix} X \\ Z \end{bmatrix} = y$

$$ER^2$$

$$ER^3$$

$$Gyu = \begin{bmatrix} G_{XF_a} & G_{XF_b} \\ G_{3F_b} & G_{3F_b} \\ G_{9F_b} & G_{9F_b} \end{bmatrix}$$

$$G_{Mg}$$

so if
$$u(t) = e^{st} \cdot u_0 \in \mathbb{R}^2$$
 then $y(t) = e^{st} \cdot Gyu(s) \cdot u_0 \in \mathbb{R}^3$

o since a complex expanential input est.
$$u_0$$
 yields complex expanential autput est. $(qyu(s)\cdot u_0)$ and $(uvt) = lm e^{iwt}$, $w \in \mathbb{R}$ and $cos(wvt) = Reeiwvt$




Figure 9.17: Bode plots for low-pass, band-pass, and high-pass filters. The upper plots are the gain curves and the lower plots are the phase curves. Each system passes frequencies in a different range and attenuates frequencies outside of that range.

* note:
$$G(s) = \frac{b_1(s) b_2(s)}{a_1(s) a_2(s)}$$
 $\Rightarrow log |G| = log |b_1| + log |b_2| - log |a_1| - log |a_2|$
 $\Rightarrow \angle G = \angle b_1 + \angle b_2 - \angle a_1 - \angle a_2$

ex: (spring-mass-damper / RLC circuit)

 $m\ddot{g} + c\ddot{g} + \ddot{g} = u \text{ or } L\ddot{g} + Rg + \frac{1}{2}g = v \quad m_1 c_1 R > 0$
 $R_1 L_1 C_2 > 0$
 $R_1 L_1 C_2 > 0$
 $R_2 L_2 C_2 + R_3 = v \text{ or } L_3 C_2 + R_3 + \frac{1}{2}g = v \text{ or } L_3 C_3 + R_3 + \frac{1}{2}g = v \text{ or } L_3 - R_3 + R_3 + \frac{1}{2}g = v \text{ or } L_3 + R_3 + \frac{1}{2}g = v \text{ or } L_3 + R_3 + \frac{1}{2}g = v \text{ or } L_3 + R_3 + \frac{1}{2}g = v \text{ or } L_3 + R_3 + \frac{1}{2}g = v \text{ or } L_3 + R_3 + \frac{1}{2$

 $\sim G(s) = \frac{1}{ms^2 + cs + k}$ or = $\frac{1}{Ls^2 + Rs + k}$ note: as $s \rightarrow 0$, $G(s) \rightarrow 1/2$ or C, i.e. $|G(s)| \rightarrow constant$ $\angle G(S) \rightarrow O$ as $s \rightarrow \infty$, $G(s) \rightarrow \frac{1}{MS^2}$ or $\frac{1}{LS^2}$, i.e. $\log |G(j\omega)| \propto -2\omega$ so we can sketch Bode plot: log/qqw) | constant = 1/k or C slope or

(c) effect of disturbances [AMV2 (ln 12.1] [NV7 Ch 7.5]

cansider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back block diagram with disturbances:

The consider negative feed back diagram with disturbances and disturbances are disturbances.

The consider negative feed back diagram with disturbances are disturbances.

The consider negative feed back diagram with disturbances are disturbances.

The consider negative feed back diagram with disturbances are disturbances.


The consider negat

* assuming input disturbance v and output disturbance w are independent of other signals in the diagram, they affect y linearly: -y=w+y=w+Pu=w+P(v+u)=w+Pv+Pce= W + PN + PC(r - y)(I+PC)y = W + PV + PCFx assuming invertible $y = (I+PC)^{-1}w + (I+PC)^{-1}Pv + (I+PC)^{-1}PCr$ Gyr Gyv in single-input (ase: 1+PC + + PC -<u>P</u> v 1470 * the "ideal" transformations are different for each transformation: -ideally Gyr ~ I so that y = Gyr - r ~ r -ideally Gyv, Gyw ~ O so that v & w don't affect y (we'll see that we can't adrieve all "ideals" at the same time) 15(je) /> : oin terms of Bode plot: ISImox [log | S(jw)] disturbance w

amplified


1 / S/in/ < 1:

let S = Gaw be




- performance of closed-loop system can be assessed using peak sensitivity | S|max or crossover frequency were

(d) fundamental limits [AMV2 Ch 12.1, 14.2] consider the negative feedback block diagram with disturbances



orecall that
$$y = Gyr \cdot r + Gyv \cdot V + Gyw \cdot W$$

= $\frac{PC}{1+PC} \cdot r + \frac{P}{1+PC} \cdot N + \frac{1}{1+PC} \cdot W$



and we want: 1°. disturbances rejected, ie. Gyv, Gyw ~ O

2° references tracked, i.e. Gyr ~ 1

- Since
$$Gyw + Gyr = \frac{1}{1+PC} + \frac{PC}{1+PC} = \frac{1+PC}{1+PC} = 1$$

so Gyr ~ 1 => Gyw ~0, which seems great?

-> but this happy coincidence is misleading
return to block diagram and consider effect of disturbances viw on input u The contract of disturbances viw on input u The contract of disturbances viw on input u The contract of disturbances viw on input u
THE CULT PIDO
$\boxed{-1} \leftarrow 9^{-W}$
-> determine Gur, Guw, Guw s.t. U = Gur. T + Guw. V + Guw.
$-u = C(r - y) = Cr - C(w + P\mu) = Cr - Cw - CP(v + v)$
(1+PC)u = Cr - PCv - Cw
$(=) u = \frac{C}{1+PC} - \frac{PC}{1+PC} - \frac{C}{1+PC} $
= Gur. r + Guw. v + Guw. W
recall. $y = Gyr \cdot r + Gyv \cdot v + Gyw \cdot w$
= PC r + P .v + 1 1+PC 1+PC
observe: Gyw-Guv=1+PC+PC=1+PC=1
but we want to reject disturbances, i.e. Gym, Gun ~ O
we can't have both o
-> there's a tradeoff
oin many sustems, frommers material: exiciuise control

oin many systems, frequency content of: exicitise control input disturbance N is low — wind pushing on car output disturbance N is high — sensor noise so if we look at Bode plots: which means we can design S = 1/1 = (qyw (sersitivity) Alog SI, log TI $T = 1 - S = \frac{PC}{|+PC|} = -G_{uv}$ (complementary sensitivity) to design frequency-dependent (complementary) sencitivity of turns out there are limits on how we can reshape S tem: (Bode integral formula / argument principle) Solog | S(jw) | dw > constant, independent of C = T. E { Rep | p is a pole of P in right-half place}

= O if process is stable * since log | SGW) | <0 (=> | SGW) | <1 (=> disturbance affervalled one range of frequencies where contabler attemates disturbance

