



Clothing

Beginner Poncho

HOOK
5.0 mm (H-8)

LEVEL
Beginner

TIME
10-11 hrs

YARN
Worsted weight (#4) acrylic or cotton blend

One size, fits most adults (S-XL). Each panel is about 28 in (71 cm) wide and 20 in (51 cm) long, with a neck opening of about 12 in (30 cm). Measurements are approx. See the tips to adjust

Materials

- Worsted weight yarn, about 670 yd (609 m)
- 5.0 mm (H-8) crochet hook
- Yarn needle
- Stitch markers or pins
- Scissors

Stitch guide (US terms)

ch = chain

sl st = slip stitch

sc = single crochet

dc = double crochet

st = stitch(es)

Pattern

Panel (make 2)

Worked in flat rows. Turning chains do not count as stitches. Both panels are identical.

Row 1	ch 93, dc in 4th ch from hook and in each ch across	(90)
Rows 2-40	ch 2, turn, dc in each st across	(90)
Finish	Fasten off and weave in the ends.	

Assembly

Lay the panels flat with right sides together and the top edges matching (the top edge is the last row).

Mark	Count 26 st in from each side edge and mark it with a pin. The 38 st in the middle are the neck opening	
Shoulders	Seam each shoulder: sl st through both layers across the 26 st, 1 sl st in each pair of st. Leave the middle unjoined. Fasten off. Do the same at the other side edge	(26)
Rnd 1	Turn right side out. Join yarn at a shoulder seam. Ch 1, sc in each st across the front neck edge (38), sc in each st across the back neck edge (38), sl st to the first sc	(76)
Rnd 2	ch 1, sc in each st around, sl st to the first sc. Fasten off and weave in the end	(76)

Finishing

1. Weave in all the ends.
2. Wet block or steam lightly. Lay the poncho flat, pat it into shape and let it dry.
3. Try it on. The side edges are open, so your arms come out at the sides and the poncho drapes over the shoulders.

Tips

- To change the width, add or remove 13 st for every 4 in (10 cm). Keep the neck opening at 38 st or more so it goes over your head.
- To change the length, work 2 rows for every 1 in (2.5 cm) you want to add or remove, on both panels.
- If your poncho is too stretchy, use a hook one size smaller for the neck rounds.

Sizes are approximate and depend on your yarn and tension. The photo is an illustration of the finished piece. For your personal use.