



Home Decor

Boho Wall Hanging

HOOK
5.0 mm (H-8)**LEVEL**
Intermediate**TIME**
2-3 hrs**YARN**
Worsted weight (#4) cotton or acrylic

About 10 in (25 cm) wide and 19 in (48 cm) long from the dowel to the tips of the fringe, approx.

Materials

- Cream yarn, about 71 yd (64 m), including the fringe and hanging cord
- Terracotta yarn, about 38 yd (34 m), including the fringe
- Sage green yarn, about 15 yd (13 m)
- 5.0 mm (H-8) crochet hook
- A wooden dowel, 12 in (30 cm) long and 3/8 in (1 cm) thick
- Yarn needle
- Scissors
- Tape measure

Stitch guide (US terms)

ch = chain**dc** = double crochet**st** = stitch(es)

Pattern

Panel

Worked flat in rows. The first 3 rows will be folded over the dowel. Carry cream up the side edge when it returns after 4 rows and cut the other colors each time you change.

Row 1	With cream, ch 35. Dc in 4th ch from hook (the 3 skipped ch count as the first dc) and in each ch across	(33)
Rows 2-6	Ch 3 (counts as first dc), turn, skip the first st, dc in each of the next 31 st, dc in the top of the turning ch. In the last dc of Row 6, change to terracotta	(33)
Rows 7-10	Repeat the row as above. In the last dc of Row 10, change to cream	(33)
Rows 11-14	Same row. In the last dc of Row 14, change to sage	(33)
Rows 15-18	Same row. In the last dc of Row 18, change to cream	(33)
Rows 19-22	Same row. In the last dc of Row 22, change to terracotta	(33)
Rows 23-26	Same row. In the last dc of Row 26, change to cream	(33)
Rows 27-30	Same row. Fasten off after Row 30 and weave in the ends	(33)

Fringe

Cut all the strands first: 51 strands of 12 in (30 cm).

Cut	Cut 27 cream strands and 24 terracotta strands, each 12 in (30 cm) long. Use 3 strands for each fringe (9 cream and 8 terracotta fringes in all).
Attach	Along the bottom edge (Row 30), fold 3 strands in half. Pull the fold through a stitch from the front with the hook, pull the ends through the loop and tighten. Add a fringe in every other st, starting with the first st (17 fringes), alternating cream and terracotta and starting and ending with cream.
Trim	Trim the fringe evenly to about 5 in (12.5 cm).

Finishing

1. Weave in the ends. Lay the panel flat with the wrong side up and fold the first 3 rows (the casing) over the dowel.
2. With cream yarn and the needle, sew the fold to the back of the panel with a running stitch, under the top row. The dowel should turn freely.

3. Cut a 30 in (76 cm) length of cream yarn (use it doubled) and tie each end to the dowel, 2 in (5 cm) in from the ends, to make a hanging loop.
4. Add the fringe along the bottom edge and trim it even.

Tips

- Check the width before you start the stripes: 33 dc should measure about 10 in (25 cm). Adjust with hook size.
- For a wider hanging, add 6 st per extra 2 in (5 cm) and a longer dowel. Keep an odd number of stitches so the fringe starts and ends on the edge.
- For a softer look, use 4 strands for each fringe and comb the ends with a wide-toothed comb.

Sizes are approximate and depend on your yarn and tension. The photo is an illustration of the finished piece. For your personal use.