# Safe module unloading and module finalization in the Oberon operating system

Andreas Pirklbauer

1.5.2022

#### Overview

Most implementations of the Oberon<sup>1</sup> operating system only check for *client* references prior to module unloading. Other types of module references are usually not checked, although various approaches are typically employed to alleviate the situation where such references do exist. In addition, the unloading of groups of modules with (potentially cyclic) references only among themselves and module finalization are usually not supported. See the appendix for historical notes on module unloading in the Oberon operating system.

Checking only some, but not all references to a module prior to unloading it leaves a system in an unsafe state, which may – and generally will – become unstable the moment another module loaded later overwrites a previously released module block.

This technical note describes an implementation of completely safe unloading of modules and module groups and module finalization, as realized in Extended Oberon<sup>2</sup>, a revision of the Project Oberon 2013 system, which is itself a reimplementation of the original Oberon system on an FPGA development board around 2013, as published at www.projectoberon.com.

# Module references in the Oberon system

An Oberon module can be viewed as a container of constants, types, variables and procedures. where variables may be procedure-typed. Global objects with an explicit name declared in a module are allocated in the *module area* when the module is loaded. If exported, such static objects may be referenced by name in client modules. Anonymous variables with no explicit name declared in a module are allocated in a dynamic space called the heap when needed during program execution through invocation of the intrinsic procedure NEW. Such dynamic objects may be reachable by named pointer variables declared in any of the loaded modules.

In the Oberon system, there exist several possible types of references to a loaded module M:

- 1. Client references exist when other loaded modules import module M. Client modules may refer by name to exported constants, types, variables or procedures declared in module M.
- 2. Type references exist when type tags (addresses of type descriptors) in dynamic objects reachable by other loaded modules refer to descriptors of types declared in module M<sup>3</sup>.

Wirth N. and Gutknecht J.: The Oberon System, Computer Science Report 88, ETH Zürich (1988).

http://www.github.com/andreaspirklbauer/Oberon-extended

Interprogramming language Oberon, pointer types are said to be "bound" to their base types, giving rise to additional (hidden) references from dynamic objects to descriptors of types declared in any of the loaded modules. The concept of "pointer binding", first implemented in the language Algol W and later adopted in Pascal, Modula-2 and Oberon, is essential for guaranteeing type safety, as it permits the validation of pointer values at the time of compilation without loss of run-time efficiency and in addition enables run-time type checks on dynamic objects

- 3. *Procedure variable references* exist when procedure variables in static or dynamic objects reachable by other loaded modules refer to procedures declared in module M.
- 4. Pointer variable references to static module data exist when pointer variables in static or dynamic objects reachable by other loaded modules refer to static objects declared in module M. Such references are only possible by resorting to low-level facilities and should be avoided (pointer variables should point exclusively to anonymous variables allocated in the heap when needed during program execution). But since they can in theory exist and the required metadata (locations of all pointer variables) is already present for other reasons<sup>4</sup>, a specific implementation may opt to also check for them prior to module unloading.

Note that pointer variable references to dynamic objects in the heap reachable by the modules to be unloaded are *not* considered as *module references* and therefore *should* not prevent module unloading. The Oberon garbage collector will handle such references during a future garbage collection cycle (heap objects that *were* reachable *only* by previously unloaded modules will automatically be collected).

# Implementing safe module unloading

In order to make module unloading *safe*, *all* possible types of references to a loaded module or module group must be checked. In Extended Oberon, this is done as follows (see Figure 1):

- If clients exist among other loaded modules, a module or module group is never unloaded.
- If no references to the module or group of modules to be unloaded exist in the remaining modules and data structures, it is unloaded *and* its associated memory is released.
- If no clients, but type, procedure or pointer variable references to static module data of the specified modules exist, the module *unload* command takes no action by default and merely displays the names of the modules and the references that caused the removal to fail.
- If, however, the *force* option /f is specified in the module *unload* command, the modules to be unloaded are initially removed only from the *list* of loaded modules, without releasing their associated memories (*module blocks*). Such "hidden" modules are later physically removed from *memory* using the command *Modules.Collect* (or the command *System.Collect* which also invokes *Modules.Collect*), as soon as no more references to these modules exist.




Figure 1: Safe module unloading in Extended Oberon

<sup>&</sup>lt;sup>4</sup> The Oberon garbage collector uses the locations of pointer variables during its "mark" phase.

Removing a module only from the module *list* amounts to *renaming* it, with the implication that a newer version of the same module with the same (original) name can be reloaded again, without having to unload (from memory) earlier versions that are still referenced by other modules<sup>5</sup>. By contrast, unloading a module from *memory* physically frees up the memory area previously occupied by its module block<sup>6</sup>. In Extended Oberon, this is only possible when no more module references of any kind to the module block exist from anywhere in the system.

To automate the process of unloading no longer referenced hidden module data from memory, the command *Modules.Collect* is included in the background task handling garbage collection<sup>7</sup>. It checks all possible combinations of *k* modules chosen from *n* hidden modules for references to them, and removes those module subgroups from memory that are no longer referenced.

In sum, module data is kept in memory for exactly as long as necessary and removed from it as soon as possible.

For example, older versions of a module's code can still be executed if they are referenced by static or dynamic procedure variables in other loaded modules, even if a newer version of the same module has been reloaded in the meantime8.

Type descriptors also remain accessible to other modules for exactly as long as needed. This covers the important case where a structure rooted in a variable of base type T declared in a base module M contains elements of an extension T' defined in a client module M', which is unloaded. Such elements typically contain both type references (type tags) and procedure variable references (installed handlers) referring to M'.

If a module *group* is to be unloaded and there exist references *only* within this group, the group is unloaded as a whole<sup>9</sup>. This can be used to remove module groups containing cyclic references<sup>10</sup>. It is also possible to release entire subsystems of modules. The command System. FreeImports attempts to unload the specified modules and all their direct and indirect imports. It may be used for conventional module stacks with a single top module, for example a compiler. By contrast, the command System. Free Clients unloads the specified modules and all their direct and indirect clients. This variant may be used for module stacks written in the object-oriented programming style with their typically inverted module hierarchy, for example a graphics editor.

Note, however, that these unloading strategies amount to heuristics and may tend to unload rather large parts of the system, which may not be desired. Therefore, the recommended way to unload modules is to use the base command System. Free with a specific set of modules provided as parameters. For added convenience, the tool commands System. ShowReferences and System. Show Group References are provided to identify all modules containing references to a given module or module group.

<sup>5</sup> Modules removed only from the module list are marked with an asterisk in the output of the command System ShowModules. Commands of such "hidden" modules can be accessed by either specifying the module number or the modified module name. Typical use cases include hidden modules that have still open viewers or installed background tasks. If the command to close a viewer is displayed in the viewer's menu bar, the user can manually edit the command text (by clicking within its bottom 2 pixel lines) and prepend an asterisk to the module name or replace it with the module number. A more convenient alternative approach is to provide a "Close" command that also accepts the marked viewer as argument, using procedure Oberon. Marked Viewer.

6 In Project Oberon 2013 and Extended Oberon, the module block also contains the module's type descriptors. In some other Oberon implementations, such as Ceres-Oberon, type descriptors are not placed in the module block, but are allocated in the heap at module load time in order to persist them beyond the lifetime of their associated modules. In Extended Oberon, no such extra precaution is necessary, as module blocks that are still referenced are only removed from the module list, but not from memory.

Note that the garbage collector itself must also include the global pointer variables of hidden modules as roots of graphs of heap objects to be traversed, as they could still be referenced, for example when a procedure of a hidden module is called or when global pointer variables of a hidden module are accessed.

If an older variable of a module is called or when global pointer variables of a hidden module are accessed.

If an older version of a module's code accesses global variables (of itself or of other modules), it will automatically access the "right" version of such variables. <sup>9</sup> Since the modules to be unloaded may have module finalization sequences, they are unloaded in the "right" order (i.e. in reverse order of loading).

Since the modules to be unbadied may have involunt minutation sequences, any are unbaded in the right white (i.e., in level as of the involunt), in the control of the involunt minutation is equence of compilation and lediting steps, it is actually possible to construct cyclic module imports, which cannot be detected by the compiler. But even though they can be created, such modules are not allowed to be loaded, as the module loader of Extended Oberon – adopting the approach chosen in Original Oberon and Project Oberon 2013 – would enter an endless recursion, eventually leading to a stack overflow or out-of-memory condition - a totally acceptable solution for such a pathological case. When unloading module groups, Extended Oberon assumes that no cyclic module imports exist.

## Implementation aspects

In our implementation, the module *unload* command *System.Free* first "selects" the module or module group to be unloaded using an auxiliary procedure *Modules.Select* before invoking the reference checking procedure *Modules.Check*.

Client references are always checked first. This is as simple as verifying whether *unselected* modules import *selected* modules<sup>11</sup>:

```
PROCEDURE FindClients*(client: ClientHandler; VAR res: INTEGER);
2
     VAR mod, imp, m: Module; p, q: INTEGER; continue: BOOLEAN;
    BEGIN res := noref; m := root; continue := client # NIL:
     WHILE continue & (m # NIL) DO
5
      IF (m.name[0] # 0X) & m.selected & (m.refcnt > 0) THEN mod := root;
6
        WHILE continue & (mod # NIL) DO
         IF (mod.name[0] # 0X) & ~mod.selected THEN p := mod.imp; q := mod.cmd;
7
8
          WHILE p < q DO (*imports*) imp := Mem[p];
9
           IF imp = m THEN INC(res, client(mod, imp, continue)); p := g ELSE INC(p, 4) END
10
          END
         END;
11
         mod := mod.next
12
13
       END
14
      END:
15
      m := m.next
16
     END
    END FindClients;
```

If clients exist among the *unselected* modules, no further action is taken and the module *unload* command exits. If no clients exist, *type*, *procedure* and *pointer variable* references from objects allocated in the heap<sup>12</sup> are checked next, using a conventional *mark-scan* scheme:

```
PROCEDURE FindDynamicReferences*(typ, ptr, pvr: RefHandler;
2
     VAR resTyp, resPtr, resPvr: INTEGER; all: BOOLEAN);
3
     VAR mod: Module:
    BEGIN mod := root;
4
     WHILE mod # NIL DO
5
      IF (mod.name[0] # 0X) & ~mod.selected THEN
7
       Kernel.Mark(mod.ptr);
       IF ~all THEN Kernel.Scan(typ, ptr, pvr, mod.name, resTyp, resPtr, resPvr) END
8
9
      END;
10
      mod := mod.next
11
     IF all THEN Kernel.Scan(typ, ptr, pvr, "", resTyp, resPtr, resPvr) END
12
    END FindDynamicReferences;
```

During the initial *mark* phase, objects reachable by all named global pointer variables of some or all *other* loaded modules are marked (line 7), thereby excluding objects reachable *only* by the modules to be unloaded. This automatically recognizes module *groups* and ensures that when a module group is referenced *only* by itself, it can still be safely unloaded. An additional boolean parameter *all* allows the caller to indicate whether the *mark* phase should first mark all heap objects reachable by *all* other loaded modules before initiating the *scan* phase *once* (used for module unloading), or whether *both* the mark and the scan phase should be initiated for *each* unselected module (used for identifying references from each unselected module *individually*).

<sup>11</sup> Mem stands for the entire memory and assignments involving Mem are expressed as SYSTEM.GET(a, x) for x := Mem[a] and SYSTEM.PUT(a, x) for Mem[a] := x.

<sup>12</sup> In Project Oberon 2013, only records can be dynamically allocated using the predefined procedure NEW. In Extended Oberon, fixed-length and open arrays can also be allocated.

The subsequent *scan* phase (line 8, 12), implemented as a separate procedure *Scan* in module *Kernel*<sup>13</sup>, scans the heap sequentially, unmarks all *marked* objects<sup>14</sup> and checks whether their *type tags* point to descriptors of *types* and whether *procedure* or *pointer variables* declared in those same objects refer to *procedures* or *static objects* of the modules to be unloaded.

In order to omit in module *Kernel* any reference to the list of modules rooted in module *Modules*, procedure *Scan* is expressed as a *generic* object traversal scheme, which accepts *parametric* handler procedures that are called for each encountered object with the *source* and *destination* of the potential reference as parameters. The following is a simplified version of this scheme<sup>15</sup>:

```
PROCEDURE Scan*(typ, ptr, pvr: Handler; s: ARRAY OF CHAR; VAR resTyp, resPtr, resPvr: INTEGER);
 2
     VAR offadr, offset, p, r, mark, tag, size, pos, len, elemsize, blktyp: LONGINT; continue: BOOLEAN;
 3
    BEGIN p := heapOrg; resTyp := 0; resPtr := 0; resPvr := 0;
 4
     continue := (typ # NIL) OR (ptr # NIL) OR (pvr # NIL);
 5
     REPEAT mark := Mem[p+4];
       IF mark < 0 THEN (*free*) size := Mem[p]
 6
       ELSE (*allocated*) tag := Mem[p]; size := Mem[tag]:
 7
 8
        IF mark > 0 THEN (*marked*) Mem[p+4] := 0;
 9
         IF continue THEN
10
           IF typ # NIL THEN INC(resTyp, typ(p, tag, s, continue)) END;
          IF continue & ((ptr # NIL) OR (pvr # NIL)) THEN
11
            offadr := tag + 16; offset := Mem[offadr]
12
13
            WHILE continue & (offset # -1) DO (*pointers*)
             IF ptr # NIL THEN r := Mem[p+8+offset]; INC(resPtr, ptr(p+8+offset, r, s, continue)) END;
14
15
             INC(offadr, 4); offset := Mem[offadr]
16
            END;
17
            IF continue & (pvr # NIL) THEN
18
             INC(offadr, 4); offset := Mem[offadr]
19
             WHILE continue & (offset # -1) DO (*procedures*) r := Mem[p+8+offset];
20
              INC(resPvr, pvr(p+8+offset, r, s, continue));
21
              INC(offadr, 4); offset := Mem[offadr]
22
             END
23
            END
24
          END
25
         END
26
        END
27
       END:
28
       INC(p, size)
29
     UNTIL p >= heapLim
    END Scan;
30
```

where the handler procedures typ, ptr and pvr are invoked as follows for each marked object:

- Procedure *typ* is called with the address of (the *type tag* of) the heap object as the *source* of the potential reference that is to be checked, followed by the address of the referenced type descriptor as its *destination* (line 10).
- Procedure ptr is called for each pointer variable in the heap object with the address of the
  pointer variable passed as the source, followed by the address of the referenced object
  passed as the destination (line 14).

<sup>&</sup>lt;sup>13</sup> The original procedure Kernel. Scan (implementing the scan phase of the Oberon garbage collector) has been renamed to Kernel. Collect – in analogy to procedure Modules. Collect.

<sup>14</sup> We could have decided not to unmark the marked heap objects at this stage and simply collect the unmarked objects using Modules. Collect in a separate scan phase, if no references to the modules to be unloaded have been found. This would effectively invoke the Oberon garbage collector immediately, i.e. during module unloading. We have refrained from introducing this (negligible) optimization, in order to guarantee that the stack is empty during garbage collection (which is not necessarily the case during module unloading, as the command Modules. Free might – in theory – be invoked by another Oberon command)

<sup>15</sup> The simplified version scans only record blocks allocated in the heap via NEW(p), where p is a POINTER TO RECORD. The full implementation also covers array blocks.

• Procedure *pvr* is called for each *procedure variable* in the heap object with the address of the procedure variable passed as the *source*, followed by the address of the referenced procedure passed as the *destination* (line 20).

The results of these calls are *separately* added up for each handler and returned via the variable parameters *resTyp*, *resPtr* and *resPvr*. By convention, a result of zero indicates that no reference has been found. Apart from that, handler procedures are free to define the semantics of their return values. An additional boolean variable parameter *continue* allows a handler procedure to indicate to the caller that it is no longer to be called (lines 9, 11, 13, 17, 19). The scan process itself continues, but only to *unmark* the remaining marked heap objects (line 8).

Finally, the check for procedure and pointer variable references to static module data of the modules to be unloaded is also performed for all *global* pointer and procedure variables of all other loaded modules, whose offsets in their corresponding module's data section are obtained from two arrays in their module's *meta* data section, headed by the links *mod.ptr* and *mod.pvr*:

```
PROCEDURE FindStaticReferences*(ptr, pvr: RefHandler; VAR resPtr, resPvr: INTEGER);
 1
     VAR mod: Module; pref, pvadr, r: LONGINT; continue: BOOLEAN;
 2
    BEGIN resPtr := noref; resPvr := noref; mod := root; continue := (ptr # NIL) OR (pvr # NIL);
 4
     WHILE continue & (mod # NIL) DO
 5
       IF (mod.name[0] # 0X) & ~mod.selected THEN
 6
        IF ptr # NIL THEN
 7
         pref := mod.ptr; pvadr := Mem[prefl:
 8
         WHILE continue & (pvadr # 0) DO (*pointers*) r := Mem[pvadr];
          INC(resPtr, ptr(pvadr, r, mod.name, continue));
 9
10
          INC(pref, 4); pvadr := Mem[pref]
         END
11
12
        END:
        IF pvr # NIL THEN
13
14
         pref := mod.pvr; pvadr := Mem[pref];
         WHILE continue & (pvadr # 0) DO (*procedures*) r := Mem[pvadr];
15
          INC(resPvr, pvr(pvadr, r, mod.name, continue));
16
17
          INC(pref, 4); pvadr := Mem[pref]
18
         END
19
        END
20
       END;
21
      mod := mod.next
22
     END
23
    END FindStaticReferences;
```

We note that the procedures *FindClients, FindDynamicReferences* and *FindStaticReferences* are also expressed as *generic* object traversal schemes, which – similar to procedure *Scan* – accept parametric handler procedures that are invoked for each encountered object. This allows these procedures to be used for other purposes as well, for example to *enumerate* all references to a given module or module group.

For example, the reference checking procedure *Modules.Check* itself passes its own (private) handler procedures, which merely set the boolean variable parameter *continue*, depending on whether a reference to any of the selected modules has been found or not anywhere in the system. In passing, we remark that *Modules.Check* is not only called when a module is unloaded by the *user*, but also by the Oberon *background task* that removes no longer referenced *hidden* module data from memory. Thus, it must be written such that it can handle both visible *and* hidden modules in the data structure rooted in module *Modules*.

## Implementation prerequisites

In order to make the outlined validation pass possible, type descriptors of dynamic objects in the heap<sup>16</sup> and descriptors of global module data in the *static* module blocks now also contain the locations of all procedure variables (in addition to the locations of all pointer variables, which are already present for other reasons) within the described object, adopting an approach employed in one of the earlier implementations of the Oberon system (MacOberon)<sup>17</sup>.

The descriptors also contain the offsets of *hidden* (not exported) procedure variables, enabling the module unload command to check all static and dynamic procedure variable locations in the entire system for possible procedure variable references to the selected modules to be unloaded. The resulting run-time representations of a heap record with its associated type descriptor and a static module block are shown in Figure 2 (the method table used to implement Oberon-2 style type-bound procedures is not discussed here).




Figure 2: Run-time representation of a dynamic record with its type descriptor and a module block in Extended Oberon

To make the offsets of hidden procedure variables in exported record types available to clients, symbol files also include them. An importing module may, for example, declare a variable of an imported record type, which contains *hidden* procedure variable fields, or declare a record type, which contains (or extends) an imported type. We recall that in Project Oberon 2013, hidden pointers, although not exported and therefore invisible in client modules, are included in symbol files because their offsets are needed for garbage collection. Similarly, in Extended Oberon, hidden procedure variables are included in symbol files because their offsets are needed for reference checking prior to module unloading, as illustrated in the following example:

<sup>16</sup> See chapter 8.2 of the book Project Oberon 2013 Edition for a description of an Oberon type descriptor. In essence, it contains information that is shared by all dynamically allocated records of the same type, such as its size, information about type extensions and the offsets of pointer and procedure variable fields. 

17 http://e-collection.library.ethz.ch/eserv/eth:3269/eth-3269-01.pdf (The Implementation of MacOberon, 1990)

```
1
    MODULE MO:
 2
     TYPE P* = PROCEDURE; R* = RECORD p: P END;
                                                                        (*hidden record field p, visible only in M0*)
 3
     PROCEDURE Init*(VAR r: R; p: P); BEGIN r.p := p END Init;
                                                                        (*install procedure p in hidden field r.p*)
 4
    END M0.
 5
 6
    MODULE M1:
 7
     IMPORT M0;
 8
     VAR r: M0.R;
                                                                        (*global variable r with hidden field r.p*)
 9
     PROCEDURE Init*(p: M0.P); BEGIN M0.Init(r, p) END Init;
10
    END M1.
11
    MODULE M2;
12
13
     IMPORT M1;
     PROCEDURE P; BEGIN END P;
14
     PROCEDURE Clear*; BEGIN M1.Init(NIL) END Clear;
15
                                                                       (*clear reference from M1.r.p*)
16
     PROCEDURE Init*; BEGIN M1.Init(P) END Init;
                                                                       (*create reference from M1.r.p to M2.P*)
17
18
                                      unloading successful (as no references to M2 exist)
19
    M2.Clear
                System.Free M2 ~
20
    M2.Init
                System.Free M2 ~
                                      unloading failed (procedures of M2 in use in global procedure variables of M1)
```

Here the global record variable *r* declared in module *M1* (line 8) is of an imported record type *M0.R*, which contains a *hidden* procedure variable field *r.p*, visible only in M0. If another module *M2* installs a procedure *M2.P* in this field (line 16), a hidden global procedure variable reference from *M1.r.p* to *M2.P* is created, with the intended effect that *M2* can no longer be unloaded (line 20). In order to be able to check for such hidden references, the location of *M1.r.p* within the module block of *M1* must be known at run time. This is accomplished as follows:

- The offset of the *hidden* record field *p* of the record type *M0.R* is also included in the *symbol* file of *M0*, when M0 is compiled.
- The location of the procedure variable *M1.r.p* within the data section of *M1* (computed as the sum of the start address of the global record *M1.r* and the offset of the hidden field *M0.R.p* imported from M0) is included in the *object* file of *M1*, when M1 is compiled.
- The location of *M1.r.p* is transferred from the object file of *M1* to the corresponding array in the *meta* data section in the module block, headed by the link *mod.pvr*, when *M1* is loaded.

Hidden *pointers* are included in symbol files without their names, and their (imported) type in the symbol table is of the form *ORB.NilTyp* (as with Project Oberon 2013). Hidden *procedure variables* are also included in symbol files without their names, but their (imported) type in the symbol table is of the form *ORB.NoTyp*<sup>18</sup>. This choice is reflected in the conditions used to find *all* pointers and procedure variables in various procedures of the compiler<sup>19</sup>, as illustrated in the following code excerpt of its symbol table handler (module ORB):

```
TYPE Ptrs* = {Pointer, NilTyp};
 1
                                                     (*NilTyp = hidden pointer variable*)
 2
     Procs* = {Proc, NoTyp};
                                                     (*NoTyp = hidden procedure variable*)
 3
    PROCEDURE FindHiddenFields(VAR R: Files.Rider; typ: Type; off: LONGINT);
 4
     VAR fld: Object; i, s: LONGINT;
 5
     IF tvp.form IN Ptrs THEN Write(R. Fld): Write(R. 0): Files.WriteNum(R. off)
     ELSIF typ.form IN Procs THEN Write(R, Fld); Write(R, 0); Files.WriteNum(R, -off-1)
     ELSIF typ.form = Record THEN fld := typ.dsc;
 9
       WHILE fld # NIL DO FindHiddenFields(R, fld.type, fld.val + off); fld := fld.next END
10
11
     ELSIF typ.form = Array THEN s := typ.base.size;
```

<sup>&</sup>lt;sup>18</sup> This is acceptable because for record fields, the types ORB.NilTyp and ORB.NoTyp are not used otherwise.

<sup>&</sup>lt;sup>19</sup> See procedures ORB.FindHiddenFields, ORG.FindRefFlds, ORG.NofRefs and ORG.FindRefs

```
FOR i := 0 TO typ.len-1 DO FindHiddenFields(R, typ.base, i*s + off) END END END FindHiddenFields;
```

The reader may wonder whether on systems, where Oberon-2 style *type bound procedures* are implemented, it is necessary to also check for *method* references. The answer is *no* for several reasons. First, if a structure rooted in a variable of base type T declared in a base module M contains elements of an *extension* T' defined in a client module M', such elements already contain *type* references (type tags) referring to module M', no matter whether the client module M' also redefines a method exported by module M. Since *type* references are always checked prior to module unloading, there is no need to *also* check for *method* references. Second, *hidden* methods are (by definition) not exported and therefore cannot be redefined in client modules.

#### Module finalization

A module can set a *module finalization* sequence using the language construct FINAL followed by the finalization sequence. A standalone program cannot set a module finalization sequence.

```
MODULE M;
2
     IMPORT Texts, Oberon;
3
     VAR W: Texts.Writer;
4
5
6
     PROCEDURE Start*;
7
     BEGIN (*load module*)
8
     END Start;
9
10
    BEGIN
     Texts.OpenWriter(W)
11
12
     Texts.WriteString(W, "Finalizing module M"); Texts.WriteLn(W); Texts.Append(Oberon.Log, W.buf)
13
14
    END M.
15
16
    ORP.Compile M.Mod/s ~
                              # compile module M
    M.Start ~
17
                              # load module M
                              # unload module M (prints "Finalizing module M")
18
    System.Free M ~
```

Alternatively, the *finalization* sequence can also be set by calling procedure *Modules.SetFinalizer* during *module initialization*. The specified routine must be a *parameterless* procedure declared in the *same* module and is executed when the module is unloaded.

```
1
    MODULE M:
2
     IMPORT Modules, Texts, Oberon;
3
4
     VAR W: Texts.Writer;
5
6
     PROCEDURE Finalize; (*module finalization sequence*)
7
     BEGIN Texts. WriteString(W, "Finalizing module M");
8
      Texts.WriteLn(W); Texts.Append(Oberon.Log, W.buf)
9
     END Finalize;
10
     PROCEDURE Start*;
11
12
     BEGIN (*load module*)
13
     END Start:
14
    BEGIN Texts.OpenWriter(W); Modules.SetFinalizer(Finalize)
15
    END M.
16
```

17

- 18 ORP.Compile M.Mod/s ~
- 19 M.Start ~
- # compile module M
- # load module M
- 20 System.Free M ~ # unload module M (prints "Finalizing module M")

#### Assessment of the outlined solution

An obvious shortcoming of the reference checking scheme outlined above is that it requires additional run-time information to be present in all type descriptors of all modules solely for the purpose of reference checking, which in turn is only needed in the relatively infrequent case of module releases. In addition, module blocks now also contain an additional meta data section containing the offsets of global procedure variables. However, since there exists only one type descriptor per declared record type rather than one per allocated heap record, and global procedure variables tend to be rare, the additional memory requirements are negligible<sup>20</sup>.

Although the operation of reference checking may appear expensive at first, in practice there is no performance issue. It is comparable in complexity to garbage collection and therefore barely noticeable – at least on systems with small to medium sized dynamic spaces (heaps). This is in spite of the fact that for each heap object encountered during the mark phase all modules to be unloaded are checked for references during the subsequent scan phase. However, reference checking stops when the first reference is detected and module unloading is rare except, perhaps, during development.

Thus, the presented solution, which was mainly chosen for its simplicity, appears to be amply sufficient for most practical purposes. We have therefore resisted the temptation to introduce additional "optimizations", whose benefits are often questionable.

<sup>&</sup>lt;sup>20</sup> Adding procedure variable offsets to type descriptors is, strictly speaking, not necessary, as the compiler can always rearrange the memory layout of a record such that all procedure variable fields are placed in a contiguous section at the beginning of it, making their offsets implicit. Thus, it is in principle possible to realize the reference checking scheme without any additional fields in type descriptors. We have refrained from implementing this refinement for two main reasons. First, it would increase the complexity of the compiler. At first glance, it might seem that in order to rearrange a record's field list, only a small change needs to be made to a single procedure in the compiler (ORP.RecordType in Project Oberon 2013). However, a complication arises because records may recursively contain other records, each again containing procedure variables at arbitrary offsets. While it is always possible to "flatten" such recursive record structures, it would make other record operations more complex. For example, assignments to subrecords would become less natural, as their fields would no longer be placed in a contiguous section in memory. Second, the memory savings in type descriptors are marginal, given that there exists only one type descriptor per record type rather than one per allocated heap record. Most applications are (or should be) programmed in the conventional programming style, where installed procedures are rare. For example, in the Oberon system, the object-oriented programming style is restricted to the viewer system, which provides distributed control in the form of installed handlers – of which there is usually only one per type of viewer. In sum, the benefit obtained by saving a few fields in a relatively small number of type descriptors is negligible, and therefore the additional effort required to implement this refinement would be hard to justify indeed.

# Appendix: Historical notes on module unloading in the Oberon operating system

Most implementations of the Oberon system only check for *client* references prior to unloading a module. Other types of references are usually not checked, although various approaches are typically employed to alleviate the situation where such references do exist.

These approaches can be broadly grouped into two main categories:

- (a) schemes that explicitly allow invalidating references
- (b) schemes where all past and future references must remain unaffected at all times
- a. Schemes that explicitly allow invalidating references

In such schemes, unloading a module from memory *may*, and in general *will*, lead to "dangling" *type*, *procedure* or *pointer variable* references<sup>21</sup> pointing to no longer valid static module data. This includes the important case where a structure rooted in a variable of base type T declared in a base module M contains elements of an extension T' defined in a client module M'. Such elements typically contain both *type* references (type tags) and *procedure variable* references (installed handlers) referring to module M'. This is common in the Oberon viewer system, where M is module *Viewers* and M' may be a graphics editor, for example. If the client module M' is unloaded and the module block previously occupied by it is overwritten by another module loaded later, any still existing references to M' become *invalid* at that moment.

Global procedure variables declared in other modules may also refer to procedures declared in module M', although this case is much less common (global procedure variables tend to be used mainly for procedures declared in the same module).

A variety of approaches have been employed in different implementations of the Oberon system to cope with the introduced "dangling" *type*, *procedure* or *pointer variable* references:

1. On systems that use a *memory management unit* to perform virtual memory management, such as Ceres-1 or Ceres-2 computers, one approach is to *unmap* the module space of an unloaded module from virtual memory, thereby *invalidating* any future references to it. When this is done, any still existing *type*, *procedure* or *pointer variable* references to static module data point to a now *unallocated* page, and consequently any attempt to access such a page later will (intentionally) result in a system *trap*.

We consider this an unfortunate proposal for several reasons. First, users generally have no way of knowing *whether* it is in fact safe to unload a module, yet they are allowed to do so. Second, even after having unloaded it, they still don't know whether references from other loaded modules still exist or not – until a *trap* occurs. But then it is often too late. While the trap itself will *prevent* a system crash (as intended), the user may *still* need to restart the system in order to recover an environment without any "frozen" parts, for example displayed viewers that may have been opened by the unloaded module. Note also that this solution requires special hardware support, which may not be available on all systems.

If the *language* Oberon or the underlying operating system supports the concept of (module or object) *finalization*, a module can provide code that is executed prior to module *unloading*, similar to the module *initialization* code that is executed after it has been *loaded*. Such a

<sup>21</sup> If the programming language Oberon-2 is used, there can also be references to method tables (which however are typically allocated within type descriptors).

mechanism can be used to close any still open viewers or delete any data elements that may have been created by a module to be unloaded. Module finalization can either be realized as a *language* feature or at the *system* level by providing a procedure that allows any module to set a finalization routine. Extended Oberon is an example of a system that supports both.

- 2. On systems that do not use virtual memory, such as Original Oberon on Ceres-3 or Project Oberon 2013 on RISC, the easiest way to cope with dangling references is to simply ignore them and to always release the memory associated with a module without any further precautions (unless, of course, clients exist). While an attempt to access an unloaded module goes undetected initially, the system is still left in an unsafe state, which may become unstable the moment another module loaded later overwrites the previously released module block and other modules or data elements still contain "dangling" references to its (now overwritten) type descriptors, procedures or other static objects. This is of course undesirable.
- 3. Another approach, which however can be used only for procedure variable references, is to identify all such references and make them refer to a dummy procedure, thereby preventing a run-time error when such "fixed up" procedures are called later. This solution requires the system to know the locations of all procedure variables in all static and dynamically allocated objects at run time (which can be achieved by including them in symbol and object files). It was used in an earlier version of Extended Oberon, but was later discarded, mainly because the resulting effect on the overall behavior of a running system is essentially impossible to predict. The fact that some procedure variables somewhere in the system no longer refer to real but to dummy procedures typically becomes "visible" only through the absence of some action such as the absence of mouse tracking if the unloaded module contained a viewer handler, for instance.
- 4. On systems that use indirection for procedure calls via a so-called "link table" (where an "address" of a procedure is not a real memory address, but an index to this translation table, which the caller consults for every procedure call in order to obtain the actual memory location of the called procedure), the same effect can be achieved by setting the link table entries for all referenced procedures of the module to be unloaded to dummy entries, rather than locating and modifying each individual procedure call in the system.

However, using a *link table* to implement indirection for procedure calls is only viable on systems that provide *efficient* hardware support for it. It was used in earlier versions of the Oberon system on Ceres-1 and Ceres-2 computers, which were based on the (now defunct) NS32000 processor. This processor featured a *call external procedure* instruction (CXP k, where k is the index of the link table entry of the called procedure), which sped up the process of calling external procedures significantly<sup>22</sup>. Later versions of the NS processor, however, internally re-implemented the *same* CPU instruction using microcode, following the general industry trend that started in the 1980s<sup>23</sup> (which has now become mainstream) of implementing only frequent, simple instructions directly with hardware, while interpreting more complex instructions using internal microcode. This internal re-implementation of the *CXP k* instruction negatively impacted its performance. For this and a variety of other reasons, this instruction – and with it the *link table* – were no longer used in later versions of Oberon.

The use of the link table also increased code density considerably (as only 8 bits for the index instead of 32 bits for the full address were needed to address a procedure in every procedure call). In addition, the link table used by the CXP instruction allowed for an expedient linking process at module load time (as there are far fewer conversions to be performed by the loader – one for every referenced procedure instead of one for every procedure call) and also eliminated the need for a fixup list (list of the locations of all external procedure references to be fixed up by the

module loader) in the object file. A disadvantage is, of course, the need for a (short) link table.

23 A number of computers from the 1960s and 1970s have been identified as forerunners of reduced instruction set computers (RISCs), but the modern concept dates to the 1980s.

5. In passing we note that for *type* references, it is actually possible to determine at *compile* time, whether a module *may* lead to references from other loaded modules at *run* time. The criteria is the following: if a module M' does *not* declare record types which are extensions T' of an imported type T, then records declared in module M' *cannot* be inserted in a data structure rooted in a variable *v* of the imported type T – precisely *because* their types are not extensions of T (in the Oberon programming language, an assignment *p* := *p'* is allowed only if the type of *p'* is the same as the type of *p* or an extension of it). One *could* therefore introduce a rule that a module M' can be safely dispensed *only* if it does *not* declare record types, which are extensions T' of an imported type T. The flip side of such a rule, however, is that modules that actually *do* declare such types can *never* be unloaded – unless, of course, other ways to safely unload such modules are implemented. In addition, *procedure variable* references are not covered by this rule (procedures of M' may be referenced by procedure variables declared in other modules or in dynamic objects)<sup>24</sup>.

Even though most of these approaches have actually been realized in various implementations of the Oberon system, we consider none of them truly satisfactory. In our view, these schemes appear to only tinker with the symptoms of a problem that would not exist, if only one adopted the rule to *disallow* the physical removal (from memory) of still referenced module data.

The main issue is that the moment one *allows* modules to release their associated memory in spite of references to them from other modules, the resulting *dangling* module references must be dealt with *somehow* in order to prevent an almost certain system *crash*. However, *fixing up* or even *invalidating* references will *always* remove essential information from the system. As a result, the run-time behavior of the modified system becomes *essentially unpredictable*, as other modules may *critically* depend on the removed functionality. For example, unloading a module that contains an installed handler of a *contents frame* may render it impossible to close the enclosing *menu viewer* that contains it, thereby leading to a system with "frozen" parts.

b. Schemes where all past and future references must remain unaffected at all times

The second possible interpretation of *unloading* a module consists of schemes where all past and future references *must* remain unaffected at all times. In such schemes, module unloading can be viewed as an implicit mandate to preserve "critical module data", as long as references to the unloaded module exist. Various possible ways to satisfy this requirement exist:

- 1. One could simply exit the module *unload* command with an error message, whenever such references are detected. The user, however, may then be "stuck" with modules that he can *never* unload because they are referenced by modules over which he has no explicit control.
- 2. But the mandate could also be fulfilled by persisting any still referenced module data to a "safe" location before unloading the associated module.

For *type descriptors* referenced by *type tags* in dynamic records a straightforward solution exists: simply allocate them *outside* their module blocks in order to persist them beyond the lifetime of their associated modules. One possibility is to allocate them in the *heap* itself at module *load* time<sup>25</sup>. This approach has been implemented in Oberon on Ceres-1 and Ceres-2. It eliminates dangling *type* references altogether and therefore also the *need* to check for them at run time, because type descriptors are now unaffected by module unloading. Such

<sup>&</sup>lt;sup>24</sup> One may attempt to "record" each assignment to a procedure variable at run time by setting a flag in the referenced procedure or module, but the performance penalty would be inacceptable.
<sup>25</sup> Note that one cannot simply move type descriptors around in memory once a module has been loaded, because their addresses are (typically) used to implement type tests and type guards.
By allocating them in the heap at module I o a d time, one avoids the need to move them to a different location when a module is later unloaded.

dynamically allocated type descriptors can themselves be deallocated if (a) their associated module has been unloaded and (b) no *regular* heap objects refer to them via their *type tags*.

For *procedures* referenced by *procedure variables* no such straightforward solution exists, as procedures may call other procedures or access global module data declared in the same or a different module. Thus, the only way to "persist" procedures (and other static objects) would be to persist the *entire* module.

We conclude that if one wants to handle all types of references, one *cannot* unload a module from memory, as long as references to it still exist from anywhere in the system<sup>26</sup>.

3. One way to automatically persist type descriptors, procedures and static objects consists of simply *never* releasing the module block of a module once it has been loaded. Instead, when the user requests the "unloading" of a module, the module is only removed from the *list* of loaded modules, without releasing its associated memory. This amounts to *renaming* the module, with the implication that a newer version of the same module with the same original name can be reloaded again. This approach has been chosen in MacOberon<sup>27</sup>, for example. Since the associated memory of a module is never released, the issue of dangling type, procedure or pointer variable references is avoided altogether, as they simply cannot exist.

But it can also lead to higher-than-necessary memory consumption, if one and the same module is repeatedly loaded and unloaded (typical during *development*). Nevertheless, such an approach may be viewed as adequate on *production* systems, where module unloading tends to be rare, or on systems that use *demand paging*, where memory pages that are not frequently referenced are automatically swapped out to a secondary store. Note, however, that with the advent of large primary stores, the concept of demand paging has lost much of its significance. It is therefore best not to rely on the presence of such a mechanism.

4. A further *refinement* of the approach outlined above consists of *initially* removing a module only from the module *list* (as is done in MacOberon), but *in addition* releasing its associated memory *as soon as* there are no more references to its static module data. If this is done in an automatic fashion, module data is truly "kept in memory for exactly as long as necessary and removed from it as soon as possible". This is the approach chosen in Extended Oberon. A variation of it was used in some versions of SparcOberon<sup>28</sup>.

In sum, module unloading schemes where references remain *unaffected* at all times avoid many of the complications that are inherent in schemes that explicitly *allow* invalidating references. A (small) price to pay is to keep modules loaded in memory, as long as references to them exist. However, on *production* systems, there is usually no need to keep multiple versions of the same module loaded in memory, while on *development* systems it is totally acceptable.

Finally, we note that on modern day computers the amount of available memory, and therefore also the amount of *dynamic* data that can be allocated by modules, typically far exceeds the size of the static module blocks holding their program code and global variables. Therefore, *not* releasing module blocks immediately after a module *unload* operation typically has a rather negligible impact on overall memory consumption.

14

<sup>&</sup>lt;sup>26</sup> Mixed variants are also possible. For example, one could allocate type descriptors in the heap at module load time (as with Ceres-Oberon), and either "fix up" procedure variable references or prevent the release of a module block if such references still exist; however, most modules referenced by type tags are a l s o referenced by procedure variables – this is in fact the typical case for dynamic records containing installed handler procedures. Thus, it seems more natural to use the s a m e approach for both type and procedure variable references.

27 http://e-collection.library.ethz.ch/eserv/eth:3268/eth-3269-01.pdf (The Implementation of MacOberon, 1990)

http://e-collection.library.ethz.ch/eserv/eth:7103/eth-7103-01.pdf (SPARC-Oberon User's Guide and Implementation, 1990/1991)