Internet Engineering Task Force (IETF)

Request for Comments: 5907 Category: Standards Track ISSN: 2070-1721

H. Gerstung Meinbera C. Elliott

B. Haberman, Ed. JHU APL June 2010

Definitions of Managed Objects for Network Time Protocol Version 4 (NTPv4)

### Abstract

The Network Time Protocol (NTP) is used in networks of all types and sizes for time synchronization of servers, workstations, and other networked equipment. As time synchronization is more and more a mission-critical service, standardized means for monitoring and management of this subsystem of a networked host are required to allow operators of such a service to set up a monitoring system that is platform- and vendor-independent. This document provides a standardized collection of data objects for monitoring the NTP entity of such a network participant and it is part of the NTP version 4 standardization effort.

#### 5Status of This Memo

This is an Internet Standards Track document.

This document is a product of the Internet Engineering Task Force (IETF). It represents the consensus of the IETF community. It has received public review and has been approved for publication by the Internet Engineering Steering Group (IESG). Further information on Internet Standards is available in Section 2 of RFC 5741.

Information about the current status of this document, any errata, and how to provide feedback on it may be obtained at http://www.rfc-editor.org/info/rfc5907.

## Copyright Notice

Copyright (c) 2010 IETF Trust and the persons identified as the document authors. All rights reserved.

This document is subject to BCP 78 and the IETF Trust's Legal Provisions Relating to IETF Documents (http://trustee.ietf.org/license-info) in effect on the date of publication of this document. Please review these documents carefully, as they describe your rights and restrictions with respect to this document. Code Components extracted from this document must include Simplified BSD License text as described in Section 4.e of the Trust Legal Provisions and are provided without warranty as described in the Simplified BSD License.

## **Table of Contents**

1.	Introduction	<u>2</u>
2.	Conventions Used in This Document	3
3.	The Internet-Standard Management Framework	3
4.	Technical Description	3
	MIB Definition	
	IANA Considerations	
	Security Considerations23	
8.	Acknowledgments	4
	References	
	9.1. Normative References	4
	9.2. Informative References	

## 1. Introduction

The NTPv4 MIB module is designed to allow Simple Network Management Protocol (SNMP) to be used to monitor and manage local NTP [RFC5905] entities. It provides a collection of data objects that can be queried using the SNMP protocol and represent the current status of the NTP entity. This includes general information about the NTP entity itself (vendor, product, version) as well as connectivity to upstream NTP servers used as sources of reference time and to hardware reference clocks like radio clocks. The most important values are included in order to be able to detect failures before they can have an impact on the overall time synchronization status of the network. There are also a collection of notification objects to inform about state changes in the NTP entity. There are objects to control these notifications as well.

### 2. Conventions Used in This Document

The capitalized key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in [RFC2119].

## 3. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

# 4. Technical Description

The NTPv4 MIB module is divided into sections for general server information, current NTP entity status, status information of all mobilized associations (e.g., unicast upstream time servers, multicast or broadcast, time references, and hardware clocks), NTP entity control objects, NTP objects used only for notifications, as well as SNMP notification definitions for core events.

The general server information section contains static information and can be queried to identify which NTP implementation is running on a host. This includes the vendor and product name of the running NTP software as well as version information, hardware/os platform identity, and the time resolution of the underlying OS.

Section 2 (current NTP status) includes data objects that represent the current operational status of the NTP entity.

The third section contains data objects that represent the set of time references ("associations") with which the NTP entity is currently working.

The fourth section contains objects that can be used to control the NTP entity. The currently defined objects control how often the heartbeat interval notification is sent out and which notifications are enabled.

Gerstung, et al.

Standards Track

[Page 3]

The fifth section contains objects that are only used as varbinds in notifications. There is currently only one object in this section -- a message that adds a cleartext event message to notifications.

Certain important events can occur while the NTP entity is running. The notification section defines SNMP notifications for a collection of the most important ones ("core events") and additionally provides a heartbeat notification as well as a test notification to allow management systems to test the reception of NTP-related notifications as well as enable heartbeat-based monitoring systems to assure that the NTP entity is still up and running.

Some values are included both in numeric and in human-readable (string) format. This has been done to simplify the representation of a status information. If the two representations of a certain value differ, the numeric representation takes precedence.

#### 5. MIB Definition

```
The Network Time Protocol Version 4
___
     Management Information Base (MIB)
--
--
     Authors: Heiko Gerstung (heiko.gerstung@meinberg.de)
--
            Chris Elliott (chelliot@pobox.com)
--
___
     for the Internet Engineering Task Force (IETF)
--
     NTP Working Group (ntpwg)
--
Rev 1.00
--
         Published as RFC 5907
--
__ *************************
NTPv4-MIB DEFINITIONS ::= BEGIN
IMPORTS
   MODULE-IDENTITY, OBJECT-TYPE, mib-2, Integer32, NOTIFICATION-TYPE,
   Unsigned32, Counter32, TimeTicks
FROM SNMPv2-SMI -- RFC 2578
   MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP
      FROM SNMPv2-CONF -- RFC 2580
   DisplayString, TEXTUAL-CONVENTION FROM SNMPv2-TC -- RFC 2579
```

InetAddressType, InetAddress
 FROM INET-ADDRESS-MIB -- RFC 4001
Utf8String
 FROM SYSAPPL-MIB: -- RFC 2287

ntpSnmpMIB MODULE-IDENTITY

LAST-UPDATED "201005170000Z" -- May 17, 2010 ORGANIZATION "The IETF NTP Working Group (ntpwg)" CONTACT-INFO

WG Email: ntpwg@lists.ntp.isc.org

Subscribe:

https://lists.ntp.isc.org/mailman/listinfo/ntpwg

Heiko Gerstung Meinberg Funkuhren Gmbh & Co. KG Lange Wand 9 Bad Pyrmont 31812 Germany

Phone: +49 5281 9309 25

Email: heiko.gerstung@meinberg.de

Chris Elliott 1516 Kent St. Durham, NC 27707 USA

Phone: +1-919-308-1216 Email: chelliot@pobox.com

Brian Haberman 11100 Johns Hopkins Road Laurel, MD 20723 USA

Phone: +1-443-778-1319

Email: brian@innovationslab.net"

**DESCRIPTION** 

"The Management Information Base for NTP time entities.

Copyright (c) 2010 IETF Trust and the persons identified as authors of the code. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, is permitted pursuant to, and subject to the license terms contained in, the Simplified BSD License set forth in Section 4.c of the IETF Trust's Legal Provisions Relating to IETF Documents

Gerstung, et al.

Standards Track

[Page 5]

```
(http://trustee.ietf.org/license-info)."
                    "201005170000Z"
    REVISION
    DESCRIPTION
         "This revision of the MIB module is published as RFC 5907."
     ::= { mib-2 197 }
ntpSnmpMIBObjects OBJECT IDENTIFIER ::= { ntpSnmpMIB 1 }
-- MIB contains 6 groups
                      OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 1 }
OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 2 }
OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 3 }
OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 4 }
ntpEntInfo
ntpEntStatus
ntpAssociation
ntpEntControl
ntpEntNotifObjects OBJECT IDENTIFIER ::= { ntpSnmpMIBObjects 5 }
-- Textual Conventions
NtpStratum ::= TEXTUAL-CONVENTION
    DISPLAY-HINT "d"
    STATUS
                  current
    DESCRIPTION
         "The NTP stratum, with 16 representing no stratum."
                  Unsigned32 (1..16)
NtpDateTime ::= TEXTUAL-CONVENTION
    DISPLAY-HINT "4d:4d:4d.4d"
    STATUS
                   current
    DESCRIPTION
         "NTP date/time on the device, in 128-bit NTP date format. If time is not syncronized, this
          field shall be a zero-length string.
          This trusted certificate (TC) is not to be used for objects
          that are used to set the time of the node querying this
          object. NTP should be used for this -- or at least SNTP."
    REFERENCE "RFC 5905, section 6"
    SYNTAX
                   OCTET STRING (SIZE (0 | 16))
-- Section 1: General NTP Entity information objects
                (relatively static information)
__
_ _
```

```
ntpEntSoftwareName OBJECT-TYPE
               Utf8String
   SYNTAX
   MAX-ACCESS
                read-only
   STATUS
                current
   DESCRIPTION
        "The product name of the running NTP version, e.g., 'ntpd'."
    ::= { ntpEntInfo 1 }
ntpEntSoftwareVersion OBJECT-TYPE
               Utf8String
   SYNTAX
   MAX-ACCESS read-only
                current
   STATUS
   DESCRIPTION
        "The software version of the installed NTP implementation
        as a full version string, e.g., 'ntpd-4.2.0b@1.1433 ...'"
    ::= { ntpEntInfo 2 }
ntpEntSoftwareVendor OBJECT-TYPE
                Utf8String
   SYNTAX
   MAX-ACCESS
                read-only
   STATUS
               current
   DESCRIPTION
        "The vendor/author of the installed NTP version."
    ::= { ntpEntInfo 3 }
ntpEntSystemType OBJECT-TYPE
               Utf8String
   SYNTAX
   MAX-ACCESS read-only
                current
   STATUS
   DESCRIPTION
        "General hardware/os platform information,
        e.g., 'Linux 2.6.12 / x86'."
    -- freely configurable, default is OS Version / Hardware platform
    ::= { ntpEntInfo 4 }
ntpEntTimeResolution OBJECT-TYPE
               Unsigned32
   SYNTAX
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION
        "The time resolution in integer format, where the resolution
        is represented as divisions of a second, e.g., a value of 1000
        translates to 1.0 ms."
    ::= { ntpEntInfo 5 }
```

```
ntpEntTimePrecision OBJECT-TYPE
    SYNTAX
                Integer32
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The entity's precision in integer format, shows the precision.
         A value of -5 would mean 2^-5 = 31.25 ms.
    ::= { ntpEntInfo 6 }
ntpEntTimeDistance OBJECT-TYPE
                DisplayString
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The distance from this NTP entity to the root time reference
        (stratum 0) source including the unit, e.g., '13.243 ms'.'
    ::= { ntpEntInfo 7 }
  Section 2: Current NTP status (dynamic information)
ntpEntStatusCurrentMode OBJECT-TYPE
    SYNTAX
                INTEGER {
                            notRunning(1),
                            notSynchronized(2),
                            noneConfigured(3),
                            syncToLocal(4)
                            syncToRefclock(5),
                            syncToRemoteServer(6),
                            unknown(99)
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The current mode of the NTP. The definition of each possible
         value is:
            notRunning(1) - NTP is not running.
            notSynchronized(2) - NTP is not synchronized to any time
                                 source (stratum = 16).
            noneConfigured(3) - NTP is not synchronized and does not
                                have a reference configured
                                 (stratum = 16).
            syncToLocal(4) - NTP is distributing time based on its
                             local clock (degraded accuracy and/or
                             reliability).
            syncToRefclock(5) - NTP is synchronized to a local
                                hardware refclock (e.g., GPS).
```

```
syncToRemoteServer(6) - NTP is synchronized to a remote
                                     NTP server ('upstream' server).
            unknown(99) - The state of NTP is unknown.
    ::= { ntpEntStatus 1 }
ntpEntStatusStratum OBJECT-TYPE
                NtpStratum
    SYNTAX
    MAX-ACCESS
                read-only
                current
    STATUS
    DESCRIPTION
        "The NTP entity's own stratum value.
                                               Should be a stratum of
    syspeer + 1 (or 16 if no syspeer)."
::= { ntpEntStatus 2 }
ntpEntStatusActiveRefSourceId OBJECT-TYPE
                Unsigned32 ( 0..99999 )
    SYNTAX
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The association ID of the current syspeer."
    ::= { ntpEntStatus 3 }
ntpEntStatusActiveRefSourceName OBJECT-TYPE
    SYNTAX
                Utf8String
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The hostname/descriptive name of the current reference source
         selected as syspeer, e.g., 'ntp1.ptb.de' or 'GPS' or
         'DCFi'
    ::= { ntpEntStatus 4 }
ntpEntStatusActiveOffset OBJECT-TYPE
                DisplayString
    SYNTAX
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        'The time offset to the current selected reference time source
         as a string including unit, e.g., '0.032 ms' or '1.232 s'."
    ::= { ntpEntStatus 5 }
ntpEntStatusNumberOfRefSources OBJECT-TYPE
    SYNTAX
                Unsigned32 (0..99)
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The number of reference sources configured for NTP."
    ::= { ntpEntStatus 6 }
```

```
ntpEntStatusDispersion OBJECT-TYPE
    SYNTAX
                 DisplayString
    MAX-ACCESS
                 read-only
    STATUS
                 current
    DESCRIPTION
        "The root dispersion of the running NTP entity, e.g., '6.927'."
    ::= { ntpEntStatus 7 }
ntpEntStatusEntityUptime OBJECT-TYPE
    SYNTAX
                 TimeTicks
    MAX-ACCESS read-only
                current
    STATUS
    DESCRIPTION
        "The uptime of the NTP entity, (i.e., the time since ntpd was (re-)initialized not sysUptime!). The time is represented in
         hundreds of seconds since Jan 1, 1970 (00:00:00.000) UTC.
    ::= { ntpEntStatus 8 }
ntpEntStatusDateTime OBJECT-TYPE
                NtpDateTime
    SYNTAX
    MAX-ACCESS read-only
                current
    STATUS
    DESCRIPTION
         "The current NTP date/time on the device. in 128-bit
         NTP date format. If time is not syncronized, this
         field shall be a zero-length string.
         This object can be used to timestamp events on this
         node and allow a management station to correlate
         different time objects. For example, a management
         station could query this object and sysUpTime in
         the same operation to be able to relate sysUpTime
         to NTP time.
         This object is not to be used to set the time of
         the node querying this object. NTP should be used for this -- or at least SNTP."
    REFERENCE "RFC 5905, section 6"
    ::= { ntpEntStatus 9 }
ntpEntStatusLeapSecond OBJECT-TYPE
                NtpDateTime
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
        "Date the next known leap second will occur. If there is
         no leap second announced, then this object should be 0."
    ::= { ntpEntStatus 10 }
```

```
ntpEntStatusLeapSecDirection OBJECT-TYPE
                Integer32 (-1..1)
    SYNTAX
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "Direction of next known leap second. If there is no
         leap second announced, then this object should be 0."
    ::= { ntpEntStatus 11 }
ntpEntStatusInPkts OBJECT-TYPE
    SYNTAX
                Counter32
                "packets"
    UNITS
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The total number of NTP messages delivered to the
         NTP entity from the transport service.
         Discountinuities in the value of this counter can occur
         upon cold start or reinitialization of the NTP entity, the
         management system and at other times as indicated by discontinuities in the value of sysUpTime."
    ::= { ntpEntStatus 12 }
ntpEntStatusOutPkts OBJECT-TYPE
    SYNTAX
                Counter32
                "packets"
    UNITS
    MAX-ACCESS read-only
                current
    STATUS
    DESCRIPTION
        "The total number of NTP messages delivered to the
         transport service by this NTP entity.
         Discountinuities in the value of this counter can occur
         upon cold start or reinitialization of the NTP entity, the
         management system and at other times as indicated by
         discontinuities in the value of sysUpTime."
    ::= { ntpEntStatus 13 }
ntpEntStatusBadVersion OBJECT-TYPE
    SYNTAX
                Counter32
                "packets"
    UNITS
    MAX-ACCESS read-only
                current
    STATUS
    DESCRIPTION
        "The total number of NTP messages that were delivered
         to this NTP entity and were for an unsupported NTP
         version.
```

```
Discountinuities in the value of this counter can occur
         upon cold start or reinitialization of the NTP entity, the
         management system and at other times as indicated by
         discontinuities in the value of sysUpTime."
    ::= { ntpEntStatus 14 }
ntpEntStatusProtocolError OBJECT-TYPE
    SYNTAX
                 Counter32
                 "packets"
    UNITS
    MAX-ACCESS read-only
    STATUS
               current
    DESCRIPTION
        "The total number of NTP messages that were delivered
         to this NTP entity and this entity was not able to process due to an NTP protocol error.
         Discountinuities in the value of this counter can occur
         upon cold start or reinitialization of the NTP entity, the
         management system and at other times as indicated by
         discontinuities in the value of sysUpTime."
    ::= { ntpEntStatus 15 }
ntpEntStatusNotifications OBJECT-TYPE
    SYNTAX
                Counter32
                 "notifications"
    UNITS
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
         "The total number of SNMP notifications that this NTP
         entity has generated.
         Discountinuities in the value of this counter can occur
         upon cold start or reinitialization of the NTP entity, the
         management system and at other times as indicated by
         discontinuities in the value of sysUpTime."
    ::= { ntpEntStatus 16 }
ntpEntStatPktModeTable OBJECT-TYPE
                      SEQUENCE OF NtpEntStatPktModeEntry
    SYNTAX
    MAX-ACCESS
                      not-accessible
    STATUS
                      current
    DESCRIPTION
    "The number of packets sent and received by packet mode.

One entry per packet mode."

::= { ntpEntStatus 17 }
ntpEntStatPktModeEntry OBJECT-TYPE
                NtpEntStatPktModeEntry
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
             current
```

```
DESCRIPTION
         "A statistical record of the number of packets sent and
         received for each packet mode."
                 { ntpEntStatPktMode }
    ::= { ntpEntStatPktModeTable 1 }
NtpEntStatPktModeEntry ::= SEQUENCE { INTEGER,
        ntpEntStatPktSent
                                          Counter32,
        ntpEntStatPktReceived
                                          Counter32
}
ntpEntStatPktMode OBJECT-TYPE
                 INTEGER {
    SYNTAX
                     symetricactive(1)
                      symetricpassive(2),
                     client(3),
                     server(4),
                     broadcastserver(5),
                     broadcastclient(6)
    MAX-ACCESS
                 not-accessible
                 current
    STATUS
    DESCRIPTION
         "The NTP packet mode."
    ::= { ntpEntStatPktModeEntry 1 }
ntpEntStatPktSent OBJECT-TYPE
    SYNTAX
                 Counter32
                 "packets"
    UNITS
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The number of NTP packets sent with this packet mode.
Discountinuities in the value of this counter can occur
         upon cold start or reinitialization of the NTP entity, the
         management system and at other times as indicated by
         discontinuities in the value of sysUpTime."
    ::= { ntpEntStatPktModeEntry 2 }
ntpEntStatPktReceived OBJECT-TYPE
    SYNTAX
                 Counter32
    UNITS
                 "packets"
    MAX-ACCESS
                 read-only
                 current
    STATUS
    DESCRIPTION
         "The number of NTP packets received with this packet mode.
```

Discountinuities in the value of this counter can occur upon cold start or reinitialization of the NTP entity, the management system and at other times as indicated by discontinuities in the value of sysUpTime."

```
::= { ntpEntStatPktModeEntry 3 }
-- Section 3: The status of all currently mobilized associations
ntpAssociationTable OBJECT-TYPE
                     SEQUENCE OF NtpAssociationEntry
    SYNTAX
    MAX-ACCESS
                     not-accessible
    STATUS
                     current
    DESCRIPTION
        "The table of currently mobilized associations."
    ::= { ntpAssociation 1 }
ntpAssociationEntry OBJECT-TYPE
    SYNTAX
                NtpAssociationEntry
    MAX-ACCESS
                not-accessible
                current
    STATUS
    DESCRIPTION
        "The table entry of currently mobilized associations."
                { ntpAssocId }
    INDEX
    ::= { ntpAssociationTable 1 }
NtpAssociationEntry ::= SEQUENCE {
        ntpAssocId
                                     Unsigned32,
                                     Utf8String,
        ntpAssocName
        ntpAssocRefId
                                     DisplayString,
        ntpAssocAddressType
                                     InetAddressType,
        ntpAssocAddress
                                     InetAddress,
        ntpAssocOffset
                                     DisplayString,
        ntpAssocStratum
                                     NtpStratum,
        ntpAssocStatusJitter
                                     DisplayString,
        ntpAssocStatusDelay
                                     DisplayString,
        ntpAssocStatusDispersion
                                     DisplayString
}
ntpAssocId
                OBJECT-TYPE
                Unsigned32 ( 1..99999 )
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "The association ID. This is an internal, unique ID."
    ::= { ntpAssociationEntry 1 }
```

```
ntpAssocName
                 OBJECT-TYPE
    SYNTAX
                 Utf8String
    MAX-ACCESS
                 read-only
    STATUS
                 current
    DESCRIPTION
        "The hostname or other descriptive name for the association."
    ::= { ntpAssociationEntry 2 }
ntpAssocRefId
                 OBJECT-TYPE
    SYNTAX
                 DisplayString
    MAX-ACCESS
                 read-only
                 current
    STATUS
    DESCRIPTION
    "The refclock driver ID, if available."
-- a refclock driver ID like "127.127.1.0" for non
    -- uni/multi/broadcast associations
    ::= { ntpAssociationEntry 3 }
ntpAssocAddressType OBJECT-TYPE
                 InetAddressType { ipv4(1), ipv6(2), ipv4z(3), ipv6z(4) }
    SYNTAX
    MAX-ACCESS
                 read-only
                 current
    STATUS
    DESCRIPTION
         'The type of address of the association.
                                                       Can be either IPv4 or
         IPv6 (both with or without zone index) and contains the type of
         address for unicast, multicast, and broadcast associations.
    ::= { ntpAssociationEntry 4 }
ntpAssocAddress OBJECT-TYPE
                 InetAddress (SIZE (4|8|16|20))
    SYNTAX
    MAX-ACCESS read-only
                 current
    STATUS
    DESCRIPTION
         "The IP address (IPv4 or IPv6, with or without zone index) of the association. The type and size depends on the
         ntpAssocAddressType object. Represents the IP address of a
         uni/multi/broadcast association.'
    ::= { ntpAssociationEntry 5 }
ntpAssocOffset OBJECT-TYPE
                 DisplayString
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The time offset to the association as a string."
    -- including unit, e.g., "0.032 ms" or "1.232 s" ::= { ntpAssociationEntry 6 }
```

```
ntpAssocStratum OBJECT-TYPE
    SYNTAX
                NtpStratum
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The association stratum value."
    ::= { ntpAssociationEntry 7 }
ntpAssocStatusJitter OBJECT-TYPE
    SYNTAX
                DisplayString
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The jitter in milliseconds as a string."
    ::= { ntpAssociationEntry 8 }
ntpAssocStatusDelay OBJECT-TYPE
    SYNTAX
                DisplayString
    MAX-ACCESS
                read-only
    STATUS
                current
    DESCRIPTION
        "The network delay in milliseconds as a string."
    ::= { ntpAssociationEntry 9 }
ntpAssocStatusDispersion OBJECT-TYPE
                DisplayString
    SYNTAX
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "The root dispersion of the association."
    -- e.g., "6.927"
    ::= { ntpAssociationEntry 10 }
ntpAssociationStatisticsTable OBJECT-TYPE
                     SEQUENCE OF NtpAssociationStatisticsEntry
    SYNTAX
    MAX-ACCESS
                     not-accessible
    STATUS
                     current
    DESCRIPTION
        "The table of statistics for current associations."
    ::= { ntpAssociation 2 }
ntpAssociationStatisticsEntry OBJECT-TYPE
    SYNTAX
                NtpAssociationStatisticsEntry
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
        "The table entry of statistics for current associations."
    INDEX
                { ntpAssocId }
```

```
::= { ntpAssociationStatisticsTable 1 }
NtpAssociationStatisticsEntry ::= SEQUENCE {
                                       Counter32,
        ntpAssocStatInPkts
        ntpAssocStatOutPkts
                                       Counter32,
        ntpAssocStatProtocolError
                                       Counter32
}
ntpAssocStatInPkts OBJECT-TYPE
    SYNTAX
                 Counter32
                 "packets"
    UNITS
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The total number of NTP messages delivered to the
         NTP entity from this association.
         Discountinuities in the value of this counter can occur
         upon cold start or reinitialization of the NTP entity, the
         management system and at other times as indicated by discontinuities in the value of sysUpTime."
    ::= { ntpAssociationStatisticsEntry 1 }
ntpAssocStatOutPkts OBJECT-TYPE
    SYNTAX
                 Counter32
                 "packets"
    UNITS
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The total number of NTP messages delivered to the
         transport service by this NTP entity for this
         association.
         Discountinuities in the value of this counter can occur
         upon cold start or reinitialization of the NTP entity, the
         management system and at other times as indicated by discontinuities in the value of sysUpTime."
    ::= { ntpAssociationStatisticsEntry 2 }
ntpAssocStatProtocolError OBJECT-TYPE
    SYNTAX
                 Counter32
    UNITS
                 "packets"
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The total number of NTP messages that were delivered
         to this NTP entity from this association and this entity
         was not able to process due to an NTP protocol error.
```

Discountinuities in the value of this counter can occur upon cold start or reinitialization of the NTP entity, the management system and at other times as indicated by discontinuities in the value of sysUpTime."

```
::= { ntpAssociationStatisticsEntry 3 }
-- Section 4: Control objects
ntpEntHeartbeatInterval OBJECT-TYPE
                  Unsigned32
    SYNTAX
                  "seconds"
    UNITS
    MAX-ACCESS read-write
    STATUS
                  current
    DESCRIPTION
         "The interval at which the ntpEntNotifHeartbeat notification
          should be sent, in seconds. If set to 0 and the
          entNotifHeartbeat bit in ntpEntNotifBits is 1, then ntpEntNotifHeartbeat is sent once. This value is stored persistently and will be restored to its
          last set value upon cold start or restart."
    DEFVAL { 60 }
    ::= { ntpEntControl 1 }
ntpEntNotifBits OBJECT-TYPE
                   BITS {
    SYNTAX
                        notUsed(0), -- Used to sync up bit and notification
                                      -- indices
                        entNotifModeChange(1),
                        entNotifStratumChange(2)
                        entNotifSyspeerChanged(3),
                        entNotifAddAssociation(4)
                        entNotifRemoveAssociation(5).
                        entNotifConfigChanged(6),
                        entNotifLeapSecondAnnounced(7),
                        entNotifHeartbeat(8)
    MAX-ACCESS read-write
    STATUS
                  current
    DESCRIPTION
         "A bit for each notification. A 1 for a particular bit enables that particular notification, a 0 disables it.
          This value is stored persistently and will be restored to its
          last set value upon cold start or restart."
    ::= { ntpEntControl 2 }
```

```
-- Section 5: Notification objects
ntpEntNotifMessage OBJECT-TYPE
                Utf8String
    SYNTAX
    MAX-ACCESS
                accessible-for-notify
    STATUS
                current
    DESCRIPTION
        'Used as a payload object for all notifications.
                                                           Holds a
         cleartext event message."
    DEFVAL { "no event" }
    ::= { ntpEntNotifObjects 1 }
-- SNMP notification definitions
ntpEntNotifications OBJECT IDENTIFIER ::= { ntpSnmpMIB 0 }
ntpEntNotifModeChange NOTIFICATION-TYPE
    OBJECTS
                { ntpEntStatusCurrentMode }
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when the NTP entity changes mode,
         including starting and stopping (if possible).
    ::= { ntpEntNotifications 1 }
ntpEntNotifStratumChange NOTIFICATION-TYPE
                { ntpEntStatusDateTime, ntpEntStatusStratum,
    OBJECTS
                  ntpEntNotifMessage }
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when stratum level of NTP changes."
    ::= { ntpEntNotifications 2 }
ntpEntNotifSyspeerChanged NOTIFICATION-TYPE
                { ntpEntStatusDateTime, ntpEntStatusActiveRefSourceId,
                  ntpEntNotifMessage }
    STATUS
                current
    DESCRIPTION
        "The notification to be sent when a (new) syspeer has been
         selected."
    ::= { ntpEntNotifications 3 }
ntpEntNotifAddAssociation NOTIFICATION-TYPE
    OBJECTS { ntpEntStatusDateTime, ntpAssocName, ntpEntNotifMessage }
    STATUS
                current
```

```
DESCRIPTION
         'The notification to be sent when a new association is
          mobilized."
    ::= { ntpEntNotifications 4 }
ntpEntNotifRemoveAssociation NOTIFICATION-TYPE
    OBJECTS { ntpEntStatusDateTime, ntpAssocName,
                                                         ntpEntNotifMessage }
    STATUS
                  current
    DESCRIPTION
         'The notification to be sent when an association is
          demobilized.
    ::= { ntpEntNotifications 5 }
ntpEntNotifConfigChanged NOTIFICATION-TYPE
                  { ntpEntStatusDateTime, ntpEntNotifMessage }
    OBJECTS
    STATUS
                  current
    DESCRIPTION
         "The notification to be sent when the NTP configuration has
          changed, e.g., when the system connected to the Internet and was assigned a new IP address by the ISPs DHCP server."
    ::= { ntpEntNotifications 6 }
ntpEntNotifLeapSecondAnnounced NOTIFICATION-TYPE
                  { ntpEntStatusDateTime, ntpEntNotifMessage }
    OBJECTS
    STATUS
                  current
    DESCRIPTION
         "The notification to be sent when a leap second has been
          announced.'
    ::= { ntpEntNotifications 7 }
ntpEntNotifHeartbeat NOTIFICATION-TYPE
                  { ntpEntStatusDateTime, ntpEntStatusCurrentMode.
    OBJECTS
                    ntpEntHeartbeatInterval, ntpEntNotifMessage }
    STATUS
                  current
    DESCRIPTION
         'The notification to be sent periodically (as defined by
          ntpEntHeartbeatInterval) to indicate that the NTP entity is
          still alive.
    ::= { ntpEntNotifications 8 }
-- Conformance/Compliance statements
ntpEntConformance OBJECT IDENTIFIER ::= { ntpSnmpMIB 2 }
ntpEntCompliances OBJECT IDENTIFIER ::= { ntpEntConformance 1 }
ntpEntGroups OBJECT IDENTIFIER ::= { ntpEntConformance 2 }
```

```
ntpEntNTPCompliance MODULE-COMPLIANCE
    STATUS
                current
    DESCRIPTION
        "The compliance statement for SNMP entities that use NTP and
         implement the NTP MIB."
    MODULE -- this module
        MANDATORY-GROUPS {
                            ntpEntObjectsGroup1
        ::= { ntpEntCompliances 1 }
ntpEntSNTPCompliance MODULE-COMPLIANCE
    STATUS
                current
    DESCRIPTION
        "The compliance statement for SNMP entities that use SNTP and
         implement the NTP MIB."
    MODULE -- this module
        MANDATORY-GROUPS {
                            ntpEntObjectsGroup1
        GROUP ntpEntObjectsGroup2
        DESCRIPTION
                 'Optional object group."
        GROUP ntpEntNotifGroup
        DESCRIPTION
                 "Optional notifications for this MIB."
        ::= { ntpEntCompliances 2 }
ntpEntObjectsGroup1 OBJECT-GROUP
    OBJECTS {
              ntpEntSoftwareName,
              ntpEntSoftwareVersion,
              ntpEntSoftwareVendor,
              ntpEntSystemType,
ntpEntStatusEntityUptime,
              ntpEntStatusDateTime,
              ntpAssocName,
              ntpAssocRefId,
              ntpAssocAddressType,
              ntpAssocAddress
    STATUS
                current
    DESCRIPTION
        "A collection of objects for the NTP MIB."
    ::= { ntpEntGroups 1 }
ntpEntObjectsGroup2 OBJECT-GROUP
    OBJECTS {
```

```
ntpEntTimeResolution,
              ntpEntTimePrecision,
              ntpEntTimeDistance,
              ntpEntStatusCurrentMode,
              ntpEntStatusStratum,
              ntpEntStatusActiveRefSourceId.
              ntpEntStatusActiveRefSourceName,
              ntpEntStatusActiveOffset,
              ntpEntStatusNumberOfRefSources,
              ntpEntStatusDispersion,
              ntpEntStatusLeapSecond,
              ntpEntStatusLeapSecDirection,
              ntpEntStatusInPkts,
              ntpEntStatusOutPkts
              ntpEntStatusBadVersion,
              ntpEntStatusProtocolError,
              ntpEntStatusNotifications.
              ntpEntStatPktSent,
              ntpEntStatPktReceived,
              ntpAssocOffset,
              ntpAssocStratum,
ntpAssocStatusJitter,
              ntpAssocStatusDelay,
              ntpAssocStatusDispersion,
              ntpAssocStatInPkts,
              ntpAssocStatOutPkts
              ntpAssocStatProtocolError,
              ntpEntHeartbeatInterval,
              ntpEntNotifBits,
              ntpEntNotifMessage
    STATUS
                current
    DESCRIPTION
        "A collection of objects for the NTP MIB."
    ::= { ntpEntGroups 2 }
ntpEntNotifGroup NOTIFICATION-GROUP
    NOTIFICATIONS {
                     ntpEntNotifModeChange,
                     ntpEntNotifStratumChange,
                     ntpEntNotifSyspeerChanged,
                     ntpEntNotifAddAssociation,
                     ntpEntNotifRemoveAssociation,
                     ntpEntNotifConfigChanged.
                     ntpEntNotifLeapSecondAnnounced,
                     ntpEntNotifHeartbeat
    STATUS
                current
```

**DESCRIPTION** 

"A collection of notifications for the NTP MIB" ::= { ntpEntGroups 3 }

**END** 

#### 6. IANA Considerations

The MIB module in this document uses the following IANA-assigned OBJECT IDENTIFIER values recorded in the SMI Numbers registry:

Descriptor OBJECT IDENTIFIER value -----ntpSnmp { mib-2 197 }

# 7. Security Considerations

There are currently two management objects defined in this MIB module with a MAX-ACCESS clause of read-write and/or read-create. Such objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations. These are the objects and their sensitivity/vulnerability:

ntpEntHeartbeatInterval controls the interval of heartbeat notifications. If set to 1, this will cause the NTP entity to send one notification each second. This is the maximum rate (1/s) that can be generated automatically. If it is set to 0, then one single hearbeat notification will be created and no further automatically generated notification is sent. This functionality can be used to create notifications at a higher rate (as high as the object can be written).

ntpEntNotifBits enables/disables notifications. Could be used to switch off notifications in order to delay or eliminate the notification for critical and important events.

Some of the readable objects in this MIB module (i.e., objects with a MAX-ACCESS other than not-accessible) may be considered sensitive or vulnerable in some network environments. It is thus important to control even GET and/or NOTIFY access to these objects and possibly to even encrypt the values of these objects when sending them over the network via SNMP. These are the tables and objects and their sensitivity/vulnerability:

ntpEntSoftwareName, ntpEntSoftwareVersion, ntpEntSoftwareVendor, and ntpEntSystemType all can be used to identify software and its version as well as the operating system and hardware platform. This might help a potential attacker to find security problems and therefore can be used in the preparation of an attack.

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPsec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB module. It is RECOMMENDED that implementers consider the security features as provided by the SNMPv3 framework (see RFC 3410 [RFC3410], section 8), including full support for the SNMPv3 cryptographic mechanisms (for authentication and privacy). Further, deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED to deploy SNMPv3 and to enable cryptographic security. It is then a customer/operator responsibility to ensure that the SNMP entity giving access to an instance of this MIB module is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

## 8. Acknowledgments

Bert Wijnen provided valuable feedback as the MIB Doctor for this document.

#### 9. References

#### 9.1. Normative References

- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [RFC5905] Mills, D., Martin, J., Ed., Burbank, J., and W. Kasch, "Network Time Protocol Version 4: Protocol and Algorithms Specification", RFC 5905, June 2010.
- [RFC2287] Krupczak, C. and J. Saperia, "Definitions of System-Level Managed Objects for Applications", RFC 2287, February 1998.
- [RFC2578] McCloghrie, K., Ed., Perkins, D., Ed., and J.
  Schoenwaelder, Ed., "Structure of Management Information
  Version 2 (SMIv2)", STD 58, RFC 2578, April 1999.

- [RFC2579] McCloghrie, K., Ed., Perkins, D., Ed., and J.
  Schoenwaelder, Ed., "Textual Conventions for SMIv2",
  STD 58, RFC 2579, April 1999.
- [RFC4001] Daniele, M., Haberman, B., Routhier, S., and J.
  Schoenwaelder, "Textual Conventions for Internet Network
  Addresses", RFC 4001, February 2005.

### 9.2. Informative References

[RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart,
"Introduction and Applicability Statements for InternetStandard Management Framework", RFC 3410, December 2002.

## **Authors' Addresses**

Heiko Gerstung Meinberg Funkuhren Gmbh & Co. KG Lange Wand 9 Bad Pyrmont 31812 Germany

Phone: +49 5281 9309 25

EMail: heiko.gerstung@meinberg.de

Chris Elliott 1516 Kent St. Durham, NC 27707 USA

Phone: +1-919-308-1216 EMail: chelliot@pobox.com

Brian Haberman (editor)
Johns Hopkins University Applied Physics Lab
11100 Johns Hopkins Road
Laurel, MD 20723-6099
US

Phone: +1 443 778 1319

EMail: brian@innovationslab.net