Network Working Group Request for Comments: 1162 Greg Satz cisco Systems, Inc. June 1990

## Connectionless Network Protocol (ISO 8473) and End System to Intermediate System (ISO 9542) Management Information Base

## **Table of Contents**

1. Status of this Memo
2. Historical Perspective
3 Ohiects
3.1 Format of Definitions
4. Object Definitions
4.1 The CLNP Group
4.1.1 The CLNP Interfaces table
4.1.2 The CLNP Routing table
4.1.3 The CLNP Address Translation Tables
4.2 The CLNP Error Group
4.3 The ESIS Group
5. Definitions
6. Identification of OBJECT instances for use with the
SNMP
6.1 clnpAddrTable Object Type Names
6.2 clnpRoutingTable Object Type Names
6.3 clnpNetToMediaTable Object Type Names
6.4 clnpMediaToNetTable Object Type Names
7. References
8. Security Considerations
9. Author's Address

### 1. Status of this Memo

This memo defines an experimental portion of the Management Information Base (MIB) for use with network management protocols in TCP/IP-based internets.

This memo does not specify a standard for the Internet community. However, after experimentation, if sufficient consensus is reached in the Internet community, then a subsequent revision of this document may be placed in the Internet-standard MIB.

Distribution of this memo is unlimited.

Satz [Page 1]

# 2. Historical Perspective

As reported in RFC 1052, IAB Recommendations for the Development of Internet Network Management Standards [1], a two-prong strategy for network management of TCP/IP-based internets was undertaken. In the short-term, the Simple Network Management Protocol (SNMP), defined in RFC 1067, was to be used to manage nodes in the Internet community. In the long-term, the use of the OSI network management framework was to be examined. Two documents were produced to define the management information: RFC 1065, which defined the Structure of Management Information (SMI), and RFC 1066, which defined the Management Information Base (MIB). Both of these documents were designed so as to be compatible with both the SNMP and the OSI network management framework.

This strategy was quite successful in the short-term: Internet-based network management technology was fielded, by both the research and commercial communities, within a few months. As a result of this, portions of the Internet community became network manageable in a timely fashion.

As reported in RFC 1109, Report of the Second Ad Hoc Network Management Review Group [2], the requirements of the SNMP and the OSI network management frameworks were more different than anticipated. As such, the requirement for compatibility between the SMI/MIB and both frameworks was suspended. This action permitted the operational network management framework, based on the SNMP, to respond to new operational needs in the Internet community by producing MIB-II.

In May of 1990, the core documents were elevated to "Standard Protocols" with "Recommended" status. As such, the Internetstandard network management framework consists of: Structure and Identification of Management Information for TCP/IP-based internets, RFC 1155 [3], which describes how managed objects contained in the MIB are defined; Management Information Base for Network Management of TCP/IP-based internets, which describes the managed objects contained in the MIB, RFC 1156 [4]; and, the Simple Network Management Protocol, RFC 1157 [5], which defines the protocol used to manage these objects.

Consistent with the IAB directive to produce simple, workable systems in the short-term, the list of managed objects defined in the Internet-standard MIB was derived by taking only those elements which are considered essential. However, the SMI defined three extensibility mechanisms: one, the addition of new standard objects through the definitions of new versions of the MIB; two, the addition of widely-available but non-standard objects through the experimental subtree; and three, the addition of private objects through the

Satz [Page 2]

enterprises subtree. Such additional objects can not only be used for vendor-specific elements, but also for experimentation as required to further the knowledge of which other objects are essential.

Since the publication of the Internet-standard MIB, experience has lead to a new document, termed MIB-II [6], being defined.

This memo defines extensions to the MIB using the second method. It contains definitions of managed objects used for experimentation. After experimentation, if sufficient consensus is reached in the Internet community, then a subsequent revision of this memo may be placed in the Internet-standard MIB.

# 3. Objects

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the subset of Abstract Syntax Notation One (ASN.1) [7] defined in the SMI. In particular, each object has a name, a syntax, and an encoding. The name is an object identifier, an administratively assigned name, which specifies an object type. The object type together with an object instance serves to uniquely identify a specific instantiation of the object. For human convenience, we often use a textual string, termed the OBJECT DESCRIPTOR, to also refer to the object type.

The syntax of an object type defines the abstract data structure corresponding to that object type. The ASN.1 language is used for this purpose. However, the SMI [3] purposely restricts the ASN.1 constructs which may be used. These restrictions are explicitly made for simplicity.

The encoding of an object type is simply how that object type is represented using the object type's syntax. Implicitly tied to the notion of an object type's syntax and encoding is how the object type is represented when being transmitted on the network.

This SMI specifies the use of the basic encoding rules of ASN.1 [8], subject to the additional requirements imposed by the SNMP.

#### 3.1. Format of Definitions

The next section contains the specification of all object types contained in the MIB. Following the conventions of the companion memo, the object types are defined using the following fields:

Satz [Page 3]

#### **OBJECT:**

-----

A textual name, termed the OBJECT DESCRIPTOR, for the object type, along with its corresponding OBJECT IDENTIFIER.

Syntax:

The abstract syntax for the object type, presented using ASN.1. This must resolve to an instance of the ASN.1 type ObjectSyntax defined in the SMI.

#### **Definition:**

A textual description of the semantics of the object type. Implementations should ensure that their interpretation of the object type fulfills this definition since this MIB is intended for use in multivendor environments. As such it is vital that object types have consistent meaning across all machines.

#### Access:

A keyword, one of read-only, read-write, write-only, or not-accessible. Note that this designation specifies the minimum level of support required. As a local matter, implementations may support other access types (e.g., an implementation may elect to permitting writing a variable marked herein as read-only). Further, protocol-specific "views" (e.g., those implied by an SNMP community) may make further restrictions on access to a variable.

# **Status:**

A keyword, one of mandatory, optional, obsolete, or deprecated. Use of deprecated implies mandatory status.

# 4. Object Definitions

**CLNS-MIB DEFINITIONS ::= BEGIN** 

**IMPORTS** 

experimental, OBJECT-TYPE, Counter
 FROM RFC1155-SMI;

-- new type of NetworkAddress

Satz [Page 4]

```
clns   OBJECT IDENTIFIER ::= { experimental 1 }

clnp   OBJECT IDENTIFIER ::= { clns 1 }
   error   OBJECT IDENTIFIER ::= { clns 2 }
   echo   OBJECT IDENTIFIER ::= { clns 3 }
   es-is   OBJECT IDENTIFIER ::= { clns 4 }

END
```

These objects can be used when the ISO Connectionless-mode Network Protocol [9] and End System to Intermediate System [10] protocols are present. No assumptions are made as to what underlying protocol is being used to carry the SNMP.

This memo uses the string encoding of [11] to textually describe OSI addresses.

The ASN.1 type ClnpAddress is used to denote an OSI address. This consists of a string of octets. The first octet of the string contains a binary value in the range of 0..20, and indicates the the length in octets of the NSAP. Following the first octet, is the NSAP, expressed in concrete binary notation, starting with the most significant octet. A zero-length NSAP is used as a "special" address meaning "the default NSAP" (analogous to the IP address of 0.0.0.0). Such an NSAP is encoded as a single octet, containing the value 0.

All other NSAPs are encoded in at least 2 octets.

### 4.1. The CLNP Group

Implementation is experimental and is recommended for all systems that support a CLNP.

```
OBJECT:
-----
    clnpForwarding { clnp 1 }

Syntax:
    INTEGER {
        is(1), -- entity is an intermediate system es(2), -- entity is an end system and does not forward PDUs
    }

Definition:
```

The indication of whether this entity is active as an

Satz [Page 5]

intermediate or end system. Only intermediate systems will forward PDUs onward that are not addressed to them.

```
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpDefaultLifeTime { clnp 2 }
Syntax:
     INTEGER
Definition:
     The default value inserted into the Lifetime field of the
     CLNP PDU header of PDUs sourced by this entity.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpInReceives { clnp 3 }
Syntax:
     Counter
Definition:
     The total number of input PDUs received from all
     connected network interfaces running CLNP, including
     errors.
Access:
     read-only.
Status:
     mandatory.
```

Satz [Page 6]

```
OBJECT:
     clnpInHdrErrors { clnp 4 }
Syntax:
     Counter
Definition:
     The number of input PDUs discarded due to errors in the
     CLNP header, including bad checksums, version mismatch,
     lifetime exceeded, errors discovered in processing
     options, etc.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInAddrErrors { clnp 5 }
Syntax:
     Counter
Definition:
     The number of input PDUs discarded because the NSAP
     address in the CLNP header's destination field was not a
     valid NSAP to be received at this entity. This count
     includes addresses not understood. For end systems, this is a count of PDUs which arrived with a destination NSAP
     which was not local.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpForwPDUs { clnp 6 }
Syntax:
     Counter
```

Satz [Page 7]

```
Definition:
     The number of input PDUs for which this entity was not
     the final destination and which an attempt was made to
     forward them onward.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInUnknownNLPs { clnp 7 }
Syntax:
     Counter
Definition:
     The number of locally-addressed PDUs successfully
     received but discarded because the network layer protocol was unknown or unsupported (e.g., not CLNP or ES-IS).
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInUnknownULPs { clnp 8 }
Syntax:
     Counter
Definition:
     The number of locally-addressed PDUs successfully
     received but discarded because the upper layer protocol
     was unknown or unsupported (e.g., not TP4).
Access:
     read-only.
Status:
     mandatory.
```

Satz [Page 8]

```
OBJECT:
      clnpInDiscards { clnp 9 }
Syntax:
      Counter
Definition:
      The number of input CLNP PDUs for which no problems were
     encountered to prevent their continued processing, but were discarded (e.g., for lack of buffer space). Note that this counter does not include any PDUs discarded while
      awaiting re-assembly.
Access:
      read-only.
Status:
      mandatory.
OBJECT:
      clnpInDelivers { clnp 10 }
Syntax:
      Counter
Definition:
      The total number of input PDUs successfully delivered to
      the CLNS transport user.
Access:
      read-only.
Status:
      mandatory.
OBJECT:
      clnpOutRequests { clnp 11 }
Syntax:
      Counter
Definition:
      The total number of CLNP PDUs which local CLNS user
```

Satz [Page 9]

```
protocols supplied to CLNP for transmission requests.
       This counter does not include any PDUs counted in
       clnpForwPDUs.
Access:
       read-only.
Status:
       mandatory.
OBJECT:
       clnpOutDiscards { clnp 12 }
Syntax:
       Counter
Definition:
      The number of output CLNP PDUs for which no other problem was encountered to prevent their transmission but were discarded (e.g., for lack of buffer space). Note this counter includes PDUs counted in clnpForwPDUs.
Access:
       read-only.
Status:
       mandatory.
OBJECT:
       clnpOutNoRoutes { clnp 13 }
Syntax:
       Counter
Definition:
       The number of CLNP PDUs discarded because no route could
       be found to transmit them to their destination. This counter includes any PDUs counted in clnpForwPDUs.
Access:
       read-only.
Status:
       mandatory.
```

Satz [Page 10]

```
OBJECT:
     clnpReasmTimeout { clnp 14 }
Syntax:
     INTEGER
Definition:
     The maximum number of seconds which received segments are
     held while they are awaiting reassembly at this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpReasmReqds { clnp 15 }
Syntax:
     Counter
Definition:
    The number of CLNP segments received which needed to be
     reassembled at this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpReasmOKs { clnp 16 }
Syntax:
     Counter
Definition:
     The number of CLNP PDUs successfully re-assembled at this
     entity.
```

Satz [Page 11]

```
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpReasmFails { clnp 17 }
Syntax:
     Counter
Definition:
     The number of failures detected by the CLNP reassembly
     algorithm (for any reason: timed out, buffer size, etc).
Access:
     read-only.
Status:
     mandatory.
OBJECT:
_____
     clnpSegOKs { clnp 18 }
Syntax:
     Counter
Definition:
     The number of CLNP PDUs that have been successfully
     segmented at this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpSegFails { clnp 19 }
```

Satz [Page 12]

```
Syntax:
     Counter
Definition:
     The number of CLNP PDUs that have been discarded because
     they needed to be fragmented at this entity but could
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpSegCreates { clnp 20 }
Syntax:
     Counter
Definition:
     The number of CLNP PDU segments that have been generated
     as a result of segmentation at this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInOpts { clnp 25 }
Syntax:
     Counter
Definition:
     The number of CLNP PDU segments that have been input with
     options at this entity.
Access:
     read-only.
```

Satz [Page 13]

```
Status:
            mandatory.
       OBJECT:
            clnpOutOpts { clnp 26 }
       Syntax:
            Counter
       Definition:
            The number of CLNP PDU segments that have been generated
            with options by this entity.
       Access:
            read-only.
       Status:
            mandatory.
     The CLNP Interfaces table
The CLNP Interfaces table contains information on the entity's
interfaces which are running the CLNP.
       OBJECT:
            clnpAddrTable { clnp 21 }
       Syntax:
            SEQUENCE OF ClnpAddrEntry
       Definition:
            The table of addressing information relevant to this
            entity's CLNP addresses.
       Access:
            not-accessible.
       Status:
            mandatory.
       OBJECT:
            clnpAddrEntry { clnpAddrTable 1 }
```

Satz [Page 14]

```
Syntax:
     ClnpAddrEntry :: = SEQUENCE {
          clnpAdEntAddr
              ClnpAddress,
          clnpAdEntIfIndex
              INTEGER,
          clnpAdEntReasmMaxSize
              INTEGER (0..65535)
     }
Definition:
     The addressing information for one of this entity's CLNP
     addresses.
Access:
     not-accessible.
Status:
     mandatory.
OBJECT:
     clnpAdEntAddr { clnpAddrEntry 1 }
Syntax:
     ClnpAddress
Definition:
     The CLNP address to which this entry's addressing
     information pertains.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpAdEntIfIndex { clnpAddrEntry 2 }
Syntax:
     INTEGER
Definition:
     The index value which uniquely identifies the interface
```

Satz [Page 15]

to which this entry is applicable. The interface identified by a particular value of this index is the same interface as identified by the same value of ifIndex.

Access:

read-only.

**Status:** 

mandatory.

**OBJECT:** 

clnpAdEntReasmMaxSize { clnpAddrEntry 3 }

Syntax:

INTEGER (0..65535)

**Definition:** 

The size of the largest CLNP PDU which this entity can re-assemble from incoming CLNP segmented PDUs received on this interface.

Access:

read-only.

Status:

mandatory.

## 4.1.2. The CLNP Routing table

The CLNP Routing table contains an entry for each route known to the entity.

**OBJECT:** 

clnpRoutingTable { clnp 22 }

Syntax:

**SEQUENCE OF ClnpRouteEntry** 

**Definition:** 

This entity's CLNP routing table.

**Access:** 

not-accessible.

Satz [Page 16]

```
Status:
     mandatory.
OBJECT:
     clnpRouteEntry { clnpRoutingTable 1 }
Syntax:
     ClnpRouteEntry ::= SEQUENCE {
          clnpRouteDest
              ClnpAddress,
          clnpRouteIfIndex
              INTEGER.
          clnpRouteMetric1
              INTEGER,
          clnpRouteMetric2
              INTEGER,
          clnpRouteMetric3
              INTEGER,
          clnpRouteMetric4
              INTEGER,
          clnpRouteNextHop
              ClnpAddress,
          clnpRouteType
              INTEGER,
          clnpRouteProto
              INTEGER,
          clnpRouteAge
              INTEGER
     }
Definition:
     A route to a particular destination.
Access:
     not-accessible.
Status:
     mandatory.
OBJECT:
     clnpRouteDest { clnpRouteEntry 1 }
Syntax:
     ClnpAddress
```

Satz [Page 17]

```
Definition:
      The destination CLNP address of this route.
Access:
      read-write.
Status:
      mandatory.
OBJECT:
      clnpRouteIfIndex { clnpRouteEntry 2 }
Syntax:
      INTEGER
Definition:
      The index value which uniquely identifies the local
     interface through which the next hop of this route should be reached. The interface identified by a particular value of this index is the same as identified by the same value of ifIndex.
Access:
      read-write.
Status:
      mandatory.
OBJECT:
      clnpRouteMetric1 { clnpRouteEntry 3 }
Syntax:
      INTEGER
Definition:
      The primary routing metric for this route. The semantics
      of this metric are determined by the routing-protocol
      specified in the route's clnpRouteProto value. If this
      metric is not used, its value should be set to -1.
Access:
      read-write.
```

Satz [Page 18]

```
Status:
     mandatory.
OBJECT:
     clnpRouteMetric2 { clnpRouteEntry 4 }
Syntax:
     INTEGER
Definition:
     An alternate routing metric for this route. The semantics of this metric are determined by the routing-
     protocol specified in the route's clnpRouteProto value.
     If this metric is not used, its value should be set to
     -1.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
_____
     clnpRouteMetric3 { clnpRouteEntry 5 }
Syntax:
     INTEGER
Definition:
     An alternate routing metric for this route. The
     semantics of this metric are determined by the routing-
     protocol specified in the route's clnpRouteProto value.
     If this metric is not used, its value should be set to
     -1.
Access:
     read-write.
Status:
     mandatory.
```

Satz [Page 19]

```
OBJECT:
     clnpRouteMetric4 { clnpRouteEntry 6 }
Syntax:
     INTEGER
Definition:
     An alternate routing metric for this route. The semantics of this metric are determined by the routing-
     protocol specified in the route's clnpRouteProto value.
     If this metric is not used, its value should be set to
     -1.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpRouteNextHop { clnpRouteEntry 7 }
Syntax:
     ClnpAddress
Definition:
     The CLNP address of the next hop of this route.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpRouteType { clnpRouteEntry 8 }
Syntax:
     INTEGER {
           other(1), -- none of the following
           invalid(2), -- an invalidated route
```

Satz [Page 20]

```
-- route to directly
          direct(3),
                          -- connected (sub-)network
                          -- route to a non-local
          remote(4)
                          -- host/network/sub-network
     }
Definition:
     The type of route.
Setting this object to the value invalid(2) has the effect of
invaliding the corresponding entry in the clnpRoutingTable.
That is, it effectively dissasociates the destination
identified with said entry from the route identified with said
entry. It is an implementation-specific matter as to whether
the agent removes an invalidated entry from the table.
Accordingly, management stations must be prepared to receive
tabular information from agents that corresponds to entries
not currently in use. Proper interpretation of such entries requires examination of the relevant clnpRouteType object.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpRouteProto { clnpRouteEntry 9 }
Syntax:
     INTEGER {
                         -- none of the following
          other(1),
                         -- non-protocol information
                               e.g., manually
          local(2),
                               configured entries
                         --
                         -- set via a network
          netmgmt(3),
                               management protocol
                         -- similar to ipRouteProto
                         -- but omits several IP-specific
                         -- protocols
          is-is(9),
```

Satz [Page 21]

```
ciscoIgrp(11),
            bbnSpfIgp(12),
            ospf(13),
            bqp(14)
Definition:
      The routing mechanism via which this route was learned.
      Inclusion of values for gateway routing protocols is not
      intended to imply that hosts should support those
      protocols.
Access:
      read-write.
Status:
      mandatory.
OBJECT:
      clnpRouteAge { clnpRouteEntry 10 }
Svntax:
      INTEGER
Definition:
      The number of seconds since this route was last updated or otherwise determined to be correct. Note that no semantics of "too old" can be implied except through
      knowledge of the routing protocol by which the route was
      learned.
```

Access:

read-write.

**Status:** 

mandatory.

#### 4.1.3. The CLNP Address Translation Tables

The Address Translation tables contain the CLNP address to physical address equivalences. Some interfaces do not use translation tables for determining address equivalences; if all interfaces are of this type, then the Address Translation table is empty, i.e., has zero entries.

Satz [Page 22]

```
OBJECT:
     clnpNetToMediaTable { clnp 23 }
Syntax:
     SEQUENCE OF ClnpNetToMediaEntry
Definition:
     The CLNP Address Translation table used for mapping from
     CLNP addresses to physical addresses.
Access:
      not-accessible
Status:
     mandatory.
OBJECT:
     clnpNetToMediaEntry { clnpNetToMediaTable 1 }
Syntax:
     ClnpNetToMediaEntry ::= SEQUENCE {
          clnpNetToMediaIfIndex
               INTEGER,
          clnpNetToMediaPhysAddress
    OCTET STRING,
          clnpNetToMediaNetAddress
               ClnpAddress,
          clnpNetToMediaType
          INTEGER,
clnpNetToMediaAge
          INTEGER,
clnpNetToMediaHoldTime
               INTEGER
     }
Definition:
     Each entry contains one CLNP address to "physical"
     address equivalence.
Access:
     not-accessible.
Status:
     mandatory.
```

Satz [Page 23]

```
OBJECT:
     clnpNetToMediaIfIndex { clnpNetToMediaEntry 1 }
Syntax:
     INTEGER
Definition:
     The interface on which this entry's equivalence is effective. The interface identified by a particular
     value of this index is the same interface as identified
     by the same value of ifIndex.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpNetToMediaPhysAddress { clnpNetToMediaEntry 2 }
Syntax:
     OCTET STRING
Definition:
     The media-dependent "physical" address.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpNetToMediaNetAddress { clnpNetToMediaEntry 3 }
Syntax:
     ClnpAddress
Definition:
     The CLNP address corresponding to the media-dependent
     "physical" address.
```

Satz [Page 24]

```
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpNetToMediaType { clnpNetToMediaEntry 4 }
Syntax:
     INTEGER {
          other(1),
invalid(2),
                            -- none of the following
                            -- an invalidated mapping
           dynamic(3),
           static(4)
     }
Definition:
     The type of mapping.
Setting this object to the value invalid(2) has the effect of
invalidating the corresponding entry in the
clnpNetToMediaTable. That is, it effectively dissassociates
the interface identified with said entry from the mapping
identified with said entry. It is an implementation-specific
matter as to whether the agent removes an invalidated entry
from the table. Accordingly, management stations must be prepared to receive tabular information from agents that
corresponds to entries not currently in use. Proper
interpretation of such entries requires examination of the
relevant clnpNetToMediaType object.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpNetToMediaAge { clnpNetToMediaEntry 5 }
Syntax:
     INTEGER
```

Satz [Page 25]

```
Definition:
     The number of seconds since this entry was last updated or otherwise determined to be correct. Note that no semantics of "too old" can be implied except through
      knowledge of the type of entry.
Access:
      read-write.
Status:
     mandatory.
OBJECT:
      clnpNetToMediaHoldTime { clnpNetToMediaEntry 6 }
Syntax:
      INTEGER
Definition:
      The time in seconds this entry will be valid. Static
      entries should always report this field as -1.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
      clnpMediaToNetTable { clnp 24 }
Syntax:
      SEQUENCE OF ClnpMediaToNetEntry
Definition:
      The CLNP Address Translation table used for mapping from
     physical addresses to CLNP addresses.
Access:
     not-accessible.
Status:
     mandatory.
```

Satz [Page 26]

```
OBJECT:
     clnpMediaToNetEntry { clnpMediaToNetTable 1 }
Syntax:
     ClnpMediaToNetEntry ::= SEQUENCE {
           clnpMediaToNetIfIndex
               INTEGER,
           clnpMediaToNetNetAddress
               ClnpAddress,
           clnpMediaToNetPhysAddress
               OCTET STRING,
           clnpMediaToNetType
               INTEGER,
           clnpMediaToNetAge
               INTEGER,
           clnpMediaToNetHoldTime
               INTEGER
     }
Definition:
     Each entry contains on ClnpAddress to "physical" address
     equivalence.
Access:
     not-accessible.
Status:
     mandatory.
OBJECT:
     clnpMediaToNetIfIndex { clnpMediaToNetEntry 1 }
Syntax:
     INTEGER
Definition:
     The interface on which this entry's equivalence is effective. The interface identified by a particular
     value of this index is the same interface as identified
     by the same value of ifIndex.
Access:
     read-write.
```

Satz [Page 27]

```
Status:
     mandatory.
OBJECT:
     clnpMediaToNetAddress { clnpMediaToNetEntry 2 }
Syntax:
     ClnpAddress
Definition:
     The ClnpAddress corresponding to the media-dependent
     "physical" address.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpMediaToNetPhysAddress { clnpMediaToNetEntry 3 }
Syntax:
     OCTET STRING
Definition:
     The media-dependent "physical" address.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpMediaToNetType { clnpMediaToNetEntry 4 }
Syntax:
     INTEGER {
                       -- none of the following-- an invalidated mapping
          other(1),
invalid(2),
           dynamic(3),
```

Satz [Page 28]

static(4)

```
}
Definition:
     The type of mapping.
Setting this object to the value invalid(2) has the effect of
invalidating the corresponding entry in the
clnpMediaToNetTable. That is, it effectively dissassociates
the interface identified with said entry from the mapping
identified with said entry. It is an implementation-specific
matter as to whether the agent removes an invalidated entry
from the table. Accordingly, management stations must be
prepared to receive tabular information from agents that corresponds to entries not currently in use. Proper
interpretation of such entries requires examination of the
relevant clnpMediaToNetType object.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
_____
     clnpMediaToNetAge { clnpMediaToNetEntry 5 }
Syntax:
     INTEGER
Definition:
     The number of seconds since this entry was last updated or otherwise determined to be correct. Note that no semantics of "too old" can be implied except through
     knowledge of the type of entry.
Access:
     read-write.
Status:
     mandatory.
OBJECT:
     clnpMediaToNetHoldTime { clnpMediaToNetEntry 6 }
```

Satz [Page 29]

```
Syntax:
               INTEGER
          Definition:
               The time in seconds this entry will be valid. Static
               entries should always report this field as -1.
          Access:
               read-write.
          Status:
               mandatory.
4.2. The CLNP Error Group
   This group records the CLNP Error protocol and is recommended for all
   systems which support CLNP.
          OBJECT:
               clnpInErrors { error 1 }
          Syntax:
               Counter
          Definition:
               The number of CLNP Error PDUs received by this entity.
          Access:
               read-only.
          Status:
               mandatory.
          OBJECT:
               clnpOutErrors { error 2 }
          Syntax:
               Counter
          Definition:
               The number of CLNP Error PDUs sent by this entity.
```

Satz [Page 30]

Access:

read-only.

```
Status:
     mandatory.
OBJECT:
     clnpInErrUnspecs { error 3 }
Syntax:
     Counter
Definition:
     The number of unspecified CLNP Error PDUs received by
     this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrProcs { error 4 }
Syntax:
     Counter
Definition:
     The number of protocol procedure CLNP Error PDUs received
     by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrCksums { error 5 }
Syntax:
     Counter
```

Satz [Page 31]

```
Definition:
     The number of checksum CLNP Error PDUs received by this
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrCongests { error 6 }
Syntax:
     Counter
Definition:
     The number of congestion drop CLNP Error PDUs received by
     this entity.
Access:
     read-only.
Status:
    mandatory.
OBJECT:
     clnpInErrHdrs { error 7 }
Syntax:
     Counter
Definition:
     The number of header syntax CLNP Error PDUs received by
     this entity.
Access:
     read-only.
Status:
     mandatory.
```

Satz [Page 32]

```
OBJECT:
     clnpInErrSegs { error 8 }
Syntax:
     Counter
Definition:
     The number of segmentation disallowed CLNP Error PDUs
     received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrIncomps { error 9 }
Syntax:
     Counter
Definition:
     The number of incomplete PDU CLNP Error PDUs received by
     this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrDups { error 10 }
Syntax:
     Counter
Definition:
     The number of duplicate option CLNP Error PDUs received
     by this entity.
```

Satz [Page 33]

```
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrUnreachDsts { error 11 }
Syntax:
     Counter
Definition:
     The number of unreachable destination CLNP Error PDUs
     received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
_____
     clnpInErrUnknownDsts { error 12 }
Syntax:
     Counter
Definition:
     The number of unknown destination CLNP Error PDUs
     received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrSRUnspecs { error 13 }
```

Satz [Page 34]

```
Syntax:
     Counter
Definition:
     The number of unspecified source route CLNP Error PDUs
     received by this entity.
Access:
     read-only.
Status:
    mandatory.
OBJECT:
     clnpInErrSRSyntaxes { error 14 }
Syntax:
     Counter
Definition:
     The number of source route syntax CLNP Error PDUs
     received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrSRUnkAddrs { error 15 }
Syntax:
     Counter
Definition:
     The number of source route unknown address CLNP Error
     PDUs received by this entity.
Access:
     read-only.
Status:
     mandatory.
```

Satz [Page 35]

```
OBJECT:
     clnpInErrSRBadPaths { error 16 }
Syntax:
     Counter
Definition:
     The number of source route bad path CLNP Error PDUs
     received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrHops { error 17 }
Syntax:
     Counter
Definition:
    The number of hop count exceeded CLNP Error PDUs received
     by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrHopReassms { error 18 }
Syntax:
     Counter
Definition:
     The number of hop count exceeded while reassembling CLNP
     Error PDUs received by this entity.
```

Satz [Page 36]

```
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrUnsOptions { error 19 }
Syntax:
     Counter
Definition:
     The number of unsupported option CLNP Error PDUs received
     by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
_____
     clnpInErrUnsVersions { error 20 }
Syntax:
     Counter
Definition:
     The number of version mismatch CLNP Error PDUs received
     by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrUnsSecurities { error 21 }
```

Satz [Page 37]

```
Syntax:
     Counter
Definition:
     The number of unsupported security option CLNP Error PDUs
     received by this entity.
Access:
     read-only.
Status:
    mandatory.
OBJECT:
     clnpInErrUnsSRs { error 22 }
Syntax:
     Counter
Definition:
     The number of unsupported source route option CLNP Error
     PDUs received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpInErrUnsRRs { error 23 }
Syntax:
     Counter
Definition:
     The number of unsupported record route option CLNP Error
     PDUs received by this entity.
Access:
     read-only.
Status:
     mandatory.
```

Satz [Page 38]

```
OBJECT:
     clnpInErrInterferences { error 24 }
Syntax:
     Counter
Definition:
     The number of reassembly interference CLNP Error PDUs
     received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrUnspecs { error 25 }
Syntax:
     Counter
Definition:
     The number of unspecified CLNP Error PDUs sent by this
     entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrProcs { error 26 }
Syntax:
     Counter
Definition:
     The number of protocol procedure CLNP Error PDUs sent by
     this entity.
```

Satz [Page 39]

```
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrCksums { error 27 }
Syntax:
     Counter
Definition:
     The number of checksum CLNP Error PDUs sent by this
     entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
_____
     clnpOutErrCongests { error 28 }
Syntax:
     Counter
Definition:
     The number of congestion drop CLNP Error PDUs sent by
     this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrHdrs { error 29 }
```

Satz [Page 40]

```
Syntax:
     Counter
Definition:
     The number of header syntax CLNP Error PDUs sent by this
     entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrSegs { error 30 }
Syntax:
     Counter
Definition:
     The number of segmentation disallowed CLNP Error PDUs
     sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrIncomps { error 31 }
Syntax:
     Counter
Definition:
     The number of incomplete PDU CLNP Error PDUs sent by this
     entity.
Access:
     read-only.
Status:
     mandatory.
```

Satz [Page 41]

```
OBJECT:
     clnpOutErrDups { error 32 }
Syntax:
     Counter
Definition:
     The number of duplicate option CLNP Error PDUs sent by
     this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrUnreachDsts { error 33 }
Syntax:
     Counter
Definition:
     The number of unreachable destination CLNP Error PDUs
     sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrUnknownDsts { error 34 }
Syntax:
     Counter
Definition:
     The number of unknown destination CLNP Error PDUs sent by
     this entity.
```

Satz [Page 42]

```
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrSRUnspecs { error 35 }
Syntax:
     Counter
Definition:
     The number of unspecified source route CLNP Error PDUs
     sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
_____
     clnpOutErrSRSyntaxes { error 36 }
Syntax:
     Counter
Definition:
     The number of source route syntax CLNP Error PDUs sent by
     this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrSRUnkAddrs { error 37 }
```

Satz [Page 43]

```
Syntax:
     Counter
Definition:
     The number of source route unknown address CLNP Error
     PDUs sent by this entity.
Access:
     read-only.
Status:
    mandatory.
OBJECT:
     clnpOutErrSRBadPaths { error 38 }
Syntax:
     Counter
Definition:
     The number of source route bad path CLNP Error PDUs sent
     by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrHopss { error 39 }
Syntax:
     Counter
Definition:
     The number of hop count exceeded CLNP Error PDUs sent by
     this entity.
Access:
     read-only.
Status:
     mandatory.
```

Satz [Page 44]

```
OBJECT:
     clnpOutErrHopReassms { error 40 }
Syntax:
     Counter
Definition:
     The number of hop count exceeded while reassembling CLNP
     Error PDUs sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrUnsOptions { error 41 }
Syntax:
     Counter
Definition:
     The number of unsupported option CLNP Error PDUs sent by
     this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrUnsVersions { error 42 }
Syntax:
     Counter
Definition:
     The number of version mismatch CLNP Error PDUs sent by
     this entity.
```

Satz [Page 45]

```
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrUnsSecurities { error 43 }
Syntax:
     Counter
Definition:
    The number of unsupported security option CLNP Error PDUs
     sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
_____
     clnpOutErrUnsSRs { error 44 }
Syntax:
     Counter
Definition:
     The number of unsupported source route option CLNP Error
     PDUs sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrUnsRRs { error 45 }
```

Satz [Page 46]

```
Syntax:
     Counter
Definition:
     The number of unsupported record route option CLNP Error
     PDUs sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     clnpOutErrInterferences { error 46 }
Syntax:
     Counter
Definition:
     The number of reassembly interference CLNP Error PDUs
     sent by this entity.
Access:
     read-only.
Status:
     mandatory.
```

# 4.3. The ESIS Group

The ESIS group contains information about the End System Intermediate System protocol used to maintain neighbor reachibility information. Both ESs and ISs are expected to implement this group if they running a CLNP.

Satz [Page 47]

```
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     esisESHout { es-is 2 }
Syntax:
     Counter
Definition:
     The number of ESH PDUs sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     esisISHin { es-is 3 }
Syntax:
     Counter
Definition:
     The number of ISH PDUs received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     esisISHout { es-is 4 }
Syntax:
     Counter
```

Satz [Page 48]

```
Definition:
     The number of ISH PDUs sent by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     esisRDUin { es-is 5 }
Syntax:
     Counter
Definition:
     The number of RDU PDUs received by this entity.
Access:
     read-only.
Status:
     mandatory.
OBJECT:
     esisRDUout { es-is 6 }
Syntax:
     Counter
Definition:
     The number of RDU PDUs sent by this entity.
Access:
     read-only.
Status:
     mandatory.
```

Satz [Page 49]

#### 5. Definitions

```
CLNS-MIB DEFINITIONS ::= BEGIN
IMPORTS
        experimental, OBJECT-TYPE, Counter
                 FROM RFC1155-SMI;
-- new type of NetworkAddress
ClnpAddress ::=
    [APPLICATION 5]
        IMPLICIT OCTET STRING (SIZE (1..21))
clns
        OBJECT IDENTIFIER ::=
                                 { experimental 1 }
        OBJECT IDENTIFIER ::=
                                  { clns 1 } { clns 2 }
clnp
        OBJECT IDENTIFIER ::=
error
        OBJECT IDENTIFIER ::= OBJECT IDENTIFIER ::=
                                  { clns 3 { clns 4
echo
es-is
-- the General CLNP group
clnpForwarding OBJECT-TYPE
                INTEGER {
        SYNTAX
                     is(1),
                              -- entity is an
                              -- intermediate system
                              -- entity is an end system
                     es(2)
                              -- and does not forward pdus
                 }
        ACCESS
                 read-write
        STATUS mandatory
        ::= { clnp 1 }
clnpDefaultLifeTime OBJECT-TYPE
        SYNTAX INTEGER
        ACCESS read-write
        STATUS mandatory
        ::= { clnp 2 }
clnpInReceives OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { clnp 3 }
```

Satz [Page 50]

```
clnpInHdrErrors OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { clnp 4 }
clnpInAddrErrors OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { clnp 5 }
clnpForwPDUs OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { clnp 6 }
clnpInUnknownNLPs OBJECT-TYPE
        SYNTAX Counter
                read-only
        ACCESS
        STATUS
               mandatory
        ::= { clnp 7 }
clnpInUnknownULPs OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { clnp 8 }
clnpInDiscards OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { clnp 9 }
clnpInDelivers OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { clnp 10 }
clnpOutRequests OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { clnp 11 }
```

Satz [Page 51]

```
clnpOutDiscards OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { clnp 12 }
clnpOutNoRoutes OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { clnp 13 }
clnpReasmTimeout OBJECT-TYPE
        SYNTAX
                INTEGER
        ACCESS
                read-only
        STATUS
                mandatory
        ::= { clnp 14 }
clnpReasmReqds
                OBJECT-TYPE
        SYNTAX
                Counter
                read-only
        ACCESS
        STATUS
                mandatory
        ::= { clnp 15 }
clnpReasmOKs
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS
                mandatory
        ::= { clnp 16 }
                OBJECT-TYPE
clnpReasmFails
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { clnp 17 }
clnpSegOKs
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { clnp 18 }
                OBJECT-TYPE
clnpSegFails
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { clnp 19 }
```

Satz [Page 52]

```
clnpSegCreates
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS
                mandatory
        ::= { clnp 20 }
                OBJECT-TYPE
clnpInOpts
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { clnp 25 }
                OBJECT-TYPE
clnpOutOpts
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS
                mandatory
        ::= { clnp 26 }
-- the CLNP Interface table
                OBJECT-TYPE
clnpAddrTable
        SYNTAX
                SEQUENCE OF ClnpAddrEntry
        ACCESS
                not-accessible
        STATUS
                mandatory
        ::= { clnp 21 }
clnpAddrEntry
                OBJECT-TYPE
        SYNTAX
                ClnpAddrEntry
        ACCESS
                not-accessible
        STATUS
                mandatory
        INDEX
                { clnpAdEntAddr }
        ::= { clnpAddrTable 1 }
ClnpAddrEntry ::= SEQUENCE {
    clnpAdEntAddr
        ClnpAddress,
    clnpAdEntIfIndex
        INTEGER,
    clnpAdEntReasmMaxSize
        INTEGER (0..65535)
}
clnpAdEntAddr OBJECT-TYPE
                ClnpAddress
        SYNTAX
        ACCESS
                read-only
        STATUS
                mandatory
        ::= { clnpAddrEntry 1 }
```

Satz [Page 53]

```
clnpAdEntIfIndex OBJECT-TYPE
        SYNTAX
                INTEGER
        ACCESS
                read-only
        STATUS
                mandatory
        ::= { clnpAddrEntry 2 }
clnpAdEntReasmMaxSize OBJECT-TYPE
        SYNTAX
                INTEGER (0..65535)
        ACCESS
                read-only
        STATUS mandatory
        ::= { clnpAddrEntry 3 }
-- the CLNP Routing table
clnpRoutingTable OBJECT-TYPE
        SYNTAX
                SEQUENCE OF ClnpRouteEntry
        ACCESS
                not-accessible
        STATUS
                mandatory
        ::= { clnp 22 }
clnpRouteEntry OBJECT-TYPE
        SYNTAX
                ClnpRouteEntry
        ACCESS
                not-accessible
        STATUS
                mandatory
                { clnpRouteDest }
        INDEX
        ::= { clnpRoutingTable 1 }
ClnpRouteEntry ::= SEQUENCE {
    clnpRouteDest
        ClnpAddress,
    clnpRouteIfIndex
        INTEGER,
    clnpRouteMetric1
        INTEGER.
    clnpRouteMetric2
        INTEGER,
    clnpRouteMetric3
        INTEGER,
    clnpRouteMetric4
        INTEGER,
    clnpRouteNextHop
        ClnpAddress,
    clnpRouteType
        INTEGER,
    clnpRouteProto
        INTEGER,
    clnpRouteAge
        INTEGER
```

Satz [Page 54]

```
}
clnpRouteDest OBJECT-TYPE
        SYNTAX
                ClnpAddress
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpRouteEntry 1 }
clnpRouteIfIndex OBJECT-TYPE
        SYNTAX INTEGER
        ACCESS
               read-write
        STATUS mandatory
        ::= { clnpRouteEntry 2 }
clnpRouteMetric1 OBJECT-TYPE
        SYNTAX
               INTEGER
        ACCESS
               read-write
        STATUS mandatory
        ::= { clnpRouteEntry 3 }
clnpRouteMetric2 OBJECT-TYPE
        SYNTAX INTEGER
        ACCESS
               read-write
        STATUS mandatory
        ::= { clnpRouteEntry 4 }
clnpRouteMetric3 OBJECT-TYPE
        SYNTAX
               INTEGER
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpRouteEntry 5 }
clnpRouteMetric4 OBJECT-TYPE
        SYNTAX
                INTEGER
                read-write
        ACCESS
        STATUS mandatory
        ::= { clnpRouteEntry 6 }
clnpRouteNextHop OBJECT-TYPE
        SYNTAX
               ClnpAddress
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpRouteEntry 7 }
clnpRouteType OBJECT-TYPE
        SYNTAX
                INTEGER {
                    other(1),
                                   -- none of the
                                   -- following
```

Satz [Page 55]

```
invalid(2),
                                    -- an invalidated
                                    -- route
                                    -- route to directly
                    direct(3),
                                    -- connected
                                    -- (sub-)network
                                    -- route to a
                                    -- non-local
                    remote(4)
                                    -- host/network
                                    -- /sub-network
        ACCESS
                read-write
                mandatory
        STATUS
        ::= { clnpRouteEntry 8 }
clnpRouteProto OBJECT-TYPE
        SYNTAX
                INTEGER {
                    other(1),
                                   -- none of the
                                   -- following
                                   -- non-protocol
                                   -- information
                                        e.g., manually
                    local(2),
                                        configured entries
                                   -- set via a network
                    netmgmt(3),
                                        management
                                        protocol
                                   -- similar to
                                   -- ipRouteProto
                                   -- but omits several
                                   -- IP-specific
                                   -- protocols
                    is-is(9),
                    ciscolgrp(11),
                    bbnSpfIgp(12),
                    ospf(13),
                    bgp(14)
        ACCESS
                read-only
        STATUS
                mandatory
        ::= { clnpRouteEntry 9 }
clnpRouteAge OBJECT-TYPE
        SYNTAX INTEGER
               read-write
        ACCESS
```

Satz [Page 56]

```
STATUS mandatory
        ::= { clnpRouteEntry 10 }
-- the CLNP Address Translation tables
clnpNetToMediaTable OBJECT-TYPE
                SEQUENCE OF ClnpNetToMediaEntry
        SYNTAX
        ACCESS
                not-accessible
        STATUS
                mandatory
        ::= { clnp 23 }
clnpNetToMediaEntry OBJECT-TYPE
                ClnpNetToMediaEntry
        SYNTAX
                not-accessible
        ACCESS
        STATUS
                mandatory
        INDEX
                { clnpNetToMediaIfIndex,
                  clnpNetToMediaNetAddress }
        ::= { clnpNetToMediaTable 1 }
ClnpNetToMediaEntry ::= SEQUENCE {
    clnpNetToMediaIfIndex
        INTEGER,
    clnpNetToMediaPhysAddress
        OCTET STRING.
    clnpNetToMediaNetAddress
        ClnpAddress,
    clnpNetToMediaType
        INTEGER,
    clnpNetToMediaAge
        INTEGER,
    clnpNetToMediaHoldTime
        INTEGER
}
clnpNetToMediaIfIndex OBJECT-TYPE
        SYNTAX INTEGER
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpNetToMediaEntry 1 }
clnpNetToMediaPhysAddress OBJECT-TYPE
        SYNTAX OCTET STRING
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpNetToMediaEntry 2 }
clnpNetToMediaNetAddress OBJECT-TYPE
        SYNTAX ClnpAddress
```

Satz [Page 57]

```
ACCESS
               read-write
        STATUS
                mandatory
        ::= { clnpNetToMediaEntry 3 }
clnpNetToMediaType OBJECT-TYPE
        SYNTAX INTEGER {
                    other(1),
                                    -- none of the
                                    -- following
                    invalid(2),
                                    -- an invalidated
                                    -- mapping
                    dynamic(3),
                    static(4)
        ACCESS
                read-write
        STATUS
                mandatory
        ::= { clnpNetToMediaEntry 4 }
clnpNetToMediaAge OBJECT-TYPE
        SYNTAX INTEGER
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpNetToMediaEntry 5 }
clnpNetToMediaHoldTime OBJECT-TYPE
        SYNTAX INTEGER
        ACCESS
               read-write
        STATUS mandatory
        ::= { clnpNetToMediaEntry 6 }
clnpMediaToNetTable OBJECT-TYPE
                SEQUENCE OF ClnpMediaToNetEntry
        SYNTAX
        ACCESS
                not-accessible
        STATUS mandatory
        ::= { clnp 24 }
clnpMediaToNetEntry OBJECT-TYPE
        SYNTAX ClipMediaToNetEntry
        ACCESS
                not-accessible
        STATUS
                mandatory
                { clnpMediaToNetIfIndex,
        INDEX
                  clnpMediaToNetPhysAddress }
        ::= { clnpMediaToNetTable 1 }
ClnpMediaToNetEntry ::= SEQUENCE {
    clnpMediaToNetIfIndex
        INTEGER,
    clnpMediaToNetNetAddress
        ClnpAddress,
```

Satz [Page 58]

```
clnpMediaToNetPhysAddress
        OCTET STRING,
    clnpMediaToNetType
        INTEGER,
    clnpMediaToNetAge
        INTEGER,
    clnpMediaToNetHoldTime
        INTEGER
}
clnpMediaToNetIfIndex OBJECT-TYPE
        SYNTAX INTEGER
        ACCESS
               read-write
        STATUS mandatory
        ::= { clnpMediaToNetEntry 1 }
clnpMediaToNetNetAddress OBJECT-TYPE
        SYNTAX
                ClnpAddress
        ACCESS read-write
        STATUS mandatory
        ::= { clnpMediaToNetEntry 2 }
clnpMediaToNetPhysAddress OBJECT-TYPE
        SYNTAX OCTET STRING
        ACCESS
               read-write
        STATUS mandatory
        ::= { clnpMediaToNetEntry 3 }
clnpMediaToNetType OBJECT-TYPE
        SYNTAX INTEGER {
                    other(1),
                                    -- none of the
                                    -- following
                    invalid(2),
                                    -- an invalidated
                                    -- mapping
                    dynamic(3),
                    static(4)
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpMediaToNetEntry 4 }
clnpMediaToNetAge OBJECT-TYPE
                INTEGER
        SYNTAX
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpMediaToNetEntry 5 }
clnpMediaToNetHoldTime OBJECT-TYPE
```

Satz [Page 59]

```
SYNTAX
                INTEGER
        ACCESS
                read-write
        STATUS mandatory
        ::= { clnpMediaToNetEntry 6 }
-- the CLNP Error Group
clnpInErrors
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS read-only
        STATUS mandatory
        ::= { error 1 }
                OBJECT-TYPE
clnpOutErrors
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 2 }
clnpInErrUnspecs OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 3 }
clnpInErrProcs OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 4 }
clnpInErrCksums OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 5 }
clnpInErrCongests OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 6 }
clnpInErrHdrs
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 7 }
```

Satz [Page 60]

```
clnpInErrSegs
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 8 }
clnpInErrIncomps OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 9 }
                OBJECT-TYPE
clnpInErrDups
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 10 }
clnpInErrUnreachDsts OBJECT-TYPE
        SYNTAX Counter
                read-only
        ACCESS
        STATUS mandatory
        ::= { error 11 }
clnpInErrUnknownDsts OBJECT-TYPE
        SYNTAX Counter
               read-only
        ACCESS
        STATUS mandatory
        ::= { error 12 }
clnpInErrSRUnspecs OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 13 }
clnpInErrSRSyntaxes OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 14 }
clnpInErrSRUnkAddrs OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 15 }
```

Satz [Page 61]

```
clnpInErrSRBadPaths OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 16 }
                OBJECT-TYPE
clnpInErrHops
        SYNTAX
                Counter
               read-only
        ACCESS
        STATUS mandatory
        ::= { error 17 }
clnpInErrHopReassms OBJECT-TYPE
        SYNTAX
               Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 18 }
clnpInErrUnsOptions OBJECT-TYPE
        SYNTAX Counter
                read-only
        ACCESS
        STATUS mandatory
        ::= { error 19 }
clnpInErrUnsVersions OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 20 }
clnpInErrUnsSecurities OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 21 }
clnpInErrUnsSRs OBJECT-TYPE
        SYNTAX Counter
        ACCESS read-only
        STATUS mandatory
        ::= { error 22 }
clnpInErrUnsRRs OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 23 }
```

Satz [Page 62]

```
clnpInErrInterferences OBJECT-TYPE
        SYNTAX Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 24 }
clnpOutErrUnspecs OBJECT-TYPE SYNTAX Counter_
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 25 }
clnpOutErrProcs OBJECT-TYPE
        SYNTAX
               Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 26 }
clnpOutErrCksums OBJECT-TYPE
        SYNTAX Counter
               read-only
        ACCESS
        STATUS mandatory
        ::= { error 27 }
clnpOutErrCongests OBJECT-TYPE
        SYNTAX Counter
                read-only
        ACCESS
        STATUS mandatory
        ::= { error 28 }
clnpOutErrHdrs OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 29 }
clnpOutErrSegs OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS read-only
        STATUS mandatory
        ::= { error 30 }
clnpOutErrIncomps OBJECT-TYPE
        SYNTAX
               Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { error 31 }
```

Satz [Page 63]

```
clnpOutErrDups
               OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 32 }
clnpOutErrUnreachDsts OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 33 }
clnpOutErrUnknownDsts OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 34 }
clnpOutErrSRUnspecs OBJECT-TYPE
        SYNTAX
               Counter
                read-only
        ACCESS
        STATUS mandatory
        ::= { error 35 }
clnpOutErrSRSyntaxes OBJECT-TYPE
        SYNTAX Counter
               read-only
        ACCESS
        STATUS mandatory
        ::= { error 36 }
clnpOutErrSRUnkAddrs OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 37 }
clnpOutErrSRBadPaths OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 38 }
clnpOutErrHops OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS read-only
        STATUS mandatory
        ::= { error 39 }
```

Satz [Page 64]

```
clnpOutErrHopReassms OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 40 }
clnpOutErrUnsOptions OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 41 }
clnpOutErrUnsVersions OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 42 }
clnpOutErrUnsSecurities OBJECT-TYPE
        SYNTAX Counter
               read-only
        ACCESS
        STATUS mandatory
        ::= { error 43 }
clnpOutErrUnsSRs OBJECT-TYPE
        SYNTAX Counter
               read-only
        ACCESS
        STATUS mandatory
        ::= { error 44 }
                        OBJECT-TYPE
clnpOutErrUnsRRs
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 45 }
clnpOutErrInterferences OBJECT-TYPE
        SYNTAX Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { error 46 }
-- the CLNP Echo Group
-- the ES-IS Group
esisESHins
                OBJECT-TYPE
```

Satz [Page 65]

```
SYNTAX
                Counter
        ACCESS
                read-only
        STATUS mandatory
        ::= { es-is 1 }
esisESHouts
                OBJECT-TYPE
        SYNTAX
                Counter
               read-only
        ACCESS
        STATUS mandatory
        ::= { es-is 2 }
esisISHins
                OBJECT-TYPE
        SYNTAX
                Counter
               read-only
        ACCESS
        STATUS
                mandatory
        ::= { es-is 3 }
esisISHouts
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS
               read-only
        STATUS mandatory
        ::= { es-is 4 }
esisRDUins
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS read-only
        STATUS mandatory
        ::= { es-is 5 }
esisRDUouts
                OBJECT-TYPE
        SYNTAX
                Counter
        ACCESS read-only
        STATUS mandatory
        ::= { es-is 6 }
```

END

6. Identification of OBJECT instances for use with the SNMP

The names for all object types in the MIB are defined explicitly either in the Internet-standard MIB or in other documents which conform to the naming conventions of the SMI. The SMI requires that conformant management protocols define mechanisms for identifying individual instances of those object types for a particular network element.

Each instance of any object type defined in the MIB is identified in SNMP operations by a unique name called its "variable name." In

Satz [Page 66]

general, the name of an SNMP variable is an OBJECT IDENTIFIER of the form x.y, where x is the name of a non-aggregate object type defined in the MIB and y is an OBJECT IDENTIFIER fragment that, in a way specific to the named object type, identifies the desired instance.

This naming strategy admits the fullest exploitation of the semantics of the powerful SNMP get-next operator, because it assigns names for related variables so as to be contiguous in the lexicographical ordering of all variable names known in the MIB.

The type-specific naming of object instances is defined below for a number of classes of object types. Instances of an object type to which none of the following naming conventions are applicable are named by OBJECT IDENTIFIERS of the form x.0, where x is the name of said object type in the MIB definition.

For example, suppose one wanted to identify an instance of the variable sysDescr in the Internet-standard MIB. The object class for sysDescr is:

iso org dod internet mgmt mib system sysDescr 1 3 6 1 2 1 1 1

Hence, the object type, x, would be 1.3.6.1.2.1.1.1 to which is appended an instance sub-identifier of 0. That is, 1.3.6.1.2.1.1.0 identifies the one and only instance of sysDescr.

## 6.1. clnpAddrTable Object Type Names

The name of an CLNP-addressable network element, x, is the OBJECT IDENTIFIER of the form z such that z is the value (in which each octet of the ClnpAddress type is expressed as a sub-identifier of the OBJECT IDENTIFIER) of that instance of the clnpAdEntAddr object type associated with x.

For each object type, t, for which the defined name, n, has a prefix of clnpAddrEntry, an instance, i, of t is named by an OBJECT IDENTIFIER of the form n.y, where y is the name of the CLNP-addressable network element about which i represents information.

For example, suppose one wanted to find the maximum reassembly size of an entry in the CLNP interface table associated with an CLNP address of NS+0504030201. Accordingly, clnpAdEntNetMask.5.5.4.3.2.1 would identify the desired instance.

## 6.2. clnpRoutingTable Object Type Names

The name of an CLNP route, x, is the OBJECT IDENTIFIER of the form z

Satz [Page 67]

such that z is the value (in which each octet of the ClnpAddress type is expressed as a sub-identifier of the OBJECT IDENTIFIER) of that instance of the clnpRouteDest object type associated with x.

For each object type, t, for which the defined name, n, has a prefix of clnpRoutingEntry, an instance, i, of t is named by an OBJECT IDENTIFIER of the form n.y, where y is the name of the CLNP route about which i represents information.

For example, suppose one wanted to find the next hop of an entry in the CLNP routing table associated with the destination of NS+0504030201. Accordingly, clnpRouteNextHop.5.5.4.3.2.1 would identify the desired instance.

At the option of the agent, multiple routes to the same destination may be visible. To realize this, the agent, while required to return a single entry for an CLNP route, x, of the form n.y, may also return information about other routes to the same destination using the form n.y.v, where v is a implementation-dependent small, non-negative integer.

### 6.3. clnpNetToMediaTable Object Type Names

The name of a cached CLNP address, x, is an OBJECT IDENTIFIER of the form s.z, such that s is the value of that instance of the clnpNetToMediaIfIndex object type associated with the entry and z is the value of the CLNP address of the clnpNetToMediaNetAddress object type associated with x, in which each octet of the ClnpAddress type is expressed as a sub-identifier of the OBJECT IDENTIFIER.

For each object type, t, for which the defined name, n, has a prefix of clnpNetToMediaEntry, an instance, i, of t is named by an OBJECT IDENTIFIER of the form n.y, where y is the name of the cached CLNP address about which i represents information.

For example, suppose one wanted to find the media address of an entry in the address translation table associated with a CLNP address of NS+0504030201 and interface 3. Accordingly, clnpNetToMediaPhysAddress.3.5.5.4.3.2.1 would identify the desired instance.

#### 6.4. clnpMediaToNetTable Object Type Names

The name of a cached media address, x, is an OBJECT IDENTIFIER of the form s.z, such that s is the value of that instance of the clnpMediaToNetIfIndex object type associated with the entry and z is the value of the media address of the clnpMediaToNetMediaAddress object type associated with x, in which each octet of the media

Satz [Page 68]

address is expressed as a sub- identifier of the OBJECT IDENTIFIER.

For each object type, t, for which the defined name, n, has a prefix of clnpMediaToNetEntry, an instance, i, of t is named by an OBJECT IDENTIFIER of the form n.y, where y is the name of the cached media address about which i represents information.

For example, suppose one wanted to find the CLNP address of an entry in the address translation table associated with a media address of 08:00:20:00:38:ba and interface 3. Accordingly, clnpMediaToNetNetAddress.3.8.0.32.0.56.186 would identify the desired instance.

#### 7. References

- [1] Cerf, V., "IAB Recommendations for the Development of Internet Network Management Standards", RFC 1052, IAB, April 1988.
- [2] Cerf, V., "Report of the Second Ad Hoc Network Management Review Group", RFC 1109, NRI, August 1989.
- [3] Rose, M., and K. McCloghrie, "Structure and Identification of Management Information for TCP/IP-based Internets", RFC 1155, Performance Systems International and Hughes LAN Systems, May 1990.
- [4] McCloghrie, K., and M. Rose, "Management Information Base for Network Management of TCP/IP-based Internets", RFC 1156, Hughes LAN Systems and Performance Systems International, May 1990.
- [5] Case, J., M. Fedor, M. Schoffstall, and J. Davin, The Simple Network Management Protocol", RFC 1157, University of Tennessee at Knoxville, Performance Systems International, Performance Systems International, and the MIT Laboratory for Computer Science, May 1990.
- [6] Rose, M., "Management Information Base for Network Management of TCP/IP-based internets: MIB-II", RFC 1158, Performance Systems International, May 1990.
- [7] Information processing systems Open Systems Interconnection, "Specification of Abstract Syntax Notation One (ASN.1)", International Organization for Standardization, International Standard 8824, December 1987.
- [8] Information processing systems Open Systems Interconnection, "Specification of Basic Encoding Rules for Abstract Notation One (ASN.1)", International Organization for Standardization,

Satz [Page 69]

International Standard 8825, December 1987.

- [9] Information processing systems Data Communications "Protocol for providing the Connectionless-mode Network Service and Provision of Underlying Service", International Organization for Standardization", International Standard 8473, May 1987.
- [10] "End System to Intermediate System Routing Exchange Protocol for Use in Conjunction with the Protocol for the Provision of the Connectionless-mode Network Service (ISO 8473)", International Draft Proposal 9542.
- [11] Kille, S., "A String Encoding of Presentation Address", Research Note RN/89/14, Department of Computer Science, University College London, February 1989.

### 8. Security Considerations

Security issues are not discussed in this memo.

### 9. Author's Address:

Greg Satz cisco Systems, Inc. 1350 Willow Road Menlo Park, CA 94025

Phone: (415) 326-1941

Email: Satz@CISCO.COM

Satz [Page 70]