Network Working Group Request for Comments: 1315 C. Brown
Wellfleet Communications, Inc.
F. Baker
Advanced Computer Communications
C. Carvalho
Advanced Computer Communications
April 1992

Management Information Base for Frame Relay DTEs

Status of this Memo

This RFC specifies an IAB standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "IAB Official Protocol Standards" for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in TCP/IP-based internets. In particular, it defines objects for managing Frame Relay.

Table of Contents

1.	The Network Management Framework
2.	Objects
2.1	Format of Definitions
3.	Overview
3.1	Frame Relay Operational Model
3.2	Textual Conventions
3.3	Structure of MIB
4.	Definitions
4.1	Data Link Connection Management Interface
4.2	Circuit Table
4.3	Error Table
	Acknowledgements
	References
7.	Security Considerations
	Authors' Addresses

1. The Network Management Framework

The Internet-standard Network Management Framework consists of three components. They are:

RFC 1155 which defines the SMI, the mechanisms used for describing and naming objects for the purpose of management. RFC 1212 defines a more concise description mechanism, which is wholly consistent with the SMI.

RFC 1156 which defines MIB-I, the core set of managed objects for the Internet suite of protocols. RFC 1213 defines MIB-II, an evolution of MIB-I based on implementation experience and new operational requirements.

RFC 1157 which defines the SNMP, the protocol used for network access to managed objects.

The Framework permits new objects to be defined for the purpose of experimentation and evaluation.

2. Objects

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the subset of Abstract Syntax Notation One (ASN.1) [7] defined in the SMI. In particular, each object has a name, a syntax, and an encoding. The name is an object identifier, an administratively assigned name, which specifies an object type. The object type together with an object instance serves to uniquely identify a specific instantiation of the object. For human convenience, we often use a textual string, termed the OBJECT DESCRIPTOR, to also refer to the object type.

The syntax of an object type defines the abstract data structure corresponding to that object type. The ASN.1 language is used for this purpose. However, the SMI [3] purposely restricts the ASN.1 constructs which may be used. These restrictions are explicitly made for simplicity.

The encoding of an object type is simply how that object type is represented using the object type's syntax. Implicitly tied to the notion of an object type's syntax and encoding is how the object type is represented when being transmitted on the network.

The SMI specifies the use of the basic encoding rules of ASN.1 [8], subject to the additional requirements imposed by the SNMP.

2.1. Format of Definitions

Section 4 contains contains the specification of all object types contained in this MIB module. The object types are defined using the conventions defined in the SMI, as amended by the extensions specified in [9,10].

Overview

3.1. Frame Relay Operational Model

For the purposes of understanding this document, Frame Relay is viewed as a multi-access media, not as a group of point-to-point connections. This model proposes that Frame Relay is a single interface to the network (physical connection) with many destinations or neighbors (virtual connections). This view enables a network manager the ability to group all virtual connections with their corresponding physical connection thereby allowing simpler diagnostics and trouble shooting.

3.2. Textual Conventions

Several new data types are introduced as a textual convention in this MIB document. These textual conventions enhance the readability of the specification and can ease comparison with other specifications if appropriate. It should be noted that the introduction of the these textual conventions has no effect on either the syntax nor the semantics of any managed objects. The use of these is merely an artifact of the explanatory method used. Objects defined in terms of one of these methods are always encoded by means of the rules that define the primitive type. Hence, no changes to the SMI or the SNMP are necessary to accommodate these textual conventions which are adopted merely for the convenience of readers and writers in pursuit of the elusive goal of clear, concise, and unambiguous MIB documents.

The new data types are Index and DLCI. Index refers to the range 1..ifNumber, and is used to establish the correspondence between ifEntries and Frame Relay Interfaces. DLCI refers to the range 0..DLCINumber, and is used to refer to the valid Data Link Connection Indices. DLCINumber is, by definition, the largest possible DLCI value possible under the configured Q.922 Address Format.

3.3. Structure of MIB

The MIB is composed of three groups, one defining the Data Link Connection Management Interface (DLCMI), one describing the Circuits, and a third describing errors.

During normal operation, Frame Relay virtual circuits will be added, deleted and change availability. The occurrence of such changes is of interest to the network manager and therefore, one trap is defined, intended to be corollary to the SNMP "Link Up" and "Link Down" traps.

4. Definitions

```
RFC1315-MIB DEFINITIONS ::= BEGIN
IMPORTS
        OBJECT-TYPE
                FROM RFC-1212
        transmission
                FROM RFC1213-MIB
        TimeTicks
                FROM RFC-1155
        TRAP-TYPE
                FROM RFC-1215;
-- Frame Relay DTE MIB
               OBJECT IDENTIFIER ::= { transmission 32 }
frame-relay
        the range of ifIndex
Index ::= INTEGER -- 1..ifNumber
        the range of a Data Link Connection Identifier
DLCI ::= INTEGER
                      -- 0..DLCINumber
   Data Link Connection Management Interface
        The variables that configure the DLC Management Interface.
frDlcmiTable OBJECT-TYPE
             SEQUENCE OF FrDlcmiEntry
    SYNTAX
    ACCESS
             not-accessible
    STATUS
            mandatory
    DESCRIPTION
       "The Parameters for the Data Link Connection Management
       Interface for the frame relay service on this
       interface."
    REFERENCE
```

```
"Draft American National Standard T1.617-1991, Annex D"
::= { frame-relay 1 }
frDlcmiEntry OBJECT-TYPE
    SYNTAX FrDlcmiEntry
             not-accessible
    ACCESS
    STATUS
             mandatory
    DESCRIPTION
       "The Parameters for a particular Data Link Con-
       nection Management Interface."
   INDEX { frDlcmiIfIndex }
   ::= { frDlcmiTable 1 }
FrDlcmiEntry ::=
    SEQUENCE {
        frDlcmiIfIndex
            Index,
        frDlcmiState
            INTEGER,
        frDlcmiAddress
            INTEGER,
        frDlcmiAddressLen
            INTEGER,
        frDlcmiPollingInterval
            INTEGER.
        frDlcmiFullEnquiryInterval
            INTEGER,
        frDlcmiErrorThreshold
            INTEGER,
        frDlcmiMonitoredEvents
            INTEGER,
        frDlcmiMaxSupportedVCs
        INTEGER, frDlcmiMulticast
            INTEGER
}
frDlcmiIfIndex OBJECT-TYPE
    SYNTAX
             Index
    ACCESS
             read-only
    STATUS
             mandatory
    DESCRIPTION
       "The ifIndex value of the corresponding ifEn-
   ::= { frDlcmiEntry 1 }
```

```
frDlcmiState OBJECT-TYPE
    SYNTAX INTEGER {
        noLmiConfigured (1),
                         (\bar{2}),
        lmiRev1
                          (3),
                                -- ANSI T1.617 Annex D
        ansiT1-617-D
                                -- ANSI T1.617 Annex B
        ansiT1-617-B
                          (4)
    ACCESS
             read-write
    ACCESS read-write STATUS mandatory
    DESCRIPTION
       "This variable states which Data Link Connec-
       tion Management scheme is active (and by impli-
       cation, what DLCI it uses) on the Frame Relay
       interfáce."
   REFERENCE
      "Draft American National Standard T1.617-1991"
  ::= { frDlcmiEntry 2 }
frDlcmiAddress OBJECT-TYPE
    SYNTAX
                 INTEGER {
                                 (1),
                 q921
                                      -- 13 bit DLCI
                 d922March90
                                 (2), -- 11 bit DLCI
                 q922November90 (3),
                                       -- 10 bit DLCI
                 q922
                                 (4)
                                       -- Final Standard
    ACCESS
            read-write
    STATUS
            mandatory
    DESCRIPTION
       "This variable states which address format is
       in use on the Frame Relay interface."
   ::= { frDlcmiEntry 3 }
frDlcmiAddressLen OBJECT-TYPE
    SYNTAX INTEGER {
             two-octets (2)
             three-octets (3),
             four-octets (4)
    ACCESS read-write
    STATUS mandatory
    DESCRIPTION
       "This variable states which address length in octets. In the case of Q922 format, the length
       indicates the entire length of the address in-
       cluding the control portion."
```

```
::= { frDlcmiEntry 4 }
frDlcmiPollingInterval OBJECT-TYPE
             INTEGER (5..30)
    SYNTAX
             read-write
    ACCESS
    STATUS
             mandatorv
    DESCRIPTION
       "This is the number of seconds between succes-
       sive status enquiry messages."
   REFERENCE
      "Draft American National
                                Standard T1.617-1991,
      Section D.7 Timer T391."
  DEFVAL { 10 }
  ::= { frDlcmiEntry 5 }
frDlcmiFullEnquiryInterval OBJECT-TYPE
    SYNTAX INTEGER (1..255)
             read-write
    ACCESS
    STATUS mandatory
    DESCRIPTION
       'Number of status enquiry intervals that pass
       before issuance of a full status enquiry mes-
       sage."
   REFERENCE
      "Draft American National Standard T1.617-1991, Section D.7 Counter N391."
  DEFVAL { 6 }
  ::= { frDlcmiEntry 6 }
frDlcmiErrorThreshold OBJECT-TYPE
    SYNTAX INTEGER (1..10)
    ACCESS
             read-write
    STATUS
             mandatorv
    DESCRIPTION
       "This is the maximum number of unanswered
       Status Enquiries the equipment shall accept be-
       fore declaring the interface down."
   REFERENCE
      "Draft American National Standard T1.617-1991,
      Section D.5.1 Counter N392."
  DEFVAL { 3 }
  ::= { frDlcmiEntry 7 }
```

```
frDlcmiMonitoredEvents OBJECT-TYPE
    SYNTAX
              INTEGER (1..10)
    ACCESS
              read-write
    STATUS
             mandatory
    DESCRIPTION
       "This is the number of status polling intervals
       over which the error threshold is counted. For example, if within 'MonitoredEvents' number of events the station receives 'ErrorThreshold'
       number of errors, the interface is marked as
       down.'
   REFERENCE
      "Draft American National Standard T1.617-1991,
      Section D.5.2 Counter N393."
  DEFVAL { 4 }
  ::= { frDlcmiEntry 8 }
frDlcmiMaxSupportedVCs OBJECT-TYPE
    SYNTAX
            INTEGER
              read-write
    ACCESS
    STATUS
              mandatory
    DESCRIPTION
       "The maximum number of Virtual Circuits allowed
            this interface. Usually dictated by the
       Frame Relay network.
       In response to a SET, if a value less than zero
            higher than the agent's maximal capability
       is configured, the agent should respond bad-
       Value"
   ::= { frDlcmiEntry 9 }
frDlcmiMulticast OBJECT-TYPE
    SYNTAX
              INTEGER {
                 nonBroadcast (1),
                 broadcast (2)
              read-write
    ACCESS
    STATUS
              mandatory
    DESCRIPTION
       "This indicates whether the Frame Relay inter-
       face is using a multicast service."
   ::= { frDlcmiEntry 10 }
```

```
-- A Frame Relay service is a multiplexing service.
-- Link Connection Identifiers enumerate virtual circuits
-- (permanent or dynamic) which are layered onto the underlying
-- circuit, represented by ifEntry. Therefore, each of the entries -- in the Standard MIB's Interface Table with an IfType of
-- Frame Relay represents a Q.922 interface. Zero or more
-- virtual circuits are layered onto this interface and provide -- interconnection with various remote destinations.
-- Each such virtual circuit is represented by an entry in the
-- circuit table.
     Circuit Table
-- The table describing the use of the DLCIs attached to
-- each Frame Relay Interface.
frCircuitTable OBJECT-TYPE
              SEQUENCE OF FrCircuitEntry
    SYNTAX
              not-accessible
    ACCESS
    STATUS
              mandatory
    DESCRIPTION
        "A table containing information about specific Data
       Link Connection Identifiers and corresponding virtual
        circuits.'
    ::= { frame-relay 2 }
    frCircuitEntry OBJECT-TYPE
         SYNTAX
                  FrCircuitEntry
         ACCESS
                  not-accessible
         STATUS
                  mandatory
         DESCRIPTION
            "The information regarding a single Data Link
            Connection Identifier."
       INDEX { frCircuitIfIndex, frCircuitDlci }
        ::= { frCircuitTable 1 }
    FrCircuitEntry ::=
         SEQUENCE {
             frCircuitIfIndex
                 Index.
             frCircuitDlci
                 DLCI,
             frCircuitState
                 INTEGER.
             frCircuitReceivedFECNs
                 Counter,
             frCircuitReceivedBECNs
```

```
Counter,
        frCircuitSentFrames
            Counter,
        frCircuitSentOctets
            Counter,
        frCircuitReceivedFrames
            Counter,
        frCircuitReceivedOctets
            Counter,
        frCircuitCreationTime
            TimeTicks,
        frCircuitLastTimeChange
            TimeTicks,
        frCircuitCommittedBurst
            INTEGER,
        frCircuitExcessBurst
            INTEGER,
        frCircuitThroughput
            INTEGER
}
frCircuitIfIndex OBJECT-TYPE
    SYNTAX
             Index
    ACCESS
STATUS
             read-only
             mandatory
    DESCRIPTION
       "The ifIndex Value of the ifEntry this virtual
       circuit is layered onto.'
   ::= { frCircuitEntry 1 }
frCircuitDlci OBJECT-TYPE
    SYNTAX
             DLCI
    ACCESS
             read-only
    STATUS
             mandatory
    DESCRIPTION
       "The Data Link Connection Identifier for this
       virtual circuit."
   REFERENCE
      "Draft American National Standard T1.618-1991,
      Section 3.3.6"
  ::= { frCircuitEntry 2 }
```

```
frCircuitState OBJECT-TYPE
    SYNTAX
               INTEGER {
                   invalid (1),
                   active (2),
                   inactive (3)
               read-write
    ACCESS
    STATUS
              mandatorv
    DESCRIPTION
        "Indicates whether the particular virtual cir-
        cuit is operational. In the absence of a Data
        Link Connection Management Interface, virtual
        circuit entries (rows) may be created by set-
        ting virtual circuit state to 'active', or deleted by changing Circuit state to 'invalid'.
        Whether or not the row actually disappears is
        left to the implementation, so this object may
   actually read as 'invalid' for some arbitrary length of time. It is also legal to set the state of a virtual circuit to 'inactive' to temporarily disable a given circuit."

DEFVAL { active }
   ::= { frCircuitEntry 3 }
frCircuitReceivedFECNs OBJECT-TYPE
    SYNTAX Counter
    ACCESS
STATUS
               read-only
               mandatory
    DESCRIPTION
        "Number of frames received from the network in-
        dicating forward congestion since the virtual
        circuit was created."
   REFERENCE
       "Draft American National Standard T1.618-1991,
       Section 3.3.3"
  ::= { frCircuitEntry 4 }
frCircuitReceivedBECNs OBJECT-TYPE
    SYNTAX Counter
    ACCESS
               read-only
    STATUS
               mandatory
    DESCRIPTION
        "Number of frames received from the network in-
        dicating backward congestion since the virtual
        circuit was created."
```

```
REFERENCE
      "Draft American National Standard T1.618-1991,
      Section 3.3.4"
  ::= { frCircuitEntry 5 }
frCircuitSentFrames OBJECT-TYPE
    SYNTAX Counter
    ACCESS read-only
STATUS mandatory
    DESCRIPTION
       "The number of frames sent from this virtual
       circuit since it was created."
   ::= { frCircuitEntry 6 }
frCircuitSentOctets OBJECT-TYPE
    SYNTAX Counter
    ACCESS read-only
STATUS mandatory
    DESCRIPTION
       "The number of octets sent from this virtual
       circuit since it was created."
   ::= { frCircuitEntry 7 }
frCircuitReceivedFrames OBJECT-TYPE
    SYNTAX Counter
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
       "Number of frames received over this virtual circuit since it was created."
   ::= { frCircuitEntry 8 }
frCircuitReceivedOctets OBJECT-TYPE
    SYNTAX Counter
    ACCESS read-only
    STATUS
             mandatory
    DESCRIPTION
       "Number of octets received over this virtual
       circuit since it was created."
   ::= { frCircuitEntry 9 }
```

```
frCircuitCreationTime OBJECT-TYPE
    SYNTAX
             TimeTicks
    ACCESS
             read-only
    STATUS
             mandatory
    DESCRIPTION
       "The value of sysUpTime when the virtual circuit was created, whether by the Data Link Connection Management Interface or by a SetRe-
       quest."
   ::= { frCircuitEntry 10 }
frCircuitLastTimeChange OBJECT-TYPE
    SYNTAX TimeTicks
    ACCESS
             read-only
    STATUS
             mandatory
    DESCRIPTION
       "The value of sysUpTime when last there was a
       change in the virtual circuit state"
   ::= { frCircuitEntry 11 }
frCircuitCommittedBurst OBJECT-TYPE
    SYNTAX INTEGER
    ACCESS
STATUS
             read-write
             mandatory
    DESCRIPTION
       "This variable indicates the maximum amount of
       data, in bits, that the network agrees to
       transfer under normal conditions, during the measurement interval."
   REFERENCE
       "Draft American National Standard T1.617-1991,
      Section 6.5.19"
           { 0 } -- the default indicates no commitment
  ::= { frCircuitEntry 12 }
frCircuitExcessBurst OBJECT-TYPE
    SYNTAX INTEGER
    ACCESS
             read-write
            mandatory
    STATUS
    DESCRIPTION
       "This variable indicates the maximum amount of
       uncommitted data bits that the network will at-
```

tempt to deliver over the measurement interval.

By default, if not configured when creating the entry, the Excess Information Burst Size is set to the value of ifSpeed."

REFERENCE

"Draft American National Standard T1.617-1991, Section 6.5.19"
::= { frCircuitEntry 13 }

frCircuitThroughput OBJECT-TYPE

SYNTAX INTEGER
ACCESS read-write
STATUS mandatory

DESCRIPTION

"Throughput is the average number of 'Frame Relay Information Field' bits transferred per second across a user network interface in one direction, measured over the measurement interval.

If the configured committed burst rate and throughput are both non-zero, the measurement interval

T=frCircuitCommittedBurst/frCircuitThroughput.

If the configured committed burst rate and throughput are both zero, the measurement interval

T=frCircuitExcessBurst/ifSpeed."

REFERENCE

"Draft American National Standard T1.617-1991, Section 6.5.19"

DEFVAL {0} -- the default value of Throughput is -- "no commitment".

::= { frCircuitEntry 14 }

- -- Error Table
- -- The table describing errors encountered on each Frame -- Relay Interface.

frErrTable OBJECT-TYPE

SYNTAX SEQUENCE OF Frerrentry

ACCESS not-accessible

```
STATUS
         mandatory
DESCRIPTION
   "A table containing information about Errors on the
   Frame Relay interface."
::= { frame-relay 3 }
frerrentry OBJECT-TYPE SYNTAX Frerrentry
            FrErrEntry
    ACCESS
              not-accessible
    STATUS mandatory
    DESCRIPTION
       "The error information for a single frame relay interface."
   INDEX { frErrIfIndex }
::= { frErrTable 1 }
FrErrEntry ::=
    SEQUENCE {
    frErrIfIndex
             Index,
         frErrType
             INTEGER.
         frErrData
             OCTET STRING,
         frErrTime
             TimeTicks
}
frErrIfIndex OBJECT-TYPE
    SYNTAX
              Index
              read-only
    ACCESS
    STATUS
              mandatory
    DESCRIPTION
        "The ifIndex Value of the corresponding ifEn-
        try."
   ::= { frErrEntry 1 }
frErrType OBJECT-TYPE
              INTEGER {
    SYNTAX
                  unknownError(1),
                  receiveShort(2),
                  receiveLong(3),
```

```
illegalDLCI(4),
                unknownDLCI(5),
                dlcmiProtoErr(6)
                dlcmiUnknownIE(7)
                dlcmiSequenceErr(8),
                dlcmiUnknownRpt(9),
                noErrorSinceReset(10)
             read-only
    ACCESS
    STATUS
             mandatory
    DESCRIPTION
       "The type of error that was last seen on this
       interface."
   ::= { frErrEntry 2 }
frErrData OBJECT-TYPE
    SYNTAX
             OCTET STRING
    ACCESS
             read-only
    STATUS
             mandatory
    DESCRIPTION
       "An octet string containing as much of the er-
            packet as possible. As a minimum, it must
       contain the Q.922 Address or as much as was
                    It is desirable to include all in-
       delivered.
   formation up to the PDU."
::= { frErrEntry 3 }
frErrTime OBJECT-TYPE
    SYNTAX TimeTicks
    ACCESS
             read-only
    STATUS
             mandatory
    DESCRIPTION
       "The value of sysUpTime at which the error was
       detected.'
   ::= { frErrEntry 4 }
-- Frame Relay Globals
frame-relay-globals OBJECT IDENTIFIER ::= { frame-relay 4 }
frTrapState OBJECT-TYPE
            INTEGER { enabled(1), disabled(2) }
read-write
    SYNTAX
    ACCESS
```

```
STATUS mandatory
DESCRIPTION
"This variable indicates whether the system
produces the frDLCIStatusChange trap."
DEFVAL { disabled }
::= { frame-relay-globals 1 }
```

-- Data Link Connection Management Interface Related Traps

```
frDLCIStatusChange TRAP-TYPE
    ENTERPRISE frame-relay
    VARIABLES { frCircuitIfIndex, frCircuitDlci, frCircuitState }
    DESCRIPTION
        "This trap indicates that the indicated Virtual
        Circuit has changed state. It has either been
        created or invalidated, or has toggled between
        the active and inactive states."
    ::= 1
```

END

5. Acknowledgements

This document was produced by the IP Over Large Public Data Networks (IPLPDN) Working Group.

The following people provided additional comments and suggestions: Art Berggreen of Advanced Computer Communications, and Jim Philippou of Xyplex Communications.

6. References

- [1] Cerf, V., "IAB Recommendations for the Development of Internet Network Management Standards", RFC 1052, NRI, April 1988.
- [2] Cerf, V., "Report of the Second Ad Hoc Network Management Review Group", RFC 1109, NRI, August 1989.
- [3] Rose M., and K. McCloghrie, "Structure and Identification of Management Information for TCP/IP-based internets", RFC 1155, Performance Systems International, Hughes LAN Systems, May 1990.
- [4] McCloghrie K., and M. Rose, "Management Information Base for Network Management of TCP/IP-based internets", RFC 1156, Hughes LAN Systems, Performance Systems International, May 1990.

- [5] Case, J., Fedor, M., Schoffstall, M., and J. Davin, "Simple Network Management Protocol", RFC 1157, SNMP Research, Performance Systems International, Performance Systems International, MIT Laboratory for Computer Science, May 1990.
- [6] McCloghrie K., and M. Rose, Editors, "Management Information Base for Network Management of TCP/IP-based internets", RFC 1213, Performance Systems International, March 1991.
- [7] Information processing systems Open Systems Interconnection Specification of Abstract Syntax Notation One (ASN.1), International Organization for Standardization, International Standard 8824, December 1987.
- [8] Information processing systems Open Systems Interconnection Specification of Basic Encoding Rules for Abstract Notation One (ASN.1), International Organization for Standardization, International Standard 8825, December 1987.
- [9] Rose, M., and K. McCloghrie, Editors, "Concise MIB Definitions", RFC 1212, Performance Systems International, Hughes LAN Systems, March 1991.
- [10] Rose, M., Editor, "A Convention for Defining Traps for use with the SNMP", RFC 1215, Performance Systems International, March 1991.
- 7. Security Considerations

Security issues are not discussed in this memo.

8. Authors' Addresses

Caralyn Brown
Wellfleet Communications, Inc.
15 Crosby Drive
Bedford, Massachusetts 01730

Phone: (617) 275-2400

EMail: cbrown@wellfleet.com

Fred Baker Advanced Computer Communications 315 Bollay Drive Sannta Barbara, California 93117

Phone: (805) 685-4455 EMail: fbaker@acc.com

Charles Carvalho Advanced Computer Communications 315 Bollay Drive Sannta Barbara, California 93117

Phone: (805) 685-4455 EMail: charles@acc.com