Network Working Group Request for Comments: 2455 Obsoletes: 2155 Category: Standards Track

B. Clouston Cisco Systems B. Moore IBM Corporation November 1998

Definitions of Managed Objects for APPN

Status of this Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The Internet Society (1998). All Rights Reserved.

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it defines objects for monitoring and controlling network devices with APPN (Advanced Peer-to-Peer Networking) capabilities. This memo identifies managed objects for the APPN protocol.

Table of Contents

1.	Introduction 2
2.	The SNMPv2 Network Management Framework 2
3.	Overview 3
3.1	Relationship with RFC 2155
3.2	APPN MIB structure
4.	Definitions 10
5.	Security Considerations
6.	Intellectual Property 136
7.	Acknowledgments 137
8.	References 137
9.	Authors' Addresses 139
10 .	Full Copyright Statement

Clouston & Moore

Standards Track

[Page 1]

1. Introduction

This document is a product of the SNA NAU Services MIB Working Group. It defines a MIB module for managing devices with Advanced Peer-to-Peer Networking (APPN) capabilities.

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in RFC 2119 [17].

2. The SNMP Network Management Framework

The SNMP Management Framework presently consists of five major components:

- o An overall architecture, described in RFC 2271 [1].
- o Mechanisms for describing and naming objects and events for the purpose of management. The first version of this Structure of Management Information (SMI) is called SMIv1 and described in STD 16, RFC 1155 [2], STD 16, RFC 1212 [3] and RFC 1215 [4]. The second version, called SMIv2, is described in RFC 1902 [5], RFC 1903 [6] and RFC 1904 [7].
- Message protocols for transferring management information. The first version of the SNMP message protocol is called SNMPv1 and described in STD 15, RFC 1157 [8]. A second version of the SNMP message protocol, which is not an Internet standards track protocol, is called SNMPv2c and described in RFC 1901 [9] and RFC 1906 [10]. The third version of the message protocol is called SNMPv3 and described in RFC 1906 [10], RFC 2272 [11] and RFC 2274 [12].
- o Protocol operations for accessing management information. The first set of protocol operations and associated PDU formats is described in STD 15, RFC 1157 [8]. A second set of protocol operations and associated PDU formats is described in RFC 1905 [13].
- A set of fundamental applications described in RFC 2273 [14] and the view-based access control mechanism described in RFC 2275 [15].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the mechanisms defined in the SMI.

This memo specifies a MIB module that is compliant to the SMIv2. A MIB conforming to the SMIv1 can be produced through the appropriate translations. The resulting translated MIB must be semantically equivalent, except where objects or events are omitted because no translation is possible (use of Counter64). Some machine readable information in SMIv2 will be converted into textual descriptions in SMIv1 during the translation process. However, this loss of machine readable information is not considered to change the semantics of the MIB.

Overview

This document identifies a set of objects for monitoring the configuration and active characteristics of devices with APPN capabilities, and for controlling certain characteristics. APPN is the aspect of Systems Network Architecture (SNA) that supports peer-to-peer networking. These networks transport both independent and dependent LU session traffic. See the SNANAU APPC MIB [21] and the SNA NAU MIB [22] for management of these sessions. See also RFC 2232, the DLUR MIB [23], and RFC 2238, the HPR MIB [24] for management of extensions to the APPN architecture. In this document, we describe APPN managed objects.

An APPN network comprises various types of nodes, and transmission groups (TGs) that connect the nodes. Network nodes (NNs) provide directory and routing functions for session establishment. NNs may be session end points or intermediate nodes in a session. A border node is a type of network node that connects networks together for session establishment without fully merging them. A branch network node (BrNN) is a network node that is similar to a border node, but with only minimal functions to build a large APPN network within an enterprise. Although a BrNN is defined to be a network node in the APPN architecture, it also has an end node (EN) appearance to upstream NNs in the network. In this MIB module it is treated as a separate node type since it does not fit cleanly as an EN or NN, and this module explicity identifies those objects returned by a BrNN. For example, a BrNN does not implement the appnNnTopo objects since it is the only node in its network topology table; but it does implement the appnSessIntermediate objects since it does have intermediate session support. It also implements two of the appnEnUniqueCaps objects that could be useful to a management application. A BrNN identifies itself as 'endNode' in the appnNodeType object but further identifies itself as a BrNN in the appnNodeBrNn object.

End nodes are session end points that receive directory and routing functions from network nodes, over control-point to control-point (CP-CP) sessions. Low-entry networking (LEN) nodes are also session

end points, but do not support CP-CP sessions, and therefore need additional manual configuration definitions to establish sessions in an APPN network. ENs and LEN nodes may have minimal directory and routing functions to establish control sessions (ENs) or to connect into the APPN network (LEN nodes).

Virtual routing nodes (VRNs) are not really nodes, but rather common definitions among actual nodes in a shared transport facility such as a local area network (LAN) that allow these actual nodes to temporarily establish a logical link with one another without defining each other's link-level addressing information.

Ports and link stations are the node's interface to the data link control (DLC), which provides the physical transport, or to another protocol such as Data Link Switching (DLSw), which provides transport over an IP network. See the SNADLC SDLC MIB[25], the SNADLC LLC MIB[26], and the DLSw MIB[27]. A link station uses a port to make a connection to another node. This connection establishes a TG between the two nodes.

The directory and routing functions enable an NN to find where an LU is located in the network, and calculate the optimal route for the session based on the requested class of service (COS). A network node saves the LU information in a directory database, which is built from LUs defined locally, LU registration from served end nodes, and LUs learned from network searches.

Each NN maintains a local COS database that assigns a routing weight, or relative cost, to each resource for each class of service. For example, the #INTER COS assigns a lower weight to TGs with a greater effective capacity, while the #BATCH COS favors TGs with a lower relative cost per byte.

A node saves network topology information (on NNs, VRNs, and TGs between them) in a network topology database. A node that supports APPN function set 1120, branch awareness, also saves information on TGs to adjacent BrNNs. The topology information includes state and routing characteristics. Topology information is exchanged between NNs over CP-CP sessions such that the database is fully replicated at each NN. Information on TGs to all node types are kept in a local topology database. Local topology information is shared with other nodes only during the session establishment process, to give the NN responsible for route calculation the necessary information for end-to-end route calculation.

A management application can show a full representation of the APPN network from the network and local topology information. To show the network topology, the application need only query the network

topology tables from a single NN. To show all of the BrNNs, the application must also directly query all destinations of TGs that indicate they are branch TGs (indicated by the appnNnTgFRBranchTg object) to see if they have any cascaded BrNNs. For any NNs that do not indicate branch awareness support (indicated by the appnNnNodeFRBranchAwareness object), the application must query each NN's appnLocalTgTable, and then the appnNodeBrNn object of each row's destination node to identify BrNNs. To show all of the nodes in the network, including ENs and LEN nodes, the application must query every NN's appnLocalTgTable, and iteratively do the same for each BrNN it finds.

SNA names such as LU names, CP names, COS names, and mode names can be padded with blanks (space characters) in SNA formats. These blanks are nonsignificant. For example, in a BIND Request Unit (RU) a COS name of "#INTER" with a length of 6 is identical to a COS name of "#INTER" with a length of 8. However, in this MIB, nonsignificant blanks are not included by the agent. Using the COS name from the previous example, an agent would return a length of 6 and the string "#INTER" with no blanks for appnCosName, regardless of how it appears in the BIND RU or in internal storage. The lone exception is the all blank mode name, for which the agent returns a length of 8 and the string " (8 blank spaces). The MIB variables that this applies to are identified by a textual convention syntax that also describes this behavior.

When an SNA name is functioning as a table index, an agent treats trailing blanks as significant. If a management station requests the objects from a row with index "#INTER", the agent does not match this to the row with index "#INTER". Since an agent has no nonsignificant blanks in any of its table indices, the only reason for a Management Station to include them would be to start GetNext processing at a chosen point in a table. For example, a GetNext request with index "M" " would start retrieval from a table at the first row with an 8-character index beginning with "M" or a letter after "M".

The SNA/APPN terms and overall architecture are documented in [18], [19], [20], and [28].

Highlights of the management functions supported by the APPN MIB module include the following:

- o Activating and deactivating ports and link stations.
- o Monitoring of configuration parameters related to the node, ports, link stations, virtual routing nodes, and classes of service.

- o Monitoring of operational parameters related to ports, link stations, virtual routing nodes, topology, directory, and intermediate sessions.
- o Historical information about link station errors during connection establishment, or that caused the connection to terminate.
- o Deactivating intermediate sessions.
- o Traps for SNA Management Services (SNA/MS) Alert conditions.

This MIB module does not support:

- o Configuration of APPN nodes.
- o Monitoring and control of endpoint sessions.
- o Dependent LU Requester (DLUR) management.
- o High-Performance Routing (HPR) management.

3.1. Relationship with RFC 2155

This MIB obsoletes RFC 2155 [29] with changes due to additions to the APPN architecture and some implementation experience of RFC 2155. The changes from RFC 2155 are as follows:

- New objects for the multi-link TG architecture enhancement: appnLsMltgMember, appnNnTgFRMltgLinkType, appnLocalTgMltgLinkType, and appnLocalEnTgMltgLinkType.
- New objects, and explanations for values for existing objects, for the branch network node architecture enhancement: appnNodeBrNn, appnNnNodeFRBranchAwareness, appnNnTgFRBranchTg, and appnLocalTgBranchLinkType.
- o New object, appnNodeLsCounterType, to indicate which type of ANR traffic is returned in the appnLsTable traffic counters.
- o Deprecated appnNodeMibVersion object.
- o Miscellaneous editorial changes.

3.2. APPN MIB Structure

The APPN MIB module contains the following groups of objects:

- o appnNode objects related to the APPN node for all node types.
- o appnNn objects to represent the network nodes, virtual routing nodes, and TGs between these nodes that make up the APPN network topology database maintained in NNs.
- o appnLocalTopology objects to represent nodes and TGs between nodes in the local topology database maintained in all nodes.
- o appnDir objects related to LU location information from the node's directory database.
- o appnCos objects related to classes of service information.
- o appnSessIntermediate objects related to intermediate sessions that pass through this node.

These groups are described below in more detail.

3.2.1. appnNode group

The appnNode group consists of the following tables and objects:

1) appnGeneralInfoAndCaps

This group of objects describes general information about the APPN node. The type of information includes the node type and the time since this node was initialized.

2) appnNnUniqueInfoAndCaps

This group of objects describes information specific to network nodes such as node routing characteristics.

3) appnEnUniqueInfoAndCaps

This group of objects describes information specific to end nodes, with two objects that also apply to branch network nodes. This group includes an object indicating the node's network node server.

4) appnPortInformation

This includes the appnPortTable, which describes the configuration and current status of the ports used by APPN, including the port state and DLC type.

5) appnLinkStationInformation

This includes the appnNodeLsTable, which describes the configuration and current status of the link stations used by APPN, including the link state and port name; and the appnLsStatusTable, which provides information about errors this node encountered with connections to adjacent nodes, such as the sense data captured during connection failures. It is a product option to decide how many appnLsStatusTable entries are kept.

6) appnVrnInfo

This includes the appnVrnTable, which describes the relationship between virtual routing nodes' TGs described in the appnLocalTgTable with ports in the appnPortTable.

3.2.2. appnNn group

The appnNn group consists of the following objects and tables

1) appnNnTopo

These objects contain general information about the network topology database including the number of nodes present, and the number of topology database updates (TDU) wars the node has detected.

2) appnNnTopology

This includes tables representing the APPN network topology database. This includes the network nodes, virtual routing nodes, and TGs between these nodes, as well as the information about these resources carried in topology updates. The tables are first indexed by the same flow reduction sequence number (FRSN) used in topology exchanges between NNs. This allows a management station to retrieve only incremental updates, since the agent will update the FRSN of new or changed resources.

3.2.3. appnLocalTopology group

The appnLocalTopology group consists of the following objects and tables:

1) appnLocalThisNode

a) appnLocalGeneral

Contains the local node and type.

b) appnLocalNnSpecific

These objects contain routing information about the local network node.

c) appnLocalTg

This table represents information about this node's local TGs.

2) appnLocalEnTopology

This table represents TG information for EN TGs learned by the NN via TG registration with the local node.

3.2.4. appnDir group

The appnDir group consists of the following objects and tables:

appnDirPerf

These objects represent information related to information about the directory database and directory searches involving this node.

2) appnDirTable

This table represents the directory database, listing LUs known to this node, along with the owning node of the LU and the serving NN of the owning node.

3.2.5. appnCos group

The appnCos group consists of the following tables:

1) appnCosModeTable

This table represents the mode to class of service mapping.

2) appnCosNameTable

This table represents the tranmission priority for each class of service.

Clouston & Moore

3) appnCosNodeRowTable

This table represents the node-row information for each class of service, including the weight of each node.

3) appnCosTGRowTable

This table represents the TG-row information for each class of service, including the weight of each TG.

3.2.6. appnSessIntermediate group

The appnSessIntermediate group consists of the following objects and tables:

1) appnIsInGlobal

These objects allow control of the collection of intermediate session information such as Route Selection Control Vectors (RSCVs) and counters.

2) appnIsInTable

This table contains information on active intermediate sessions.

3) appnIsRtpTable

This table contains information on active intermediate sessions that are being transported on Rapid Transport Protocol (RTP) connections by High Performance Routing (HPR).

3.2.7. appnTraps

One APPN trap is defined. It is intended to correspond to SNA/MS Alerts, but is optional for a product to implement this trap. The trap identifies the Alert ID number and, where possible, the affected resource.

4. Definitions

APPN-MIB DEFINITIONS

::= BEGIN

IMPORTS

IANAifType

FROM IANAifType-MIB

DisplayString, VariablePointer, RowPointer, DateAndTime,

Clouston & Moore

TruthValue, TimeStamp, TEXTUAL-CONVENTION FROM SNMPv2-TC

Counter32, Gauge32, Unsigned32, TimeTicks, OBJECT-TYPE, MODULE-IDENTITY, NOTIFICATION-TYPE FROM SNMPv2-SMI

MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP FROM SNMPv2-CONF

snanauMIB

FROM SNA-NAU-MIB;

appnMIB MODULE-IDENTITY

LAST-UPDATED "9807151800Z" -- July 15, 1998
ORGANIZATION "IETF SNA NAU MIB WG / AIW APPN MIBs SIG"
CONTACT-INFO

11

Bob Clouston
Cisco Systems
7025 Kit Creek Road
P.O. Box 14987
Research Triangle Park, NC 27709, USA
Tel: 1 919 472 2333
E-mail: clouston@cisco.com

Bob Moore
IBM Corporation
4205 S. Miami Boulevard
BRQA/501
P.O. Box 12195
Research Triangle Park, NC 27709, USA
Tel: 1 919 254 4436
E-mail: remoore@us.ibm.com

- 11

DESCRIPTION

"This is the MIB module for objects used to manage network devices with APPN capabilities."

-- Revision tracking starts with Proposed Standard (RFC 2155) REVISION "9807151800Z" DESCRIPTION

"Minor editorial fixes; new value 'none(5)' added to the enumeration for the appnLocalTgBranchLinkType object."

Clouston & Moore

```
"9805261800Z"
     REVISION
     DESCRIPTION
              "Post-RFC 2155 conformance definitions added,
              appnNodeLsCounterType and appnNodeBrNn objects
              added, appnNodeMibVersion object deprecated."
     REVISION
              "9707311800Z"
     DESCRIPTION
              "Branch network node (Branch Extender) objects added."
     REVISION
              "9703311800Z"
     DESCRIPTION
              "MLTG objects added."
              "9703201200Z"
     REVISION
     DESCRIPTION
              "RFC 2155 (Proposed Standard)"
::= { snanauMIB 4 }
-- snanauMIB ::= { mib-2 34 }
Textual Conventions
SnaNodeIdentification ::= TEXTUAL-CONVENTION
     STATUS current
     DESCRIPTION
         "An SNA Node Identification consists of two parts, which
         together comprise four bytes of hexadecimal data. In SNA the Node Identification is transported in bytes 2-5 of the XID.
```

The block number is the first three digits of the Node Identification. These 3 hexadecimal digits identify the

The ID number is the last 5 digits of the Node Identification. These 5 hexadecimal digits are administratively defined and combined with the 3-digit block number form the 8-digit Node Identification. A unique value is required for connections to SNA subarea. In some implementations, the value 'bbb00000' (where 'bbb' represents a 3-digit block number) is returned to mean that the ID number is not unique on this node.

An SNA Node Identification is represented as eight ASCII-encoded hexadecimal digits, using the characters '0' - '9' and 'A' - 'F'."

SYNTAX OCTET STRING (SIZE (8))

product.

SnaControlPointName ::= TEXTUAL-CONVENTION

STATUS current DESCRIPTION

"A fully qualified SNA control point name, consisting of a 1 to 8 character network identifier (NetId), a period ('.'), and a 1 to 8 character control point name (CpName).

The NetId and CpName are constructed from the uppercase letters 'A' - 'Z' and the numerics '0' - '9', all encoded in ASCII, with the restriction that the first character of each must be a letter. Trailing blanks are not allowed.

Earlier versions of SNA permitted three additional characters in NetIds and CpNames: '#', '@', and '\$'. While this use of these characters has been retired, a Management Station should still accept them for backward compatibility."

SYNTAX OCTET STRING (SIZE (3..17))

"An SNA class-of-service (COS) name, ranging from 1 to 8 ASCII characters. COS names take one of two forms:

- a user-defined COS name is constructed from the uppercase letters 'A' - 'Z' and the numerics '0' - '9', with the restriction that the first character of the name must be a letter.
- an SNA-defined user-session COS name begins with the character '#', which is followed by up to seven additional characters from the set of uppercase letters and numerics.

Trailing blanks are not allowed in either form of COS name.

A zero-length string indicates that a COS name is not available."

SYNTAX OCTET STRING (SIZE (0..8))

SnaModeName ::= TEXTUAL-CONVENTION

STATUS current DESCRIPTION

"An SNA mode name, ranging from 1 to 8 ASCII characters.
Mode names take one of two forms:

 a user-defined mode name is constructed from the uppercase letters 'A' - 'Z' and the numerics '0' - '9',

Clouston & Moore

with the restriction that the first character of the name must be a letter.

 an SNA-defined user-session mode name begins with the character '#', which is followed by up to seven additional characters from the set of uppercase letters and numerics.

Trailing blanks are not allowed in either form of mode name, with the single exception of the all-blank mode name, where a string consisting of 8 blanks is returned.

A zero-length string indicates that a mode name is not available."

SYNTAX OCTET STRING (SIZE (0..8))

SnaSenseData ::= TEXTUAL-CONVENTION
 STATUS current
 DESCRIPTION

"To facilitate their display by a Management Station, sense data objects in the MIB are represented as OCTET STRINGS containing eight ASCII characters. Eight '0' characters indicates that no sense data identifying an SNA error condition is available.

An SNA sense data is represented as eight hexadecimal digits, using the characters '0' - '9' and 'A' - 'F'."

SYNTAX OCTET STRING (SIZE (8))

DisplayableDlcAddress ::= TEXTUAL-CONVENTION STATUS current DESCRIPTION

"DLC address of a port or link station, represented as an OCTET STRING containing 0 to 64 ASCII characters. A Management Station should use a value of this type only for display. The 'real' DLC address, i.e., the sequence of bytes that flow in the DLC header, is often available in a DLC-specific MIB.

The zero-length string indicates that the DLC address in question is not known to the agent."

SYNTAX OCTET STRING (SIZE (0..64))

AppnNodeCounter ::= TEXTUAL-CONVENTION STATUS current DESCRIPTION

Clouston & Moore

"An object providing global statistics for the entire APPN node. A Management Station can detect discontinuities in this counter by monitoring the appnNodeCounterDisconTime object."

SYNTAX Counter32

AppnPortCounter ::= TEXTUAL-CONVENTION

STATUS current DESCRIPTION

"An object providing statistics for an APPN port. A Management Station can detect discontinuities in this counter by monitoring the appnPortCounterDisconTime object."

SYNTAX Counter32

AppnLinkStationCounter ::= TEXTUAL-CONVENTION

STATUS current DESCRIPTION

"An object providing statistics for an APPN link station. A Management Station can detect discontinuities in this counter by monitoring the appnLsCounterDisconTime object."

SYNTAX Counter32

AppnTopologyEntryTimeLeft ::= TEXTUAL-CONVENTION

STATUS current DESCRIPTION

"Number of days before deletion of this entry from the topology database. Range is 0-15. A value of 0 indicates that the entry is either in the process of being deleted, or is being marked for deletion at the next garbage collection cycle."

SYNTAX INTEGER (0..15)

AppnTgDlcData ::= TEXTUAL-CONVENTION

STATUS current DESCRIPTION

"DLC-specific data related to a connection network transmission group. For other TGs, a zero-length string is returned.

Examples of the type of data returned by an object with this syntax include the following:

Token-Ring - MAC/SAP
X.25 Switched - dial digits
X.21 Switched - dial digits
Circuit Switch - dial digits

This MIB does not specify formats for these or any other types of DLC-specific data. Formats may, however, be specified in documents related to a particular DLC.

The contents of an object with this syntax correspond to the contents of the DLC-specific subfields of cv46, documented in (6)."

SYNTAX OCTET STRING (SIZE (0..64))

AppnTgEffectiveCapacity ::= TEXTUAL-CONVENTION STATUS current DESCRIPTION

"A value representing the effective capacity of a transmission group. This is an administratively assigned value derived from the link bandwidth and maximum load factor. It is encoded in the same way as byte 7 of cv47, and represents a floating-point number in units of 300 bits per second."

SYNTAX OCTET STRING (SIZE (1))

AppnTgSecurity ::= TEXTUAL-CONVENTION STATUS current DESCRIPTION

"A value representing the level of security on a transmission group. A class of service definition includes an indication of the acceptable TG security value(s) for that class of service.

The following seven values are defined:

nonsecure(1) -(X'01'): none of the values listed below; for example, satellite-connected or located in a nonsecure country publicSwitchedNetwork(32) -(X'20'): public switched network; secure in the sense that there is no predetermined route that traffic will take undergroundCable(64) -(X'40'): underground cable; located in a secure country (as determined by the network administrator) secureConduit(96) (X'60'): secure conduit, not guarded; for example, pressurized pipe quardedConduit(128) -(X'80'): guarded conduit; protected against physical tapping

Clouston & Moore

```
encrypted(160) -
                             (X'A0'): link-level encryption is provided
           quardedRadiation(192) -
                             (X'CO'): guarded conduit containing the
                             transmission medium; protected against
                             physical and radiation tapping"
     SYNTAX INTEGER {
                                               -- X'01'
                    nonsecure(1),
                    publicSwitchedNetwork(32),
                                               -- X'20'
                    undergroundCable(64),
                                               -- X'40'
                    secureConduit(96)
                                               -- X'60'
                    guardedConduit(128),
                                               -- X'80'
                                               -- X'ĀŌ'
                    encrypted(160),
                                               -- X'C0'
                    guardedRadiation(192)
AppnTgDelay ::= TEXTUAL-CONVENTION
     STATÚS current
     DESCRIPTION
         "Relative amount of time that it takes for a signal to travel
the length of a logical link. This time is represented in
         microseconds, using the same encoding scheme used in cv47 in a
         topology update. Some of the more common values, along with
         their encoded hex values, are:
                                               X'00'
                    minimum(0)
                                               X'4C'
                    negligible(384)
                                               X'71'
                    terrestrial(9216),
                    packet(147456),
                                               X'91'
                                               X'99'
                    long(294912),
                    maximum(2013265920)
                                               X'FF'
         п
     SYNTAX OCTET STRING (SIZE (1))
appn0bjects
                         OBJECT IDENTIFIER ::= { appnMIB 1 }
-- ************* The APPN Node Group ***************
                     OBJECT IDENTIFIER ::= { appnObjects 1 }
appnNode
                             OBJECT IDENTIFIER ::= { appnNode 1 }
  appnGeneralInfoAndCaps
                             OBJECT IDENTIFIER ::= { appnNode 2
  appnNnUniqueInfoAndCaps
                             OBJECT IDENTIFIER ::= { appnNode 3 OBJECT IDENTIFIER ::= { appnNode 4
  appnEnUniqueCaps
  appnPortInformation
```

```
OBJECT IDENTIFIER ::= { appnNode 5 } OBJECT IDENTIFIER ::= { appnNode 6 }
  appnLinkStationInformation -
  appnVrnInfo
-- This group provides global information about an APPN network node,
-- an APPN end node, an APPN branch network node, or an LEN node.
-- APPN General Information
-- This section applies to APPN network nodes, end nodes, and branch
-- network nodes, as well as to LEN end nodes.
appnNodeCpName OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Administratively assigned network name for this node."
      ::= { appnGeneralInfoAndCaps 1 }
-- appnNodeMibVersion OBJECT-TYPE (deprecated: moved to end of module)
appnNodeId OBJECT-TYPE
      SYNTAX SnaNodeIdentification
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "This node's Node Identification, which it sends in bytes
          2-5 of XID."
      ::= { appnGeneralInfoAndCaps 3 }
appnNodeType OBJECT-TYPE
      SYNTAX INTEGER {
                      networkNode(1).
                      endNode(2),
                      t21len(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Type of APPN node:
                 networkNode(1) - APPN network node
                 endNode(2) - APPN end node
t21len(4) - LEN end node
          Note: A branch network node SHALL return endNode(2)
          as the value of this object. A management application
```

```
can distinguish between a branch network node and an
          actual end node by retrieving the appnNodeBrNn object."
      ::= { appnGeneralInfoAndCaps 4 }
appnNodeUpTime OBJECT-TYPE
      SYNTAX TimeTicks
UNITS "hundredths of a second"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Amount of time (in hundredths of a second) since the APPN node
          was last reinitialized."
      ::= { appnGeneralInfoAndCaps 5 }
appnNodeParallelTg OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          "Indicates whether this node supports parallel TGs."
      ::= { appnGeneralInfoAndCaps 6 }
appnNodeAdaptiveBindPacing OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether this node supports adaptive bind pacing for
          dependent LUs."
      ::= { appnGeneralInfoAndCaps 7 }
appnNodeHprSupport OBJECT-TYPE
      SYNTAX INTEGER {
                  noHprSupport(1),
                  hprBaseOnly(2),
                 rtpTower(3),
                  controlFlowsOverRtpTower(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates this node's level of support for high-performance
          routing (HPR):
```

```
noHprSupport(1)
                                        - no HPR support
             hprBaseOnly(2)
                                        - HPR base (option set 1400)
                                          supported
                                        - HPR base and RTP tower
             rtpTower(3)
                                           (option set 1401) supported
            (option set 1402) supported
          This object corresponds to cv4580, byte 9, bits 3-4."
      ::= { appnGeneralInfoAndCaps 8 }
appnNodeMaxSessPerRtpConn OBJECT-TYPE
      SYNTAX Gauge32
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "This object represents a configuration parameter indicating
          the maximum number of sessions that the APPN node is to put on
          any HPR connection. The value is zero if not applicable.
      ::= { appnGeneralInfoAndCaps 9 }
appnNodeHprIntRteSetups OBJECT-TYPE
      SYNTAX AppnNodeCounter
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          'The total number of HPR route setups received for routes
          passing through this node since the node was last reinitialized."
      ::= { appnGeneralInfoAndCaps 10 }
appnNodeHprIntRteRejects OBJECT-TYPE
      SYNTAX AppnNodeCounter
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The number of HPR route setups rejected by this node for
          routes passing through it since the node was last
          reinitialized.
      ::= { appnGeneralInfoAndCaps 11 }
appnNodeHprOrgRteSetups OBJECT-TYPE
      SYNTAX AppnNodeCounter
```

```
MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The total number of HPR route setups sent for routes
           originating in this node since the node was last
           reinitialized."
      ::= { appnGeneralInfoAndCaps 12 }
appnNodeHprOrgRteRejects OBJECT-TYPE
      SYNTAX AppnNodeCounter
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The number of HPR route setups rejected by other nodes for
           routes originating in this node since the node was last
           reinitialized."
      ::= { appnGeneralInfoAndCaps 13 }
appnNodeHprEndRteSetups OBJECT-TYPE
      SYNTAX AppnNodeCounter
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The total number of HPR route setups received for routes
           ending in this node since the node was last reinitialized."
      ::= { appnGeneralInfoAndCaps 14 }
appnNodeHprEndRteRejects OBJECT-TYPE
      SYNTAX AppnNodeCounter
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "The number of HPR route setups rejected by this node for routes ending in it since the node was last reinitialized."
      ::= { appnGeneralInfoAndCaps 15 }
appnNodeCounterDisconTime OBJECT-TYPE
      SYNTAX TimeStamp
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The value of the sysUpTime object the last time the APPN node was reinitialized."
```

```
::= { appnGeneralInfoAndCaps 16 }
appnNodeLsCounterType OBJECT-TYPE
      SYNTAX INTEGER {
                   other(1),
                   noAnr(2),
                   anrForLocalNces(3).
                   allAnr(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates which ANR traffic, if any, the node includes in the counts returned by the APPN link station counters
           appnLsInXidBytes, appnLsInMsgBytes, appnLsInXidFrames,
           appnLsInMsgFrames, appnLsOutXidBytes, appnLsOutMsgBytes, appnLsOutXidFrames, and appnLsOutMsgFrames. These counters
           are always incremented for ISR traffic.
           The following values are defined:
                                       - the node does something different
               other(1)
                                         from all the options listed below
                                       - the node does not include any ANR
               noAnr(2)
                                         traffic in these counts
               anrForLocalNces(3)
                                       - the node includes in these counts
                                         ANR traffic for RTP connections that terminate in this node, but not ANR traffic for RTP connections
                                         that pass through this node without
                                         terminating in it
               allAnr(4)
                                       - the node includes all ANR traffic
                                         in these counts."
       ::= { appnGeneralInfoAndCaps 17 }
appnNodeBrNn OBJECT-TYPE
       SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether this node is currently configured as a
           branch network node.
                   throughout the remainder of this MIB module, branch
           network node is treated as a third node type, parallel to
           network node and end node. This is not how branch network
           nodes are treated in the base APPN architecture, but it
```

```
increases clarity to do it here."
     ::= { appnGeneralInfoAndCaps 18 }
-- APPN Network Node Information
appnNodeNnCentralDirectory OBJECT-TYPE
     SYNTAX TruthValue
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
         "Indicates whether this node supports central directory
        services.
        This object corresponds to cv4580, byte 8, bit 1."
     ::= { appnNnUniqueInfoAndCaps 1 }
appnNodeNnTreeCache OBJECT-TYPE
     SYNTAX INTEGER {
                  noCache(1),
                  cacheNoIncrUpdate(2)
                  cacheWithIncrUpdate(3)
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
         "Indicates this node's level of support for caching of route
               Three levels are specified:
           noCache(1)
                                - caching of route trees is not
                                 supported
           cacheNoIncrUpdate(2)
                                - caching of route trees is
                                 supported, but without incremental
                                 updates
           cacheWithIncrUpdate(3) - caching of route trees with
                                 incremental updates is supported"
     ::= { appnNnUniqueInfoAndCaps 2 }
appnNodeNnRouteAddResist OBJECT-TYPE
     SYNTAX INTEGER (0..255)
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
```

"Route addition resistance.

This administratively assigned value indicates the relative desirability of using this node for intermediate session traffic. The value, which can be any integer 0-255, is used in route computation. The lower the value, the more desirable the node is for intermediate routing.

This object corresponds to cv4580, byte 6."

```
::= { appnNnUniqueInfoAndCaps 3 }
appnNodeNnIsr OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the node supports intermediate session
          routing.
          This object corresponds to cv4580, byte 8, bit 2."
      ::= { appnNnUniqueInfoAndCaps 4 }
appnNodeNnFrsn OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          'The last flow-reduction sequence number (FRSN) sent by this
          node in a topology update to an adjacent network node.
      ::= { appnNnUniqueInfoAndCaps 5 }
appnNodeNnPeriBorderSup OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether this node has peripheral border node
          support.
          This object corresponds to cv4580, byte 9, bit 0."
      ::= { appnNnUniqueInfoAndCaps 6 }
appnNodeNnInterchangeSup OBJECT-TYPE
      SYNTAX TruthValue
```

```
MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether this node has interchange node support.
          This object corresponds to cv4580, byte 9, bit 1."
      ::= { appnNnUniqueInfoAndCaps 7 }
appnNodeNnExteBorderSup OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether this node has extended border node support.
          This object corresponds to cv4580, byte 9, bit 2."
      ::= { appnNnUniqueInfoAndCaps 8 }
appnNodeNnSafeStoreFreq OBJECT-TYPE
      SYNTAX INTEGER (0..32767)
      UNITS "TDUs"
      MAX-ACCESS read-write
      STATUS current
      DESCRIPTION
           "The topology safe store frequency.
          If this number is not zero, then the topology database is saved
          each time the total number of topology database updates (TDUs) received by this node increases by this number. A value of
          zero indicates that the topology database is not being saved."
      ::= { appnNnUniqueInfoAndCaps 9 }
appnNodeNnRsn OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Resource sequence number for this node, which it assigns and
          controls.
          This object corresponds to the numeric value in cv4580, bytes
          2-5."
      ::= { appnNnUniqueInfoAndCaps 10 }
```

```
appnNodeNnCongested OBJECT-TYPE
     SYNTAX TruthValue
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
          "Indicates whether this node is congested. Other network nodes
         stop routing traffic to this node while this flag is on.
         This object corresponds to cv4580, byte 7, bit 0."
      ::= { appnNnUniqueInfoAndCaps 11 }
appnNodeNnIsrDepleted OBJECT-TYPE
     SYNTAX TruthValue
     MAX-ACCESS read-only
     STATUS current DESCRIPTION
          'Indicate whether intermediated session routing resources are
         depleted. Other network nodes stop routing traffic through
         this node while this flag is on.
         This object corresponds to cv4580, byte 7, bit 1."
      ::= { appnNnUniqueInfoAndCaps 12 }
appnNodeNnOuiescing OBJECT-TYPE
     SYNTAX TruthValue
     MAX-ACCESS read-only
     STATUS current DESCRIPTION
          'Indicates whether the node is quiescing.
         This object corresponds to cv4580, byte 7, bit 5."
      ::= { appnNnUniqueInfoAndCaps 13 }
appnNodeNnGateway OBJECT-TYPE
     SYNTAX TruthValue
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
          "Indicates whether the node has gateway services support.
         This object corresponds to cv4580, byte 8, bit 0."
      ::= { appnNnUniqueInfoAndCaps 14 }
```

```
-- APPN End Node Information
-- This section provides global information about an APPN end node.
                                                                     Two
-- of the objects are also implemented by a branch network node.
appnNodeEnModeCosMap OBJECT-TYPE
     SYNTAX TruthValue MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether this end node supports mode name to COS name
          mapping."
      ::= { appnEnUniqueCaps 1 }
appnNodeEnNnServer OBJECT-TYPE
      SYNTAX OCTET STRING (SIZE (0 | 3..17))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The fully qualified name of the current NN server for this end node. An NN server is identified using the format specified in the SnaControlPointName textual convention. The value is a
          zero-length string when there is no active NN server.
          A branch network node shall also implement this object."
      ::= { appnEnUniqueCaps 2 }
appnNodeEnLuSearch OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the node is to be searched for LUs as part
          of a network broadcast search.
          A branch network node shall also implement this object."
      ::= { appnEnUniqueCaps 3 }
-- ********************************
-- APPN Port information
-- This section provides information about an APPN node's ports.
-- ********************************
```

```
appnPortTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnPortEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "The Port table describes the configuration and current status
           of the ports used by APPN. When it is known to the APPN component, an OBJECT IDENTIFIER pointing to additional information related to the port is included. This may, but
           need not, be a RowPointer to an ifTable entry for a DLC
           interface immediately 'below' the port."
       ::= { appnPortInformation 1 }
appnPortEntry OBJECT-TYPE
      SYNTAX AppnPortEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "The port name is used as the index to this table."
      INDEX
              { appnPortName }
       ::= { appnPortTable 1 }
AppnPortEntry ::= SEQUENCE {
      appnPortName
                                       DisplayString,
                                       INTEGER,
      appnPortCommand
      appnPortOperState
                                       INTEGER,
      appnPortDlcType
                                       IANAifType,
      appnPortPortType
                                       INTEGER,
      appnPortSIMRIM
                                       TruthValue,
      appnPortLsRole
                                       INTEGER.
                                       TruthValue.
      appnPortNegotLs
      appnPortDynamicLinkSupport
                                       TruthValue,
      appnPortMaxRcvBtuSize
                                       INTEGER,
      appnPortMaxIframeWindow
                                       Gauge32.
      appnPortDefLsGoodXids
                                       AppnPortCounter,
      appnPortDefLsBadXids
                                       AppnPortCounter,
      appnPortDynLsGoodXids
                                       AppnPortCounter,
      appnPortDynLsBadXids
                                       AppnPortCounter,
      appnPortSpecific
                                       RowPointer,
                                       DisplayabléDlcAddress,
      appnPortDlcLocalAddr
      appnPortCounterDisconTime
                                       TimeStamp
appnPortName OBJECT-TYPE
```

```
SYNTAX DisplayString (SIZE (1..10))
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Administratively assigned name for this APPN port."
       ::= { appnPortEntry 1 }
appnPortCommand OBJECT-TYPE
       SYNTAX INTEGER {
                           deactivate(1),
                           activate(2),
                           recycle(3),
                           ready(4)
       MAX-ACCESS read-write
       STATUS current
       DESCRIPTION
            "Object by which a Management Station can activate, deactivate, or recycle (i.e., cause to be deactivated and then immediately activated) a port, by setting the value to activate(1),
            deactivate(2), or recycle(3), respectively. The value ready(4) is returned on GET operations until a SET has been processed;
            after that the value received on the most recent SET is
            returned."
       ::= { appnPortEntry 2 }
appnPortOperState OBJECT-TYPE
       SYNTAX INTEGER
                               inactive(1)
                               pendactive(2),
                              active(3),
pendinact(4)
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Indicates the current state of this port:
                 inactive(1) - port is inactive
                 pendactive(2) - port is pending active
                 active(3)
                                  - port is active
                 pendinact(4) - port is pending inactive"
       ::= { appnPortEntry 3 }
```

```
appnPortDlcType OBJECT-TYPE SYNTAX IANAifType
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The type of DLC interface, distinguished according to the protocol immediately 'below' this layer."
      ::= { appnPortEntry 4 }
appnPortPortType OBJECT-TYPE
      SYNTAX ÍNTEGER {
                       leased(1)
                       switched(2),
                       sharedAccessFacilities(3)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Identifies the type of line used by this port:
               leased(1)
                                            - leased line
               switched(2)
                                            - switched line
               sharedAccessFacilities(3) - shared access facility, such
                                              as a LAN."
      ::= { appnPortEntry 5 }
appnPortSIMRIM OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether Set Initialization Mode (SIM) and Receive
           Initialization Mode (RIM) are supported for this port."
      ::= { appnPortEntry 6 }
appnPortLsRole OBJECT-TYPE
      SYNTAX INTEGER {
                       primary(1),
                       secondary(2)
                       negotiable(3),
                       abm(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
```

"Initial role for link stations activated through this port. The values map to the following settings in the initial XID, where 'ABM' indicates asynchronous balanced mode and 'NRM' indicated normal response mode:

```
ABM support = 0
                 primary(1):
                                                      (=NRM)
                                                        = primary)
                                  role = 01
                                                      ( = \dot{N}RM)
                                  ABM support = 0
                 secondary(2):
                                                      ( = secondary)
                                  role = 00
                                 ABM support = 0
                                                      ( = NRM)
                 negotiable(3):
                                  role = 11
                                                      ( = negotiable)
                 abm(4):
                                  ABM support = 1
                                                      ( = ABM)
                                  role = 11
                                                      ( = negotiable)"
      ::= { appnPortEntry 7 }
appnPortNegotLs OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the node supports negotiable link stations
          for this port."
      ::= { appnPortEntry 8 }
appnPortDynamicLinkSupport OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether this node allows call-in on this port from
          nodes not defined locally."
      ::= { appnPortEntry 9 }
appnPortMaxRcvBtuSize OBJECT-TYPE
      SYNTAX INTEGER (99..32767)
      UNITS "bytes"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          'Maximum Basic Transmission Unit (BTU) size that a link station
          on this port can receive.
          This object corresponds to bytes 21-22 of XID3."
      ::= { appnPortEntry 10 }
```

```
appnPortMaxIframeWindow OBJECT-TYPE
      SYNTAX Gauge32 UNITS "I-frames"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "Maximum number of I-frames that can be received by the XID sender before an acknowledgement is received."
       ::= { appnPortEntry 11 }
appnPortDefLsGoodXids OBJECT-TYPE
       SYNTAX AppnPortCounter
      UNITS "XID exchanges' MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
           "The total number of successful XID exchanges that have occurred on all defined link stations on this port since the
           last time this port was started."
       ::= { appnPortEntry 12 }
appnPortDefLsBadXids OBJECT-TYPE
       SYNTAX AppnPortCounter
       UNITS "XID exchanges"
       MAX-ACCESS read-only
       STATUS current DESCRIPTION
            "The total number of unsuccessful XID exchanges that have
           occurred on all defined link stations on this port since the
           last time this port was started."
       ::= { appnPortEntry 13 }
appnPortDynLsGoodXids OBJECT-TYPE
       SYNTAX AppnPortCounter
       UNITS "XID exchanges"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The total number of successful XID exchanges that have
           occurred on all dynamic link stations on this port since the
           last time this port was started."
       ::= { appnPortEntry 14 }
appnPortDynLsBadXids OBJECT-TYPE
```

```
SYNTAX AppnPortCounter UNITS "XID exchanges"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The total number of unsuccessful XID exchanges that have
          occurred on all dynamic link stations on this port since the last time this port was started."
      ::= { appnPortEntry 15 }
appnPortSpecific OBJECT-TYPE
      SYNTAX RowPointer
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Identifies the object, e.g., one in a DLC-specific MIB, that can provide additional information related to this port.
          If the agent is unable to identify such an object, the value
          0.0 is returned."
      ::= { appnPortEntry 16 }
appnPortDlcLocalAddr OBJECT-TYPE
      SYNTAX DisplayableDlcAddress
      MAX-ACCESS read-only
     STATUS current
DESCRIPTION
          "Local DLC address of this port."
      ::= { appnPortEntry 17 }
appnPortCounterDisconTime OBJECT-TYPE
      SYNTAX TimeStamp
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The value of the sysUpTime object the last time the port was
          started."
      ::= { appnPortEntry 18 }
-- APPN Link Station Information
-- This section provides information about an APPN node's link stations.
```

```
appnLsTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnLsEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "This table contains detailed information about the link
          station configuration and its current status.'
      ::= { appnLinkStationInformation 1 }
appnLsEntry OBJECT-TYPE
      SYNTAX AppnLsEntry
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
          "This table is indexed by the link station name."
      INDEX
             { appnLsName }
      ::= { appnLsTable 1 }
AppnLsEntry ::= SEQUENCE {
                                   DisplayString.
      appnLsName
      appnLsCommand
                                   INTEGER,
      appnLsOperState
                                   INTEGER,
                                   DisplayString,
      appnLsPortName
                                   IANAifType,
      appnLsDlcType
                                   TruthValue,
      appnLsDynamic
                                   OCTET STRING,
      appnLsAdjCpName
      appnLsAdjNodeType
                                   INTEGER,
      appnLsTgNum
                                   INTEGER
      appnLsLimResource
                                   TruthValue,
      appnLsActOnDemand
                                   TruthValue,
      appnLsMigration
                                   TruthValue,
                                   SnaNodeIdentification,
      appnLsPartnerNodeId
      appnLsCpCpSessionSupport
                                   TruthValue,
      appnLsMaxSendBtuSize
                                   INTEGER,
-- performance data
      appnLsInXidBytes
                                   AppnLinkStationCounter,
                                   AppnLinkStationCounter,
      appnLsInMsgBytes
      appnLsInXidFrames
                                   AppnLinkStationCounter,
                                   AppnLinkStationCounter,
      appnLsInMsgFrames
      appnLsOutXidBytes
                                   AppnLinkStationCounter,
      appnLsOutMsgBytes
                                   AppnLinkStationCounter,
```

```
appnLsOutXidFrames
                                     AppnLinkStationCounter,
      appnLsOutMsgFrames
                                     AppnLinkStationCounter,
   propagation delay
                                     AppnLinkStationCounter,
      appnLsEchoRsps
      appnLsCurrentDelay
                                     Gauge32,
      appnLsMaxDelay
                                     Gauge32,
      appnLsMinDelay
appnLsMaxDelayTime
                                     Gauge32,
DateAndTime,
-- XID Statistics
      appnLsGoodXids
                                     AppnLinkStationCounter,
      appnLsBadXids
                                     AppnLinkStationCounter,
-- DLC-specific
      appnLsSpecific
                                     RowPointer,
      appnLsActiveTime
                                     Unsigned32,
      appnLsCurrentStateTime
                                     TimeTicks,
   HPR-specific
      appnLsHprSup
                                     INTEGER,
      appnLsErrRecoSup
                                     TruthValue.
      appnLsForAnrLabel
                                     OCTET STRING,
                                     OCTET STRING,
OCTET STRING,
OCTET STRING,
      appnLsRevAnrLabel
      appnLsCpCpNceId
      appnLsRouteNceId
      appnLsBfNceId
                                     OCTET STRING,
      appnLsLocalAddr
                                     DisplayableDlcAddress,
      appnLsRemoteAddr
                                     DisplayableDlcAddress,
      appnLsRemoteLsName
                                     DisplayString,
      appnLsCounterDisconTime
                                     TimeStamp,
      appnLsMltgMember
                                     TruthValue
appnLsName OBJECT-TYPE
      SYNTAX DisplayString (SIZE (1..10))
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
           'Administratively assigned name for the link station.
            The name can be from one to ten characters.'
      ::= { appnLsEntry 1 }
appnLsCommand OBJECT-TYPE
      SYNTAX INTEGER {
                        deactivate(1),
                        activate(2),
                        recycle(3),
                        ready(4)
```

```
MAX-ACCESS read-write
        STATUS current
        DESCRIPTION
               "Object by which a Management Station can activate, deactivate,
              or recycle (i.e., cause to be deactivated and then immediately reactivated) a link station, by setting the value to activate(1), deactivate(2), or recycle(3), respectively. The value ready(4) is returned on GET operations until a SET has been processed; after that the value received on the most
               recent SET is returned.'
         ::= { appnLsEntry 2 }
appnLsOperState OBJECT-TYPE
        SYNTAX INTEGER
               inactive(1).
              sentConnectOut(2), -- pending active pendXidExch(3), -- pending active sendActAs(4), -- pending active sendSetMode(5), -- pending active otherPendingActive(6),-- pending active
               active(7),
               sentDeactÁsOrd(8), -- pending inactive
               sentDiscOrd(9),
              sentDiscOrd(9), -- pending inactive
sentDiscImmed(10), -- pending inactive
otherPendingInact(11) -- pending inactive
                                                -- pending inactive
        MAX-ACCESS read-only
        STATUS current
        DESCRIPTION
               "State of this link station. The comments map these more
               granular states to the 'traditional' four states for SNA
               resources. Values (2) through (5) represent the normal
               progression of states when a link station is being activated.
              Value (6) represents some other state of a link station in the process of being activated. Values (8) through (10)
               represent different ways a link station can be deactivated.
               Value (11) represents some other state of a link station in the process of being deactivated."
         ::= { appnLsEntry 3 }
appnLsPortName OBJECT-TYPE
         SYNTAX DisplayString (SIZE (1..10))
        MAX-ACCESS read-only
        STATUS current
        DESCRIPTION
               "Administratively assigned name for the port associated with
```

```
this link station.
                                  The name can be from one to ten
           characters.'
       ::= { appnLsEntry 4 }
appnLsDlcType OBJECT-TYPE
      SYNTAX IANAifType
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The type of DLC interface, distinguished according to the protocol immediately 'below' this layer."
       ::= { appnLsEntry 5 }
appnLsDynamic OBJECT-TYPE
       SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Identifies whether this is a dynamic link station. Dynamic link stations are created when links that have not been locally
           defined are established by adjacent nodes."
       ::= { appnLsEntry 6 }
appnLsAdjCpName OBJECT-TYPE SYNTAX OCTET STRING (SIZE (0 | 3..17))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Fully qualified name of the adjacent node for this link
           station. An adjacent node is identified using the format
           specified in the SnaControlPointName textual convention.
           The value of this object is determined as follows:
               1. If the adjacent node's name was received on XID, it
                  is returned.
               2. If the adjacent node's name was not received on XID,
                  but a locálly-defined value is available, it is
                  returned.
               3. Otherwise a string of length 0 is returned, indicating
```

::= { appnLsEntry 7 }

that no name is known for the adjacent node."

```
appnLsAdjNodeType OBJECT-TYPE
      SYNTAX INTEGER {
                      networkNode(1),
                      endNode(2),
                      t21len(4),
                      unknown (255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Node type of the adjacent node on this link:
                 networkNode(1) - APPN network node
                                  - APPN end node
                 endNode(2)
                 t21len(4)
                                 - LEN end node
                 unknown(255)
                                 - the agent does not know the node type
                                   of the adjacent node
      ::= { appnLsEntry 8 }
appnLsTgNum OBJECT-TYPE
      SYNTAX INTEGER (0..256)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number associated with the TG to this link station, with a range from 0 to 256. A value of 256 indicates that the TG
          number has not been negotiated and is unknown at this time."
      ::= { appnLsEntry 9 }
appnLsLimResource OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether the link station is a limited resource.
          link station that is a limited resource is deactivated when it
          is no longer in use."
      ::= { appnLsEntry 10 }
appnLsActOnDemand OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
```

"Indicates whether the link station is activatable on demand.

Such a link station is reported in the topology as active regardless of its actual state, so that it can be considered in route calculations. If the link station is inactive and is chosen for a route, it will be activated at that time."

```
::= { appnLsEntry 11 }
```

appnLsMigration OBJECT-TYPE
SYNTAX TruthValue
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"Indicates whether this link station will be used for connections to down-level or migration partners.

In general, migration nodes do not append their CP names on XID3. Such nodes: (1) will not support parallel TGs, (2) should be sent an ACTIVATE PHYSICAL UNIT (ACTPU), provided that the partner supports ACTPUs, and (3) should not be sent segmented BINDs. However, if this node receives an XID3 with an appended CP name, then the partner node will not be treated as a migration node.

In the case of DYNAMIC TGs this object should be set to 'no'."

::= { appnLsEntry 12 }

appnLsPartnerNodeId OBJECT-TYPE
SYNTAX SnaNodeIdentification
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The partner's Node Identification, from bytes 2-5 of the XID received from the partner. If this value is not available, then the characters '00000000' are returned."

::= { appnLsEntry 13 }

appnLsCpCpSessionSupport OBJECT-TYPE
SYNTAX TruthValue
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"Indicates whether CP-CP sessions are supported by this link station. For a dynamic link, this object represents the default ('Admin') value."

```
::= { appnLsEntry 14 }
appnLsMaxSendBtuSize OBJECT-TYPE
       SYNTAX INTEGER (99..32767)
       UNITS "bytes"
       MAX-ACCESS read-only
       STATUS current DESCRIPTION
             "Numeric value between 99 and 32767 inclusive indicating the
            maximum number of bytes in a Basic Transmission Unit (BŤU) sent
            on this link.
            When the link state (returned by the appnLsOperState object) is inactive or pending active, the value configured at this node is returned. When the link state is active, the value that was
            negotiated for it is returned. This negotiated value is the smaller of the value configured at this node and the partner's
            maximum receive BTU length, received in XID.
       ::= { appnLsEntry 15 }
appnLsInXidBytes OBJECT-TYPE
       SYNTAX AppnLinkStationCounter
       UNITS "bytes"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Number of XID bytes received. All of the bytes in the SNA basic transmission unit (BTU), i.e., all of the bytes in the
            DLC XID Information Field, are counted.'
       ::= { appnLsEntry 16 }
appnLsInMsgBytes OBJECT-TYPE
       SYNTAX AppnLinkStationCounter UNITS "bytes"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
             "Number of message (I-frame) bytes received. All of the bytes
            in the SNA basic transmission unit (BTU), including the
            transmission header (TH), are counted.'
       ::= { appnLsEntry 17 }
appnLsInXidFrames OBJECT-TYPE
       SYNTAX AppnLinkStationCounter
       UNITS "XID frames"
```

```
MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Number of XID frames received."
       ::= { appnLsEntry 18 }
appnLsInMsgFrames OBJECT-TYPE
      SYNTAX AppnLinkStationCounter UNITS "I-frames"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Number of message (I-frame) frames received."
       ::= { appnLsEntry 19 }
appnLsOutXidBytes OBJECT-TYPE
      SYNTAX AppnLinkStationCounter
      UNITS "bytes"
      MAX-ACCEŚS read-only
      STATUS current
      DESCRIPTION
           "Number of XID bytes sent. All of the bytes in the SNA basic
           transmission unit (BTU), i.e., all of the bytes in the DLC XID Information Field, are counted."
       ::= { appnLsEntry 20 }
appnLsOutMsgBytes OBJECT-TYPE
       SYNTAX AppnLinkStationCounter
      UNITS "bytes"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Number of message (I-frame) bytes sent. All of the bytes in the SNA basic transmission unit (BTU), including the
           transmission header (TH), are counted."
       ::= { appnLsEntry 21 }
appnLsOutXidFrames OBJECT-TYPE
      SYNTAX AppnLinkStationCounter
      UNITS "XID frames"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Number of XID frames sent."
```

```
::= { appnLsEntry 22 }
appnLsOutMsgFrames OBJECT-TYPE
       SYNTAX AppnLinkStationCounter
       UNITS "I-frames"
       MAX-ACCESS read-only
       STATUS current DESCRIPTION
            "Number of message (I-frame) frames sent."
       ::= { appnLsEntry 23 }
appnLsEchoRsps OBJECT-TYPE
      SYNTAX AppnLinkStationCounter UNITS "echo responses"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Number of echo responses returned from adjacent link station.
           A response should be returned for each test frame sent by this node. Test frames are sent to adjacent nodes periodically to verify connectivity and to measure the actual round trip time,
           that is, the time interval from when the test frame is sent
           until when the response is received."
       ::= { appnLsEntry 24 }
appnLsCurrentDelay OBJECT-TYPE
       SYNTAX Gauge32
       UNITS "milliseconds"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The time that it took for the last test signal to be sent and
           returned from this link station to the adjacent link station.
           This time is represented in milliseconds.
       ::= { appnLsEntry 25 }
appnLsMaxDelay OBJECT-TYPE
      SYNTAX Gauge32 UNITS "milliseconds"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The longest time it took for a test signal to be sent and
           returned from this link station to the adjacent link station.
```

This time is represented in milliseconds .

The value 0 is returned if no test signal has been sent and returned."

::= { appnLsEntry 26 }

appnLsMinDelay OBJECT-TYPE
SYNTAX Gauge32
UNITS "milliseconds"
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The shortest time it took for a test signal to be sent and returned from this link station to the adjacent link station. This time is represented in milliseconds.

The value 0 is returned if no test signal has been sent and returned."

::= { appnLsEntry 27 }

appnLsMaxDelayTime OBJECT-TYPE
SYNTAX DateAndTime
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The time when the longest delay occurred. This time can be used to identify when this high water mark occurred in relation to other events in the APPN node, for example, the time at which an APPC session was either terminated or failed to be established. This latter time is available in the appcHistSessTime object in the APPC MIB.

The value 00000000 is returned if no test signal has been sent and returned."

::= { appnLsEntry 28 }

appnLsGoodXids OBJECT-TYPE
SYNTAX AppnLinkStationCounter
UNITS "XID exchanges"
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The total number of successful XID exchanges that have occurred on this link station since the time it was started."

```
::= { appnLsEntry 29 }
appnLsBadXids OBJECT-TYPE
      SYNTAX AppnLinkStationCounter
      UNITS "XID exchanges"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "The total number of unsuccessful XID exchanges that have
           occurred on this link station since the time it was started."
      ::= { appnLsEntry 30 }
appnLsSpecific OBJECT-TYPE
      SYNTAX RowPointer
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Identifies the object, e.g., one in a DLC-specific MIB, that can provide additional information related to this link
           station.
           If the agent is unable to identify such an object, the value
           0.0 is returned."
      ::= { appnLsEntry 31 }
appnLsActiveTime OBJECT-TYPE
      SYNTAX Unsigned32
UNITS "hundredths of a second"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The cumulative amount of time since the node was last
           reinitialized, measured in hundredths of a second, that this
           link station has been in the active state. A zero value
           indicates that the link station has never been active since
           the node was last reinitialized.'
      ::= { appnLsEntry 32 }
appnLsCurrentStateTime OBJECT-TYPE
      SYNTAX TimeTicks
      UNITS "hundredths of a second"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The amount of time, measured in hundredths of a second, that
```

```
the link station has been in its current state."
      ::= { appnLsEntry 33 }
appnLsHprSup OBJECT-TYPE
      SYNTAX INTEGER {
                  noHprSupport(1),
                 hprBaseOnly(2),
                 rtpTower(3),
                  controlFlowsOverRtpTower(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates the level of high performance routing (HPR) support
          over this link:
             noHprSupport(1)
                                           - no HPR support
             hprBaseOnly(2)
                                           - HPR base (option set 1400)
                                             supported
                                           - HPR base and RTP tower
             rtpTower(3)
                                             (option set 1401) supported
             controlFlowsOverRtpTower(4) - HPR base, RTP tower, and control flows over RTP
                                             (option set 1402) supported
          If the link is not active, the defined value is returned."
      ::= { appnLsEntry 34 }
appnLsErrRecoSup OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Indicates whether the link station is supporting
           HPR link-level error recovery."
      ::= { appnLsEntry 35 }
appnLsForAnrLabel OBJECT-TYPE
      SYNTAX OCTET STRING (SIZE (0..8))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The forward Automatic Network Routing (ANR) label for this
          link station. If the link does not support HPR or the value is
          unknown, a zero-length string is returned."
```

```
::= { appnLsEntry 36 }
appnLsRevAnrLabel OBJECT-TYPE
       SYNTAX OCTET STRING (SIZE (0..8))
       MAX-ACCESS read-only
       STATUS current DESCRIPTION
            "The reverse Automatic Network Routing (ANR) label for this link station. If the link does not support HPR or the value is
            link station.
            unknown, a zero-length string is returned.'
       ::= { appnLsEntry 37 }
appnLsCpCpNceId OBJECT-TYPE SYNTAX OCTET STRING (SIZE (0..8))
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The network connection endpoint identifier (NCE ID) for CP-CP
            sessions if this node supports the HPR transport tower, a zero-length string if the value is unknown or not meaningful
            for this node.'
       ::= { appnLsEntry 38 }
appnLsRouteNceId OBJECT-TYPE
       SYNTAX OCTET STRING (SIZE (0..8))
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The network connection endpoint identifier (NCE ID) for Route
            Setup if this node supports the HPR transport tower, a zero-
            length string if the value is unknown or not meaningful for
            this node."
       ::= { appnLsEntry 39 }
appnLsBfNceId OBJECT-TYPE
       SYNTAX OCTET STRING (SIZE (0..8))
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The network connection endpoint identifier (NCE ID) for the
            APPN/HPR boundary function if this node supports the HPR
           transport tower, a zero-length string if the value is unknown or not meaningful for this node."
       ::= { appnLsEntry 40 }
```

```
appnLsLocalAddr OBJECT-TYPE
      SYNTAX DisplayableDlcAddress
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Local address of this link station."
      ::= { appnLsEntry 41 }
appnLsRemoteAddr OBJECT-TYPE
      SYNTAX DisplayableDlcAddress
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          "Address of the remote link station on this link."
      ::= { appnLsEntry 42 }
appnLsRemoteLsName OBJECT-TYPE
      SYNTAX DisplayString (SIZE (0..10))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Remote link station discovered from the XID exchange.
          The name can be from one to ten characters. A zero-length
          string indicates that the value is not known."
      ::= { appnLsEntry 43 }
appnLsCounterDisconTime OBJECT-TYPE
      SYNTAX TimeStamp
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          "The value of the sysUpTime object the last time the link
          station was started.'
      ::= { appnLsEntry 44 }
appnLsMltgMember OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the link is a member of a multi-link TG. If
          the link's TG has been brought up as a multi-link TG, then the
          link is reported as a member of a multi-link TG, even if it is
```

```
currently the only active link in the TG."
      ::= { appnLsEntry 45 }
-- This table provides information about errors this node encountered
-- with connections to adjacent nodes. Entries are added for exceptional -- conditions encountered establishing connections, and for exceptional
-- conditions that resulted in termination of a connection. It is an
-- implementation option when entries are removed from this table.
appnLsStatusTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnLsStatusEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "This table contains information related to exceptional and
          potentially exceptional conditions that occurred during the activation, XID exchange, and termination of a connection. No entries are created when these activities proceed normally.
          It is an implementation option when entries are removed from
          this table.
      ::= { appnLinkStationInformation 2 }
appnLsStatusEntry OBJECT-TYPE
      SYNTAX AppnLsStatusEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "This table is indexed by the LsStatusIndex, which is an
          integer that is continuously updated until it eventually
          wraps."
      INDEX
             { appnLsStatusIndex }
      ::= { appnLsStatusTable 1 }
AppnLsStatusEntry ::= SEQUENCE {
      appnLsStatusIndex
                                       INTEGER.
                                       DateAndTime,
      appnLsStatusTime
      appnLsStatusLsName
                                       DisplayString,
      appnLsStatusCpName
                                       DisplayString,
```

```
appnLsStatusPartnerId
                                           SnaNodeIdentification,
       appnLsStatusTgNum
                                           INTEGER,
                                           SnaSenseData,
       appnLsStatusGeneralSense
                                           TruthValue,
       appnLsStatusRetry
       appnLsStatusEndSense
                                           SnaSenseData,
       appnLsStatusXidLocalSense
                                           SnaSenseData.
       appnLsStatusXidRemoteSense
                                           SnaSenseData,
       appnLsStatusXidByteInError
                                           INTEGER,
       appnLsStatusXidBitInError
                                           INTEGER,
                                           IANAifType,
       appnLsStatusDlcType
       appnLsStatusLocalAddr
                                           DisplayableDlcAddress,
       appnLsStatusRemoteAddr
                                           DisplayableDlcAddress
                        }
appnLsStatusIndex OBJECT-TYPE
       SYNTAX INTEGER (0..2147483647)
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
            "Table index. The value of the index begins at zero and is incremented up to a maximum value of 2**31-1
             (2,147,483,647) before wrapping."
       ::= { appnLsStatusEntry 1 }
appnLsStatusTime OBJECT-TYPE
       SYNTAX DateAndTime
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Time when the exception condition occurred. This time can be
           used to identify when this event occurred in relation to other
           events in the APPN node, for example, the time at which an APPC session was either terminated or failed to be established. This latter time is available in the appcHistSessTime object in
           the APPC MIB.'
       ::= { appnLsStatusEntry 2 }
appnLsStatusLsName OBJECT-TYPE
       SYNTAX DisplayString (SIZE (1..10))
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Administratively assigned name for the link station
           experiencing the condition."
```

```
::= { appnLsStatusEntry 3 }
appnLsStatusCpName OBJECT-TYPE
       SYNTAX DisplayString (SIZE (0 | 3..17))
       MAX-ACCESS read-only
       STATUS current DESCRIPTION
            "Fully qualified name of the adjacent node for this link station. An adjacent node is identified using the format
            specified in the SnaControlPointName textual convention.
            The value of this object is determined as follows:
               1. If the adjacent node's name was received on XID, it
                   is returned.
               2. If the adjacent node's name was not received on XID,
                   but a locally-defined value is available, it is
                   returned.
               3. Otherwise a string of length 0 is returned, indicating that no name is known for the adjacent node."
       ::= { appnLsStatusEntry 4 }
appnLsStatusPartnerId OBJECT-TYPE
       SYNTAX SnaNodeIdentification
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "The partner's Node Identification, from bytes 2-5 of the XID
            received from the partner. If this value is not available, then the characters '00000000' are returned."
       ::= { appnLsStatusEntry 5 }
appnLsStatusTqNum OBJECT-TYPE
       SYNTAX INTEGER (0..256)
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Number associated with the TG to this link station, with a range from 0 to 256. A value of 256 indicates that the TG
            number was unknown at the time of the failure.
       ::= { appnLsStatusEntry 6 }
appnLsStatusGeneralSense OBJECT-TYPE
```

```
SYNTAX SnaSenseData
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The error sense data associated with the start sequence of
          activation of a link up to the beginning of the XID sequence.
          This is the sense data that came from Configuration Services
          whenever the link did not activate or when it went inactive."
      ::= { appnLsStatusEntry 7 }
appnLsStatusRetry OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether the node will retry the start request to
          activate the link."
      ::= { appnLsStatusEntry 8 }
appnLsStatusEndSense OBJECT-TYPE
      SYNTAX SnaSenseData
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The sense data associated with the termination of the link
          connection to adjacent node.
          This is the sense data that came from the DLC layer."
      ::= { appnLsStatusEntry 9 }
appnLsStatusXidLocalSense OBJECT-TYPE
      SYNTAX SnaSenseData
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The sense data associated with the rejection of the XID.
          This is the sense data that came from the local node (this node) when it built the XID Negotiation Error control vector
          (cv22) to send to the remote node."
      ::= { appnLsStatusEntry 10 }
appnLsStatusXidRemoteSense OBJECT-TYPE
```

```
SYNTAX SnaSenseData
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The sense data the adjacent node returned to this node
          indicating the reason the XID was rejected.
          This is the sense data that came from the remote node in the
          XID Negotiation Error control vector (cv22) it sent to the
          local node (this node).'
      ::= { appnLsStatusEntry 11 }
appnLsStatusXidByteInError OBJECT-TYPE
      SYNTAX INTÉGER (0..65536)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "This object identifies the actual byte in the XID that caused
          the error. The value 65536 indicates that the object has no
          meaning.
          For values in the range 0-65535, this object corresponds to
          bytes 2-3 of the XID Negotiation (X'22') control vector."
      ::= { appnLsStatusEntry 12 }
appnLsStatusXidBitInError OBJECT-TYPE
      SYNTAX INTEGER (0..8)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "This object identifies the actual bit in error (0 through 7)
          within the errored byte of the XID. The value 8 indicates that
          this object has no meaning.
          For values in the range 0-7, this object corresponds to byte 4 of the XID Negotiation (X'22') control vector."
      ::= { appnLsStatusEntry 13 }
appnLsStatusDlcType OBJECT-TYPE
      SYNTAX IANAifType
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The type of DLC interface, distinguished according to the protocol immediately 'below' this layer."
```

```
::= { appnLsStatusEntry 14 }
appnLsStatusLocalAddr OBJECT-TYPE
     SYNTAX DisplayableDlcAddress
     MAX-ACCESS read-only
     STATUS current DESCRIPTION
         'Local address of this link station."
     ::= { appnLsStatusEntry 15 }
appnLsStatusRemoteAddr OBJECT-TYPE
     SYNTAX DisplayableDlcAddress
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
         'Address of the remote link station on this link."
     ::= { appnLsStatusEntry 16 }
-- APPN Virtual Routing Node Information
-- This section provides information relating a virtual routing node to
-- an APPN port.
appnVrnTable OBJECT-TYPE SYNTAX SEQUENCE OF AppnVrnEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
         "This table relates a virtual routing node to an APPN port."
     ::= { appnVrnInfo 1 }
appnVrnEntry OBJECT-TYPE
     SYNTAX AppnVrnEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
         "This table is indexed by the virtual routing node name, TG
         number, and port name. There will be a matching entry in the
         appnLocalTgTable to represent status and characteristics of the
         TG representing each virtual routing node definition."
     INDEX
            { appnVrnName, appnVrnTgNum, appnVrnPortName }
```

```
::= { appnVrnTable 1 }
AppnVrnEntry ::= SEQUENCE {
      appnVrnName
                                 SnaControlPointName,
      appnVrnTgNum
                                 INTEGER,
      appnVrnPortName
                                 DisplayString
}
appnVrnName OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "Administratively assigned name of the virtual routing node.
This is a fully qualified name, and matches the appnLocalTgDest
           name in the appnLocalTgTable.'
       ::= { appnVrnEntry 1 }
appnVrnTgNum OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "Number associated with the transmission group representing
           this virtual routing node definition."
       ::= { appnVrnEntry 2 }
appnVrnPortName OBJECT-TYPE
      SYNTAX DisplayString (SIZE (1..10))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The name of the port this virtual routing node definition is
           defined to."
       ::= { appnVrnEntry 3 }
-- ******* The APPN Topology Group *****************
appnNn
                        OBJECT IDENTIFIER ::= { appnObjects 2 }
                     OBJECT IDENTIFIER ::= { appnNn 1 }
appnNnTopo
appnNnTopology
                     OBJECT IDENTIFIER ::= { appnNn 2 }
-- This group is used to represent the entire APPN network-node topology
-- including network nodes, virtual routing nodes and all TGs associated -- with these nodes, including intersubnetwork TGs (ISTGs) and branch TGs.
```

```
-- Network nodes
-- The APPN topology database consists of information about every APPN
-- network node in this network node's topology subnetwork.
-- information is learned over time as each network node exchanges
   topology information with the network nodes adjacent to it. The database consists of information about each node, and information
   about all of the transmission groups used by these nodes.
-- Virtual routing nodes
-- Information about virtual routing nodes (representing connection
-- networks) is treated in the same way as information about network
-- nodes, and is replicated at each network node. The FRSN, node name,
-- and node type are the only meaningful fields for a virtual routing -- node. The other node objects return unspecified values. Each
-- node that has defined a TG with this virtual routing node as the
-- destination also defines a TG on this virtual routing node. There
-- is a TG record for each node that uses this virtual routing node.
-- The APPN node table represents node information from the APPN topology
-- database, with the FRSN and APPN fully qualified CP name serving as -- the index. The FRSN is the agent's relative time stamp of an update
-- to the network topology database. After collecting the entire database -- once, a management application can issue GET NEXT commands starting
-- from the last rows it has retrieved from the appnNnTopologyFRTable and
-- from the appnNnTgTopologyFRTable. When the response to either of these
-- GET NEXT commands returns another row of its respective table, this -- indicates a change to the agent's topology database. The management -- application can then retrieve only the updates to the table, using
   GET NEXT commands starting from the last retrieved node or TG entry.
--
-- The format of the actual APPN topology database is as follows:
___
   Node table (entry for each node in network)
TG table (entry for each TG owned by node)
-- Due to SNMP's ASN.1 limitations, we cannot represent the TG table
-- within the node table in this way. We define separate tables for
-- nodes and TGs, adding the node name to each TG entry to provide a
-- means of correlating the TG with its originating node.
appnNnTopoMaxNodes OBJECT-TYPE
       SYNTAX Gauge32
       UNITS "node entries"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Maximum number of node entries allowed in the APPN topology
```

database. It is an implementation choice whether to count only network-node entries, or to count all node entries. If the number of node entries exceeds this value, APPN will issue an Alert and the node can no longer participate as a network node. The value 0 indicates that the local node has no defined limit, and the number of node entries is bounded only by memory."

::= { appnNnTopo 1 } appnNnTopoCurNumNodes OBJECT-TYPE SYNTAX Gauge32 UNITS "node entries" MAX-ACCESS read-only STATUS current DESCRIPTION "Current number of node entries in this node's topology database. It is an implementation choice whether to count only network-node entries, or to count all node entries, but an implementation must make the same choice here that it makes for the appnNnTopoMaxNodes object. If this value exceeds the maximum number of nodes allowed (appnNnTopoMaxNodes, if that field in not 0), APPN Alert CPDB002 is issued." ::= { appnNnTopo 2 } appnNnTopoNodePurges OBJECT-TYPE SYNTAX AppnNodeCounter UNITS "node entries" MAX-ACCESS read-only STATUS current **DESCRIPTION** "Total number of topology node records purged from this node's topology database since the node was last reinitialized." ::= { appnNnTopo 3 } appnNnTopoTgPurges OBJECT-TYPE SYNTAX AppnNodeCounter UNITS "TG entries" MAX-ACCESS read-only **STATUS** current **DESCRIPTION** "Total number of topology TG records purged from this node's topology database since the node was last reinitialized. ::= { appnNnTopo 4 }

appnNnTopoTotalTduWars OBJECT-TYPE

```
SYNTAX AppnNodeCounter UNITS "TDU wars"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of TDU wars detected by this node since its last
          initialization."
      ::= { appnNnTopo 5 }
-- APPN network node topology table (using FRSN and name as index)
-- This table describes every APPN network node and virtual routing node
-- represented in this node's topology database.
appnNnTopologyFRTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnNnTopologyFREntry
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
           "Portion of the APPN topology database that describes all of
          the APPN network nodes and virtual routing nodes known to this
          node."
      ::= { appnNnTopology 3 }
appnNnTopologyFREntry OBJECT-TYPE
      SYNTAX AppnNnTopologyFREntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "The FRSN and the fully qualified node name are used to index
          this table."
      INDEX
             {appnNnNodeFRFrsn,
              appnNnNodeFRName}
      ::= { appnNnTopologyFRTable 1 }
AppnNnTopologyFREntry ::= SEQUENCE {
      appnNnNodeFRFrsn
                                             Unsigned32
                                             SnaControlPointName,
      appnNnNodeFRName
      appnNnNodeFREntryTimeLeft
                                             AppnTopologyEntryTimeLeft,
      appnNnNodeFRType
                                             INTEGER,
```

```
appnNnNodeFRRsn
                                             Unsigned32,
      appnNnNodeFRRouteAddResist
                                             INTEĞER,
      appnNnNodeFRCongested
                                             TruthValue.
      appnNnNodeFRIsrDepleted
                                             TruthValue,
      appnNnNodeFRQuiescing
                                             TruthValue,
      appnNnNodeFRGateway
                                             TruthValue.
      appnNnNodeFRCentralDirectory
                                             TruthValue.
      appnNnNodeFRIsr
                                             TruthValue,
      appnNnNodeFRGarbageCollect
                                             TruthValue,
      appnNnNodeFRHprSupport
                                             INTEGER.
      appnNnNodeFRPeriBorderSup
                                             TruthValue,
      appnNnNodeFRInterchangeSup
                                             TruthValue,
                                             TruthValue,
      appnNnNodeFRExteBorderSup
      appnNnNodeFRBranchAwareness
                                             TruthValue
}
appnNnNodeFRFrsn OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
          "Flow reduction sequence numbers (FRSNs) are associated with
          Topology Database Updates (TDUs) and are unique only within
          each APPN network node. A TDU can be associated with multiple
          APPN resources. This FRSN indicates the last relative time
          this resource was updated at the agent node."
      ::= { appnNnTopologyFREntry 1 }
appnNnNodeFRName OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
          "Administratively assigned network name that is locally defined
          at each network node.'
      ::= { appnNnTopologyFREntry 2 }
appnNnNodeFREntryTimeLeft OBJECT-TYPE
      SYNTAX AppnTopologyEntryTimeLeft UNITS "days"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of days before deletion of this network node entry."
```

```
::= { appnNnTopologyFREntry 3 }
appnNnNodeFRType OBJECT-TYPE
      SYNTAX ÍNTEGER {
                      networkNode(1),
                      virtualRoutingNode(3)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Type of APPN node."
      ::= { appnNnTopologyFREntry 4 }
appnNnNodeFRRsn OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Resource sequence number, which is assigned and controlled by
the network node that owns this resource. An odd number
          indicates that information about the resource is inconsistent.
          This object corresponds to the numeric value in cv4580, bytes
          2-5."
      ::= { appnNnTopologyFREntry 5 }
appnNnNodeFRRouteAddResist OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Route addition resistance.
          This administratively assigned value indicates the relative
          desirability of using this node for intermediate session
                     The value, which can be any integer 0-255, is used
          in route computation. The lower the value, the more
          desirable the node is for intermediate routing.
          This object corresponds to cv4580, byte 6."
      ::= { appnNnTopologyFREntry 6 }
appnNnNodeFRCongested OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
```

```
STATUS current
      DESCRIPTION
          "Indicates whether this node is congested. This node is not be
          included in route selection by other nodes when this congestion
          This object corresponds to cv4580, byte 7, bit 0."
      ::= { appnNnTopologyFREntry 7 }
appnNnNodeFRIsrDepleted OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          "Indicates whether intermediate session routing resources are
          depleted. This node is not included in intermediate route
          selection by other nodes when resources are depleted.
          This object corresponds to cv4580, byte 7, bit 1."
      ::= { appnNnTopologyFREntry 8 }
appnNnNodeFROuiescing OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the node is quiescing. This node is not
          included in route selection by other nodes when the node is
          quiescing.
          This object corresponds to cv4580, byte 7, bit 5."
      ::= { appnNnTopologyFREntry 9 }
appnNnNodeFRGateway OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the node provide gateway services.
          This object corresponds to cv4580, byte 8, bit 0."
      ::= { appnNnTopologyFREntry 10 }
```

```
appnNnNodeFRCentralDirectory OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the node supports central directory
          services.
          This object corresponds to cv4580, byte 8, bit 1."
      ::= { appnNnTopologyFREntry 11 }
appnNnNodeFRIsr OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the node supports intermediate session
          routing (ISR).
          This object corresponds to cv4580, byte 8, bit 2."
      ::= { appnNnTopologyFREntry 12 }
appnNnNodeFRGarbageCollect OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the node has been marked for garbage
          collection (deletion from the topology database) upon the next
          garbage collection cycle.
          This object corresponds to cv4580, byte 7, bit 3."
      ::= { appnNnTopologyFREntry 13 }
appnNnNodeFRHprSupport OBJECT-TYPE
      SYNTAX INTEGER {
                 noHprSupport(1),
                 hprBaseOnly(2),
                 rtpTower(3),
                 controlFlowsOverRtpTower(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
```

```
"Indicates the node's level of support for high-performance
          routing (HPR):
             noHprSupport(1)
                                          - no HPR support
             hprBaseOnly(2)
                                          - HPR base (option set 1400)
                                            supported
             rtpTower(3)
                                          - HPR base and RTP tower
                                            (option set 1401) supported
             controlFlowsOverRtpTower(4) - HPR base, RTP tower, and control flows over RTP
                                            (option set 1402) supported
          This object corresponds to cv4580, byte 9, bits 3-4."
      ::= { appnNnTopologyFREntry 14 }
appnNnNodeFRPeriBorderSup OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether this node has peripheral border node
          support.
          This object corresponds to cv4580, byte 9, bit 0."
      ::= { appnNnTopologyFREntry 15 }
appnNnNodeFRInterchangeSup OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether this node has interchange node support.
          This object corresponds to cv4580, byte 9, bit 1."
      ::= { appnNnTopologyFREntry 16 }
appnNnNodeFRExteBorderSup OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether this node has extended border node
           support.
          This object corresponds to cv4580, byte 9, bit 2."
```

```
::= { appnNnTopologyFREntry 17 }
appnNnNodeFRBranchAwareness OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           'Indicates whether this node supports branch awareness.
          This object corresponds to cv4580, byte 8, bit 4."
      ::= { appnNnTopologyFREntry 18 }
--APPN transmission group (TG) table
-- This table describes the TGs associated with all the APPN network
-- nodes known to this node. The originating (owning) node for each
-- TG is repeated here to provide a means of correlating the TGs with
-- the nodes.
appnNnTgTopologyFRTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnNnTgTopologyFREntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Portion of the APPN topology database that describes all of
          the APPN transmissions groups between nodes in the database."
      ::= { appnNnTopology 4 }
appnNnTgTopologyFREntry OBJECT-TYPE
      SYNTAX AppnNnTgTopologyFREntry
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
          "This table is indexed by four columns: FRSN, TG owner fully
          qualified node name, TG destination fully qualified node name,
          and TG number.'
      INDEX
             {appnNnTgFRFrsn,
              appnNnTgFROwner,
              appnNnTgFRDest,
              appnNnTgFRNum}
      ::= { appnNnTqTopologyFRTable 1 }
```

```
AppnNnTgTopologyFREntry ::= SEQUENCE {
      appnNnTgFRFrsn
                                Unsigned32
                                SnaControlPointName,
      appnNnTgFR0wner
      appnNnTgFRDest
                                SnaControlPointName,
      appnNnTgFRNum
                                INTEGER.
      appnNnTgFREntryTimeLeft
                                AppnTopologyEntryTimeLeft,
      appnNnTgFRDestVirtual
                                TruthValue,
      appnNnTgFRDlcData
                                AppnTgDlcData,
      appnNnTgFRRsn
                                Unsigned32,
      appnNnTgFROperational
                                TruthValue,
      appnNnTgFRQuiescing
                                TruthValue.
      appnNnTgFRCpCpSession
                                INTEGER
                                AppnTqEffectiveCapacity.
      appnNnTgFREffCap
                                INTEGER,
      appnNnTqFRConnCost
      appnNnTgFRByteCost
                                INTEGER,
      appnNnTgFRSecurity
                                AppnTgSecurity,
      appnNnTgFRDelay
                                AppnTgDelay,
      appnNnTgFRUsr1
                                INTEGER,
      appnNnTgFRUsr2
                                INTEGER,
      appnNnTgFRUsr3
                                INTEGER,
      appnNnTgFRGarbageCollect TruthValue.
      appnNnTgFRSubareaNum
                                Unsigned32,
      appnNnTqFRHprSup
                                TruthValue.
      appnNnTgFRDestHprTrans
                                TruthValue,
      appnNnTgFRTypeIndicator
                                INTEGER,
                                TruthValue,
      appnNnTgFRIntersubnet
      appnNnTgFRMltgLinkType
                                TruthValue,
      appnNnTgFRBranchTg
                                TruthValue
}
appnNnTgFRFrsn OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Flow reduction sequence numbers (FRSNs) are associated with
          Topology Database Updates (TDUs) and are unique only within
          each APPN network node. A TDU can be associated with multiple
                          This FRSN indicates the last time this
          APPN resources.
          resource was updated at this node."
      ::= { appnNnTgTopologyFREntry 1 }
```

```
appnNnTgFROwner OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Administratively assigned name for the originating node for
          this TG. This is the same name specified in the node table."
      ::= { appnNnTgTopologyFREntry 2 }
appnNnTgFRDest OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
          "Administratively assigned fully qualified network name for the
          destination node for this TG."
      ::= { appnNnTgTopologyFREntry 3 }
appnNnTgFRNum OBJECT-TYPE
      SÝNTAX INTEGER (0..255)
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Number associated with this transmission group. Range is
          0-255."
      ::= { appnNnTgTopologyFREntry 4 }
appnNnTgFREntryTimeLeft OBJECT-TYPE
      SYNTAX AppnTopologyEntryTimeLeft
      UNITS "days"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           'Number of days before deletion of this network node TG entry
          if it is not operational or has an odd (inconsistent) RSN."
      ::= { appnNnTgTopologyFREntry 5 }
appnNnTgFRDestVirtual OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the destination node is a virtual routing
          node."
```

```
::= { appnNnTgTopologyFREntry 6 }
appnNnTgFRDlcData OBJECT-TYPE
      SYNTAX AppnTqDlcData
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           'DLC-specific data related to a link connection network."
      ::= { appnNnTgTopologyFREntry 7 }
appnNnTgFRRsn OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Current owning node's resource sequence number for this
          resource. An odd number indicates that information about the
          resource is inconsistent.
          This object corresponds to the numeric value in cv47, bytes
          2-5'
      ::= { appnNnTqTopologvFREntry 8 }
appnNnTgFROperational OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether the transmission group is operational.
          This object corresponds to cv47, byte 6, bit 0."
      ::= { appnNnTgTopologyFREntry 9 }
appnNnTgFRQuiescing OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the transmission group is quiescing.
          If the TG owner is either an extended border node or a
          branch-aware network node (indicated, respectively, by
          the appnNnNodeFRExteBorderSup and appnNnNodeFRBranchAwareness
          objects in the corresponding appnNnTopologyFREntry), then this indicator is artificially set to TRUE in the APPN
```

```
topology database, to remove the TG from other nodes'
           route calculations. A management application can
           determine whether the TG is actually quiescing by
           examining its appnLocalTgQuiescing object at the TG owner.
           This object corresponds to cv47, byte 6, bit 2."
       ::= { appnNnTgTopologyFREntry 10 }
appnNnTgFRCpCpSession OBJECT-TYPE
      SYNTAX INTEGER {
                       supportedUnknownStatus(1),
                       supportedActive(2),
                       notSupported(3)
                       supportedNotActive(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether CP-CP sessions are supported on this TG, and
           whether the TG owner's contention-winner session is active on
this TG. Some nodes in the network are not able to
           differentiate support and status of CP-CP sessions, and thus
           may report the 'supportedUnknownStatus' value.
           This object corresponds to cv47, byte 6, bits 3-4."
       ::= { appnNnTqTopologyFREntry 11 }
appnNnTgFREffCap OBJECT-TYPE
      SYNTAX AppnTgEffectiveCapacity
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Effective capacity for this TG."
       ::= { appnNnTqTopologyFREntry 12 }
appnNnTgFRConnCost OBJECT-TYPE
      SŸNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Cost per connect time.
           This is an administratively assigned value representing the relative cost per unit of time to use this TG. Range is from
```

```
0, which means no cost, to 255, which indicates maximum cost.
          This object corresponds to cv47, byte 13."
      ::= { appnNnTqTopologyFREntry 13 }
appnNnTgFRByteCost OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Cost per byte transmitted.
          This is an administratively assigned value representing the relative cost of transmitting a byte over this TG. Range is
          from 0, which means no cost, to 255, which indicates maximum
          cost.
          This object corresponds to cv47, byte 14."
      ::= { appnNnTqTopologyFREntry 14 }
appnNnTgFRSecurity OBJECT-TYPE
      SYNTAX AppnTgSecurity
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Administratively assigned security level of this TG.
          This object corresponds to cv47, byte 16."
      ::= { appnNnTgTopologyFREntry 15 }
appnNnTgFRDelay OBJECT-TYPE
      SYNTAX AppnTgDelay
MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Administratively assigned delay associated with this TG.
          This object corresponds to cv47, byte 17."
      ::= { appnNnTqTopologyFREntry 16 }
appnNnTgFRUsr1 OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
```

```
DESCRIPTION
          "First user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG.
          This object corresponds to cv47, byte 19."
      ::= { appnNnTqTopologyFREntry 17 }
appnNnTgFRUsr2 OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Second user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG.
          This object corresponds to cv47, byte 20."
      ::= { appnNnTgTopologyFREntry 18 }
appnNnTgFRUsr3 OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Third user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG.
          This object corresponds to cv47, byte 21."
      ::= { appnNnTgTopologyFREntry 19 }
appnNnTgFRGarbageCollect OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          'Indicates whether the TG has been marked for garbage
          collection (deletion from the topology database) upon the next
          garbage collection cycle.
          This object corresponds to cv47, byte 6, bit 1."
      ::= { appnNnTqTopologyFREntry 20 }
appnNnTgFRSubareaNum OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS read-only
```

```
STATUS current
      DESCRIPTION
          "The subarea number associated with this TG.
          This object corresponds to cv4680, bytes m+2 through m+5."
      ::= { appnNnTqTopologyFREntry 21 }
appnNnTgFRHprSup OBJECT-TYPE
      SÝNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether high performance routing (HPR)
          is supported over this TG.
          This object corresponds to cv4680, byte m+1, bit 2."
      ::= { appnNnTgTopologyFREntry 22 }
appnNnTgFRDestHprTrans OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the destination node supports
          high performance routing (HPR) transport tower.
          This object corresponds to cv4680, byte m+1, bit 7."
      ::= { appnNnTgTopologyFREntry 23 }
appnNnTgFRTypeIndicator OBJECT-TYPE
      SYNTAX INTEGER {
                      unknown(1),
appn0rBfTg(2),
                      interchangeTg(3).
                      virtualRouteTg(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates the type of the TG.
          This object corresponds to cv4680, byte m+1, bits 3-4."
      ::= { appnNnTgTopologyFREntry 24 }
```

```
appnNnTgFRIntersubnet OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the transmission group is an intersubnet TG,
          which defines a border between subnetworks.
          This object corresponds to cv4680, byte m+1, bit 5."
      ::= { appnNnTgTopologyFREntry 25 }
appnNnTgFRMltgLinkType OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "This object indicates whether the transmission group is a
          multi-link TG. A TG that has been brought up as a multi-link
          TG is reported as one, even if it currently has only one link
          active.
          This object corresponds to cv47, byte 6, bit 5."
      ::= { appnNnTgTopologyFREntry 26 }
appnNnTgFRBranchTg OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the transmission group is a branch TG
          (equivalently, whether the destination of the transmission
          group is a branch network node).
          This object corresponds to cv4680, byte m+1, bit 1."
      ::= { appnNnTgTopologyFREntry 27 }
-- ******** The APPN Local Topology Group **************
-- This MIB Group represents the local topology maintained in
-- APPN network nodes, end nodes, and branch network nodes. It consists
-- of two tables:
      - a table containing information about all of the TGs owned
___
        by this node, which is implemented by all node types.
_ _
      - a table containing all of the information known to this node
_ _
        about the TGs owned by its end nodes, which is implemented only
__
        by network nodes.
```

```
OBJECT IDENTIFIER ::= { appn0bjects 3 }
appnLocalTopology
-- APPN Local Transmission Group (TG) table
-- This table describes the TGs associated with this node only.
appnLocalTqTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnLocalTgEntry MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "TG Table describes all of the TGs owned by this node.
          destination can be a virtual node, network node, LEN node, or
          end node."
      ::= { appnLocalTopology 1 }
appnLocalTgEntry OBJECT-TYPE
      SYNTAX AppnLocalTgEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "This table is indexed by the destination CpName and the TG
          number."
      INDEX
             {appnLocalTqDest,
              appnLocalTqNum}
      ::= { appnLocalTgTable 1 }
AppnLocalTgEntry ::= SEQUENCE {
                                   SnaControlPointName,
      appnLocalTgDest
                                   INTEGER,
      appnLocalTqNum
      appnLocalTgDestVirtual
                                   TruthValue,
      appnLocalTgDlcData
                                   AppnTgDlcData,
      appnLocalTgPortName
                                   DisplayString,
      appnLocalTgQuiescing
                                   TruthValue,
      appnLocalTgOperational
                                   TruthValue,
      appnLocalTgCpCpSession
                                   INTEGER
                                   AppnTgEffectiveCapacity.
      appnLocalTgEffCap
      appnLocalTgConnCost
                                   INTEGER,
      appnLocalTgByteCost
                                   INTEGER,
      appnLocalTgSecurity
                                   AppnTgSecurity,
      appnLocalTgDelay
                                   AppnTgDelay,
                                   INTEGÉR,
      appnLocalTqUsr1
      appnLocalTqUsr2
                                   INTEGER,
```

```
appnLocalTgUsr3
                                    INTEGER,
      appnLocalTgHprSup
                                    INTEGER,
      appnLocalTgIntersubnet
                                    TruthValue,
      appnLocalTqMltqLinkType
                                    TruthValue,
      appnLocalTgBranchLinkType
                                    INTEGER
appnLocalTgDest OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Administratively assigned name of the destination node for this TG. This is the fully qualified name of a network node,
          end node, LEN node, or virtual routing node.
      ::= { appnLocalTqEntry 1 }
appnLocalTgNum OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "Number associated with this transmission group."
      ::= { appnLocalTgEntry 2 }
appnLocalTgDestVirtual OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether the destination node for this TG is a
          virtual routing node."
      ::= { appnLocalTgEntry 3 }
appnLocalTgDlcData OBJECT-TYPE
      SYNTAX AppnTgDlcData
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           'DLC-specific data related to a link connection network."
      ::= { appnLocalTqEntry 4 }
appnLocalTgPortName OBJECT-TYPE
      SYNTAX DisplayString (SIZE (0..10))
```

```
MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Administratively assigned name for the local port associated
          with this TG. A zero-length string indicates that this value
          is unknown."
      ::= { appnLocalTgEntry 5 }
appnLocalTgQuiescing OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the transmission group is quiescing."
      ::= { appnLocalTqEntry 6 }
appnLocalTgOperational OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the transmission group is operational."
      ::= { appnLocalTgEntry 7 }
appnLocalTgCpCpSession OBJECT-TYPE
      SYNTĂX INTEGER {
                     supportedUnknownStatus(1),
                     supportedActive(2),
                     notSupported(3),
                     supportedNotActive(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether CP-CP sessions are supported on this TG, and
          whether the TG owner's contention-winner session is active on
          this TG. Some nodes in the network are not able to
          differentiate support and status of CP-CP sessions, and thus
          may report the 'supportedUnknownStatus' value.'
      ::= { appnLocalTqEntry 8 }
appnLocalTgEffCap OBJECT-TYPE
      SYNTAX AppnTgEffectiveCapacity
      MAX-ACCESS read-only
```

```
STATUS current DESCRIPTION
           "Effective capacity for this TG."
      ::= { appnLocalTqEntry 9 }
appnLocalTgConnCost OBJECT-TYPE
      SYNTĂX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Cost per connect time: a value representing the relative cost
          per unit of time to use the TG. Range is from 0, which means no cost, to 255."
      ::= { appnLocalTgEntry 10 }
appnLocalTgByteCost OBJECT-TYPE
      SYNTÂX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Relative cost of transmitting a byte over this link.
          Range is from 0 (lowest cost) to 255."
      ::= { appnLocalTgEntry 11 }
appnLocalTgSecurity OBJECT-TYPE
      SYNTAX AppnTgSecurity
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Administratively assigned security level of this TG."
      ::= { appnLocalTgEntry 12 }
appnLocalTgDelay OBJECT-TYPE
      SYNTAX AppnTqDelay
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Administratively assigned delay associated with this TG."
      ::= { appnLocalTqEntry 13 }
appnLocalTqUsr1 OBJECT-TYPE
      SYNTĂX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
```

```
DESCRIPTION
          "First user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG.
      ::= { appnLocalTqEntry 14 }
appnLocalTqUsr2 OBJECT-TYPE
      SYNTĂX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Second user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG."
      ::= { appnLocalTqEntry 15 }
appnLocalTqUsr3 OBJECT-TYPE
      SYNTÂX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Third user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG."
      ::= { appnLocalTgEntry 16 }
appnLocalTgHprSup OBJECT-TYPE
      SYNTĂX INTEGER {
                 noHprSupport(1),
                 hprBaseOnly(2),
                 rtpTower(3),
                 controlFlowsOverRtpTower(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates the level of high performance routing (HPR) support
          over this TG:
             noHprSupport(1)
                                          - no HPR support
                                          - HPR base (option set 1400)
             hprBaseOnly(2)
                                            supported
                                          - HPR base and RTP tower
             rtpTower(3)
                                            (option set 1401) supported
             controlFlowsOverRtpTower(4) - HPR base, RTP tower, and control flows over RTP
                                            (option set 1402) supported"
```

```
::= { appnLocalTgEntry 17 }
appnLocalTgIntersubnet OBJECT-TYPE
      SYNTĂX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Indicates whether the transmission group is an intersubnet TG,
          which defines a border between subnetworks.'
      ::= { appnLocalTgEntry 18 }
appnLocalTgMltgLinkType OBJECT-TYPE
      SYNTĂX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "This object indicates whether the transmission group is a
          multi-link TG. A TG that has been brought up as a multi-link
          TG is reported as one, even if it currently has only one link
          active."
      ::= { appnLocalTgEntry 19 }
appnLocalTgBranchLinkTvpe OBJECT-TYPE
      SYNTÄX INTEGER {
                     other(1)
                     uplink(2)
                     downlink(3),
                     downlinkToBranchNetworkNode(4),
                     none(5),
                     unknown (255)
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          "Branch link type of this TG:
                                   = the agent has determined the TG's
             other(1)
                                     branch link type to be a value other
                                     than branch uplink or branch
                                     downlink. This is the value used
                                     for a connection network TG owned by
                                     a branch network node.
             uplink(2)
                                   = the TG is a branch uplink.
                                   = the TG is a branch downlink to an
             downlink(3)
                                     end node.
             downlinkToBranchNetworkNode(4) = the TG is a branch
                                     downlink to a cascaded branch
```

```
network node.
                                   = the TG is not a branch TG.
             none(5)
             unknown(255)
                                   = the agent cannot determine the
                                     branch link type of the TG."
      ::= { appnLocalTgEntry 20 }
-- APPN Local End Node Transmission Group (TG) table
-- This table describes the TGs associated with all of the end nodes
-- known to this node.
appnLocalEnTgTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnLocalEnTgEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Table describing all of the TGs owned by the end nodes known
          to this node via TG registration. This node does not represent
          its own view of the TG on behalf of the partner node in this
          table. The TG destination can be a virtual routing node, network node, or end node."
      ::= { appnLocalTopology 2 }
appnLocalEnTgEntry OBJECT-TYPE
      SYNTAX AppnLocalEnTgEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "This table requires multiple indexes to uniquely identify each
               They are originating CPname, destination CPname, and the
          TG number."
      INDEX
             {appnLocalEnTgOrigin,
              appnLocalEnTgDest,
              appnLocalEnTgNum}
      ::= { appnLocalEnTgTable 1 }
AppnLocalEnTgEntry ::= SEQUENCE {
                                  SnaControlPointName,
      appnLocalEnTgOrigin
      appnLocalEnTqDest
                                  SnaControlPointName,
      appnLocalEnTqNum
                                  INTEGER.
      appnLocalEnTgEntryTimeLeft AppnTopologyEntryTimeLeft.
      appnLocalEnTqDestVirtual
                                  TruthValue,
```

```
appnLocalEnTgDlcData
                                  AppnTgDlcData,
      appnLocalEnTgOperational
                                  TruthValue,
      appnLocalEnTqCpCpSession
                                  INTEGER.
                                  AppnTgEffectiveCapacity.
      appnLocalEnTgEffCap
      appnLocalEnTgConnCost
                                  INTEGER,
      appnLocalEnTgByteCost
                                  INTEGER,
      appnLocalEnTgSecurity
                                  AppnTgSecurity,
      appnLocalEnTgDelay
                                  AppnTgDelay,
      appnLocalEnTgUsr1
                                  INTEGER,
                                  INTEGER,
      appnLocalEnTgUsr2
      appnLocalEnTgUsr3
                                  INTEGER,
      appnLocalEnTgMltgLinkType
                                 TruthValue
appnLocalEnTgOrigin OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          'Administratively assigned name of the origin node for this
          TG. This is a fully qualified network name."
      ::= { appnLocalEnTgEntry 1 }
appnLocalEnTgDest OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Administratively assigned name of the destination node for
          this TG. This is the fully qualified name of a network node,
          end node, LEN node, or virtual routing node."
      ::= { appnLocalEnTgEntry 2 }
appnLocalEnTgNum OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Number associated with this transmission group."
      ::= { appnLocalEnTgEntry 3 }
appnLocalEnTgEntryTimeLeft OBJECT-TYPE
      SYNTAX AppnTopologyEntryTimeLeft UNITS "days"
```

```
MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Number of days before deletion of this end node TG entry."
      ::= { appnLocalEnTgEntry 4 }
appnLocalEnTgDestVirtual OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether the destination node is a virtual routing
          node."
      ::= { appnLocalEnTgEntry 5 }
appnLocalEnTqDlcData OBJECT-TYPE
      SYNTAX AppnTgDlcData
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "DLC-specific data related to a link connection network."
      ::= { appnLocalEnTgEntry 6 }
appnLocalEnTgOperational OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether the transmission group is operational."
      ::= { appnLocalEnTgEntry 7 }
appnLocalEnTgCpCpSession OBJECT-TYPE
      SYNTAX INTEGER {
                      supportedUnknownStatus(1).
                      supportedActive(2),
                      notSupported(3)
                      supportedNotActive(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Indicates whether CP-CP sessions are supported on this TG, and
          whether the TG owner's contention-winner session is active on
this TG. Some nodes in the network are not able to
```

```
differentiate support and status of CP-CP sessions, and thus
          may report the 'supportedUnknownStatus' value.'
      ::= { appnLocalEnTgEntry 8 }
appnLocalEnTgEffCap OBJECT-TYPE
      SYNTAX AppnTgEffectiveCapacity MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Effective capacity for this TG."
      ::= { appnLocalEnTgEntry 9 }
appnLocalEnTgConnCost OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Cost per connect time: a value representing the relative cost
          per unit of time to use the TG. Range is from 0, which means no cost, to 255."
      ::= { appnLocalEnTgEntry 10 }
appnLocalEnTgByteCost OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Relative cost of transmitting a byte over this link.
          Range is from 0, which means no cost, to 255."
      ::= { appnLocalEnTgEntry 11 }
appnLocalEnTgSecurity OBJECT-TYPE
      SYNTAX AppnTgSecurity
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Administratively assigned security level of this TG."
      ::= { appnLocalEnTgEntry 12 }
appnLocalEnTgDelay OBJECT-TYPE
      SYNTAX AppnTgDelay
      MAX-ACCESS read-only
      STATUS current
```

```
DESCRIPTION
             "Administratively assigned delay associated with this TG."
      ::= { appnLocalEnTgEntry 13 }
appnLocalEnTqUsr1 OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "First user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG.
      ::= { appnLocalEnTgEntry 14 }
appnLocalEnTgUsr2 OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           'Second user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG.
      ::= { appnLocalEnTgEntry 15 }
appnLocalEnTgUsr3 OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Third user-defined TG characteristic for this TG. This is
          an administratively assigned value associated with the TG.
      ::= { appnLocalEnTgEntry 16 }
appnLocalEnTgMltgLinkType OBJECT-TYPE
      SYNTAX TruthValue
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "This object indicates whether the transmission group is a multi-link TG. A TG that has been brought up as a multi-link
          TG is reported as one, even if it currently has only one link
          active.
      ::= { appnLocalEnTgEntry 17 }
-- ******* The APPN Directory Group *******************
```

```
OBJECT IDENTIFIER ::= { appnObjects 4 }
appnDir
appnDirPerf OBJECT IDENTIFIER ::= { appnDir 1 }
-- The APPN Directory Group
-- The APPN Directory Database
-- Each APPN network node and branch network node maintains directories
-- containing information on which LUs (applications) are available and -- where they are located. LUs can be located in an APPN network node, -- in any of its attached end nodes or branch network nodes, or in any
-- of the nodes below one of its attached branch network nodes.
appnDirMaxCaches OBJECT-TYPE
       SYNTAX Unsigned32
UNITS "directory entries"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Maximum number of cache entries allowed. This is an administratively assigned value."
       ::= { appnDirPerf 1 }
appnDirCurCaches OBJECT-TYPE
       SYNTAX Gauge32
       UNITS "directory entries"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
             "Current number of cache entries."
       ::= { appnDirPerf 2 }
appnDirCurHomeEntries OBJECT-TYPE
       SYNTAX Gauge32
UNITS "directory entries"
       MAX-ACCESS read-only
       STATUS current
       DESCRIPTION
            "Current number of home entries."
       ::= { appnDirPerf 3 }
appnDirRegEntries OBJECT-TYPE
       SYNTAX Gauge32
       UNITS "directory entries"
       MAX-ACCESS read-only
```

```
STATUS current
      DESCRIPTION
          "Current number of registered entries."
      ::= { appnDirPerf 4 }
appnDirInLocates OBJECT-TYPE
      SYNTAX AppnNodeCounter UNITS "Locate messages"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of directed Locates received since the node was last
          reinitialized."
      ::= { appnDirPerf 5 }
appnDirInBcastLocates OBJECT-TYPE
      SYNTAX AppnNodeCounter
      UNITS "Locate messages"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of broadcast Locates received since the node was last
          reinitialized."
      ::= { appnDirPerf 6 }
appnDirOutLocates OBJECT-TYPE
      SYNTAX AppnNodeCounter
      UNITS "Locate messages"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of directed Locates sent since the node was last
          reinitialized."
      ::= { appnDirPerf 7 }
appnDirOutBcastLocates OBJECT-TYPE
      SYNTAX AppnNodeCounter
      UNITS "Locate messages"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of broadcast Locates sent since the node was last
          reinitialized."
```

```
::= { appnDirPerf 8 }
appnDirNotFoundLocates OBJECT-TYPE
      SYNTAX AppnNodeCounter
      UNITS "Locate messages"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Number of directed Locates returned with a 'not found' since
           the node was last reinitialized.'
      ::= { appnDirPerf 9 }
appnDirNotFoundBcastLocates OBJECT-TYPE
      SYNTAX AppnNodeCounter UNITS "Locate messages"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Number of broadcast Locates returned with a 'not found' since
           the node was last reinitialized."
      ::= { appnDirPerf 10 }
appnDirLocateOutstands OBJECT-TYPE
      SYNTAX Gauge32
      UNITS "Locate messages"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Current number of outstanding Locates, both directed and
           broadcast. This value varies. A value of zero indicates that no Locates are unanswered."
      ::= { appnDirPerf 11 }
--APPN Directory table
-- This table contains information about all known LUs.
appnDirTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnDirEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "Table containing information about all known LUs."
```

```
::= { appnDir 2 }
appnDirEntry OBJECT-TYPE
      SYNTAX AppnDirEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "This table is indexed by the LU name."
      INDEX
             {appnDirLuName}
      ::= { appnDirTable 1 }
AppnDirEntry ::= SEQUENCE {
      appnDirLuName
                                        DisplayString,
                                        SnaControlPointName,
      appnDirNnServerName
      appnDirLuOwnerName
                                        SnaControlPointName,
      appnDirLuLocation
                                        INTEGER,
      appnDirType
                                        INTEGER.
      appnDirApparentLuOwnerName
                                        DisplayString
appnDirLuName OBJECT-TYPE
      SYNTAX DisplayString (SIZE (1..17))
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Fully qualified network LU name in the domain of the
           serving network node. Entries take one of three forms:

    Explicit entries do not contain the character '*'.

              - Partial wildcard entries have the form 'ccc*', where
                'ccc' represents one to sixteen characters in a legal SNA LuName.
              - A full wildcard entry consists of the single character '*'"
      ::= { appnDirEntry 1 }
appnDirNnServerName OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Fully qualified control point (CP) name of the network node
          server. For unassociated end node entries, a zero-length
          string is returned."
```

```
::= { appnDirEntry 2 }
appnDirLuOwnerName OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Fully qualified CP name of the node at which the LU is
           located. This name is the same as the serving NN name when
           the LU is located at a network node. It is also the same as the fully qualified LU name when this is the control point
           LU for this node."
      ::= { appnDirEntry 3 }
appnDirLuLocation OBJECT-TYPE
      SYNTAX INTEGER {
                       local(1),
                                      --Local
                                    --Local
--Domain
--Cross I
                       domain(2),
                       xdomain(3)
                                       --Cross Domain
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Specifies the location of the LU with respect to the local
           node."
      ::= { appnDirEntry 4 }
appnDirType OBJECT-TYPE
      SYNTAX INTEGER {
                       home(1), --defined as home entry cache(2), --learned over time
                       registered(3) --registered by end node
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Directory types are:
             1 - Home
                    The LU is in the domain of the local node, and the LU
                    information has been configured at the local node.
             2 - Cache
                    The LU has previously been located by a broadcast
                    search, and the location information has been saved.
```

3 - Registered

The LU is at an end node that is in the domain of the local network node. Registered entries are registered by the served end node."

::= { appnDirEntry 5 }

appnDirApparentLuOwnerName OBJECT-TYPE
 SYNTAX DisplayString (SIZE (0 | 3..17))
 MAX-ACCESS read-only
 STATUS current
 DESCRIPTION

"Fully qualified CP name of the node at which the LU appears to be located. This object and the appnDirLuOwnerName object are related as follows:

Implementations that support this object save in their directory database information about an LU's owning control point that was communicated in two control vectors:

- an Associated Resource Entry (X'3C') CV with resource type X'00F4' (ENCP)
- a Real Owning Control Point (X'4A') CV.

The X'4A' CV is created by a branch network node to preserve the name of the real owning control point for an LU below the branch network node, before it overwrites this name with its own name in the X'3C' CV. The X'4A' CV is not present for LUs that are not below branch network nodes.

If the information a node has about an LU's owning CP came only in a X'3C' CV, then the name from the X'3C' is returned in the appnDirLuOwnerName object, and a null string is returned in this object.

If the information a node has about an LU's owning CP came in both X'3C' and X'4A' CVs, then the name from the X'4A' is returned in the appnDirLuOwnerName object, and the name from the X'3C' (which will be the branch network node's name) is returned in this object."

::= { appnDirEntry 6 }

-- ******** The APPN Class of Service Group **************

Clouston & Moore

Standards Track

[Page 88]

```
-- The APPN Class of Service (COS)
-- Class of Service is a means of expressing the quality of routes and -- the transmission priority of traffic that flows on these routes.
appnCosModeTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnCosModeEntry
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
          "Table representing all of the defined mode names for this
          node. The table contains the matching COS name for each
          mode name."
      ::= { appnCos 1 }
appnCosModeEntry OBJECT-TYPE
      SYNTAX AppnCosModeEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "This table is indexed by the mode name."
      INDEX
             {appnCosModeName}
      ::= { appnCosModeTable 1 }
AppnCosModeEntry ::= SEQUENCE {
      appnCosModeName
                          SnaModeName.
      appnCosModeCosName SnaClassOfServiceName
appnCosModeName OBJECT-TYPE
      SYNTAX SnaModeName
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Administratively assigned name for this mode."
      ::= { appnCosModeEntry 1 }
appnCosModeCosName OBJECT-TYPE
```

```
SYNTAX SnaClassOfServiceName
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
          "Administratively assigned name for this class of service."
      ::= { appnCosModeEntry 2 }
appnCosNameTable OBJECT-TYPE
     SYNTAX SEQUENCE OF AppnCosNameEntry
     MAX-ACCESS not-accessible
     STATUS current DESCRIPTION
          "Table mapping all of the defined class-of-service names for
         this node to their network transmission priorities.
      ::= { appnCos 2 }
appnCosNameEntry OBJECT-TYPE
     SYNTAX AppnCosNameEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
          "The COS name is the index to this table."
     INDEX
            {appnCosName}
      ::= { appnCosNameTable 1 }
AppnCosNameEntry ::= SEQUENCE {
     appnCosName
                            SnaClassOfServiceName.
     appnCosTransPriority
                            INTEGER
appnCosName OBJECT-TYPE
     SYNTAX SnaClassOfServiceName
     MAX-ACCESS not-accessible
     STATUS current DESCRIPTION
          "Administratively assigned name for this class of service."
      ::= { appnCosNameEntry 1 }
appnCosTransPriority OBJECT-TYPE
```

```
SYNTAX INTEGER {
                     ľow(1),
                                           --X'01'
                                           --X'02'
                     medium(2),
                                           --X'03'
                     high(3),
                                           --X'04'
                     network(4)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Transmission priority for this class of service:
                         - (X'01'):
                                     low priority
              low(1)
              medium(2) - (X'02'):
high(3) - (X'03'):
network(4) - (X'04'):
                                     medium priority
                                     high priority
                                     network priority"
      ::= { appnCosNameEntry 2 }
appnCosNodeRowTable OBJECT-TYPE
      SYNTAX SEQUENCE OF AppnCosNodeRowEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "This table contains all node-row information for all classes
          of service defined in this node."
      ::= { appnCos 3 }
appnCosNodeRowEntry OBJECT-TYPE
      SYNTAX AppnCosNodeRowEntry
      MAX-ACCESS not-accessible
      STATUS current DESCRIPTION
          "A node entry for a given class of service."
      INDEX
             {appnCosNodeRowName,
              appnCosNodeRowIndex}
      ::= { appnCosNodeRowTable 1 }
AppnCosNodeRowEntry ::= SEQUENCE {
      appnCosNodeRowName
                                         SnaClassOfServiceName,
      appnCosNodeRowIndex
                                         INTEGER,
                                         DisplayString,
      appnCosNodeRowWgt
      appnCosNodeRowResistMin
                                         INTEGER,
```

```
appnCosNodeRowResistMax
                                             INTEGER,
      appnCosNodeRowMinCongestAllow
                                             INTEGER,
                                             INTEGER
      appnCosNodeRowMaxCongestAllow
appnCosNodeRowName OBJECT-TYPE
      SYNTAX SnaClassOfServiceName MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "Administratively assigned name for this class of service."
      ::= { appnCosNodeRowEntry 1 }
appnCosNodeRowIndex OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "Subindex under appnCosNodeRowName, corresponding to a row in
          the node table for the class of service identified in
          appnCosNodeRowName.
          For each class of service, this subindex orders rows in the appnCosNodeRowTable in the same order as that used for route
          calculation in the APPN node."
      ::= { appnCosNodeRowEntry 2 }
appnCosNodeRowWgt OBJECT-TYPE
      SYNTAX DisplayString (SIZE (1..64))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Weight to be associated with the nodes that fit the criteria
          specified by this node row.
          This value can either be a character representation of an
          integer, or a formula for calculating the weight.'
      ::= { appnCosNodeRowEntry 3 }
appnCosNodeRowResistMin OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Minimum route addition resistance value for this node.
```

Range of values is 0-255. The lower the value, the more desirable the node is for intermediate routing."

::= { appnCosNodeRowEntry 4 }

appnCosNodeRowResistMax OBJECT-TYPE SYNTAX INTEGER (0..255) MAX-ACCESS read-only STATUS current DESCRIPTION

> "Maximum route addition resistance value for this node. Range of values is 0-255. The lower the value, the more desirable the node is for intermediate routing."

::= { appnCosNodeRowEntry 5 }

appnCosNodeRowMinCongestAllow OBJECT-TYPE

SYNTAX INTEGER (0..1)
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"Indicates whether low congestion will be tolerated. This object and appnCosNodeRowMaxCongestAllow together delineate a range of acceptable congestion states for a node. For the ordered pair (minimum congestion allowed, maximum congestion allowed), the values are interpreted as follows:

- (0,0): only low congestion is acceptable

- (0,1): either low or high congestion is acceptable

- (1,1): only high congestion is acceptable.

Note that the combination (1,0) is not defined, since it would identify a range whose lower bound was high congestion and whose upper bound was low congestion."

::= { appnCosNodeRowEntry 6 }

MAX-ACCESS read-only

STATUS current DESCRIPTION

"Indicates whether low congestion will be tolerated. This object and appnCosNodeRowMinCongestAllow together delineate a range of acceptable congestion states for a node. For the ordered pair (minimum congestion allowed, maximum congestion allowed), the values are interpreted as follows:

```
-(0,0):
                    only low congestion is acceptable
                    either low or high congestion is acceptable
          -(0,1):
          - (1,1):
                    only high congestion is acceptable.
         Note that the combination (1,0) is not defined, since it
         would identify a range whose lower bound was high congestion
         and whose upper bound was low congestion."
      ::= { appnCosNodeRowEntry 7 }
appnCosTgRowTable OBJECT-TYPE
     SYNTAX SEQUENCE OF AppnCosTgRowEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
          "Table containing all the TG-row information for all classes of
         service defined in this node."
      ::= { appnCos 4 }
appnCosTgRowEntry OBJECT-TYPE
     SYNTAX AppnCosTgRowEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
          "A TG entry for a given class of service."
     INDEX
            {appnCosTgRowName,
             appnCosTgRowIndex}
      ::= { appnCosTgRowTable 1 }
AppnCosTgRowEntry ::= SEQUENCE {
                                      SnaClassOfServiceName,
     appnCosTgRowName
     appnCosTgRowIndex
                                      INTEGER.
                                      DisplayString,
     appnCosTgRowWgt
     appnCosTgRowEffCapMin
                                      AppnTgEffectiveCapacity,
                                      AppnTgEffectiveCapacity,
     appnCosTgRowEffCapMax
                                      INTEGER,
     appnCosTgRowConnCostMin
                                      INTEGER,
     appnCosTgRowConnCostMax
     appnCosTqRowByteCostMin
                                      INTEGER,
     appnCosTgRowByteCostMax
                                      INTEGER,
     appnCosTgRowSecurityMin
                                      AppnTgSecurity,
     appnCosTgRowSecurityMax
                                      AppnTgSecurity,
     appnCosTgRowDelayMin
                                      AppnTgDelay,
```

```
appnCosTgRowDelayMax
                                           AppnTgDelay,
                                           INTEGĒR,
      appnCosTgRowUsr1Min
                                           INTEGER,
      appnCosTgRowUsr1Max
      appnCosTqRowUsr2Min
                                           INTEGER,
                                           INTEGER,
      appnCosTgRowUsr2Max
      appnCosTgRowUsr3Min
                                          INTEGER,
      appnCosTgRowUsr3Max
                                           INTEGER
appnCosTgRowName OBJECT-TYPE
      SYNTAX SnaClassOfServiceName
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
          "Administratively assigned name for this class of service."
      ::= { appnCosTqRowEntry 1 }
appnCosTgRowIndex OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
           "Subindex under appnCosTgRowName, corresponding to a row in the
          TG table for the class of service identified in
          appnCosTgRowName.
          For each class of service, this subindex orders rows in the appnCosTgRowTable in the same order as that used for route
          calculation in the APPN node.
      ::= { appnCosTgRowEntry 2 }
appnCosTqRowWqt OBJECT-TYPE
      SYNTAX DisplayString (SIZE (1..64))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Weight to be associated with the TGs that fit the criteria
          specified by this TG row.
          This value can either be a character representation of an
          integer, or a formula for calculating the weight."
      ::= { appnCosTqRowEntry 3 }
appnCosTgRowEffCapMin OBJECT-TYPE
      SYNTAX AppnTgEffectiveCapacity
```

```
MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Minimum acceptable capacity for this class of service."
      ::= { appnCosTgRowEntry 4 }
appnCosTgRowEffCapMax OBJECT-TYPE
      SYNTAX AppnTgEffectiveCapacity
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Maximum acceptable capacity for this class of service."
      ::= { appnCosTqRowEntry 5 }
appnCosTqRowConnCostMin OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Minimum acceptable cost per connect time for this class of
          service.
          Cost per connect time: a value representing the relative
          cost per unit of time to use this TG. Range is from 0, which
          means no cost, to 255."
      ::= { appnCosTgRowEntry 6 }
appnCosTgRowConnCostMax OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
     STATUS current DESCRIPTION
          "Maximum acceptable cost per connect time for this class of
          service.
          Cost per connect time: a value representing the relative
          cost per unit of time to use this TG. Range is from 0, which
          means no cost, to 255."
      ::= { appnCosTqRowEntry 7 }
appnCosTgRowByteCostMin OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
```

```
DESCRIPTION
           "Minimum acceptable cost per byte transmitted for this class
           of service.
           Cost per byte transmitted: a value representing the relative
           cost per unit of time to use this TG. Range is from 0, which means no cost, to 255."
       ::= { appnCosTqRowEntry 8 }
appnCosTgRowByteCostMax OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Maximum acceptable cost per byte transmitted for this class
           of service.
           Cost per byte transmitted: a value representing the relative cost of transmitting a byte over this TG. Range is from 0,
           which means no cost, to 255."
       ::= { appnCosTgRowEntry 9 }
appnCosTqRowSecuritvMin OBJECT-TYPE
      SYNTAX AppnTgSecurity
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
            'Minimum acceptable security for this class of service."
       ::= { appnCosTgRowEntry 10 }
appnCosTqRowSecurityMax OBJECT-TYPE
      SYNTAX AppnTgSecurity MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Maximum acceptable security for this class of service."
       ::= { appnCosTgRowEntry 11 }
appnCosTgRowDelayMin OBJECT-TYPE
       SYNTAX AppnTqDelay
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Minimum acceptable propagation delay for this class of
```

```
service."
      ::= { appnCosTgRowEntry 12 }
appnCosTqRowDelayMax OBJECT-TYPE
      SYNTAX AppnTgDelay
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Maximum acceptable propagation delay for this class of
          service."
      ::= { appnCosTgRowEntry 13 }
appnCosTgRowUsr1Min OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Minimum acceptable value for this user-defined
          characteristic.'
      ::= { appnCosTgRowEntry 14 }
appnCosTqRowUsr1Max OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
DESCRIPTION
           'Maximum acceptable value for this user-defined
          characteristic."
      ::= { appnCosTgRowEntry 15 }
appnCosTgRowUsr2Min OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Minimum acceptable value for this user-defined
          characteristic."
      ::= { appnCosTqRowEntry 16 }
appnCosTqRowUsr2Max OBJECT-TYPE
      SYNTAX INTEGER (0..255)
      MAX-ACCESS read-only
      STATUS current
```

```
DESCRIPTION
        "Maximum acceptable value for this user-defined
        characteristic.
     ::= { appnCosTqRowEntry 17 }
appnCosTgRowUsr3Min OBJECT-TYPE
    SYNTAX INTEGER (0..255)
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
        "Minimum acceptable value for this user-defined
        characteristic."
     ::= { appnCosTqRowEntry 18 }
appnCosTqRowUsr3Max OBJECT-TYPE
     SYNTAX INTEGER (0..255)
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
        "Maximum acceptable value for this user-defined
        characteristic."
     ::= { appnCosTgRowEntry 19 }
-- Intermediate Session Information
appnSessIntermediate OBJECT IDENTIFIER ::= { appnObjects 6 }
-- Intermediate Session Information Global Objects
__ *************************
-- The following simple objects allow the collection of intermediate -- session Information to be started and stopped.
__ ***********************************
appnIsInGlobal OBJECT IDENTIFIER ::= { appnSessIntermediate 1 }
appnIsInGlobeCtrAdminStatus OBJECT-TYPE
    SYNTAX INTEGER {
                  notActive(1),
                  active(2),
                  ready(3)
    MAX-ACCESS read-write
    STATUS current
    DESCRIPTION
```

"Object by which a Management Station can deactivate or activate capture of intermediate-session counts and names, by setting the value to notActive(1) or active(2), respectively. The value ready(3) is returned on GET operations until a SET has been processed; after that the value received on the most recent SET is returned.

The counts referred to here are the eight objects in the AppnIsInTable, from appnIsInP2SFmdPius through appnIsInS2PNonFmdBytes. The names are the four objects in this table, from appnIsInPriLuName through appnIsInCosName.

Setting this object to the following values has the following effects:

notActive(1) stop collecting count data. If a count is queried, it returns the value 0. Collection of names may, but need not be, disabled.

active(2) start collecting count data. If it is supported, collection of names is enabled."

::= { appnIsInGlobal 1 }

notActive(1),
active(2)

MAX-ACCESS read-only STATUS current DESCRIPTION

"Indicates whether or not the intermediate session counts are active. The counts referred to here are the eight objects in the AppnIsInTable, from appnIsInP2SFmdPius through appnIsInS2PNonFmdBytes. These eight counts are of type Unsigned32 rather than Counter32 because when this object enters the notActive state, either because a Management Station has set appnInInGlobeCtrAdminStatus to notActive or because of a locally-initiated transition, the counts are all reset to 0.

The values for this object are:

Clouston & Moore

Standards Track

```
::= { appnIsInGlobal 2 }
appnIsInGlobeCtrStatusTime OBJECT-TYPE
      SYNTAX TimeTicks
      UNITS "hundredths of a second"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          "The time since the appnIsInGlobeCtrOperStatus object last
          changed, measured in hundredths of a second. This time can be
          used to identify when this change occurred in relation to other
          events in the agent, such as the last time the APPN node was
          reinitialized."
      ::= { appnIsInGlobal 3 }
appnIsInGlobeRscv OBJECT-TYPE
      SYNTAX INTEGER {
                       notActive(1),
                       active(2)
      MAX-ACCESS read-write
      STATUS current
      DESCRIPTION
          "Indicates the current route selection control vector (RSCV)
          collection option in effect, and allows a Management Station to
          change the option.
          The values for this object are:
             notActive(1): collection of route selection control vectors
                            is not active.
             active(2):
                            collection of route selection control vectors
                            is active."
      ::= { appnIsInGlobal 4 }
appnIsInGlobeRscvTime OBJECT-TYPE
      SYNTAX TimeTicks
      UNITS "hundredths of a second"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
          "The time since the appnIsInGlobeRscv object last changed,
          measured in hundredths of a second. This time can be used to
          identify when this change occurred in relation to other events
          in the agent, such as the last time the APPN node was reinitialized."
```

```
::= { appnIsInGlobal 5 }
appnIsInGlobeActSess OBJECT-TYPE
     SYNTAX Gauge32
     UNITS "sessions"
     MAX-ACCESS read-only
     STATUS current DESCRIPTION
        "The number of currently active intermediate sessions."
     ::= { appnIsInGlobal 6 }
appnIsInGlobeHprBfActSess OBJECT-TYPE
    SYNTAX Gauge32 UNITS "sessions"
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
        "The number of currently active HPR intermediate sessions."
     ::= { appnIsInGlobal 7 }
-- Intermediate Session Information Table
-- This table contains information on intermediate sessions
appnIsInTable OBJECT-TYPE
     SYNTAX SEQUENCE OF AppnIsInEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
        "Intermediate Session Information Table"
     ::= { appnSessIntermediate 2 }
appnIsInEntry OBJECT-TYPE
     SYNTAX AppnIsInEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
        "Entry of Intermediate Session Information Table."
     INDEX
           { appnIsInFqCpName,
            appnIsInPcid }
```

```
::= { appnIsInTable 1 }
AppnIsInEntry ::= SEQUENCE {
      appnIsInFqCpName
                                   SnaControlPointName,
                                   OCTET STRING,
      appnIsInPcid
      appnIsInSessState
                                   INTEGER.
                                   DisplayString,
      appnIsInPriLuName
      appnIsInSecLuName
                                   DisplayString,
      appnIsInModeName
                                   SnaModeName,
                                   SnaClassOfServiceName,
      appnIsInCosName
      appnIsInTransPriority
                                   INTEGER,
                                   INTEGER.
      appnIsInSessType
      appnIsInSessUpTime
                                   TimeTicks,
      appnIsInCtrUpTime
                                   TimeTicks,
      appnIsInP2SFmdPius
                                   Unsigned32,
      appnIsInS2PFmdPius
                                   Unsigned32,
                                   Unsigned32,
      appnIsInP2SNonFmdPius
      appnIsInS2PNonFmdPius
                                   Unsigned32,
      appnIsInP2SFmdBytes
                                   Unsigned32,
      appnIsInS2PFmdBytes
                                   Unsigned32,
      appnIsInP2SNonFmdBvtes
                                   Unsigned32.
      appnIsInS2PNonFmdBytes
                                   Unsigned32,
                                   SnaControlPointName,
      appnIsInPsAdjCpName
      appnIsInPsAdjTgNum
                                   INTEGER,
      appnIsInPsSendMaxBtuSize
                                   INTEGER,
      appnIsInPsSendPacingType
                                   INTEGER,
                                   Gauge32,
      appnIsInPsSendRpc
      appnIsInPsSendNxWndwSize
                                   Gauge32,
      appnIsInPsRecvPacingType
                                   INTEGER,
      appnIsInPsRecvRpc
                                   Gauge32,
                                   Gauge32,
      appnIsInPsRecvNxWndwSize
      appnIsInSsAdjCpName
                                   SnaControlPointName,
      appnIsInSsAdjTgNum
                                   INTEGER,
      appnIsInSsSendMaxBtuSize
                                   INTEGER,
                                   INTEGER,
      appnIsInSsSendPacingType
      appnIsInSsSendRpc
                                   Gauge32,
      appnIsInSsSendNxWndwSize
                                   Gauge32,
      appnIsInSsRecvPacingType
                                   INTEGER,
      appnIsInSsRecvRpc
                                   Gauge32,
      appnIsInSsRecvNxWndwSize
                                   Gauge32,
      appnIsInRouteInfo
                                   OCTET STRING,
      appnIsInRtpNceId
                                   OCTET STRING,
```

```
OCTET STRING
       appnIsInRtpTcid
appnIsInFqCpName OBJECT-TYPE
       SYNTAX SnaControlPointName
       MAX-ACCESS not-accessible
       STATUS current DESCRIPTION
            "The network-qualified control point name of the node at which
            the session and PCID originated. For APPN and LEN nodes, this is either CP name of the APPN node at which the origin LU is
            located or the CP name of the NN serving the LEN node at which the origin LU is located. For resources served by a dependent LU requester (DLUR), it is the name of the owning system services control point (SSCP)."
       ::= { appnIsInEntry 1 }
appnIsInPcid OBJECT-TYPE
       SYNTAX OCTET STRING (SIZE (8))
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
             "The procedure correlation identifier (PCID) of a session.
                                                                                        Ιt
            is an 8-byte value assigned by the primary LU."
       ::= { appnIsInEntry 2 }
appnIsInSessState OBJECT-TYPE
       SYNTAX INTEGER
                               inactive(1).
                               pendactive(2),
                               active(3),
                               pendinact(4)
       MAX-ACCESS read-write
       STATUS current
       DESCRIPTION
             "Indicates the state of the session:
                 inactive(1) - session is inactive
                 pendactive(2) - session is pending active

    session is active

                 active(3)
                 pendinact(4) - session is pending inactive
            Active sessions can be deactivated by setting this object to inactive(1)."
```

```
::= { appnIsInEntry 3 }
appnIsInPriLuName OBJECT-TYPE
      SYNTAX DisplayString (SIZE (0..17))
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "The primary LU name of the session. A zero-length
          string indicates that this name is not available.
      ::= { appnIsInEntry 4 }
appnIsInSecLuName OBJECT-TYPE
      SYNTAX DisplayString (SIZE (0..17))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The secondary LU name of the session. A zero-length
          string indicates that this name is not available.'
      ::= { appnIsInEntry 5 }
appnIsInModeName OBJECT-TYPE
      SYNTAX SnaModeName
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The mode name used for this session."
      ::= { appnIsInEntry 6 }
appnIsInCosName OBJECT-TYPE
      SYNTAX SnaClassOfServiceName
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "The Class of Service (COS) name used for this session."
      ::= { appnIsInEntry 7 }
appnIsInTransPriority OBJECT-TYPE
      SYNTAX INTEGER {
                                             --X'01'
                      low(1),
                      medium(2),
                                             --X'02'
                      high(3),
network(4)
                                             --X'03'
                                             --X'04'
      MAX-ACCESS read-only
```

```
STATUS current
      DESCRIPTION
           "Transmission priority for this class of service. Values are:
                             - (X'01'):
                                           low priority
                low(1)
                medium(2) - (X'02'):
                                           medium priority
                high(3) - (X'03'):
network(4) - (X'04'):
                                           high priority network priority"
       ::= { appnIsInEntry 8 }
appnIsInSessType OBJECT-TYPE
      SYNTAX INTEGER {
                        unknown(1),
                        lu62(2),
                        luOthrú3(3),
                        lu62dlur(4),
                        lu0thru3dlur(5)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The type of intermediate session. Defined values are
                unknown
                               The session type is not known.
                lu62
                               A session between LUs of type 6.2
                               (as indicated by the LU type in Bind)
                lu0thru3
                               A session between LUs of type 0, 1, 2, or 3
                               (as indicated by the LU type in Bind)
                lu62dlur
                               A session between LUs of type 6.2
                               (as indicated by the LU type in Bind).
One of the LUs is a dependent LU supported
                               by the dependent LU requester (DLUR)
                               function at this node.
                luOthru3dlur A session between LUs of type 0, 1, 2, or 3
                               (as indicated by the LU type in Bind)
One of the LUs is a dependent LU supported
by the dependent LU requester (DLUR)
                               function at this node.
       ::= { appnIsInEntry 9 }
appnIsInSessUpTime OBJECT-TYPE
      SYNTAX TimeTicks
```

```
UNITS "hundredths of a second"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Length of time the session has been active, measured in
          hundredths of a second."
      ::= { appnIsInEntry 10 }
appnIsInCtrUpTime OBJECT-TYPE
      SYNTAX TimeTicks
      UNITS "hundredths of a second"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "Length of time the session counters have been active, measured
          in hundredths of a second.'
      ::= { appnIsInEntry 11 }
appnIsInP2SFmdPius OBJECT-TYPE
      SYNTAX Unsigned32 UNITS "path information units (PIUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Number of function management data (FMD) path information
          units (PIUs) sent from the Primary LU to the Secondary LU since
          the counts were last activated.
      ::= { appnIsInEntry 12 }
appnIsInS2PFmdPius OBJECT-TYPE
      SYNTAX Unsigned32 UNITS "path information units (PIUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "Number of FMD PIUs sent from the Secondary LU to the Primary
          LU since the counts were last activated."
      ::= { appnIsInEntry 13 }
appnIsInP2SNonFmdPius OBJECT-TYPE
      SYNTAX Unsigned32
      UNITS "path information units (PIUs)" MAX-ACCESS read-only
      STATUS current
```

```
DESCRIPTION
          "Number of non-FMD PIUs sent from the Primary LU to the
          Secondary LU since the counts were last activated.'
      ::= { appnIsInEntry 14 }
appnIsInS2PNonFmdPius OBJECT-TYPE
      SYNTAX Unsigned32
UNITS "path information units (PIUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of non-FMD PIUs sent from the Secondary LU to the
          Primary LU since the counts were last activated.'
      ::= { appnIsInEntry 15 }
appnIsInP2SFmdBytes OBJECT-TYPE
      SYNTAX Unsigned32
      UNITS "bytes"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of FMD bytes sent from the Primary LU to the Secondary
          LU since the counts were last activated.'
      ::= { appnIsInEntry 16 }
appnIsInS2PFmdBytes OBJECT-TYPE
      SYNTAX Unsigned32
      UNITS "bytes"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           'Number of FMD bytes sent from the Secondary LU to the Primary
          LU since the counts were last activated."
      ::= { appnIsInEntry 17 }
appnIsInP2SNonFmdBytes OBJECT-TYPE
      SYNTAX Unsigned32 UNITS "bytes"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "Number of non-FMD bytes sent from the Primary LU to the
          Secondary LU since the counts were last activated."
```

```
::= { appnIsInEntry 18 }
appnIsInS2PNonFmdBytes OBJECT-TYPE
      SYNTAX Unsigned32
      UNITS "bytes"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           'Number of non-FMD bytes sent from the Secondary LU to the
           Primary LU since the counts were last activated.
      ::= { appnIsInEntry 19 }
appnIsInPsAdjCpName OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The primary stage adjacent CP name of this session. If the
           session stage traverses an RTP connection, the CP name of the
           remote RTP endpoint is returned."
      ::= { appnIsInEntry 20 }
appnIsInPsAdiTaNum OBJECT-TYPE
      SYNTAX INTEGER (0..300)
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "The primary stage adjacent transmission group (TG) number
           associated with this session. If the session stage traverses
           an RTP connection, the value 256 is returned.
           Values between 257 and 300 are available for other possible TG 'stand-ins' that may be added to APPN in the future."
      ::= { appnIsInEntry 21 }
appnIsInPsSendMaxBtuSize OBJECT-TYPE
      SYNTAX INTEGER (99..32767)
      UNITS "bytes"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The primary stage maximum basic transmission unit (BTU) size
           for sending data."
      ::= { appnIsInEntry 22 }
```

```
appnIsInPsSendPacingType OBJECT-TYPE
      SYNTAX INTEGER
                       fixed(1),
                       adaptive(2)
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "The primary stage type of pacing being used for sending data."
      ::= { appnIsInEntry 23 }
appnIsInPsSendRpc OBJECT-TYPE
      SYNTAX Gauge32
UNITS "message units (MUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The primary stage send residual pace count. This represents
           the primary stage number of message units (MUs) that can still be sent in the current session window."
      ::= { appnIsInEntry 24 }
appnIsInPsSendNxWndwSize OBJECT-TYPE
      SYNTAX Gauge32
      UNITS "message units (MUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The primary stage size of the next window which will be used to send data."
      ::= { appnIsInEntry 25 }
appnIsInPsRecvPacingType OBJECT-TYPE
      SYNTAX INTEGER
                       fixed(1).
                       adaptive(2)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The primary stage type of pacing being used for receiving
      ::= { appnIsInEntry 26 }
```

```
appnIsInPsRecvRpc OBJECT-TYPE
      SYNTAX Gauge32
      UNITS "message units (MUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The primary stage receive residual pace count. This
           represents the primary stage number of message units (MUs) that can still be received in the current session window."
      ::= { appnIsInEntry 27 }
appnIsInPsRecvNxWndwSize OBJECT-TYPE
      SYNTAX Gauge32
UNITS "message units (MUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The primary stage size of the next window which will be used
           to receive data.
      ::= { appnIsInEntry 28 }
appnIsInSsAdiCpName OBJECT-TYPE
      SYNTAX SnaControlPointName
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The secondary stage adjacent CP name of this session. If the
           session stage traverses an RTP connection, the CP name of the
           remote RTP endpoint is returned."
      ::= { appnIsInEntry 29 }
appnIsInSsAdjTgNum OBJECT-TYPE
      SYNTAX INTEGER (0..300)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The secondary stage adjacent transmission group (TG) number
           associated with this session. If the session stage traverses an RTP connection, the value 256 is returned.
           Values between 257 and 300 are available for other possible
           TG 'stand-ins' that may be added to APPN in the future."
      ::= { appnIsInEntry 30 }
```

```
appnIsInSsSendMaxBtuSize OBJECT-TYPE
      SYNTAX INTEGER (99..32767) UNITS "bytes"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The secondary stage maximum basic transmission unit (BTU) size
           for sending data."
      ::= { appnIsInEntry 31 }
appnIsInSsSendPacingType OBJECT-TYPE
      SYNTAX INTEGER
                       fixed(1)
                       adaptive(2)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The secondary stage type of pacing being used for sending
           data."
      ::= { appnIsInEntry 32 }
appnIsInSsSendRpc OBJECT-TYPE
      SYNTAX Gauge32
      UNITS "message units (MUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
           "The secondary stage send residual pace count. This represents
           the secondary stage number of message units (MUs) that can still be sent in the current session window."
      ::= { appnIsInEntry 33 }
appnIsInSsSendNxWndwSize OBJECT-TYPE
      SYNTAX Gauge32
      UNITS "message units (MUs)"
      MAX-ACCESS read-only
      STATUS current DESCRIPTION
           "The secondary stage size of the next window which will be used
           to send data.
      ::= { appnIsInEntry 34 }
appnIsInSsRecvPacingType OBJECT-TYPE
```

```
SYNTAX INTEGER { fixed(1),
                      adaptive(2)
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The secondary stage type of pacing being used for receiving data."
      ::= { appnIsInEntry 35 }
appnIsInSsRecvRpc OBJECT-TYPE
      SYNTAX Gauge32
UNITS "message units (MUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The secondary stage receive residual pace count. This
          represents the secondary stage number of message units (MUs)
          that can still be received in the current session window.'
      ::= { appnIsInEntry 36 }
appnIsInSsRecvNxWndwSize OBJECT-TYPE
      SYNTAX Gauge32
      UNITS "message units (MUs)"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The secondary stage size of the next window which will be used
          to receive data."
      ::= { appnIsInEntry 37 }
appnIsInRouteInfo OBJECT-TYPE
      SYNTAX OCTET STRING (SIZE (0..255))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The route selection control vector (RSCV X'2B') used for this
          session. It is present for APPN nodes; but is not present for
          LEN nodes. The format of this vector is described in SNA
          Formats. If no RSCV is available, a zero-length string is returned."
      ::= { appnIsInEntry 38 }
```

```
appnIsInRtpNceId OBJECT-TYPE
     SYNTAX OCTET STRING (SIZE (1..8))
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
        "The HPR local Network Connection Endpoint of the session."
     ::= { appnIsInEntry 39 }
appnIsInRtpTcid OBJECT-TYPE
     SYNTÂX OCTET STRING (SIZE (8))
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
        "The RTP connection local TCID of the session."
     ::= { appnIsInEntry 40 }
-- *********************************
-- Intermediate Session RTP Table
This table contains information on intermediate sessions that are
-- being transported on Rapid Transport Protocol (RTP) connections by
appnIsRtpTable OBJECT-TYPE
     SYNTAX SEQUENCE OF AppnIsRtpEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
         "A table indicating how many ISR sessions are transported by
        each RTP connection."
     ::= { appnSessIntermediate 3 }
appnIsRtpEntry OBJECT-TYPE
     SYNTAX AppnIsRtpEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
        "Entry of Intermediate Session RTP Table."
     INDEX
           { appnIsRtpNceId,
             appnIsRtpTcid }
     ::= { appnIsRtpTable 1 }
```

```
AppnIsRtpEntry ::= SEQUENCE {
                              OCTET STRING, OCTET STRING,
     appnIsRtpNceId
     appnIsRtpTcid
     appnIsRtpSessions
                              Gauge32
appnIsRtpNceId OBJECT-TYPE
     SYNTAX OCTET STRING (SIZE (1..8))
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
         "The local Network Connection Endpoint of the RTP connection."
     ::= { appnIsRtpEntry 1 }
appnIsRtpTcid OBJECT-TYPE
     SYNTAX OCTET STRING (SIZE (8))
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
         "The local TCID of the RTP connection."
     ::= { appnIsRtpEntry 2 }
appnIsRtpSessions OBJECT-TYPE
     SYNTAX Gauge32
     UNITS "sessions"
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
         "The number of intermediate sessions using this RTP
         connection."
     ::= { appnIsRtpEntry 3 }
OBJECT IDENTIFIER ::= { appnMIB 2 }
 appnTraps
alertTrap NOTIFICATION-TYPE
     OBJECTS { alertIdNumber, affectedObject }
     STATUS current
     DESCRIPTION
         "This trap carries a 32-bit SNA Management Services (SNA/MS)
         Alert ID Number, as specified in SNA/MS Formats."
     ::= { appnTraps 1 }
```

```
alertIdNumber OBJECT-TYPE
     SYNTAX OCTET STRING (SIZE (4))
     MAX-ACCESS accessible-for-notify
     STATUS current
     DESCRIPTION
          "A 32-bit SNA Management Services (SNA/MS) Alert ID Number, as
         specified in SNA/MS Formats."
      ::= { appnTraps 2 }
affectedObiect OBJECT-TYPE
     SYNTAX VariablePointer
     MAX-ACCESS accessible-for-notify
     STATUS current DESCRIPTION
          "The MIB object associated with the Alert condition, if there
         is an object associated with it. If no associated object can
         be identified, the value 0.0 is passed in the trap."
      ::= { appnTraps 3 }
-- Conformance information
__ ***********************************
                     OBJECT IDENTIFIER ::= { appnMIB 3 }
appnConformance
                     OBJECT IDENTIFIER ::= { appnConformance 1 }
OBJECT IDENTIFIER ::= { appnConformance 2 }
appnCompliances
appnGroups
-- Compliance statements
-- appnCompliance MODULE-COMPLIANCE (deprecated: moved to end of module)
appnCompliance2 MODULE-COMPLIANCE
       STATUS current
       DESCRIPTION
            "The compliance statement for the SNMPv2 entities that
           implement the APPN MIB.
           In the descriptions for the conditionally mandatory groups that
           follow, the branch network node is treated as a third node type,
           parallel to network node and end node. This is not how branch
           network nodes are treated in the base APPN architecture, but it
           increases clarity here to do it."
       MODULE -- this module
       Unconditionally mandatory groups
```

```
MANDATORY-GROUPS {
        appnGeneralConfGroup2,
        appnPortConfGroup,
        appnLinkConfGroup2.
        appnLocalTgConfGroup2,
        appnDirTableConfGroup2
 }
```

Conditionally mandatory groups GROUP appnNnUniqueConfGroup

DESCRIPTION

"The appnNnUniqueConfGroup is mandatory for network nodes.

GROUP appnEnUniqueConfGroup DESCRIPTION

> "The appnEnUniqueConfGroup is mandatory for end nodes.

GROUP appnVrnConfGroup DESCRIPTION

"The appnVrnConfGroup is mandatory for network nodes, end nodes, and branch network nodes that implement virtual routing node support."

GROUP appnNnTopoConfGroup2 DESCRIPTION

> "The appnNnTopoConfGroup2 is mandatory for network nodes.'

GROUP appnLocalEnTopoConfGroup2 **DESCRIPTION**

"The appnLocalEnTopoConfGroup2 is mandatory for network nodes."

GROUP appnLocalDirPerfConfGroup DESCRIPTION

"The appnLocalDirPerfConfGroup is mandatory for APPN network nodes, end nodes, and branch network nodes."

GROUP appnCosConfGroup DESCRIPTION

"The appnCosConfGroup is mandatory for APPN network nodes, end nodes, and branch network nodes."

GROUP appnIntSessConfGroup

DESCRIPTION

Clouston & Moore

```
"The appnIntSessConfGroup is mandatory for
                     network nodes and branch network nodes.
                 GROUP appnHprBaseConfGroup
                 DESCRIPTION
                     "The appnHprBaseConfGroup is mandatory for nodes that implement the HPR base (APPN option set 1400)."
                 GROUP appnHprRtpConfGroup
                 DESCRIPTION
                     "The appnHprRtpConfGroup is mandatory for nodes
                     that implement the HPR RTP tower (APPN option set
                     1401)."
                 GROUP appnHprCtrlFlowsRtpConfGroup
                 DESCRIPTION
                     "The appnHprCtrlFlowsRtpConfGroup is mandatory for
                     nodes that implement the HPR Control Flows over
                     RTP tower (APPN option set 1402)."
                 GROUP appnHprBfConfGroup
                 DESCRIPTION
                     "The appnHprBfConfGroup is mandatory for nodes
                     that implement the APPN/HPR boundary function."
                 GROUP appnTrapConfGroup
                 DESCRIPTION
                     "Traps are optional for all nodes."
                 GROUP appnTrapNotifGroup
                 DESCRIPTION
                     "Traps are optional for all nodes."
                 GROUP appnBrNnConfGroup
                 DESCRIPTION
                     "The appnBrNnConfGroup is mandatory for branch
                     network nodes.
        ::= { appnCompliances 3 }
         -- { appnCompliances 2 } is used by the APPN-TRAP-MIB
-- Units of conformance
appnGeneralConfGroup2 OBJECT-GROUP
        OBJECTS
                  appnNodeCpName,
                  appnNodeId,
                  appnNodeType,
                  appnNodeUpTime,
```

Standards Track

[Page 118]

```
appnNodeParallelTg,
                 appnNodeAdaptiveBindPacing,
                 appnNodeHprSupport,
                 appnNodeCounterDisconTime,
                 appnNodeLsCounterType,
                 appnNodeBrNn
        STATUS current
        DESCRIPTION
            "A collection of objects providing the instrumentation of
            APPN general information and capabilities."
        ::= { appnGroups 26 }
         -- { appnGroups 21 - 25 } are used by the APPN-TRAP-MIB
appnPortConfGroup OBJECT-GROUP
        OBJECTS
                 appnPortCommand,
                 appnPortOperState,
                 appnPortDlcType,
                 appnPortPortType,
                 appnPortSIMRIM,
                 appnPortLsRole,
                 appnPortNegotLs.
                 appnPortDynamicLinkSupport,
                 appnPortMaxRcvBtuSize,
                 appnPortMaxIframeWindow,
                 appnPortDefLsGoodXids,
                 appnPortDefLsBadXids,
                 appnPortDynLsGoodXids,
                 appnPortDynLsBadXids,
                 appnPortSpecific,
                 appnPortDlcLocalAddr,
                 appnPortCounterDisconTime
        STATUS current
        DESCRIPTION
            "A collection of objects providing the instrumentation of
            APPN port information."
        ::= { appnGroups 2 }
appnLinkConfGroup2 OBJECT-GROUP
        OBJECTS
                 appnLsCommand,
                 appnLsOperState,
                 appnLsPortName,
                 appnLsDlcType,
                 appnLsDynamic,
```

```
appnLsAdjCpName,
appnLsAdjNodeType,
appnLsTgNum,
appnLsLimResource,
appnLsActOnDemand,
appnLsMigration,
appnLsPartnerNodeId,
appnLsCpCpSessionSupport,
appnLsMaxSendBtuSize,
appnLsInXidBytes,
appnLsInMsgBytes,
appnLsInXidFrames,
appnLsInMsgFrames,
appnLsOutXidBytes,
appnLsOutMsgBytes,
appnLsOutXidFrames,
appnLsOutMsqFrames,
appnLsEchoRsps,
appnLsCurrentDelay,
appnLsMaxDelay,
appnLsMinDelay,
appnLsMaxDelayTime,
appnLsGoodXids,
appnLsBadXids.
appnLsSpecific,
appnLsActiveTime,
appnLsCurrentStateTime,
appnLsHprSup,
appnLsLocalAddr,
appnLsRemoteAddr,
appnLsRemoteLsName,
appnLsStatusTime,
appnLsStatusLsName,
appnLsStatusCpName.
appnLsStatusPartnerId,
appnLsStatusTgNum,
appnLsStatusGeneralSense.
appnLsStatusRetry,
appnLsStatusEndSense
appnLsStatusXidLocalSense,
appnLsStatusXidRemoteSense,
appnLsStatusXidByteInError,
appnLsStatusXidBitInError,
appnLsStatusDlcType.
appnLsStatusLocalAddr,
appnLsStatusRemoteAddr,
appnLsCounterDisconTime,
appnLsMltgMember
```

```
}
        STATUS current
        DESCRIPTION
            "A collection of objects providing the instrumentation of
            APPN link information."
        ::= { appnGroups 27 }
appnLocalTgConfGroup2 OBJECT-GROUP
        OBJECTS
                 appnLocalTqDestVirtual,
                 appnLocalTgDlcData,
                 appnLocalTgPortName,
                 appnLocalTgQuiescing.
                 appnLocalTgOperational,
                 appnLocalTgCpCpSession,
                 appnLocalTgEffCap,
                 appnLocalTqConnCost,
                 appnLocalTgByteCost,
                 appnLocalTgSecurity,
                 appnLocalTqDelay,
                 appnLocalTgUsr1,
                 appnLocalTgUsr2,
                 appnLocalTgUsr3,
                 appnLocalTgHprSup,
                 appnLocalTgIntersubnet,
                 appnLocalTgMltgLinkType
        STATUS
              current
        DESCRIPTION
            "A collection of objects providing the instrumentation of
            APPN local TG information."
        ::= { appnGroups 28 }
appnDirTableConfGroup2 OBJECT-GROUP
        OBJECTS
                 appnDirNnServerName,
                 appnDirLuOwnerName,
                 appnDirLuLocation,
                 appnDirType,
                 appnDirApparentLuOwnerName
        STATUS current
        DESCRIPTION
            "A collection of objects providing the instrumentation of the
            APPN directory database.
        ::= \{ appnGroups 29 \}
appnNnUniqueConfGroup OBJECT-GROUP
```

```
OBJECTS
                   appnNodeNnCentralDirectory,
                   appnNodeNnTreeCache,
                   appnNodeNnRouteAddResist,
                   appnNodeNnIsr,
                   appnNodeNnFrsn
                   appnNodeNnPeriBorderSup.
                   appnNodeNnInterchangeSup,
                   appnNodeNnExteBorderSup,
                   appnNodeNnSafeStoreFreq,
                   appnNodeNnRsn,
                   appnNodeNnCongested,
                   appnNodeNnIsrDepleted,
                   appnNodeNnQuiescing,
                   appnNodeNnGateway
         STATUS current
         DESCRIPTION
             "A collection of objects providing instrumentation unique
             to APPN network nodes."
         ::= { appnGroups 6 }
appnEnUniqueConfGroup OBJECT-GROUP
         OBJECTS
                   appnNodeEnModeCosMap.
                   appnNodeEnNnServer,
                   appnNodeEnLuSearch
         STATUS current
         DESCRIPTION
             "A collection of objects providing instrumentation for APPN end nodes. Some of these objects also appear in the
             instrumentation for a branch network node."
         ::= { appnGroups 7 }
appnVrnConfGroup
                         OBJECT-GROUP
         OBJECTS
                   appnVrnPortName
         STATUS current
         DESCRIPTION
             "An object providing the instrumentation for virtual routing node support in an APPN node."
         ::= { appnGroups 8 }
appnNnTopoConfGroup2
                           OBJECT-GROUP
         OBJECTS
                   appnNnTopoMaxNodes,
```

```
appnNnTopoCurNumNodes,
         appnNnTopoNodePurges,
         appnNnTopoTgPurges,
         appnNnTopoTotalTduWars,
         appnNnNodeFREntryTimeLeft,
         appnNnNodeFRType,
         appnNnNodeFRRsn,
         appnNnNodeFRRouteAddResist,
         appnNnNodeFRCongested,
         appnNnNodeFRIsrDepleted,
         appnNnNodeFRQuiescing,
         appnNnNodeFRGateway
         appnNnNodeFRCentralDirectory,
         appnNnNodeFRIsr,
appnNnNodeFRGarbageCollect,
         appnNnNodeFRHprSupport,
         appnNnNodeFRPeriBorderSup,
         appnNnNodeFRInterchangeSup,
         appnNnNodeFRExteBorderSup,
         appnNnNodeFRBranchAwareness,
         appnNnTgFREntryTimeLeft,
         appnNnTgFRDestVirtual,
         appnNnTgFRDlcData,
         appnNnTqFRRsn.
         appnNnTgFROperational,
         appnNnTgFRQuiescing,
         appnNnTgFRCpCpSession,
         appnNnTgFREffCap,
         appnNnTgFRConnCost,
         appnNnTgFRByteCost,
         appnNnTgFRSecurity,
         appnNnTgFRDelay,
         appnNnTgFRUsr1,
         appnNnTqFRUsr2.
         appnNnTgFRUsr3,
         appnNnTgFRGarbageCollect,
         appnNnTgFRSubareaNum,
         appnNnTgFRHprSup,
         appnNnTgFRDestHprTrans,
         appnNnTgFRTypeIndicator,
         appnNnTgFRIntersubnet,
         appnNnTgFRMltgLinkType,
         appnNnTgFRBranchTg
STATUS current
DESCRIPTION
    "The appnNnTopoConfGroup is mandatory only for network
    nodes.
```

```
::= { appnGroups 30 }
appnLocalEnTopoConfGroup2
                            OBJECT-GROUP
        OBJECTS
                 appnLocalEnTgEntryTimeLeft,
                 appnLocalEnTgDestVirtual,
                 appnLocalEnTgDlcData,
                 appnLocalEnTgOperational,
                 appnLocalEnTgCpCpSession,
                 appnLocalEnTgEffCap,
                 appnLocalEnTgConnCost,
                 appnLocalEnTgByteCost,
                 appnLocalEnTgSecurity,
                 appnLocalEnTgDelay,
                 appnLocalEnTgUsr1,
                 appnLocalEnTgUsr2,
                 appnLocalEnTqUsr3,
                 appnLocalEnTgMltgLinkType
        STATUS current
        DESCRIPTION
            "A collection of objects providing the instrumentation
            of the information that a network node possesses about
            the end nodes directly attached to it.
        ::= { appnGroups 31 }
appnLocalDirPerfConfGroup OBJECT-GROUP
        OBJECTS
                 appnDirMaxCaches,
                 appnDirCurCaches,
                 appnDirCurHomeEntries,
                 appnDirRegEntries,
                 appnDirInLocates,
                 appnDirInBcastLocates.
                 appnDirOutLocates,
                 appnDirOutBcastLocates,
                 appnDirNotFoundLocates,
                 appnDirNotFoundBcastLocates.
                 appnDirLocateOutstands
        STATUS current
        DESCRIPTION
            "The appnLocalDirPerfConfGroup is mandatory only for APPN
            network nodes and end nodes.'
        ::= { appnGroups 11 }
appnCosConfGroup
                          OBJECT-GROUP
        OBJECTS {
```

```
appnCosModeCosName,
                  appnCosTransPriority,
                  appnCosNodeRowWgt,
                  appnCosNodeRowResistMin,
                  appnCosNodeRowResistMax,
                  appnCosNodeRowMinCongestAllow,
                  appnCosNodeRowMaxCongestAllow,
                  appnCosTgRowWgt,
appnCosTgRowEffCapMin,
                  appnCosTgRowEffCapMax,
                  appnCosTgRowConnCostMin,
                  appnCosTgRowConnCostMax,
                  appnCosTgRowByteCostMin,
                  appnCosTgRowByteCostMax,
                  appnCosTgRowSecurityMin,
                  appnCosTgRowSecurityMax,
                  appnCosTqRowDelayMin,
                  appnCosTgRowDelayMax,
                  appnCosTgRowUsr1Min,
                  appnCosTgRowUsr1Max,
                  appnCosTgRowUsr2Min,
                  appnCosTgRowUsr2Max,
                  appnCosTgRowUsr3Min,
                  appnCosTgRowUsr3Max
        STATUS
               current
        DESCRIPTION
             "The appnCosConfGroup is mandatory only for APPN network
            nodes and end nodes.
        ::= { appnGroups 12 }
appnIntSessConfGroup
                         OBJECT-GROUP
        OBJECTS
                  appnIsInGlobeCtrAdminStatus.
                  appnIsInGlobeCtrOperStatus,
                  appnIsInGlobeCtrStatusTime,
                  appnIsInGlobeRscv,
                  appnIsInGlobeRscvTime,
                  appnIsInGlobeActSess,
                  appnIsInSessState,
                  appnIsInPriLuName,
                  appnIsInSecLuName,
                  appnIsInModeName,
                  appnIsInCosName,
                  appnIsInTransPriority,
                  appnIsInSessType,
                  appnIsInSessUpTime,
                  appnIsInCtrUpTime,
```

```
appnIsInP2SFmdPius,
                 appnIsInS2PFmdPius,
                 appnIsInP2SNonFmdPius,
                 appnIsInS2PNonFmdPius,
                 appnIsInP2SFmdBytes,
                 appnIsInS2PFmdBytes
                 appnIsInP2SNonFmdBytes,
                 appnIsInS2PNonFmdBytes,
                 appnIsInPsAdjCpName,
                 appnIsInPsAdjTgNum,
                 appnIsInPsSendMaxBtuSize.
                 appnIsInPsSendPacingType,
                 appnIsInPsSendRpc,
                 appnIsInPsSendNxWndwSize,
                 appnIsInPsRecvPacingType,
                 appnIsInPsRecvRpc,
                 appnIsInPsRecvNxWndwSize,
                 appnIsInSsAdjCpName,
                 appnIsInSsAdjTgNum,
                 appnIsInSsSendMaxBtuSize,
                 appnIsInSsSendPacingType,
                 appnIsInSsSendRpc,
                 appnIsInSsSendNxWndwSize,
                 appnIsInSsRecvPacingTvpe.
                 appnIsInSsRecvRpc,
                 appnIsInSsRecvNxWndwSize,
                 appnIsInRouteInfo
        STATUS current
        DESCRIPTION
            "The appnIntSessConfGroup is mandatory only for network
            nodes.
        ::= { appnGroups 13 }
appnHprBaseConfGroup
                        OBJECT-GROUP
        OBJECTS
                 appnNodeHprIntRteSetups,
                 appnNodeHprIntRteRejects,
                 appnLsErrRecoSup,
                 appnLsForAnrLabel,
                 appnLsRevAnrLabel
        STATUS current
        DESCRIPTION
            "The appnHprBaseConfGroup is mandatory only for nodes that
            implement the HPR base (APPN option set 1400)."
        ::= \{ appnGroups 14 \}
```

```
appnHprRtpConfGroup
                       OBJECT-GROUP
        OBJECTS
                 appnNodeMaxSessPerRtpConn,
                 appnNodeHprOrgRteSetups.
                 appnNodeHprOrgRteRejects,
                 appnNodeHprEndRteSetups,
                 appnNodeHprEndRteRejects,
                 appnLsBfNceId
        STATUS current
        DESCRIPTION
            "The appnHprRtpConfGroup is mandatory only for nodes that
            implement the HPR RTP tower (APPN option set 1401)."
        ::= { appnGroups 15 }
appnHprCtrlFlowsRtpConfGroup
                                OBJECT-GROUP
        OBJECTS
                 appnLsCpCpNceId,
                 appnLsRouteNceId
        STATUS current
        DESCRIPTION
            "The appnHprCtrlFlowsRtpConfGroup is mandatory only for nodes
            that implement the HPR Control Flows over RTP tower (APPN
            option set 1402)."
        ::= \{ appnGroups 16 \}
appnHprBfConfGroup
                      OBJECT-GROUP
        OBJECTS
                 appnIsInGlobeHprBfActSess,
                 appnIsInRtpNceId,
                 appnIsInRtpTcid,
                 appnIsRtpSessions
        STATUS current
        DESCRIPTION
            "The appnHprBfConfGroup is mandatory only for nodes that
            implement the APPN/HPR boundary function.
        ::= { appnGroups 17 }
appnTrapConfGroup
                     OBJECT-GROUP
        OBJECTS
                 alertIdNumber,
                 affectedObject
        STATUS current
        DESCRIPTION
            "The appnTrapConfGroup is optional for all APPN nodes.
                                                                      Nodes
```

```
implementing this group shall also implement the
           appnTrapNotifGroup.'
       ::= { appnGroups 18 }
appnTrapNotifGroup
                    NOTIFICATION-GROUP
       NOTIFICATIONS {
                    alertTrap
       STATUS current
       DESCRIPTION
           "The appnTrapNotifGroup is optional for all APPN nodes.
           Nodes implementing this group shall also implement the
           appnTrapConfGroup.
       ::= { appnGroups 19 }
appnBrNnConfGroup
                   OBJECT-GROUP
       OBJECTS
               appnNodeEnNnServer,
               appnNodeEnLuSearch,
               appnLocalTgBranchLinkType
       STATUS current
       DESCRIPTION
           "A collection of objects providing instrumentation for
           branch network nodes. Some of these objects also appear
           in the instrumentation for an end node.
           Note: A branch network node always returns endNode(2)
           as the value of the appnNodeType object from the
           appnGeneralConfGroup2 conformance group.
       ::= { appnGroups 20 }
-- ****************************
  Deprecated definitions
appnNodeMibVersion OBJECT-TYPE
     SYNTAX DisplayString (SIZE (11))
     MAX-ACCESS read-only
     STATUS deprecated DESCRIPTION
         "The value of LAST-UPDATED from this module's MODULE-IDENTITY
         macro. This object gives a Management Station an easy way of
         determining the level of the MIB supported by an agent.
         Since this object incorporates the Year 2000-unfriendly
         2-digit year specified in SMI for the LAST-UPDATED field, and
```

```
since it was not found to be particularly useful, it has been
           deprecated. No replacement object has been defined.
       ::= { appnGeneralInfoAndCaps 2 }
appnCompliance
                  MODULE-COMPLIANCE
         STATUS deprecated
         DESCRIPTION
              "The compliance statement for the SNMPv2 entities that
             implement the APPN MIB.
             This is the compliance statement for the RFC 2155-level version
             of the APPN MIB. It was deprecated as new objects were added to the MIB for MLTG, branch network node, and other extensions
             to the APPN architecture.
         MODULE -- this module
        Unconditionally mandatory groups
                  MANDATORY-GROUPS
                           appnGeneralConfGroup,
                           appnPortConfGroup,
                           appnLinkConfGroup,
                           appnLocalTgConfGroup,
                           appnDirTableConfGroup
                   }
        Conditionally mandatory groups
GROUP appnNnUniqueConfGroup
                  DESCRIPTION
                       "The appnNnUniqueConfGroup is mandatory only for
                       network nodes.
                  GROUP appnEnUniqueConfGroup
                  DESCRIPTION
                       "The appnEnUniqueConfGroup is mandatory only for end
                      nodes.
                  GROUP appnVrnConfGroup
                  DESCRIPTION
                      "The appnVrnConfGroup is mandatory only for network nodes and end nodes that implement virtual routing
                      node support."
                  GROUP appnNnTopoConfGroup
                  DESCRIPTION
                       "The appnNnTopoConfGroup is mandatory only for
```

network nodes."

GROUP appnLocalEnTopoConfGroup DESCRIPTION

"The appnLocalEnTopoConfGroup is mandatory only for network nodes."

GROUP appnLocalDirPerfConfGroup DESCRIPTION

"The appnLocalDirPerfConfGroup is mandatory only for APPN network nodes and end nodes."

GROUP appnCosConfGroup DESCRIPTION

"The appnCosConfGroup is mandatory only for APPN network nodes and end nodes."

GROUP appnIntSessConfGroup DESCRIPTION

"The appnIntSessConfGroup is mandatory only for network nodes."

GROUP appnHprBaseConfGroup DESCRIPTION

"The appnHprBaseConfGroup is mandatory only for nodes that implement the HPR base (APPN option set 1400)."

GROUP appnHprRtpConfGroup DESCRIPTION

"The appnHprRtpConfGroup is mandatory only for nodes that implement the HPR RTP tower (APPN option set 1401)."

GROUP appnHprCtrlFlowsRtpConfGroup
DESCRIPTION

"The appnHprCtrlFlowsRtpConfGroup is mandatory only for nodes that implement the HPR Control Flows over RTP tower (APPN option set 1402)."

GROUP appnHprBfConfGroup DESCRIPTION

"The appnHprBfConfGroup is mandatory only for nodes that implement the APPN/HPR boundary function."

GROUP appnTrapConfGroup DESCRIPTION

"Traps are optional for all nodes."

GROUP appnTrapNotifGroup DESCRIPTION

"Traps are optional for all nodes."

```
::= { appnCompliances 1 }
appnGeneralConfGroup OBJECT-GROUP
        OBJECTS
                 appnNodeCpName,
                 appnNodeMibVersion,
                 appnNodeId,
                 appnNodeType,
                 appnNodeUpTime,
                 appnNodeParallelTg,
                 appnNodeAdaptiveBindPacing,
                 appnNodeHprSupport,
                 appnNodeCounterDisconTime
               deprecated
        STATUS
        DESCRIPTION
            "A collection of objects providing the instrumentation of
            APPN general information and capabilities.
            This RFC 2155-level group was deprecated when the
            appnNodeMibVersion object was removed and the
            appnNodeLsCounterType and appnNodeBrNn objects were added."
        ::= { appnGroups 1 }
appnLinkConfGroup OBJECT-GROUP
        OBJECTS
                 appnLsCommand,
                 appnLsOperState,
                 appnLsPortName,
                 appnLsDlcType,
                 appnLsDynamic,
                 appnLsAdjCpName,
                 appnLsAdjNodeType,
                 appnLsTgNum,
                 appnLsLimResource,
                 appnLsActOnDemand,
                 appnLsMigration,
                 appnLsPartnerNodeId,
                 appnLsCpCpSessionSupport,
                 appnLsMaxSendBtuSize,
                 appnLsInXidBytes,
                 appnLsInMsgBytes,
                 appnLsInXidFrames,
                 appnLsInMsqFrames,
                 appnLsOutXidBytes,
                 appnLsOutMsgBytes,
                 appnLsOutXidFrames,
                 appnLsOutMsgFrames,
```

```
appnLsEchoRsps,
                 appnLsCurrentDelay,
                 appnLsMaxDelay,
                 appnLsMinDelay,
                 appnLsMaxDelayTime.
                 appnLsGoodXids,
                 appnLsBadXids,
                 appnLsSpecific,
                 appnLsActiveTime,
                 appnLsCurrentStateTime,
                 appnLsHprSup,
                 appnLsLocalAddr,
                 appnLsRemoteAddr.
                 appnLsRemoteLsName,
                 appnLsStatusTime,
                 appnLsStatusLsName,
                 appnLsStatusCpName,
                 appnLsStatusPartnerId.
                 appnLsStatusTgNum,
                 appnLsStatusGeneralSense,
                 appnLsStatusRetry,
                 appnLsStatusEndSense,
                 appnLsStatusXidLocalSense,
                 appnLsStatusXidRemoteSense,
                 appnLsStatusXidByteInError,
                 appnLsStatusXidBitInError,
                 appnLsStatusDlcType,
                 appnLsStatusLocalAddr,
                 appnLsStatusRemoteAddr,
                 appnLsCounterDisconTime
        STATUS deprecated
        DESCRIPTION
            "A collection of objects providing the instrumentation of
            APPN link information.
            This RFC 2155-level group was deprecated when the
            appnLsMltgMember object was added."
        ::= { appnGroups 3 }
appnLocalTgConfGroup OBJECT-GROUP
        OBJECTS
                 appnLocalTqDestVirtual,
                 appnLocalTqDlcData,
                 appnLocalTgPortName,
                 appnLocalTgQuiescing,
                 appnLocalTgOperational,
```

```
appnLocalTgCpCpSession,
                 appnLocalTgEffCap,
                 appnLocalTgConnCost,
                 appnLocalTgByteCost,
                 appnLocalTgSecurity,
                 appnLocalTqDelay,
                 appnLocalTgUsr1,
                 appnLocalTgUsr2,
                 appnLocalTgUsr3,
                 appnLocalTgHprSup,
                 appnLocalTgIntersubnet
               deprecated
        STATUS
        DESCRIPTION
            "A collection of objects providing the instrumentation of
            APPN local TG information.
            This RFC 2155-level group was deprecated when the
            appnLocalTgMltgLinkType object was added."
        ::= { appnGroups 4 }
appnDirTableConfGroup OBJECT-GROUP
        OBJECTS
                 appnDirNnServerName,
                 appnDirLuOwnerName,
                 appnDirLuLocation,
                 appnDirType
        STATUS
               deprecated
        DESCRIPTION
            "A collection of objects providing the instrumentation of the
            APPN directory database.
            This RFC 2155-level group was deprecated when the
            appnDirApparentLuOwnerName object was added."
        ::= { appnGroups 5 }
                       OBJECT-GROUP
appnNnTopoConfGroup
        OBJECTS
                 appnNnTopoMaxNodes,
                 appnNnTopoCurNumNodes,
                 appnNnTopoNodePurges,
                 appnNnTopoTgPurges.
                 appnNnTopoTotalTduWars,
                 appnNnNodeFREntryTimeLeft,
                 appnNnNodeFRType,
```

appnNnNodeFRRsn,

```
appnNnNodeFRRouteAddResist,
                 appnNnNodeFRCongested,
                 appnNnNodeFRIsrDepleted.
                 appnNnNodeFRQuiescing,
                 appnNnNodeFRGateway, appnNnNodeFRCentralDirectory,
                 appnNnNodeFRIsr,
                 appnNnNodeFRGarbageCollect,
                 appnNnNodeFRHprSupport,
                 appnNnNodeFRPeriBorderSup,
                 appnNnNodeFRInterchangeSup,
                 appnNnNodeFRExteBorderSup,
                 appnNnTgFREntryTimeLeft,
                 appnNnTgFRDestVirtual,
                 appnNnTgFRDlcData,
                 appnNnTgFRRsn,
                 appnNnTgFROperational.
                 appnNnTgFRQuiescing,
                 appnNnTgFRCpCpSession,
                 appnNnTgFREffCap,
                 appnNnTgFRConnCost,
                 appnNnTgFRByteCost,
                 appnNnTgFRSecurity.
                 appnNnTgFRDelay,
                 appnNnTgFRUsr1,
                 appnNnTgFRUsr2,
                 appnNnTgFRUsr3,
                 appnNnTgFRGarbageCollect,
                 appnNnTgFRSubareaNum,
                 appnNnTgFRHprSup,
                 appnNnTgFRDestHprTrans,
                 appnNnTgFRTypeIndicator,
                  appnNnTgFRIntersubnet
        STATUS deprecated
        DESCRIPTION
            "The appnNnTopoConfGroup is mandatory only for network
            nodes.
            This RFC 2155-level group was deprecated when the
            appnNnNodeFRBranchAwareness, appnNnTgFRMltgLinkType, and
            appnNnFRBranchTq objects were added.
        ::= { appnGroups 9 }
                            OBJECT-GROUP
appnLocalEnTopoConfGroup
        OBJECTS {
```

```
appnLocalEnTgEntryTimeLeft,
         appnLocalEnTgDestVirtual,
         appnLocalEnTgDlcData,
         appnLocalEnTqOperational,
         appnLocalEnTgCpCpSession,
         appnLocalEnTgEffCap,
         appnLocalEnTgConnCost,
         appnLocalEnTgByteCost,
         appnLocalEnTgSecurity,
         appnLocalEnTgDelay,
         appnLocalEnTgUsr1,
         appnLocalEnTgUsr2,
         appnLocalEnTgUsr3
STATUS deprecated
DESCRIPTION
    "The appnLocalEnTopoConfGroup is mandatory only for network
    nodes.
    This RFC 2155-level group was deprecated when the
    appnLocalEnTgMltgLinkType object was added."
```

END

5. Security Considerations

 $::= \{ appnGroups 10 \}$

Certain management information defined in this MIB may be considered sensitive in some network environments. Therefore, authentication of received SNMP requests and controlled access to management information SHOULD be employed in such environments. An authentication protocol is defined in [12]. A protocol for access control is defined in [15].

The read-only objects appnNnTgFRSecurity, appnLocalTgSecurity, appnLocalEnTgSecurity, appnCosTgRowSecurityMin, and appnCosTgRowSecurityMax can be used to determine the potential path of secure data. While these objects cannot be changed by a management application using this MIB, these objects could be used to determine where a security exposure exists due to an improper configuration on the agent.

None of the other read-only objects in the APPN MIB reports a password, user data, or anything else that is particularly sensitive. Some enterprises view their network configuration itself, as well as

Clouston & Moore

Standards Track

information about network usage and performance, as corporate assets; such enterprises may wish to restrict SNMP access to most of the objects in the MIB.

Four of the read-write objects in the MIB can affect network operations; it is recommended that SNMP access to these objects be restricted. The four objects are:

- o appnNodeNnSafeStoreFreq: Setting this object to 0, or to a very large value, effectively turns off safe storing of topology data.
- o appnPortCommand, appnLsCommand: These two objects allow an APPN port or link station to be activated, deactivated, or recycled via an SNMP operation. The latter two operations may disrupt current users of the network.
- o appnIsInSessState: Setting this object to 'inactive' causes an active SNA session to be deactivated.

Other read-write objects control the gathering of network management data; controlling access to these objects is less critical.

6. Intellectual Property

The IETF takes no position regarding the validity or scope of any intellectual property or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; neither does it represent that it has made any effort to identify any such rights. Information on the IETF's procedures with respect to rights in standards-track and standards-related documentation can be found in BCP-11 [16]. Copies of claims of rights made available for publication and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF Secretariat.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights which may cover technology that may be required to practice this standard. Please address the information to the IETF Executive Director.

7. Acknowledgments

This MIB module is the product of the IETF SNA NAU MIB WG and the AIW APPN/HPR MIBs SIG. Thanks to Wayne Clark, Cisco Systems; Jim Cobban, Nortel; Rich Daugherty, IBM Corporation; Mark Regan, Cisco Systems; and Leo Temoshenko, IBM Corporation, for their contributions and review.

8. References

- [1] Harrington, D., Presuhn, R., and B. Wijnen, "An Architecture for Describing SNMP Management Frameworks", RFC 2271, January 1998.
- [2] Rose, M., and K. McCloghrie, "Structure and Identification of Management Information for TCP/IP-based Internets", STD 16, RFC 1155, May 1990.
- [3] Rose, M., and K. McCloghrie, "Concise MIB Definitions", STD 16, RFC 1212, March 1991.
- [4] Rose, M., "A Convention for Defining Traps for use with the SNMP", RFC 1215, March 1991.
- [5] Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Structure of Management Information for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1902, January 1996.
- [6] Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Textual Conventions for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1903, January 1996.
- [7] Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Conformance Statements for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1904, January 1996.
- [8] Case, J., Fedor, M., Schoffstall, M., and J. Davin, "Simple Network Management Protocol", STD 15, RFC 1157, May 1990.
- [9] Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Introduction to Community-based SNMPv2", RFC 1901, January 1996.
- [10] Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Transport Mappings for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1906, January 1996.

- [11] Case, J., Harrington D., Presuhn R., and B. Wijnen, "Message Processing and Dispatching for the Simple Network Management Protocol (SNMP)", RFC 2272, January 1998.
- [12] Blumenthal, U., and B. Wijnen, "User-based Security Model (USM) for version 3 of the Simple Network Management Protocol (SNMPv3)", RFC 2274, January 1998.
- [13] Case, J., McCloghrie, K., Rose, M., and S. Waldbusser, "Protocol Operations for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1905, January 1996.
- [14] Levi, D., Meyer, P., and B. Stewart, "SNMPv3 Applications", RFC 2273, January 1998.
- [15] Wijnen, B., Presuhn, R., and K. McCloghrie, "View-based Access Control Model (VACM) for the Simple Network Management Protocol (SNMP)", RFC 2275, January 1998.
- [16] Hovey, R., and S. Bradner, "The Organizations Involved in the IETF Standards Process", BCP 11, RFC 2028, October 1996.
- [17] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [18] IBM, Systems Network Architecture Technical Overview, GC30-3073.
- [19] IBM, Systems Network Architecture APPN Architecture Reference, SC30-3422
- [20] IBM, Systems Network Architecture Formats, SC30-3346.
- [21] Allen, M., Clouston, B., Kielczewski, Z., Kwan, W., and B. Moore, "Definition of Managed Objects for APPC", RFC 2051, December 1995.
- [22] Kielczewski, Z., Kostick D., and K. Shih, "Definition of Managed Objects for SNA NAUs using SMIv2", RFC 1666, August 1994.
- [23] Clouston, B., and B. Moore, "Definitions of Managed Objects for DLUR", RFC 2232, November 1996.
- [24] Clouston, B., and B. Moore, "Definitions of Managed Objects for HPR", RFC 2238, November 1996.

- [25] SNA DLC Services MIB Working Group, Hilgeman, J., Nix, S., Bartky, A., and W. Clark, "Definitions of Managed Objects for SNA Data Link Control (SDLC) using SMIv2", RFC 1747, January 1995.
- [26] SNA DLC Services MIB Working Group, Berl, S., Nix, S., and W. Clark, "Definitions of Managed Objects for SNA Data Link Control: LLC", May 1995.
- [27] Chen, D., Gayek, P., and S. Nix, "Definitions of Managed Objects for Data Link Switching using SNMPv2", RFC 2024, October 1995.
- [28] IBM, Systems Network Architecture Management Services Formats, GC31-8302.
- [29] Clouston, B., and B. Moore, "Definitions of Managed Objects for APPN", RFC 2155, June 1997.

9. Authors' Addresses

Bob Clouston Cisco Systems 7025 Kit Creek Road P.O. Box 14987 Research Triangle Park, NC 27709, USA

Phone: +1 919 472 2333 EMail: clouston@cisco.com

Robert Moore
Dept. BRQA/Bldg. 501/G114
IBM Corporation
P.O.Box 12195
3039 Cornwallis
Research Triangle Park, NC 27709, USA

Phone: +1 919 254 4436 EMail: remoore@us.ibm.com

10. Full Copyright Statement

Copyright (C) The Internet Society (1998). All Rights Reserved.

This document and translations of it may be copied and furnished to others, and derivative works that comment on or otherwise explain it or assist in its implementation may be prepared, copied, published and distributed, in whole or in part, without restriction of any kind, provided that the above copyright notice and this paragraph are included on all such copies and derivative works. However, this document itself may not be modified in any way, such as by removing the copyright notice or references to the Internet Society or other Internet organizations, except as needed for the purpose of developing Internet standards in which case the procedures for copyrights defined in the Internet Standards process must be followed, or as required to translate it into languages other than English.

The limited permissions granted above are perpetual and will not be revoked by the Internet Society or its successors or assigns.

This document and the information contained herein is provided on an "AS IS" basis and THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Clouston & Moore Standards Track [Page 140]