Network Working Group Request for Comments: 2981 Category: Standards Track R. Kavasseri (Editor of this version) B. Stewart (Author of previous version) Cisco Systems, Inc. October 2000

Event MIB

Status of this Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The Internet Society (2000). All Rights Reserved.

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it describes managed objects that can be used to manage and monitor MIB objects and take action through events.

The Event MIB provides the ability to monitor MIB objects on the local system or on a remote system and take simple action when a trigger condition is met.

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in RFC 2119.

Table of Contents

1	The SNMP Management Framework
2	Overview
3	Relationship to Other MIBs
4	MIB Sections
5	Operation !
6	Security
7	Definitions
8	Intellectual Property 47
9	Acknowledgements 47

Kavasseri & Stewart

Standards Track

[Page 1]

	References
11	Security Considerations
12	Author's Address
	Editor's Address
	Full Copyright Statement

1. The SNMP Management Framework

The SNMP Management Framework presently consists of five major components:

- An overall architecture, described in RFC 2571 [RFC2571].
- Mechanisms for describing and naming objects and events for the purpose of management. The first version of this Structure of Management Information (SMI) is called SMIv1 and described in STD 16, RFC 1155 [RFC1155], STD 16, RFC 1212 [RFC1212] and RFC 1215 [RFC1215]. The second version, called SMIv2, is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].
- Message protocols for transferring management information. 0 first version of the SNMP message protocol is called SNMPv1 and described in STD 15, RFC 1157 [RFC1157]. A second version of the SNMP message protocol, which is not an Internet standards track protocol, is called SNMPv2c and described in RFC 1901 [RFC1901] and RFC 1906 [RFC1906]. The third version of the message protocol is called SNMPv3 and described in RFC 1906 [RFC1906], RFC 2572 [RFC2572] and RFC 2574 [RFC2574].
- Protocol operations for accessing management information. first set of protocol operations and associated PDU formats is described in STD 15, RFC 1157 [RFC1157]. A second set of protocol operations and associated PDU formats is described in RFC 1905 [RFC1905].
- A set of fundamental applications described in RFC 2573 [RFC2573] and the view-based access control mechanism described in RFC 2575 [RFC2575].

A more detailed introduction to the current SNMP Management Framework can be found in RFC 2570 [RFC2570].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the mechanisms defined in the SMI.

This memo specifies a MIB module that is compliant to the SMIv2. MIB conforming to the SMIv1 can be produced through the appropriate The resulting translated MIB must be semantically equivalent, except where objects or events are omitted because no translation is possible (use of Counter64). Some machine readable information in SMIv2 will be converted into textual descriptions in SMIv1 during the translation process. However, this loss of machine readable information is not considered to change the semantics of the It may not be possible to meaningfully monitor Counter64 objects using an SMIv1 version of the MIB.

2. Overview

With network sizes well beyond the ability of people to manage them directly, automated, distributed management is vital. An important aspect of such management is the ability of a system to monitor itself or for some other system to monitor it.

The Event MIB provides the ability to monitor MIB objects on the local system or on a remote system and take simple action when a trigger condition is met.

The MIB is intended to suit either a relatively powerful manager or mid-level manager, as well as a somewhat more limited self-managing system.

3. Relationship to Other MIBs

The Event MIB is based on extensive experience with the RMON MIB [RFC1757] and provides a superset of the capabilities of the RMON alarm and event groups. Conceptually, the key extension is the ability to allow alarms to be generated for MIB objects that are on another network element. The Event MIB calls "triggers" what the RMON MIB called "alarms," but the concepts are the same. Event MIB triggers maintain the RMON handling of thresholds and add the concept of booleans. Event MIB events maintain the RMON concept of sending an SNMP notification in response to a trigger and add the concept of setting a MIB object.

The Event MIB is the successor and update to SNMPv2's Manager-to-Manager MIB [RFC1451] which was declared Historic pending this work.

The Event MIB depends on the services of the SNMPv3 Management Target and Notification MIBs [RFC2573].

The Event MIB is nicely complemented by the Distributed Management Expression MIB [RFC2982], which is the expected source of boolean objects to monitor. Note that there is considerable overlap between

the wildcard and delta sample capabilities of the Event and Expression MIBs. A carefully-planned implementation might well use common code to provide the overlapping functions.

4. MIB Sections

The MIB has four sections: triggers, objects, events, and notifications. Triggers define the conditions that lead to events. Events may cause notifications.


The trigger table lists what objects are to be monitored and how and relates each trigger to an event. It has supplementary, companion tables for additional objects that depend on the type of test done for the trigger.

The objects table lists objects that can be added to notifications based on the trigger, the trigger test type, or the event that resulted in the notification.

The event table defines what happens when an event is triggered: sending a notification, setting a MIB object or both. It has supplementary, companion tables for additional objects that depend on the action taken.

The notification section defines a set of generic notifications to go with the events and for Event MIB error handling, and it defines a set of objects to put in those notifications.

The following diagram describes the relationships between the tables in the Event MIB.



5. Operation

The Event MIB is instrumentation for a distributed management application that monitors MIB objects. In its simplest form this application monitors individual, local MIB objects, just as an RMON probe fulfills the functions implied by RMON's alarm and event operation. Additionally the application can monitor remote objects and wildcarded groups of objects.

Remote monitoring uses the tag service of the Management Target MIB [RFC2573] to select and access remote systems as an ordinary SNMP-based management application. Local monitoring may be via a more intimate, local interface which may, for example, bypass SNMP encoding but otherwise is functionally identical to remote SNMP operation, including the application of access control. A self-management only system MAY not implement remote monitoring.

Wildcards indicate that the application SHOULD use a GetNext-type operation to find the zero or more instances implied by a truncated object identifier, just like an ordinary SNMP-based management application. Each instance of a wildcard is treated as if it were a separate entry, that is the instances of a wildcarded object are independent of one another. For example, a wild-carded object may trigger an event, and result in the setting of another wildcarded object. The instance that satisfied the trigger function is used to perform the set function. All of this takes place independently of any additional instances that may fill the wildcard.

Error handling is by notification. These error notifications SHOULD be enabled only for the diagnosis of problems indicated by error counters. If minimizing the probability of notification loss is a concern they SHOULD be transmitted as Inform PDUs as described in the [SNMP-TARGET-MIB] or directed to a log as described in the Notification Log MIB [rfcNotificationLogMIB]. Note that this does not mean the Notification Log MIB is REQUIRED, since in fact notifications usually are not lost, but that the Notification Log MIB can be helpful with this as well as other MIBs that include notifications.

Although like most MIBs this one has no explicit controls for the persistence of the values set in configuring events, a robust, polite implementation would certainly not force its managing applications to reconfigure it whenever it resets.

Again, as with most MIBs, it is implementation-specific how a system provides and manages such persistence. To speculate, one could imagine, for example, that persistence depended on the context in which the expression was configured, or perhaps system-specific characteristics of the expression's owner. Or perhaps everything in a MIB such as this one, which is clearly aimed at persistent configuration, is automatically part of a system's other persistent configuration.

6. Security

Security of Event MIB entries depends on SNMPv3 access control for the entire MIB or for subsets based on entry owner names.

Security of monitored objects for remote access depends on the Management Target MIB [RFC2573]. Security for local access can depend on the Management Target MIB or on recording appropriate security credentials of the creator of an entry and using those to access the local objects. These security credentials are the parameters necessary as inputs to isAccessAllowed from the Architecture for Describing SNMP Management Frameworks. When accessing local objects without using a local target tag, the system MUST (conceptually) use isAccessAllowed to ensure that it does not violate security.

To facilitate the provisioning of access control by a security administrator for this MIB itself using the View-Based Access Control Model (VACM) defined in RFC 2275 [RFC2575] for tables in which multiple users may need to independently create or modify entries, the initial index is used as an "owner index". Such an initial index has a syntax of SnmpAdminString, and can thus be trivially mapped to a securityName or groupName as defined in VACM, in accordance with a security policy.

If a security administrator were to employ such an approach, all entries in related tables belonging to a particular user will have the same value for this initial index. For a given user's entries in a particular table, the object identifiers for the information in these entries will have the same sub-identifiers (except for the "column" sub-identifier) up to the end of the encoded owner index. To configure VACM to permit access to this portion of the table, one would create vacmViewTreeFamilyTable entries with the value of vacmViewTreeFamilySubtree including the owner index portion, and vacmViewTreeFamilyMask "wildcarding" the column sub-identifier. More elaborate configurations are possible.

7. Definitions

DISMAN-EVENT-MIB DEFINITIONS ::= BEGIN

IMPORTS

MODULE-IDENTITY, OBJECT-TYPE, Integer32, Unsigned32, NOTIFICATION-TYPE, Counter32, Gauge32, mib-2, zeroDotZero FROM SNMPv2-SMI TEXTUAL-CONVENTION, RowStatus, FROM SNMPv2-TC **TruthValue**

```
MODULE-COMPLIANCE, OBJECT-GROUP,
FROM SNMPv2-CONF
                                   FROM SNMPv2-MIB
    sysUpTime
                                   FROM SNMP-TARGET-MIB
    SnmpTagValue
    SnmpAdminString
                                   FROM SNMP-FRAMEWORK-MIB:
dismanEventMIB MODULE-IDENTITY
    LAST-UPDATED "200010160000Z" -- 16 October 20 ORGANIZATION "IETF Distributed Management Working Group"
                                                    -- 16 October 2000
    CONTACT-INFO "Ramanathan Kavasseri
                     Cisco Systems, Inc.
                     170 West Tasman Drive,
                     San Jose CA 95134-1706.
                     Phone: +1 408 526 4527
                     Email: ramk@cisco.com"
    DESCRIPTION
      "The MIB module for defining event triggers and actions
      for network management purposes."
-- Revision History
                       "200010160000Z"
        REVISION
                                                        -- 16 October 2000
                       "This is the initial version of this MIB.
        DESCRIPTION
                       Published as RFC 2981"
     ::= { mib-2 88 }
dismanEventMIBObjects OBJECT IDENTIFIER ::= { dismanEventMIB 1 }
-- Management Triggered Event (MTE) objects
                          OBJECT IDENTIFIER ::= { dismanEventMIBObjects 1 }
OBJECT IDENTIFIER ::= { dismanEventMIBObjects 2 }
OBJECT IDENTIFIER ::= { dismanEventMIBObjects 3 }
mteResource
mteTrigger
mteObjects
                          OBJECT IDENTIFIER ::= { dismanEventMIBObjects 4 }
mteEvent
-- Textual Conventions
FailureReason ::= TEXTUAL-CONVENTION
    STATUS
                 current
    DESCRIPTION
         "Reasons for failures in an attempt to perform a management
         request.
         The first group of errors, numbered less than 0, are related
         to problems in sending the request. The existence of a particular error code here does not imply that all
         implementations are capable of sensing that error and
```

returning that code.

The second group, numbered greater than 0, are copied directly from SNMP protocol operations and are intended to carry exactly the meanings defined for the protocol as returned in an SNMP response.

```
localResourceLack
                        some local resource such as memory
                        lacking or
                        mteResourceSampleInstanceMaximum
                        exceeded
badDestination
                        unrecognized domain name or otherwise
                        invalid destination address
                        can't get to destination address
destinationUnreachable
                        no response to SNMP request
noResponse
badType
                        the data syntax of a retrieved object
                        as not as expected
                        another sample attempt occurred before
sampleOverrun
                        the previous one completed"
```

SYNTAX

```
INTEGER { localResourceLack(-1),
          badDestination(-2),
          destinationUnreachable(-3),
          noResponse(-4),
          badType(-5),
          sampleOverrun(-6),
          noError(0),
          tooBig(1),
          noSuchName(2),
          badValue(3),
          readOnly(4),
          qenErr(5)
          noAccess(6)
          wrongType(7)
          wrongLength(8)
          wrongEncoding(9),
          wrongValue(10),
          noCreation(11)
          inconsistentValue(12)
          resourceUnavailable(13),
          commitFailed(14),
          undoFailed(15),
          authorizationError(16),
          notWritable(17),
```

inconsistentName(18) }

-- Resource Control Section

--

mteResourceSampleMinimum OBJECT-TYPE

SYNTAX Integer32 (1..2147483647)

UNITS "seconds"
MAX-ACCESS read-write
STATUS current
DESCRIPTION

"The minimum mteTriggerFrequency this system will accept. A system may use the larger values of this minimum to lessen the impact of constant sampling. For larger sampling intervals the system samples less often and suffers less overhead. This object provides a way to enforce such lower overhead for all triggers created after it is set.

Unless explicitly resource limited, a system's value for this object SHOULD be 1, allowing as small as a 1 second interval for ongoing trigger sampling.

Changing this value will not invalidate an existing setting of mteTriggerFrequency."

::= { mteResource 1 }

mteResourceSampleInstanceMaximum OBJECT-TYPE

SYNTAX Unsigned32
UNITS "instances"
MAX-ACCESS read-write
STATUS current

DESCRIPTION

"The maximum number of instance entries this system will support for sampling.

These are the entries that maintain state, one for each instance of each sampled object as selected by mteTriggerValueID. Note that wildcarded objects result in multiple instances of this state.

A value of 0 indicates no preset limit, that is, the limit is dynamic based on system operation and resources.

Unless explicitly resource limited, a system's value for this object SHOULD be 0.

Changing this value will not eliminate or inhibit existing sample state but could prevent allocation of additional state information."

```
::= { mteResource 2 }
mteResourceSampleInstances OBJECT-TYPE
    SYNTAX
                 Gauge32
                 "instances"
    UNITS
    MAX-ACCESS
                 read-only
    STATUS
                 current
    DESCRIPTION
         "The number of currently active instance entries as
        defined for mteResourceSampleInstanceMaximum."
    ::= { mteResource 3 }
mteResourceSampleInstancesHigh OBJECT-TYPE
                 Gauge32
    SYNTAX
                 "instances"
    UNITS
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The highest value of mteResourceSampleInstances that has
        occurred since initialization of the management system."
    ::= { mteResource 4 }
mteResourceSampleInstanceLacks OBJECT-TYPE
    SYNTAX
                 Counter32
                 "instances"
    UNITS
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The number of times this system could not take a new sample
        because that allocation would have exceeded the limit set by
        mteResourceSampleInstanceMaximum.'
    ::= { mteResource 5 }
-- Trigger Section
-- Counters
mteTriggerFailures OBJECT-TYPE
                 Counter32
    SYNTAX
                 "failures"
    UNITS
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
         "The number of times an attempt to check for a trigger
        condition has failed. This counts individually for each attempt in a group of targets or each attempt for a
```

```
wildcarded object."
    ::= { mteTrigger 1 }
-- Trigger Table
mteTriggerTable OBJECT-TYPE
    SYNTAX
                SEQUENCE OF MteTriggerEntry
    MAX-ACCESS not-accessible
    STATUS
               current
    DESCRIPTION
        "A table of management event trigger information."
    ::= { mteTrigger 2 }
mteTriggerEntry OBJECT-TYPE
                MteTriggerEntry
    SYNTAX
    MAX-ACCESS
                not-accessible
    STATUS
                current
    DESCRIPTION
        "Information about a single trigger. Applications create and
        delete entries using mteTriggerEntryStatus."
                { mteOwner, IMPLIED mteTriggerName }
    INDEX
    ::= { mteTriggerTable 1 }
MteTriggerEntry ::= SEQUENCE {
    mte0wner
                                         SnmpAdminString,
                                         SnmpAdminString,
    mteTriggerName
    mteTriggerComment
                                         SnmpAdminString,
    mteTriggerTest
                                         BITS,
                                         INTEGER,
    mteTriggerSampleType
                                         OBJECT IDENTIFIER,
    mteTriggerValueID
    mteTriggerValueIDWildcard
                                         TruthValue,
    mteTriggerTargetTag
                                         SnmpTagValue.
    mteTriggerContextName
                                         SnmpAdminString,
    mteTriggerContextNameWildcard
                                         TruthValue,
    mteTriggerFrequency
                                         Unsigned32
    mteTriggerObjectsOwner
                                         SnmpAdminString,
    mteTriggerObjects
                                         SnmpAdminString,
    mteTriggerEnabled
                                         TruthValue,
    mteTriggerEntryStatus
                                         RowStatus
}
mteOwner OBJECT-TYPE
               SnmpAdminString (SIZE(0..32))
   SYNTAX
   MAX-ACCESS
               not-accessible
   STATUS
               current
   DESCRIPTION
```

```
"The owner of this entry. The exact semantics of this string are subject to the security policy defined by the
          security administrator."
     ::= { mteTriggerEntry 1 }
mteTriggerName OBJECT-TYPE
                   SnmpAdminString (SIZE (1..32))
     SYNTAX
     MAX-ACCESS not-accessible
                  current
     STATUS
     DESCRIPTION
          "A locally-unique, administratively assigned name for the
          trigger within the scope of mteOwner."
     ::= { mteTriggerEntry 2 }
mteTriggerComment OBJECT-TYPE
     SYNTAX
                SnmpAdminString
     MAX-ACCESS read-create
     STATUS
                   current
     DESCRIPTION
          "A description of the trigger's function and use."
     DEFVAL { ''H }
     ::= { mteTriggerEntry 3 }
mteTriagerTest OBJECT-TYPE
                   BITS { existence(0), boolean(1), threshold(2) }
     SYNTAX
     MAX-ACCESS read-create
     STATUS
                   current
     DESCRIPTION
          "The type of trigger test to perform. For 'boolean' and
          'threshold' tests, the object at mteTriggerValueID MUST
          evaluate to an integer, that is, anything that ends up encoded for transmission (that is, in BER, not ASN.1) as an integer.
          For 'existence', the specific test is as selected by
         mteTriggerExistenceTest. When an object appears, vanishes or changes value, the trigger fires. If the object's appearance caused the trigger firing, the object MUST
          vanish before the trigger can be fired again for it, and
          vice versa. If the trigger fired due to a change in the object's value, it will be fired again on every successive
          value change for that object.
          For 'boolean', the specific test is as selected by
```

For 'threshold' the test works as described below for

become false and come back to true.

mteTriggerBooleanTest. If the test result is true the trigger fires. The trigger will not fire again until the value has

```
\label{lem:mteTriggerThresholdStartup} \mbox{ $\tt mteTriggerThresholdRising, and } \\ \mbox{ $\tt mteTriggerThresholdFalling.}
```

Note that combining 'boolean' and 'threshold' tests on the same object may be somewhat redundant."

DEFVAL { { boolean } }
::= { mteTriggerEntry 4 }

mteTriggerSampleType OBJECT-TYPE

SYŇŤAX i INTEGER { absoluteValue(1), deltaValue(2) }

MAX-ACCESS read-create

STATUS current

DESCRIPTION

"The type of sampling to perform.

An 'absoluteValue' sample requires only a single sample to be meaningful, and is exactly the value of the object at mteTriggerValueID at the sample time.

A 'deltaValue' requires two samples to be meaningful and is thus not available for testing until the second and subsequent samples after the object at mteTriggerValueID is first found to exist. It is the difference between the two samples. For unsigned values it is always positive, based on unsigned arithmetic. For signed values it can be positive or negative.

For SNMP counters to be meaningful they should be sampled as a 'deltaValue'.

For 'deltaValue' mteTriggerDeltaTable contains further parameters.

If only 'existence' is set in mteTriggerTest this object has
no meaning."

DEFVAL { absoluteValue }
::= { mteTriggerEntry 5 }

mteTriggerValueID OBJECT-TYPE

SYNTAX OBJECT IDENTIFIER

MAX-ACCESS read-create

STATUS current

DESCRIPTION

"The object identifier of the MIB object to sample to see if the trigger should fire.

This may be wildcarded by truncating all or part of the instance portion, in which case the value is obtained as if with a GetNext function, checking multiple values

if they exist. If such wildcarding is applied,
mteTriggerValueIDWildcard must be 'true' and if not it must
be 'false'.

Bad object identifiers or a mismatch between truncating the identifier and the value of mteTriggerValueIDWildcard result in operation as one would expect when providing the wrong identifier to a Get or GetNext operation. The Get will fail or get the wrong object. The GetNext will indeed get whatever is next, proceeding until it runs past the initial part of the identifier and perhaps many unintended objects for confusing results. If the value syntax of those objects is not usable, that results in a 'badType' error that terminates the scan.

Each instance that fills the wildcard is independent of any additional instances, that is, wildcarded objects operate as if there were a separate table entry for each instance that fills the wildcard without having to actually predict all possible instances ahead of time."

DEFVAL { zeroDotZero }
::= { mteTriggerEntry 6 }

mteTriggerValueIDWildcard OBJECT-TYPE

SYNTAX TruthValue
MAX-ACCESS read-create
STATUS current
DESCRIPTION

"Control for whether mteTriggerValueID is to be treated as
fully-specified or wildcarded, with 'true' indicating wildcard."
DEFVAL { false }

::= { mteTriggerEntry 7 }

mteTriggerTargetTag OBJECT-TYPE
SYNTAX SnmpTagValue
MAX-ACCESS read-create
STATUS current
DESCRIPTION

"The tag for the target(s) from which to obtain the condition for a trigger check.

A length of 0 indicates the local system. In this case, access to the objects indicated by mteTriggerValueID is under the security credentials of the requester that set mteTriggerEntryStatus to 'active'. Those credentials are the input parameters for isAccessAllowed from the Architecture for Describing SNMP Management Frameworks.

Otherwise access rights are checked according to the security

```
parameters resulting from the tag."
     DEFVAL { ''H }
     ::= { mteTriggerEntry 8 }
mteTriggerContextName OBJECT-TYPE
     SYNTAX
                    SnmpAdminString
     MAX-ACCESS
                    read-create
                   current
     STATUS
     DESCRIPTION
           'The management context from which to obtain mteTriggerValueID.
          This may be wildcarded by leaving characters off the end.
          example use 'Repeater' to wildcard to 'Repeater1', 'Repeater2', 'Repeater-999.87b', and so on. To indicate such wildcarding is intended, mteTriggerContextNameWildcard must
          be 'true'.
          Each instance that fills the wildcard is independent of any
          additional instances, that is, wildcarded objects operate
          as if there were a separate table entry for each instance that fills the wildcard without having to actually predict all possible instances ahead of time.
          Operation of this feature assumes that the local system has a
          list of available contexts against which to apply the
          wildcard. If the objects are being read from the local
          system, this is clearly the system's own list of contexts. For a remote system a local version of such a list is not defined by any current standard and may not be available, so
     this function MAY not be supported."
DEFVAL { ''H }
     ::= { mteTriggerEntry 9 }
mteTriggerContextNameWildcard OBJECT-TYPE
     SYNTAX
                    TruthValue
     MAX-ACCESS read-create
     STATUS
                   current
     DESCRIPTION
          "Control for whether mteTriggerContextName is to be treated as
          fully-specified or wildcarded, with 'true' indicating wildcard."
     DEFVAL { false }
     ::= { mteTriggerEntry 10 }
mteTriggerFrequency OBJECT-TYPE
                    Unsigned32
     SYNTAX
                    "seconds"
     UNITS
     MAX-ACCESS read-create
     STATUS
                    current
```

DESCRIPTION

"The number of seconds to wait between trigger samples. encourage consistency in sampling, the interval is measured from the beginning of one check to the beginning of the next and the timer is restarted immediately when it expires, not when the check completes.

If the next sample begins before the previous one completed the system may either attempt to make the check or treat this as an error condition with the error 'sampleOverrun'.

A frequency of 0 indicates instantaneous recognition of the condition. This is not possible in many cases, but may be supported in cases where it makes sense and the system is able to do so. This feature allows the MIB to be used in implementations where such interrupt-driven behavior is possible and is not likely to be supported for all MIB objects even then since such sampling generally has to be tightly integrated into low-level code.

Systems that can support this SHOULD document those cases where it can be used. In cases where it can not, setting this object to 0 should be disallowed."

DEFVAL { 600 } ::= { mteTriggerEntry 11 }

mteTriggerObjectsOwner OBJECT-TYPE SYNTAX

SnmpAdminString (SIZE (0..32))

MAX-ACCESS read-create **STATUS** current

DESCRIPTION

"To go with mteTriggerObjects, the mteOwner of a group of objects from mteObjectsTable.

DEFVAL { ''H }

::= { mteTriggerEntry 12 }

mteTriggerObjects OBJECT-TYPE

SYNTAX SnmpAdminString (SIZE (0..32))

MAX-ACCESS read-create

STATUS current

DESCRIPTION

"The mteObjectsName of a group of objects from mteObjectsTable. These objects are to be added to any Notification resulting from the firing of this trigger.

A list of objects may also be added based on the event or on the value of mteTriggerTest.

```
A length of 0 indicates no additional objects."
    DEFVAL { ''H }
    ::= { mteTriggerEntry 13 }
mteTriggerEnabled OBJECT-TYPE
    SYNTAX
                TruthValue
    MAX-ACCESS read-create
               current
    STATUS
    DESCRIPTION
        "A control to allow a trigger to be configured but not used.
        When the value is 'false' the trigger is not sampled."
    DEFVAL { false }
    ::= { mteTriggerEntry 14 }
mteTriggerEntryStatus OBJECT-TYPE
    SYNTAX
               RowStatus
    MAX-ACCESS read-create
    STATUS
                current
    DESCRIPTION
        "The control that allows creation and deletion of entries.
        Once made active an entry may not be modified except to
        delete it.
    ::= { mteTriggerEntry 15 }
-- Trigger Delta Table
mteTriggerDeltaTable OBJECT-TYPE
                SEQUENCE OF MteTriggerDeltaEntry
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "A table of management event trigger information for delta
        sampling.'
    ::= { mteTrigger 3 }
mteTriggerDeltaEntry OBJECT-TYPE
                MteTriggerDeltaEntry
    SYNTAX
    MAX-ACCESS
              not-accessible
    STATUS
                current
    DESCRIPTION
        "Information about a single trigger's delta sampling. Entries
        automatically exist in this this table for each mteTriggerEntry
        that has mteTriggerSampleType set to 'deltaValue'."
                { mteOwner, IMPLIED mteTriggerName }
    ::= { mteTriggerDeltaTable 1 }
```

```
MteTriggerDeltaEntry ::= SEQUENCE {
    mteTriggerDeltaDiscontinuityID
                                                     OBJECT IDENTIFIER,
    mteTriggerDeltaDiscontinuityIDWildcard
                                                     TruthValue,
    mteTriggerDeltaDiscontinuityIDType
                                                     INTEGER
}
sysUpTimeInstance OBJECT IDENTIFIER ::= { sysUpTime 0 }
mteTriggerDeltaDiscontinuityID OBJECT-TYPE
                 OBJECT IDENTIFIER
    SYNTAX
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "The OBJECT IDENTIFIER (OID) of a TimeTicks, TimeStamp, or
        DateAndTime object that indicates a discontinuity in the value
        at mteTriggerValueID.
        The OID may be for a leaf object (e.g. sysUpTime.0) or may
        be wildcarded to match mteTriggerValueID.
        This object supports normal checking for a discontinuity in a
        counter. Note that if this object does not point to sysUpTime
        discontinuity checking MUST still check sysUpTime for an overall
        discontinuity.
        If the object identified is not accessible the sample attempt
        is in error, with the error code as from an SNMP request.
        Bad object identifiers or a mismatch between truncating the
        identifier and the value of mteDeltaDiscontinuityIDWildcard
        result in operation as one would expect when providing the
        wrong identifier to a Get operation. The Get will fail or get
the wrong object. If the value syntax of those objects is not
        usable, that results in an error that terminates the sample with a 'badType' error code."
    DEFVAL { sysUpTimeInstance }
    ::= { mteTriggerDeltaEntry 1 }
mteTriggerDeltaDiscontinuityIDWildcard OBJECT-TYPE
     SYNTAX
               TruthValue
     MAX-ACCESS read-write
     STATUS
                  current
     DESCRIPTION
        "Control for whether mteTriggerDeltaDiscontinuityID is to be
        treated as fully-specified or wildcarded, with 'true'
        indicating wildcard. Note that the value of this object will
        be the same as that of the corresponding instance of
        mteTriggerValueIDWildcard when the corresponding
```

```
mteTriggerSampleType is 'deltaValue'."
    DEFVAL { false }
    ::= { mteTriggerDeltaEntry 2 }
mteTriggerDeltaDiscontinuityIDType OBJECT-TYPE
                 INTEGER { timeTicks(1), timeStamp(2), dateAndTime(3) }
    SYNTAX
    MAX-ACCESS
                 read-write
                 current
    STATUS
    DESCRIPTION
         'The value 'timeTicks' indicates the
        mteTriggerDeltaDiscontinuityID of this row is of syntax TimeTicks. The value 'timeStamp' indicates syntax TimeStamp.
        The value 'dateAndTime' indicates syntax DateAndTime."
    DEFVAL { timeTicks }
    ::= { mteTriggerDeltaEntry 3 }
-- Trigger Existence Table
mteTriggerExistenceTable OBJECT-TYPE
    SYNTAX
                 SEQUENCE OF MteTriggerExistenceEntry
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
         "A table of management event trigger information for existence
         triggers."
    ::= { mteTrigger 4 }
mteTriggerExistenceEntry OBJECT-TYPE
                 MteTriggerExistenceEntry
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
         "Information about a single existence trigger.
        automatically exist in this this table for each mteTriggerEntry that has 'existence' set in mteTriggerTest."
                 { mteOwner, IMPLIED mteTriggerName }
    ::= { mteTriggerExistenceTable 1 }
MteTriggerExistenceEntry ::= SEQUENCE {
                                             BITS,
    mteTriggerExistenceTest
    mteTriggerExistenceStartup
                                             BITS,
                                             SnmpAdminString,
    mteTriggerExistenceObjectsOwner
    mteTriggerExistenceObjects
                                             SnmpAdminString,
    mteTriggerExistenceEventOwner
                                             SnmpAdminString,
                                             SnmpAdminString
    mteTriggerExistenceEvent
}
```

```
mteTriggerExistenceTest OBJECT-TYPE
                 BITS { present(0), absent(1), changed(2) }
    SYNTAX
    MAX-ACCESS
                 read-write
    STATUS
                 current
    DESCRIPTION
        "The type of existence test to perform. The trigger fires when the object at mteTriggerValueID is seen to go from
         present to absent, from absent to present, or to have it's
         value changed, depending on which tests are selected:
        present(0) - when this test is selected, the trigger fires
        when the mteTriggerValueID object goes from absent to present.
        absent(1) - when this test is selected, the trigger fires
when the mteTriggerValueID object goes from present to absent.
         changed(2) - when this test is selected, the trigger fires
         the mteTriggerValueID object value changes.
        Once the trigger has fired for either presence or absence it
        will not fire again for that state until the object has been
         to the other state.
    DEFVAL { { present, absent } }
    ::= { mteTriggerExistenceEntry 1 }
mteTriggerExistenceStartup OBJECT-TYPE
                BITS { present(0), absent(1) }
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
         "Control for whether an event may be triggered when this entry
         is first set to 'active' and the test specified by
        mteTriggerExistenceTest is true. Setting an option causes
         that trigger to fire when its test is true."
    DEFVAL { { present, absent } }
::= { mteTriggerExistenceEntry 2 }
mteTriggerExistenceObjectsOwner OBJECT-TYPE
    SYNTAX
                 SnmpAdminString (SIZE (0..32))
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
         "To go with mteTriggerExistenceObjects, the mteOwner of a
         group of objects from mteObjectsTable.
    DEFVĂL { ''H }
    ::= { mteTriggerExistenceEntry 3 }
mteTriggerExistenceObjects OBJECT-TYPE
                 SnmpAdminString (SIZE (0..32))
    SYNTAX
```

```
MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "The mteObjectsName of a group of objects from
        mteObjectsTable. These objects are to be added to any
        Notification resulting from the firing of this trigger for
        this test.
        A list of objects may also be added based on the overall
        trigger, the event or other settings in mteTriggerTest.
        A length of 0 indicates no additional objects."
    DEFVAL { T'H }
    ::= { mteTriggerExistenceEntry 4 }
mteTriggerExistenceEventOwner OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "To go with mteTriggerExistenceEvent, the mteOwner of an event
    entry from the mteEventTable."

DEFVAL { ''H }
    ::= { mteTriggerExistenceEntry 5 }
mteTriggerExistenceEvent OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS read-write
                current
    STATUS
    DESCRIPTION
        "The mteEventName of the event to invoke when mteTriggerType is
        'existence' and this trigger fires. A length of 0 indicates no
        event.
    DEFVAL { ''H }
    ::= { mteTriggerExistenceEntry 6 }
-- Trigger Boolean Table
mteTriggerBooleanTable OBJECT-TYPE
    SYNTAX
                SEQUENCE OF MteTriggerBooleanEntry
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "A table of management event trigger information for boolean
        triggers."
    ::= { mteTrigger 5 }
```

```
mteTriggerBooleanEntry OBJECT-TYPE
    SYNTAX
                 MteTriggerBooleanEntry
    MAX-ACCESS
                 not-accessible
    STATUS
                 current
    DESCRIPTION
         "Information about a single boolean trigger. Entries
        automatically exist in this this table for each mteTriggerEntry that has 'boolean' set in mteTriggerTest."
                 { mteOwner, IMPLIED mteTriggerName }
    ::= { mteTriggerBooleanTable 1 }
MteTriggerBooleanEntry ::= SEQUENCE {
    mteTriggerBooleanComparison
                                             INTEGER.
    mteTriggerBooleanValue
                                             Integer32,
    mteTriggerBooleanStartup
                                             TruthValue,
    mteTriggerBooleanObjectsOwner
                                             SnmpAdminString,
    mteTriggerBooleanObjects
                                             SnmpAdminString,
    mteTriggerBooleanEventOwner
                                             SnmpAdminString,
                                             SnmpAdminString
    mteTriggerBooleanEvent
}
mteTriggerBooleanComparison OBJECT-TYPE
    SYNTAX
                 INTEGER { unequal(1), equal(2),
                  less(3), lessOrEqual(4),
                  greater(5), greaterOrEqual(6) }
    MAX-ACCESS
                 read-write
    STATUS
                 current
    DESCRIPTION
         "The type of boolean comparison to perform.
        The value at mteTriggerValueID is compared to
        mteTriggerBooleanValue, so for example if mteTriggerBooleanComparison is 'less' the result would be true
        if the value at mteTriggerValueID is less than the value of
        mteTriggerBooleanValue.
    DEFVAL { unequal }
    ::= { mteTriggerBooleanEntry 1 }
mteTriggerBooleanValue OBJECT-TYPE
                 Integer32
    SYNTAX
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
         "The value to use for the test specified by
        mteTriggerBooleanTest."
    DEFVAL { 0
    ::= { mteTriggerBooleanEntry 2 }
```

```
mteTriggerBooleanStartup OBJECT-TYPE
                TruthValue
    SYNTAX
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "Control for whether an event may be triggered when this entry
        is first set to 'active' or a new instance of the object at
        mteTriggerValueID is found and the test specified by
        mteTriggerBooleanComparison is true. In that case an event is
        triggered if mteTriggerBooleanStartup is 'true'.'
    DEFVAL { true }
    ::= { mteTriggerBooleanEntry 3 }
mteTriggerBooleanObjectsOwner OBJECT-TYPE
    SYNTAX
                SnmpAdminString (SIZE (0..32))
    MAX-ACCESS
                read-write
    STATUS
                current
    DESCRIPTION
        "To go with mteTriggerBooleanObjects, the mteOwner of a group
        of objects from mteObjectsTable.'
    DEFVAL { ''H }
    ::= { mteTriggerBooleanEntry 4 }
mteTriggerBooleanObjects OBJECT-TYPE
    SYNTAX
                SnmpAdminString (SIZE (0..32))
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "The mteObjectsName of a group of objects from
        mteObjectsTable. These objects are to be added to any
        Notification resulting from the firing of this trigger for
        this test.
        A list of objects may also be added based on the overall
        trigger, the event or other settings in mteTriggerTest.
        A length of 0 indicates no additional objects."
    DEFVAL { ''H }
    ::= { mteTriggerBooleanEntry 5 }
mteTriggerBooleanEventOwner OBJECT-TYPE
    SYNTAX
                SnmpAdminString (SIZE (0..32))
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "To go with mteTriggerBooleanEvent, the mteOwner of an event
    entry from mteEventTable."
DEFVAL { ''H }
```

```
::= { mteTriggerBooleanEntry 6 }
mteTriggerBooleanEvent OBJECT-TYPE
                 SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS
                 read-write
    STATUS
                 current
    DESCRIPTION
         'The mteEventName of the event to invoke when mteTriggerType is
         'boolean' and this trigger fires. A length of 0 indicates no
        event."
    DEFVAL { ''H }
    ::= { mteTriggerBooleanEntry 7 }
-- Trigger Threshold Table
mteTriggerThresholdTable OBJECT-TYPE
                 SEQUENCE OF MteTriggerThresholdEntry
    SYNTAX
    MAX-ACCESS
                 not-accessible
    STATUS
                 current
    DESCRIPTION
         "A table of management event trigger information for threshold
        triagers.'
    ::= { mteTrigger 6 }
mteTriggerThresholdEntry OBJECT-TYPE
    SYNTAX
                 MteTriggerThresholdEntry
    MAX-ACCESS
               not-accessible
    STATUS
                 current
    DESCRIPTION
                                                            Entries
         "Information about a single threshold trigger.
         automatically exist in this table for each mteTriggerEntry
    that has 'threshold' set in mteTriggerTest."

INDEX { mteOwner, IMPLIED mteTriggerName }
::= { mteTriggerThresholdTable 1 }
MteTriggerThresholdEntry ::= SEQUENCE {
    mteTriggerThresholdStartup
                                                    INTEGER.
    mteTriggerThresholdRising
                                                    Integer32,
                                                    Integer32,
    mteTriggerThresholdFalling
                                                    Integer32,
    mteTriggerThresholdDeltaRising
    mteTriggerThresholdDeltaFalling
                                                    Integer32,
    mteTriggerThresholdObjectsOwner
                                                    SnmpAdminString,
    mteTriggerThresholdObjects
                                                    SnmpAdminString,
    mteTriggerThresholdRisingEventOwner
                                                    SnmpAdminString,
    mteTriggerThresholdRisingEvent
                                                    SnmpAdminString,
    mteTriggerThresholdFallingEventOwner
                                                    SnmpAdminString,
```

```
mteTriggerThresholdFallingEvent
                                                       SnmpAdminString,
    mteTriggerThresholdDeltaRisingEventOwner
                                                       SnmpAdminString,
    mteTriggerThresholdDeltaRisingEvent
                                                       SnmpAdminString,
    mteTriggerThresholdDeltaFallingEventOwner
                                                       SnmpAdminString,
    mteTriggerThresholdDeltaFallingEvent
                                                       SnmpAdminString
}
mteTriggerThresholdStartup OBJECT-TYPE
                  INTEGER { rising(1), falling(2), risingOrFalling(3) }
    SYNTAX
    MAX-ACCESS read-write
                 current
    STATUS
    DESCRIPTION
         "The event that may be triggered when this entry is first
         set to 'active' and a new instance of the object at
         mteTriggerValueID is found. If the first sample after this
         instance becomes active is greater than or equal to
         mteTriggerThresholdRising and mteTriggerThresholdStartup is
         equal to 'rising' or 'risingOrFalling', then one mteTriggerThresholdRisingEvent is triggered for that instance.
         If the first sample after this entry becomes active is less than or equal to mteTriggerThresholdFalling and
         mteTriggerThresholdStartup is equal to 'falling' or
         'risingOrFalling', then one mteTriggerThresholdRisingEvent is triggered for that instance."
    DEFVAL { risingOrFalling }
     ::= { mteTriggerThresholdEntry 1 }
mteTriggerThresholdRising OBJECT-TYPE
    SYNTAX
                 Integer32
    MAX-ACCESS read-write
    STATUS
                  current
    DESCRIPTION
         "A threshold value to check against if mteTriggerType is
         'threshold'.
         When the current sampled value is greater than or equal to
         this threshold, and the value at the last sampling interval
         was less than this threshold, one
         mteTriggerThresholdRisingEvent is triggered.
                                                              That event is
         also triggered if the first sample after this entry becomes active is greater than or equal to this threshold and mteTriggerThresholdStartup is equal to 'rising' or
         'risingOrFalling'.
         After a rising event is generated, another such event is not
         triggered until the sampled value falls below this threshold
         and reaches mteTriggerThresholdFalling."
    DEFVAL { 0 }
```

```
::= { mteTriggerThresholdEntry 2 }
mteTriggerThresholdFalling OBJECT-TYPE
     SYNTAX
                   Integer32
     MAX-ACCESS read-write
     STATUS
                   current
     DESCRIPTION
          'A threshold value to check against if mteTriggerType is
          'threshold'.
         When the current sampled value is less than or equal to this
         threshold, and the value at the last sampling interval was
         greater than this threshold, one
         mteTriggerThresholdFallingEvent is triggered. That event is
         also triggered if the first sample after this entry becomes
         active is less than or equal to this threshold and
         mteTriggerThresholdStartup is equal to 'falling' or
          'risingOrFalling'.
         After a falling event is generated, another such event is not triggered until the sampled value rises above this threshold
         and reaches mteTriggerThresholdRising.
     DEFVAL { 0 }
     ::= { mteTriggerThresholdEntry 3 }
mteTriggerThresholdDeltaRising OBJECT-TYPE
     SYNTAX
                  Integer32
     MAX-ACCESS read-write
                   current
     STATUS
     DESCRIPTION
          "A threshold value to check against if mteTriggerType is
          'threshold'.
         When the delta value (difference) between the current sampled value (value(n)) and the previous sampled value (value(n-1)) is greater than or equal to this threshold, and the delta value calculated at the last sampling interval
          (i.e. value(n-1) - value(n-2)) was less than this threshold,
         one mteTriggerThresholdDeltaRisingEvent is triggered. That event
         is also triggered if the first delta value calculated after this
```

After a rising event is generated, another such event is not triggered until the delta value falls below this threshold and reaches mteTriggerThresholdDeltaFalling."

DEFVAL { 0 }

entry becomes active, i.e. value(2) - value(1), where value(1) is the first sample taken of that instance, is greater than or

equal to this threshold.

```
::= { mteTriggerThresholdEntry 4 }
mteTriggerThresholdDeltaFalling OBJECT-TYPE
    SYNTAX
                 Integer32
    MAX-ACCESS
                read-write
    STATUS
                 current
    DESCRIPTION
         'A threshold value to check against if mteTriggerType is
         'threshold'.
        When the delta value (difference) between the current sampled
         value (value(n)) and the previous sampled value (value(n-1))
         is less than or equal to this threshold,
         and the delta value calculated at the last sampling interval
         (i.e. value(n-1) - value(n-2)) was greater than this threshold,
         one mteTriggerThresholdDeltaFallingEvent is triggered. That event
         is also triggered if the first delta value calculated after this
         entry becomes active, i.e. value(2) - value(1), where value(1)
is the first sample taken of that instance, is less than or
         equal to this threshold.
        After a falling event is generated, another such event is not triggered until the delta value falls below this threshold and
         reaches mteTriggerThresholdDeltaRising."
    DEFVAL { 0 }
    ::= { mteTriggerThresholdEntry 5 }
mteTriggerThresholdObjectsOwner OBJECT-TYPE
    SYNTAX
                 SnmpAdminString (SIZE (0..32))
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
         "To go with mteTriggerThresholdObjects, the mteOwner of a group
         of objects from mteObjectsTable."
    DEFVAL { ''H }
    ::= { mteTriggerThresholdEntry 6 }
mteTriggerThresholdObjects OBJECT-TYPE
                 SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS
                 read-write
    STATUS
                 current
    DESCRIPTION
         "The mteObjectsName of a group of objects from
         mteObjectsTable. These objects are to be added to any
         Notification resulting from the firing of this trigger for
         this test.
        A list of objects may also be added based on the overall
```

```
trigger, the event or other settings in mteTriggerTest.
        A length of 0 indicates no additional objects."
    DEFVAL { T'H }
    ::= { mteTriggerThresholdEntry 7 }
mteTriagerThresholdRisingEventOwner OBJECT-TYPE
    SYNTAX
                SnmpAdminString (SIZE (0..32))
    MAX-ACCESS
                read-write
    STATUS
                current
    DESCRIPTION
        "To go with mteTriggerThresholdRisingEvent, the mteOwner of an
        event entry from mteEventTable."
    DEFVAL { ''H }
    ::= { mteTriggerThresholdEntry 8 }
mteTriggerThresholdRisingEvent OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "The mteEventName of the event to invoke when mteTriggerType is
        'threshold' and this trigger fires based on
        mteTriggerThresholdRising. A length of 0 indicates no event."
    DEFVAL { 'ĬH }
    ::= { mteTriggerThresholdEntry 9 }
mteTriggerThresholdFallingEventOwner OBJECT-TYPE
    SYNTAX
                SnmpAdminŠtring (SIZE (0..32))
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "To go with mteTriggerThresholdFallingEvent, the mteOwner of an
    event entry from mteEventTable."
DEFVAL { ''H }
    ::= { mteTriggerThresholdEntry 10 }
mteTriggerThresholdFallingEvent OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS
                read-write
    STATUS
                current
    DESCRIPTION
        "The mteEventName of the event to invoke when mteTriggerType is
        'threshold' and this trigger fires based on
        mteTriggerThresholdFalling. A length of 0 indicates no event."
    DEFVAL { 'ĬĦ }
    ::= { mteTriggerThresholdEntry 11 }
```

```
mteTriggerThresholdDeltaRisingEventOwner OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS
                read-write
    STATUS
                current
    DESCRIPTION
        "To go with mteTriggerThresholdDeltaRisingEvent, the mteOwner
        of an event entry from mteEventTable."
    DEFVAL { ''H }
    ::= { mteTriggerThresholdEntry 12 }
mteTriggerThresholdDeltaRisingEvent OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS
                read-write
    STATUS
                current
    DESCRIPTION
        "The mteEventName of the event to invoke when mteTriggerType is
        'threshold' and this trigger fires based on
        mteTriggerThresholdDeltaRising. A length of 0 indicates
        no event."
    DEFVAL { ''H }
    ::= { mteTriggerThresholdEntry 13 }
mteTriggerThresholdDeltaFallingEventOwner OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS
                read-write
    STATUS
                current
    DESCRIPTION
        "To go with mteTriggerThresholdDeltaFallingEvent, the mteOwner
    of an event entry from mteEventTable."

DEFVAL { ''H }
    ::= { mteTriggerThresholdEntry 14 }
mteTriggerThresholdDeltaFallingEvent OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS
                read-write
                current
    STATUS
    DESCRIPTION
        "The mteEventName of the event to invoke when mteTriggerType is
        'threshold' and this trigger fires based on
        mteTriggerThresholdDeltaFalling. A length of 0 indicates
        no event."
    DEFVAL { ''H }
    ::= { mteTriggerThresholdEntry 15 }
-- Objects Table
```

```
mteObjectsTable OBJECT-TYPE
                  SEQUENCE OF MteObjectsEntry
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                  current
    DESCRIPTION
         "A table of objects that can be added to notifications based
         on the trigger, trigger test, or event, as pointed to by entries in those tables."
    ::= { mteObjects 1 }
mteObjectsEntry OBJECT-TYPE
                  MteObjectsEntry
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                  current
    DESCRIPTION
         "A group of objects. Applications create and delete entries
         using mteObjectsEntryStatus.
         When adding objects to a notification they are added in the
         lexical order of their index in this table. Those associated with a trigger come first, then trigger test, then event."

[X] { mteOwner, mteObjectsName, mteObjectsIndex }
    ::= { mteObjectsTable 1 }
MteObiectsEntry ::= SEOUENCE {
    mteObjectsName
                                             SnmpAdminString,
    mteObjectsIndex
mteObjectsID
                                             Unsigned32
                                             OBJEČT IDENTIFIER,
    mteObjectsIDWildcard
                                             TruthValue,
                                             RowStatus
    mteObjectsEntryStatus
mteObjectsName OBJECT-TYPE
    SYNTAX
                  SnmpAdminString (SIZE (1..32))
    MAX-ACCESS not-accessible
                 current
    STATUS
    DESCRIPTION
         "A locally-unique, administratively assigned name for a group
         of objects."
    ::= { mteObjectsEntry 1 }
mteObjectsIndex OBJECT-TYPE
                  Unsigned32 (1..4294967295)
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                  current
    DESCRIPTION
         "An arbitrary integer for the purpose of identifying
         individual objects within a mteObjectsName group.
```

Objects within a group are placed in the notification in the numerical order of this index.

Groups are placed in the notification in the order of the selections for overall trigger, trigger test, and event. Within trigger test they are in the same order as the numerical values of the bits defined for mteTriggerTest.

Bad object identifiers or a mismatch between truncating the identifier and the value of mteDeltaDiscontinuityIDWildcard result in operation as one would expect when providing the wrong identifier to a Get operation. The Get will fail or get the wrong object. If the object is not available it is omitted from the notification."

::= { mteObjectsEntry 2 }

mteObjectsID OBJECT-TYPE

OBJECT IDENTIFIER SYNTAX

MAX-ACCESS read-create DESCRIPTION

"The object identifier of a MIB object to add to a Notification that results from the firing of a trigger.

This may be wildcarded by truncating all or part of the instance portion, in which case the instance portion of the OID for obtaining this object will be the same as that used in obtaining the mteTriggerValueID that fired. If such wildcarding is applied, mteObjectsIDWildcard must be 'true' and if not it must be 'false'.

Each instance that fills the wildcard is independent of any additional instances, that is, wildcarded objects operate as if there were a separate table entry for each instance that fills the wildcard without having to actually predict all possible instances ahead of time.

DEFVAL { zeroDotZero } ::= { mteObjectsEntry 3 }

mteObjectsIDWildcard OBJECT-TYPE

SYNTAX TruthValue MAX-ACCESS read-create **STATUS** current

DESCRIPTION

"Control for whether mteObjectsID is to be treated as fully-specified or wildcarded, with 'true' indicating wildcard." DEFVAL { false }

::= { mteObjectsEntry 4 }

```
mteObjectsEntryStatus OBJECT-TYPE
               RowStatus
    SYNTAX
    MAX-ACCESS read-create
    STATUS
               current
    DESCRIPTION
        "The control that allows creation and deletion of entries.
       Once made active an entry MAY not be modified except to delete it."
    ::= { mteObjectsEntry 5 }
-- Event Section
-- Counters
mteEventFailures OBJECT-TYPE
    SYNTAX
               Counter32
    MAX-ACCESS read-only
    STATUS
               current
    DESCRIPTION
        "The number of times an attempt to invoke an event
       has failed. This counts individually for each
        attempt in a group of targets or each attempt for a
       wildcarded trigger object.
    ::= { mteEvent 1 }
-- Event Table
mteEventTable OBJECT-TYPE
               SEQUENCE OF MteEventEntry
    SYNTAX
    MAX-ACCESS not-accessible
              current
    STATUS
    DESCRIPTION
        "A table of management event action information."
    ::= { mteEvent 2 }
mteEventEntry OBJECT-TYPE
               MteEventEntry
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
               current
    DESCRIPTION
        "Information about a single event. Applications create and
        delete entries using mteÉventEntryStatus."
```

```
MteEventEntry ::= SEQUENCE {
    mteEventName
                                          SnmpAdminString,
    mteEventComment
                                          SnmpAdminString,
    mteEventActions
                                          BITS,
    mteEventEnabled
                                          TruthValue,
    mteEventEntryStatus
                                          RowStatus
mteEventName OBJECT-TYPE
                 SnmpAdminString (SIZE (1..32))
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "A locally-unique, administratively assigned name for the
        event.
    ::= { mteEventEntry 1 }
mteEventComment OBJECT-TYPE
                 SnmpAdminString
    SYNTAX
    MAX-ACCESS
                 read-create
    STATUS
                 current
    DESCRIPTION
        "A description of the event's function and use."
    DEFVAL { ''H }
    ::= { mteEventEntry 2 }
mteEventActions OBJECT-TYPE
                 BITS { notification(0), set(1) }
    SYNTAX
    MAX-ACCESS read-create
    STATUS
                 current
    DESCRIPTION
        "The actions to perform when this event occurs.
        For 'notification', Traps and/or Informs are sent according to the configuration in the SNMP Notification MIB.
        For 'set', an SNMP Set operation is performed according to
        control values in this entry."
    DEFVAL { {} } -- No bits set.
    ::= { mteEventEntry 3 }
mteEventEnabled OBJECT-TYPE
                TruthValue
    SYNTAX
    MAX-ACCESS read-create
    STATUS
                current
    DESCRIPTION
        "A control to allow an event to be configured but not used.
        When the value is 'false' the event does not execute even if
```

```
triggered."
    DEFVAL { false }
    ::= { mteEventEntry 4 }
mteEventEntryStatus OBJECT-TYPE
    SYNTAX
                RowStatus
    MAX-ACCESS
                read-create
    STATUS
                current
    DESCRIPTION
        "The control that allows creation and deletion of entries.
        Once made active an entry MAY not be modified except to
        delete it."
    ::= { mteEventEntry 5 }
-- Event Notification Table
mteEventNotificationTable OBJECT-TYPE
                SEQUENCE OF MteEventNotificationEntry
    SYNTAX
    MAX-ACCESS not-accessible
               current
    STATUS
    DESCRIPTION
        "A table of information about notifications to be sent as a
        consequence of management events."
    ::= { mteEvent 3 }
mteEventNotificationEntry OBJECT-TYPE
    SYNTAX
                MteEventNotificationEntry
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "Information about a single event's notification. Entries
        automatically exist in this this table for each mteEventEntry that has 'notification' set in mteEventActions."
    INDEX
MteEventNotificationEntry ::= SEQUENCE {
                                         OBJECT IDENTIFIER,
    mteEventNotification
    mteEventNotificationObjectsOwner
                                         SnmpAdminString,
    mteEventNotificationObjects
                                         SnmpAdminString
    }
mteEventNotification OBJECT-TYPE
                OBJECT IDENTIFIER
    SYNTAX
    MAX-ACCESS read-write
    STATUS
              current
```

```
DESCRIPTION
        "The object identifier from the NOTIFICATION-TYPE for the
        notification to use if metEventActions has 'notification' set."
    DEFVAL { zeroDotZero }
    ::= { mteEventNotificationEntry 1 }
mteEventNotificationObjectsOwner OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    SYNTAX
    MAX-ACCESS
                read-write
    STATUS
                current
    DESCRIPTION
        "To go with mteEventNotificationObjects, the mteOwner of a
        group of objects from mteObjectsTable.'
    DEFVĀL { ''H }
    ::= { mteEventNotificationEntry 2 }
mteEventNotificationObjects OBJECT-TYPE
                SnmpAdminString (SIZE (0..32))
    MAX-ACCESS
              read-write
    STATUS
                current
    DESCRIPTION
        "The mteObjectsName of a group of objects from
        mteObjectsTable if mteEventActions has 'notification' set.
        These objects are to be added to any Notification generated by
        this event.
        Objects may also be added based on the trigger that stimulated
        the event.
        A length of 0 indicates no additional objects."
    DEFVAL { T'H }
    ::= { mteEventNotificationEntry 3 }
-- Event Set Table
mteEventSetTable OBJECT-TYPE
                SEQUENCE OF MteEventSetEntry
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "A table of management event action information."
    ::= { mteEvent 4 }
mteEventSetEntry OBJECT-TYPE
                MteEventSetEntry
    SYNTAX
    MAX-ACCESS not-accessible
```

```
STATUS
               current
    DESCRIPTION
        "Information about a single event's set option. Entries
        automatically exist in this this table for each mteEventEntry
        that has 'set' set in mteEventActions."
    MteEventSetEntry ::= SEQUENCE {
    mteEventSetObject
                                        OBJECT IDENTIFIER,
    mteEventSetObjectWildcard
                                        TruthValue,
    mteEventSetValue
                                        Integer32,
                                        SnmpTagValue,
    mteEventSetTargetTag
                                        SnmpAdminString,
    mteEventSetContextName
    mteEventSetContextNameWildcard
                                        TruthValue
mteEventSetObject OBJECT-TYPE
               OBJECT IDENTIFIER
    SYNTAX
    MAX-ACCESS read-write
    DESCRIPTION
        "The object identifier from the MIB object to set if
        mteEventActions has 'set' set.
        This object identifier may be wildcarded by leaving
        sub-identifiers off the end, in which case
        nteEventSetObjectWildCard must be 'true'.
        If mteEventSetObject is wildcarded the instance used to set the
        object to which it points is the same as the instance from the
        value of mteTriggerValueID that triggered the event.
        Each instance that fills the wildcard is independent of any
        additional instances, that is, wildcarded objects operate
        as if there were a separate table entry for each instance
        that fills the wildcard without having to actually predict
        all possible instances ahead of time.
        Bad object identifiers or a mismatch between truncating the
        identifier and the value of mteSetObjectWildcard
        result in operation as one would expect when providing the
        wrong identifier to a Set operation. The Set will fail or set
the wrong object. If the value syntax of the destination
        object is not correct, the Set fails with the normal SNMP
        error code."
    DEFVAL { zeroDotZero }
```

::= { mteEventSetEntry 1 }

```
mteEventSetObjectWildcard OBJECT-TYPE
                 TruthValue
    SYNTAX
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
        "Control over whether mteEventSetObject is to be treated as
        fully-specified or wildcarded, with 'true' indicating wildcard if mteEventActions has 'set' set."
    DEFVAL { false }
    ::= { mteEventSetEntry 2 }
mteEventSetValue OBJECT-TYPE
    SYNTAX
                 Integer32
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
         "The value to which to set the object at mteEventSetObject
        if mteEventActions has 'set' set.
    DEFVAL { 0 }
    ::= { mteEventSetEntry 3 }
mteEventSetTargetTag OBJECT-TYPE
    SYNTAX
                 SnmpTagValue
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "The tag for the target(s) at which to set the object at
        mteEventSetObject to mteEventSetValue if mteEventActions
        has 'set' set.
        Systems limited to self management MAY reject a non-zero
        length for the value of this object.
        A length of 0 indicates the local system. In this case.
        access to the objects indicated by mteEventSetObject is under
        the security credentials of the requester that set mteTriggerEntryStatus to 'active'. Those credentials are the
        input parameters for isAccessAllowed from the Architecture for
        Describing SNMP Management Frameworks.
        Otherwise access rights are checked according to the security
        parameters resulting from the tag."
    DEFVAL { ''H }
    ::= { mteEventSetEntry 4 }
mteEventSetContextName OBJECT-TYPE
                 SnmpAdminString
    SYNTAX
    MAX-ACCESS read-write
```

```
STATUS
                current
    DESCRIPTION
        "The management context in which to set mteEventObjectID.
        if mteEventActions has 'set' set.
        This may be wildcarded by leaving characters off the end. To
        indicate such wildcarding mteEventSetContextNameWildcard must
        be 'true'.
        If this context name is wildcarded the value used to complete
        the wildcarding of mteTriggerContextName will be appended."
    DEFVAL { ''H }
    ::= { mteEventSetEntry 5 }
mteEventSetContextNameWildcard OBJECT-TYPE
    SYNTAX
               TruthValue
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "Control for whether mteEventSetContextName is to be treated as
        fully-specified or wildcarded, with 'true' indicating wildcard if mteEventActions has 'set' set."
    DEFVAL { false }
    ::= { mteEventSetEntrv 6 }
-- Notifications
dismanEventMIBNotificationPrefix OBJECT IDENTIFIER ::=
    { dismanEventMIB 2 }
dismanEventMIBNotifications OBJECT IDENTIFIER ::=
    { dismanEventMIBNotificationPrefix 0 }
dismanEventMIBNotificationObjects OBJECT IDENTIFIER
   ::= { dismanEventMIBNotificationPrefix 1 }
-- Notification Objects
mteHotTrigger OBJECT-TYPE
    SYNTAX
                SnmpAdminString
    MAX-ACCESS accessible-for-notify
    STATUS
                current
    DESCRIPTION
        "The name of the trigger causing the notification."
    ::= { dismanEventMIBNotificationObjects 1 }
```

```
mteHotTargetName OBJECT-TYPE
    SYNTAX
                SnmpAdminString
    MAX-ACCESS accessible-for-notify
    STATUS
                current
    DESCRIPTION
        "The SNMP Target MIB's snmpTargetAddrName related to the
        notification.
    ::= { dismanEventMIBNotificationObjects 2 }
mteHotContextName OBJECT-TYPE
                SnmpAdminString
    MAX-ACCESS accessible-for-notify
    STATUS
                current
    DESCRIPTION
        "The context name related to the notification. This MUST be as
        fully-qualified as possible, including filling in wildcard
        information determined in processing.
    ::= { dismanEventMIBNotificationObjects 3 }
mteHotOID OBJECT-TYPE
                OBJECT IDENTIFIER
    SYNTAX
    MAX-ACCESS accessible-for-notify
    STATUS current
    DESCRIPTION
        "The object identifier of the destination object related to the
        notification. This MUST be as fully-qualified as possible,
        including filling in wildcard information determined in
        processing.
        For a trigger-related notification this is from
        mteTriggerValueID.
        For a set failure this is from mteEventSetObject."
    ::= { dismanEventMIBNotificationObjects 4 }
mteHotValue OBJECT-TYPE
                Integer32
    SYNTAX
    MAX-ACCESS accessible-for-notify
    STATUS
               current
    DESCRIPTION
        "The value of the object at mteTriggerValueID when a
        trigger fired."
    ::= { dismanEventMIBNotificationObjects 5 }
mteFailedReason OBJECT-TYPE
              FailureReason
    SYNTAX
    MAX-ACCESS accessible-for-notify
    STATUS current
```

```
DESCRIPTION
        "The reason for the failure of an attempt to check for a
        trigger condition or set an object in response to an event."
    ::= { dismanEventMIBNotificationObjects 6 }
-- Notifications
mteTriggerFired NOTIFICATION-TYPE
    OBJECTS { mteHotTrigger,
              mteHotTargetName,
              mteHotContextName,
              mteHotOID,
              mteHotValue }
    STATUS current
    DESCRIPTION
        "Notification that the trigger indicated by the object
        instances has fired, for triggers with mteTriggerType 'boolean' or 'existence'."
    ::= { dismanEventMIBNotifications 1 }
mteTriggerRising NOTIFICATION-TYPE
    OBJECTS { mteHotTrigger,
              mteHotTargetName.
              mteHotContextName,
              mteHotOID,
              mteHotValue }
    STATUS current
    DESCRIPTION
        "Notification that the rising threshold was met for triggers
        with mteTriggerType 'threshold'."
    ::= { dismanEventMIBNotifications 2 }
mteTriggerFalling NOTIFICATION-TYPE
    OBJECTS { mteHotTrigger,
              mteHotTargetName,
              mteHotContextName,
              mteHotOID.
              mteHotValue }
    STATUS current
    DESCRIPTION
        "Notification that the falling threshold was met for triggers
        with mteTriggerType 'threshold'
    ::= { dismanEventMIBNotifications 3 }
mteTriggerFailure NOTIFICATION-TYPE
    OBJECTS { mteHotTrigger,
```

```
mteHotTargetName,
               mteHotContextName,
               mteHotOID,
               mteFailedReason }
    STATUS
             current
    DESCRIPTION
         "Notification that an attempt to check a trigger has failed.
         The network manager must enable this notification only with
         a certain fear and trembling, as it can easily crowd out more
         important information. It should be used only to help diagnose
         a problem that has appeared in the error counters and can not
         be found otherwise."
    ::= { dismanEventMIBNotifications 4 }
mteEventSetFailure NOTIFICATION-TYPE
    OBJECTS { mteHotTrigger,
               mteHotTargetName,
               mteHotContextName,
               mteHotOID.
               mteFailedŔeason }
    STATUS current
    DESCRIPTION
         "Notification that an attempt to do a set in response to an
         event has failed.
         The network manager must enable this notification only with a certain fear and trembling, as it can easily crowd out more important information. It should be used only to help diagnose
         a problem that has appeared in the error counters and can not
be found otherwise."
    ::= { dismanEventMIBNotifications 5 }
-- Conformance
dismanEventMIBConformance OBJECT IDENTIFIER ::= { dismanEventMIB 3 }
dismanEventMIBCompliances OBJECT IDENTIFIER ::=
    { dismanEventMIBConformance 1 }
                             OBJECT IDENTIFIER ::=
dismanEventMIBGroups
    { dismanEventMIBConformance 2 }
-- Compliance
dismanEventMIBCompliance MODULE-COMPLIANCE
         STATUS current
         DESCRIPTION
```

```
"The compliance statement for entities which implement
        the Event MIB.
MODULE
        -- this module
        MANDATORY-GROUPS {
                dismanEventResourceGroup,
                dismanEventTriggerGroup,
                dismanEventObjectsGroup,
                dismanEventEventGroup,
                dismanEventNotificationObjectGroup,
                dismanEventNotificationGroup
        }
        OBJECT mteTriggerTargetTag
        MIN-ACCESS read-only
        DESCRIPTION
                "Write access is not required, thus limiting
                monitoring to the local system or pre-configured
                remote systems."
        OBJECT mteEventSetTargetTag
        MIN-ACCESS read-only
        DESCRIPTION
                "Write access is not required, thus limiting
                setting to the local system or pre-configured
                remote systems."
        OBJECT mteTriggerValueIDWildcard
        MIN-ACCESS read-only
        DESCRIPTION
                "Write access is not required, thus allowing
                the system not to implement wildcarding.'
        OBJECT mteTriggerContextNameWildcard
        MIN-ACCESS read-only
        DESCRIPTION
                "Write access is not required, thus allowing
                the system not to implement wildcarding."
        OBJECT mteObjectsIDWildcard
        MIN-ACCESS read-only
        DESCRIPTION
                "Write access is not required, thus allowing
                the system not to implement wildcarding.
        OBJECT mteEventSetContextNameWildcard
        MIN-ACCESS read-only
        DESCRIPTION
```

```
"Write access is not required, thus allowing
                        the system not to implement wildcarding.'
        ::= { dismanEventMIBCompliances 1 }
-- Units of Conformance
dismanEventResourceGroup OBJECT-GROUP
        OBJECTS {
                mteResourceSampleMinimum,
                mteResourceSampleInstanceMaximum,
                mteResourceSampleInstances,
                mteResourceSampleInstancesHigh,
                mteResourceSampleInstanceLacks
        STATUS current
        DESCRIPTION
                "Event resource status and control objects."
        ::= { dismanEventMIBGroups 1 }
dismanEventTriggerGroup OBJECT-GROUP
        OBJECTS {
                mteTriggerFailures,
                mteTriggerComment,
                mteTriggerTest,
                mteTriggerSampleType,
                mteTriggerValueID
                mteTriggerValueIDWildcard,
                mteTriggerTargetTag,
                mteTriggerContextName,
                mteTriggerContextNameWildcard,
                mteTriggerFrequency,
                mteTriggerObjectsOwner,
                mteTriggerObjects,
                mteTriggerEnabled,
                mteTriggerEntryStatus,
                mteTriggerDeltaDiscontinuityID,
                mteTriggerDeltaDiscontinuityIDWildcard,
                mteTriggerDeltaDiscontinuityIDType,
                mteTriggerExistenceTest,
                mteTriggerExistenceStartup,
                mteTriggerExistenceObjectsOwner,
                mteTriggerExistenceObjects,
                mteTriggerExistenceEventOwner,
                mteTriggerExistenceEvent,
```

```
mteTriggerBooleanComparison,
                 mteTriggerBooleanValue,
                 mteTriggerBooleanStartup.
                 mteTriggerBooleanObjectsOwner.
                 mteTriggerBooleanObjects,
                 mteTriggerBooleanEventOwner,
                 mteTriggerBooleanEvent,
                 mteTriggerThresholdStartup,
                 mteTriggerThresholdObjectsOwner,
                 mteTriggerThresholdObjects,
                 mteTriggerThresholdRising,
                 mteTriggerThresholdFalling,
                 mteTriggerThresholdDeltaRising,
                 mteTriggerThresholdDeltaFalling,
                 mteTriggerThresholdRisingEventOwner,
                 mteTriggerThresholdRisingEvent,
                 mteTriggerThresholdFallingEventOwner,
                 mteTriggerThresholdFallingEvent,
                 mteTriggerThresholdDeltaRisingEventOwner,
                mteTriggerThresholdDeltaRisingEvent,
mteTriggerThresholdDeltaFallingEventOwner,
                 mteTriggerThresholdDeltaFallingEvent
        STATUS current
        DESCRIPTION
                 "Event triggers."
        ::= { dismanEventMIBGroups 2 }
dismanEventObjectsGroup OBJECT-GROUP
        OBJECTS {
                 mteObjectsID,
                 mteObjectsIDWildcard,
                 mteObjectsEntryStatus
        STATUS current
        DESCRIPTION
                 "Supplemental objects."
        ::= { dismanEventMIBGroups 3 }
dismanEventEventGroup OBJECT-GROUP
        OBJECTS {
                 mteEventFailures.
                 mteEventComment,
                 mteEventActions,
                 mteEventEnabled,
                 mteEventEntryStatus,
```

```
mteEventNotification,
                mteEventNotificationObjectsOwner,
                mteEventNotificationObjects,
                mteEventSetObject,
                mteEventSetObjectWildcard,
                mteEventSetValue,
mteEventSetTargetTag,
                mteEventSetContextName,
                mteEventSetContextNameWildcard
        STATUS current
        DESCRIPTION
                 "Events."
        ::= { dismanEventMIBGroups 4 }
dismanEventNotificationObjectGroup OBJECT-GROUP
        OBJECTS {
                mteHotTrigger,
                mteHotTargetName,
                mteHotContextName,
                mteHotOID,
                mteHotValue,
                mteFailedReason
        STATUS current
        DESCRIPTION
                 "Notification objects."
        ::= { dismanEventMIBGroups 5 }
dismanEventNotificationGroup NOTIFICATION-GROUP
        NOTIFICATIONS {
                mteTriggerFired,
                mteTriggerRising,
                mteTriggerFalling,
                mteTriggerFailure,
                mteEventSetFailuré
        STATUS current
        DESCRIPTION
                 "Notifications."
        ::= { dismanEventMIBGroups 6 }
END
```

8. Intellectual Property

The IETF takes no position regarding the validity or scope of any intellectual property or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; neither does it represent that it has made any effort to identify any such rights. Information on the IETF's procedures with respect to rights in standards-track and standards- related documentation can be found in BCP-11. Copies of claims of rights made available for publication and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementors or users of this specification can be obtained from the IETF Secretariat.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights which may cover technology that may be required to practice this standard. Please address the information to the IETF Executive Director.

9. Acknowledgements

This MIB contains considerable contributions from the RMON MIB. the Distributed Management Design Team (Andy Bierman, Maria Greene, Bob Stewart, and Steve Waldbusser), the Distributed Management Working Group, and colleagues at Cisco.

10. References

- [RFC2571] Harrington, D., Presuhn, R. and B. Wijnen, "An Architecture for Describing SNMP Management Frameworks", RFC 2571, April 1999.
- [RFC1155] Rose, M. and K. McCloghrie, "Structure and Identification of Management Information for TCP/IP-based Internets", STD 16, RFC 1155, May 1990.
- [RFC1212] Rose, M. and K. McCloghrie, "Concise MIB Definitions", STD 16, RFC 1212, March 1991.
- Rose, M., "A Convention for Defining Traps for use with the SNMP", RFC 1215, March 1991. [RFC1215]

- McCloghrie, K., Perkins, D., Schoenwaelder, J., Case, J., Rose, M. and S. Waldbusser, "Structure of Management Information Version 2 (SMIv2)", STD 58, RFC 2578, April [RFC2578] 1999.
- McCloghrie, K., Perkins, D., Schoenwaelder, J., Case, J., Rose, M. and S. Waldbusser, "Textual Conventions for SMIv2", STD 58, RFC 2579, April 1999. [RFC2579]
- McCloghrie, K., Perkins, D., Schoenwaelder, J., Case, J., Rose, M. and S. Waldbusser, "Conformance Statements for [RFC2580] SMIv2", STD 58, RFC 2580, April 1999.
- Case, J., Fedor, M., Schoffstall, M. and J. Davin, "Simple Network Management Protocol", STD 15, RFC 1157, [RFC1157] May 1990.
- [RFC1901] Case, J., McCloghrie, K., Rose, M. and S. Waldbusser, "Introduction to Community-based SNMPv2", RFC 1901, January 1996.
- Case, J., McCloghrie, K., Rose, M. and S. Waldbusser, "Transport Mappings for Version 2 of the Simple Network [RFC1906] Management Protocol (SNMPv2)", RFC 1906, January 1996.
- Case, J., Harrington D., Presuhn R. and B. Wijnen, [RFC2572] "Message Processing and Dispatching for the Simple Network Management Protocol (SNMP)", RFC 2572, April
- Blumenthal, U. and B. Wijnen, "User-based Security Model [RFC2574] (USM) for version 3 of the Simple Network Management Protocol (SNMPv3)", RFC 2574, April 1999.
- Case, J., McCloghrie, K., Rose, M. and S. Waldbusser, "Protocol Operations for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1905, January 1996. [RFC1905]
- Levi, D., Meyer, P. and B. Stewart, "SNMPv3 [RFC2573] Applications", RFC 2573, April 1999.
- Wijnen, B., Presuhn, R. and K. McCloghrie, "View-based Access Control Model (VACM) for the Simple Network [RFC2575] Management Protocol (SNMP)", RFC 2575, April 1999.
- Case, J., Mundy, R., Partain, D. and B. Stewart, "Introduction to Version 3 of the Internet-standard Network Management Framework", RFC 2570, April 1999. [RFC2570]

- [RFC1903] Case, J., McCloghrie, K., Rose, M. and S. Waldbusser, "Coexistence between Version 1 and version 2 of the Internet-standard Network Management Framework", RFC 1903, January 1996.
- [RFC2981] Stewart, B., "Event MIB", RFC 2981, October 2000.
- [RFC1757] Waldbusser, S., "Remote Network Monitoring Management Information Base", RFC 1757, February 1995.
- [RFC1451] Case, J., McCloghrie, K., Rose, M. and S. Waldbusser, "Manager-to- Manager Management Information Base", RFC 1451, April 1993.
- [RFC2982] Stewart, B., "Distributed Management Expression MIB", RFC 2982, October 2000.
- [LOG-MIB] Stewart, B., "Notification Log MIB", Work in Progress.

11. Security Considerations

Security issues are discussed in the Security section and in the DESCRIPTION clauses of relevant objects.

12. Author's Address

Bob Stewart Cisco Systems, Inc. 170 West Tasman Drive San Jose, CA 95134-1706 U.S.A.

13. Editor's Address

Ramanathan Kavasseri Cisco Systems, Inc. 170 West Tasman Drive San Jose, CA 95134-1706 U.S.A.

Phone: +1 408 527 2446 EMail: ramk@cisco.com

14. Full Copyright Statement

Copyright (C) The Internet Society (2000). All Rights Reserved.

This document and translations of it may be copied and furnished to others, and derivative works that comment on or otherwise explain it or assist in its implementation may be prepared, copied, published and distributed, in whole or in part, without restriction of any kind, provided that the above copyright notice and this paragraph are included on all such copies and derivative works. However, this document itself may not be modified in any way, such as by removing the copyright notice or references to the Internet Society or other Internet organizations, except as needed for the purpose of developing Internet standards in which case the procedures for copyrights defined in the Internet Standards process must be followed, or as required to translate it into languages other than English.

The limited permissions granted above are perpetual and will not be revoked by the Internet Society or its successors or assigns.

This document and the information contained herein is provided on an "AS IS" basis and THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.