

Unchanged options	
<code>l</code>	Left adjusted column.
<code>c</code>	Centered adjusted column.
<code>r</code>	Right adjusted column.
<code>p{width}</code>	Equivalent to <code>\parbox[t]{width}</code> .
<code>@{decl.}</code>	Suppresses inter-column space and inserts <code>decl.</code> instead.
New options	
<code>m{width}</code>	Defines a column of width <code>width</code> . Every entry will be centered in proportion to the rest of the line. It is somewhat like <code>\parbox{width}</code> .
<code>b{width}</code>	Coincides with <code>\parbox[b]{width}</code> .
<code>>{decl.}</code>	Can be used before an <code>l</code> , <code>r</code> , <code>c</code> , <code>p</code> , <code>m</code> or a <code>b</code> option. It inserts <code>decl.</code> directly in front of the entry of the column.
<code><{decl.}</code>	Can be used after an <code>l</code> , <code>r</code> , <code>c</code> , <code>p{...}</code> , <code>m{...}</code> or a <code>b{...}</code> option. It inserts <code>decl.</code> right after the entry of the column.
<code> </code>	Inserts a vertical line. The distance between two columns will be enlarged by the width of the line in contrast to the original definition of L ^A T _E X.
<code>!{decl.}</code>	Can be used anywhere and corresponds with the <code> </code> option. The difference is that <code>decl.</code> is inserted instead of a vertical line, so this option doesn't suppress the normally inserted space between columns in contrast to <code>@{...}</code> .
<code>w{align}{width}</code>	Sets the cell content in a box of the specified <code>width</code> aligned according to the <code>align</code> parameter which could be either <code>l</code> , <code>c</code> or <code>r</code> . Works essentially like <code>\makebox[width][align]{cell}</code> so silently overprints if the cell content is wider than the specified width. If that is not desired use <code>W</code> instead.
<code>W{align}{width}</code>	Like <code>w</code> but spits out an overfull box warning (and an overfullrule marker in draft mode) when the cell content is too wide to fit. This also means that the alignment is different if there is too much material, because it then always protrudes to the right!

Table 1: The preamble options.

- In columns which have been generated with `p`, `m` or `b`, the default value of `\parindent` is `0pt`. This can be changed with `>\setlength{\parindent}{1cm}}p`.
- The `>`- and `<`-options were originally developed for the following application: `>{$}c<{$}` generates a column in math mode in a `tabular`-environment. If you use this type of a preamble in an `array`-environment, you get a column in LR mode because the additional `$`'s cancel the existing `$`'s.
Note that the arguments should only contain declarations, see the section below.
- Using `c!{\hspace{1cm}}c` you get space between two columns which is enlarged by one centimeter, while `c@{\hspace{1cm}}c` gives you exactly one centimeter space