# TEACUP v1.1 – A System for Automated TCP Testbed Experiments

Editors: Sebastian Zander, Grenville Armitage s.zander@murdoch.edu.au, garmitage@swin.edu.au

Abstract—Over the last few decades several TCP congestion control algorithms were developed in order to optimise TCP's behaviour in certain situations. While TCP was traditionally used mainly for file transfers, more recently it is also becoming the protocol of choice for streaming applications, for example video streaming from YouTube and Netflix is TCP-based [1], [2] and there is an ISO standard for Dynamic Adaptive Streaming over HTTP (DASH) [3]. However, the impact of different TCP congestion control algorithms on TCP-based streaming flows (within a mix of other typical traffic) is not well understood. Experiments in a controlled testbed allow shedding more light on this issue. This report describes TEACUP (TCP Experiment Automation Controlled Using Python) version 1.1 - a software tool for running automated TCP experiments in a testbed. Based on a configuration file TEACUP can perform a series of experiments with different traffic mixes, different bottleneck configurations (such as bandwidths, queue mechanisms), different emulated network delays and/or loss rates, and different host settings (e.g. used TCP congestion control algorithm). For each experiment TEACUP automatically collects relevant information that allows analysing TCP behaviour, such as tcpdump files and TCP stack information.

#### Index Terms—TCP, experiments, automated control

	CONTENTS			V	Config File – format and functionality		13
					V-A	Location of config.py	13
I	Introdu	ıction	3		V-B	V_variables	14
					V-C	Fabric configuration	14
II	<b>TEACUP Motivation and Design</b>		3		V-D	Testbed configuration	14
	II-A	Motivations and requirements	3		V-E	Sanity checks settings	14
	II-B	Overall design	4		V-F	General experiment settings	15
	II-C	Experiment naming and process flow	5		V-G	tcpdump/pcap snaplen configuration	15
	II-D	Fabric – overview and installation	5		V-H	Topology configuration	15
					V-I	Rebooting, OS selection and	
III	Traffic Generation and Logging		6			power cycling	16
	III-A	Traffic sources and sinks	6		V-J	Clock offset measurement (broad-	
	III-B	Loggers	7			cast pings)	18
	III-C	Log file naming – syntax and			V-K	Custom host init commands	18
		structure	8		V-L	Router queue setup	19
	III-D	Host and router information logging	9		V-M	Traffic generator setup	20
	III-E	Config information logging	10		V-N	Mandatory experiment variables .	21
			4.0		V-O	Experiment-specific variables	23
IV	Host and Router Configuration		10		V-P	Defining parameters to vary	23
	IV-A	Host setup	10 10		V-Q	Adding new V_ variables	24
	IV-B	Linux-based bottleneck router setup			, ~	ridding new v_ variables	
	IV-C	FreeBSD-based bottleneck router		VI	Availal	ole traffic generators	24
		setup	12			start inerf	2/

	VI-B	start_ping	25		X-A	Additional host setup	44
	VI-C	start_http_server	25		X-B	New TCP congestion control al-	
	VI-D	start_nginx_server	25			gorithm	44
	VI-E	create_http_dash_content	25		X-C	New traffic generator	44
	VI-F	create_http_incast_content	25		X-D	New data logger	45
	VI-G	start_httperf	26		X-E	New analysis method	46
	VI-H	start_httperf_dash	26				
	VI-I	start_dash_streaming_dashjs	27	XI	Knowi	n Issues	46
	VI-J	start_httperf_incast	27	<b>X</b> / <b>XX</b>	<i>C</i> 1	• 154 157	4.5
	VI-K	start_nttcp	27	XII	Concil	usions and Future Work	47
	VI-L	start_httperf_incast_n	27	Dofor	rences		47
	VI-M	start_fps_game	28	Kerei	ciices		7/
VII	Running Experiments						
	VII-A	Initial steps	29				
	VII-B	Example config	29				
	VII-C	Running experiments	29				
	VII-D	TEACUP variable information					
		logged	31				
VIII	<b>Host Control Utility Functions</b>		31				
	VIII-A	Remote command execution	31				
	VIII-B	Copying files to testbed hosts	31				
	VIII-C	Installing ssh keys	32				
	VIII-D	Topology configuration	32				
	VIII-E	Initialise hosts to a specific operating system	32				
	VIII-F	Power cycling	33				
	VIII-G	Check software installations on	33				
	VIII-O	testbed hosts	33				
	VIII-H	Check testbed host connectivity .	33				
	VIII-II VIII-I	Check TEACUP config file	33				
IX	Experir	ment Examples	33				
	IX-A Overview						
	IX-B	Scenario 1: Two TCP flows from	33				
		data sender to receiver	34				
	IX-C	Scenario 2: Scenario 1 plus auto-					
		matic booting of hosts	38				
	IX-D	Scenario 3: Scenario 1 plus power					
		control	39				
	IX-E	Scenario 4: TCP flows with same					
		bottleneck queue but different delay	40				
	IX-F	Scenario 5: Partially overlapping					
		TCP flows with different TCP CC	41				
	IX-G	Scenario 6: One HTTP-based					
		(DASH) video streaming client	43				
	IX-H	Scenario 7: Incast problem scenario	43				
X	<b>Extending TEACUP Functionality</b>						

#### I. Introduction

Over the last few decades several TCP congestion control algorithms were developed in order to optimise TCP's behaviour in certain situations. While TCP was traditionally used mainly for file transfers, more recently it is also becoming the protocol of choice for streaming applications, for example video streaming from YouTube and Netflix is TCP-based [1], [2] and there is an ISO standard for Dynamic Adaptive Streaming over HTTP (DASH) [3]. However, the impact of different TCP congestion control algorithms on TCP-based streaming flows (within a mix of other typical traffic) is not well understood. Experiments in a controlled testbed allow shedding more light on this issue.

This report<sup>1</sup> describes TEACUP (TCP Experiment Automation Controlled Using Python) version 1.1 – a software tool for running automated TCP experiments in a testbed. The TEACUP project originated at Swinburne University of Technology's Centre for Advanced Internet Architectures (http://caia.swin.edu.au/tools/teacup), and from version 1.0 the source code is freely available on SourceForge at http://sourceforge.net/projects/teacup

Based on a python configuration file, TEACUP can perform a series of experiments with different traffic mixes, different bottlenecks (such as bandwidths, queue mechanisms), different emulated network delays and/or loss rates, and different host settings (e.g. TCP congestion control algorithm). For each experiment TEACUP automatically collects relevant information that allows analysing TCP behaviour, such as tcpdump files, SIFTR [5] and Web10G [6] logs. A related technical report [7] describes the design and implementation of a specific testbed designed to be controlled by TEACUP.

TEACUP also provides a number of tasks for the analysis of data collected during experiments. The analysis aspect of TEACUP is quite distinct from the tasks that actually run experiments and gather testbed data, hence these are described in the accompanying technical report [8].

This report is organised as follows. Section II describes the overall design of TEACUP – the testbed network model, process flow and use of Fabric. Section III outlines the traffic generators and logging available under

TEACUP, while host and bottleneck router configuration is summarised in Section IV. Section V describes the configuration options available when running experiments as described in Section VII. Section VIII describes utility functions that can be used for host maintenance. Section X outlines how to extend TEACUP. Section XI lists known issues. Section XII concludes and outlines future work.

#### II. TEACUP MOTIVATION AND DESIGN

This section describes the goals that motivated TEACUP's design. We first list the intended requirements. Then we describe the overall functional block design and the process flow. Finally, we describe the naming scheme for log files.

# A. Motivations and requirements

Here we describe the requirements that motivated our design of TEACUP.

- 1) General: Create a system to automate performing a series of TCP experiments with varying parameters.
- 2) Topology: TEACUP runs experiments in a controlled environment like that shown in Figure 1 [7], where one bottleneck router interconnects two *experiment networks*. The experiment networks contain hosts that can act as traffic sources and sinks. The router, all hosts and TEACUP (on a control server) are also connected to a separate *control network*.<sup>2</sup> TEACUP configures hosts before each experiment and collects data from hosts after each experiment.<sup>3</sup> Where the control network is a private network, the control server may act as a NAT gateway enabling all testbed hosts to access the public Internet if necessary.
- 3) TCP algorithms: Multiple TCP congestion control algorithms must be supported, including: NewReno and CUBIC (representing classic loss-based algorithms), CompoundTCP (Microsoft's hybrid), CDG (CAIA's hybrid), and HD (Hamilton Institutes' delay-based TCP). Optionally other TCPs may be supported. All the noted TCP algorithms are sender-side variants, so the destination can be any standard TCP implementation.

<sup>&</sup>lt;sup>1</sup>Available online at https://sourceforge.net/projects/teacup/files/ TEACUP-System-v1.1.pdf and updating a previous report that covered TEACUP version 1.0 [4].

<sup>&</sup>lt;sup>2</sup>The control server also runs a DHCP+TFTP server for the PXE boot setup described in [7].

<sup>&</sup>lt;sup>3</sup>If the networks are implemented as VLANs on a suitable Ethernet switch, TEACUP can also automate the assignment of hosts to one or the other experiment network and associated VLAN (Section V-H).




Figure 1: Testbed topology

- 4) Path characteristics: The system must be able to create bottleneck bandwidth limits to represent likely consumer experience (e.g. ADSL) and some data centre scenarios. Emulation of constant path delay and loss in either direction is required to simulate different conditions between traffic sources and sinks. The emulation is implemented by the bottleneck node (router).
- 5) Bottleneck AQM: The following Active Queuing Management (AQM) mechanisms are required: Tail-Drop/FIFO, CoDel, PIE, FQ-CoDel, RED. Optionally other AQM mechanisms may be supported, with the router being able to run either Linux or FreeBSD (10.3 onwards). The buffer size must be configurable.
- 6) ECN Support: It must be possible to enable/disable Explicit Congestion Notification (ECN) on hosts and/or router.
- 7) Host OS: TEACUP is largely OS-agnostic. However, to cover the various TCP algorithms and their common implementations TEACUP must support scenarios where sources and/or destinations are Windows (Compound), Linux (NewReno, CUBIC), FreeBSD (NewReno, CUBIC, CDG, HD) or Mac OS X (NewReno). Cygwin is used to instrument Windows [7].
- 8) Traffic loads: The following traffic loads must be supported: Streaming media over HTTP/TCP (DASH-like), TCP bulk transfer, UDP flows (VoIP-like), and data centre query/response patterns (one query to N responders, correlated return traffic causing incast congestion).

#### B. Overall design

TEACUP is built on Fabric [9] (Section II-D), a Python (2.5 or higher) library and command-line tool for streamlining the remote application deployment or system administration tasks using SSH. Our design is based on multiple small tasks that are combined to run an experiment or a series of experiments (where some may also be executed directly from the command line). Functions which are not Fabric tasks are ordinary Python functions. Currently, we do not make use of the object-oriented capabilities of Python.

Figure 2 shows the main functional building blocks. All the blocks in the diagram have corresponding Python files. However, we have summarised a number of Python files in the helper\_functions block. The fabfile block is the entry point for the user. It implements tasks for running a single experiment or a series of similar experiments with different parameters. The fabfile block also provides access to all other tasks via Python imports.

The experiment block implements the main function that controls a single experiment and uses a number of functions of other blocks. The sanity\_checks block implements functions to check the config file, the presence of tools on the hosts, the connectivity between hosts, and a function to kill old processes that are still running. The host\_setup block implements all functions to setup networking on the testbed hosts (including basic setup of the testbed router). The router\_setup block implements

the functions that set up the queues on the router and the delay/loss emulation. The loggers block implements the start and stop functions of the loggers, such as tcpdump and SIFTR/web10g loggers. The traffic\_gens block implements the start and stop functions of all traffic generators.

The util block contains utility tasks that can be executed from the command line, such as executing a command on a number of testbed hosts or copying a file to a number of testbed hosts. The analysis block contains all the post-processing functions that extract measurement metrics from log files and plot graphs.

# C. Experiment naming and process flow

An individual experiment consists of running one or more traffic generators for configurable periods of time across a path emulating specific network conditions. TEACUP identifies individual experiments by their **test ID**, a text string used to construct experiment-specific log files (such as testbed metadata, captured system state and captured traffic). TEACUP also allows grouping of closely related experiments under a common **test ID prefix**, where individual experiments (testIDs) are generated for each iteration over a range of values for a subset of parameters controlling testbed conditions (see section III-C). The test ID prefix for an experiment or group of experiments is also used to name distinct subdirectories for storing groups of log files and related metadata.

The following list explains the main steps that are executed during an experiment or a series of experiments.

- I) Initialise and check config file
- II) Get parameter combination for next experiment
- III) Start experiment based on config and parameter configuration
  - 1) Log experiment **test ID** in file experiments\_started.txt
  - Get host information: OS, NIC names, NIC MAC addresses
  - 3) Reboot hosts: reboot hosts as required given the configuration
  - 4) Topology reconfiguration (assign hosts to subnets)
  - 5) Get host information again: OS, NIC names, NIC MAC addresses
  - 6) Run sanity checks

- Check that tools to be used exist
- Check connectivity between hosts
- Kill any leftover processes on hosts
- 7) Initialise hosts
  - Configure NICs (e.g. disable TSO)
  - Configure ECN use
  - Configure TCP congestion control
  - Initialise router queues
- 8) Configure router queues: set router queues based on config
- 9) Log host state: log host information (see Section III-D)
- 10) Start all logging processes: tcpdump, SIFTR/Web10G etc.
- 11) Start all traffic generators: start traffic generators based on config
- 12) Wait for experiment to finish
- 13) Stop all running processes on hosts
- 14) Collect all log files from logging and traffic generating processes
- 15) Log experiment test ID in file experiments\_completed.txt
- IV) If the config specifies another parameter combination to run under the same test ID prefix, go to step III, otherwise finish

#### D. Fabric - overview and installation

Fabric [9] provides several basic operations for executing local or remote shell commands and uploading/downloading files, as well as auxiliary functions, such as prompting the user for input, or aborting execution of the current task. Typically, with Fabric one creates a Python module where some functions are marked as Fabric tasks (using a Python function decorator).

These tasks can then be executed directly from the command line using the Fabric tool fab. The entry point of the module is a file commonly named fabfile.py, which is typically located in a directory from which we execute Fabric tasks (if the file is named differently we must use fab -f <name>.py). The complete list of tasks available in fabfile.py can be viewed with the command fab -1. Parameters can be passed to Fabric tasks, however a limitation is that all parameter values are passed as strings. A Fabric task may also execute another Fabric task with Fabric's execute() function.

Sections VII and VIII contain a number of examples of how to run various TEACUP tasks.




Figure 2: TEACUP main functional blocks

TEACUP was developed with Fabric versions 1.8–1.10, but it should also run with newer versions of Fabric. The easiest way to install the latest version of Fabric is using the tool pip. Under FreeBSD pip can be installed with portmaster:

#### > portmaster devel/py-pip

On Linux pip can be installed with the package manager, for example on openSUSE it can be installed as follows:

```
> zypper install python-pip
```

Then to install Fabric execute:

```
> pip install fabric
```

You can test that Fabric is correctly installed:

```
> fab --version
Fabric 1.8.0
Paramiko 1.12.0
```

The Fabric manual provides more information about installing Fabric [10].

# III. TRAFFIC GENERATION AND LOGGING

This section describes the implemented traffic sources/sinks and loggers, the range of information logged and the log file naming schemes.

#### A. Traffic sources and sinks

We now describe TEACUP's available traffic generator functions that control underlying applications such as iperf, httperf, ping and so forth. These underlying applications must be separately installed on the end hosts before TEACUP can control them. Use of these generators is described in more detail in Section VI.

- 1) iperf: The tool iperf [11] can be used to generate TCP bulk transfer flows. Note that the iperf client pushes data to the iperf server, so the data flows in the opposite direction compared to httperf. iperf can also be used to generate unidirectional UDP flows with a specified bandwidth and two iperfs can be combined to generate bidirectional UDP flows.
- 2) ping: This starts a ping from one host to another (generating pairs of ICMP Echo Request and Echo Reply packets). The rate of pings is configurable for FreeBSD and Linux but limited to one ping per second for Windows.
- 3) lighttpd: A lighttpd [12] web server is started. This can be used as traffic source for httperf-based sinks. There are also scripts to setup fake content for DASH-like streaming and incast scenario traffic. In addition, lighttpd can be used as a web server that serves genuine DASH content to a client started by dash\_streaming\_dashjs. However, for specific experiments one may need to setup web server content manually or create new scripts to do this.
- 4) nginx (new in TEACUP 1.1): An nginx [13] web server is started. This traffic source can be used as an alternative to lighttpd for serving genuine DASH content to a client started by dash\_streaming\_dashjs. It is currently only available under FreeBSD-based and Linux-based hosts.
- 5) httperf: The tool httperf [14] can be used to simulate an HTTP client. It can generate simple request patterns, such as accessing some .html file n times per second.

It can also generate complex workloads based on work session log files (c.f. httperf man page at [14]).

6) dash\_streaming\_dashjs (new in TEACUP 1.1): This starts a HTML-5 based dash.js [15] client inside a Chrome or Firefox web-browser on one host, which then retrieves video content served by a regular web server (e.g lighttpd) on other host. The client's host system must have Xorg, and either Chrome or Firefox installed.

In DASH systems [16], video content is encoded into multiple versions at different discrete bitrates (*representations*). Each encoded video is then fragmented into small video segments (*chunks*), each containing a few seconds worth of video. Chunks with different bitrates are all aligned in video timeline so that at chunk boundaries the client can smoothly switch bitrates, if necessary.

When a streaming session starts, DASH client will request the Media Presentation Description (MPD) file which describes content information (available representations, metadata, download URLs), then start requesting video chunks as fast as possible to fill the playout buffer. Once the playout buffer is pre-filled, DASH client enters a steady-state phase where it retrieves video chunks periodically (every *t* seconds, where *t* is the chunk size in seconds), resulting in an ON-OFF traffic pattern as described in Figure 3. A particular adaptive bitrate algorithm (ABR) [17] will be used by the client to determine the representation to be selected for the next video chunk.

**NOTE:** dash\_streaming\_dashjs uses an actual DASH client (with real ABR heuristics) with genuine video content. Setting up an appropriately configured host and using dash\_streaming\_dashjs is strongly preferred over the DASH-like traffic emulation of httperf\_dash.

7) httperf\_dash (deprecated in TEACUP 1.1 but still available): This starts a httperf client [18] that simplistically emulates the behaviour of DASH or other similar HTTP-based chunked-transfer streaming algorithms [1], [2]. In the initial buffering phase the client will download content as fast as possible. Then the client will fetch successive blocks of content every t seconds. The video rate and the cycle length are configurable (and the size of the data blocks depends on these).

**NOTE:** This generator is deprecated in TEACUP version 1.1. If you have installed the required Xorg and Chrome or Firefox packages on your intended client end host, we




Figure 3: Simplified illustration of TCP traffic generated by *dash\_streaming\_dashjs* 

recommend using *dash\_streaming\_dashjs* to launch and control a standards-compliant DASH client.

- 8)  $httperf\_incast$ : This starts an httperf client for the incast scenario. The client will request a block of content from n servers every t seconds. The requests are sent as close together as possible to make sure the servers respond simultaneously. The size of the data blocks is configurable. Note that emulating the incast problem in a physical testbed is difficult, if the number of hosts (number of responders) is relatively small.
- 9) nttcp: This starts an nttcp [19] client and an nttcp server for simple unidirectional UDP VoIP flow emulation. The fixed packet size and inter-packet time can be configured. Note, nttcp also opens a TCP control connection between client and server. However, on this connection only a few packets are exchanged before and after the data flow.
- 10) pktgen: TEACUP knows how to use pktgen 0.3.1 [20] to crudely emulate the UDP traffic of first person shooter (FPS) games such as Quake III Arena. Note that pktgen 0.3.1 can only generate a single UDP unidirectional traffic flow, so TEACUP launches a pair of pktgen instances between the server and every nominated client (one sending client-to-server traffic and the other sending server-to-client traffic).

#### B. Loggers

Currently, there are a range of loggers that log information on all hosts. All *host-to-host* and *cross router* traffic is logged with tcpdump while *TCP state information* on each host is logged with different OS-specific tools.

- 1) Traffic logger: tcpdump is used to capture the traffic on all testbed NICs on all hosts. All traffic is captured. The snap size defaults to 80 bytes but can be increased in the config file.
- 2) TCP statistics logger: Different tools are used to log TCP state information on all hosts except the router. On FreeBSD we use SIFTR [5]. On Linux we use Web10G [6] (polling) or ttprobe [21] (event driven). Web10g implements the TCP EStats MIB [22] inside the Linux kernel, with our own logging tool based on the Web10G library. TEACUP directly interprets ttprobe output. For Windows 7 we implemented our own logging tool, which can access the TCP EStats MIB inside the Windows 7 kernel. SIFTR has not been ported to Mac OS X, so for Mac OS X we implemented our own logging tool that outputs TCP statistics logs in SIFTR format based on DTrace [23]. Note that the DTrace tool collects most but not all statistics collected by SIFTR (the tool's documentation describes these limitations).

The statistics collected by SIFTR are described in the SIFTR README [24]. The statistics collected by our Web10G client and the Windows 7 EStats logger are described as part of the web100 (the predecessor of Web10G) documentation [25].

# C. Log file naming – syntax and structure

1) test IDs and test ID prefixes: As noted in Section II-C, TEACUP identifies individual experiments by a **test ID**, a unique string used to construct names for log files specific to individual experiments (such as testbed metadata, captured system state and captured traffic). A test ID is constructed from a **test ID prefix** and selected parameter name-value pairs describing a given experiment as follows:

<testID> = <testIDprefix>\_[<parName>\_<parVal>\_] \*

The **test ID prefix**, <testIDprefix>, groups together related experiments generated by iterating over range of values for a subset of testbed parameters. This prefix is either specified in the config file or on the command line (as described in Section VII). Certain metadata common to all experiments in a group are stored under filenames constructed from <testIDprefix> alone, rather than the full <testID>. Our recommended (and default) <testIDprefix> is a string of the form 'exp\_YYYYMMDD-HHMMSS' (based on the date and time when the experiment or group of experiments

was launched).<sup>4</sup> [<parName>\_<parVal>\_] \* represents zero to n parameter name-value pairs separated by underscores. Parameter names (<parName>) must not contain underscores (by definition) and TEACUP forces all underscores in parameter values (<parVal>) to hyphens when an experiment is run.<sup>5</sup>

2) Grouping experiments under a test ID prefix: If an experiment is started with run\_experiment\_single there are no parameter name-value pairs encoded in the testID, and <testID> is just <testIDprefix>. All testbed parameter values set in the experiment's config are archived for post-processing in a separate file named <testIDprefix>\_tpconf\_vars.log.gz.

However, the more common TEACUP use-case is to launch a group of related experiments with run\_experiment\_multiple, which iterates across a range of values for a subset of testbed configuration parameters. In this case each test ID has a list of parameter name-value pairs reflecting the list of parameter names specified in configuration variable TPCONF\_vary\_parameters (see section V-P). We end up with as many unique test IDs under a common test ID prefix as there are unique combinations of parameter values for parameters listed in TPCONF\_vary\_parameters.

Note: You can also run a single experiment using run\_experiment\_multiple. Do this by specifying only one possible value for any parameters listed in TPCONF\_vary\_parameters. TEACUP then runs a single experiment (as it would with run\_experiment\_single) but with a test ID containing a more informative list of parameter name-value pairs.<sup>7</sup>

3) File name formats: Finally, most TEACUP log file and metadata file names share the following format:

<sup>&</sup>lt;sup>4</sup>Changed from the pre TEACUP v1.0 default of 'YYYYMMDD-HHMMSS\_experiment' to simplify test ID parsing.

<sup>&</sup>lt;sup>5</sup>This allows later parsing of the name-value pairs using the underscores as separators. Note the default 'exp\_YYYYMMDD-HHMMSS' testID prefix may also be parsed as a parameter 'exp' whose *value* is the date of an experiment (or group of experiments).

<sup>&</sup>lt;sup>6</sup>In other words, the <testID> only contains name-value pairs for parameters that are being varied as part of a group of experiments under a given <testIDprefix>. The entire set of varied and non-varied parameters are also stored in a separate file named <testIDprefix>\_tpconf\_vars.log.gz.

<sup>&</sup>lt;sup>7</sup>In practical terms run\_experiment\_single is a subset of run\_experiment\_multiple that ignores the contents of TPCONF\_vary\_parameters.

```
filename = <testID>_<host>_
[<traffgenID>_]<fileName>.<extension>[.gz]
```

The <host> part specifies the IP or name of the testbed host a log file was collected from. This corresponds to an entry in TPCONF\_router or TPCONF\_hosts.

If the log file is from a traffic generator specified in TPCONF\_traffic\_gens, the traffic generator number follows the host identifier ([<traffgenID>]). Otherwise, <traffgenID> does not exist.

The <fileName> depends on which process logged the data. For example it set to 'uname' for uname information collected, it is set to 'httperf\_dash' for an httperf client emulating DASH, set to 'web10g' for a Web10G log file, and so forth. tcpdump files are special in that they have an empty file name for tcpdumps collected on hosts (assuming they only have one testbed NIC), or the file name is <int\_name>\_router for tcpdumps collected on the router, where <int\_name> is the name of the NIC (e.g. eth1).

The <extension> is either 'dmp' indicating a tcpdump file or 'log' for all other log files. Gzip'ed log files have file names ending with '.gz'.

Figure 4 shows an example name for a tcpdump file collected on host testhost2 for an experiment where two parameters (dash, tcp) where varied, and an example name for the output of one httperf traffic generator (traffic generator number 3) executed on host testhost2 for the same experiment.

4) Storing results per test ID prefix: When using the provided launch scripts, all log files for one experiment (fab run\_experiment\_single) or a group of experiments (fab run\_experiment\_multiple) are stored under a sub directory named <testIDprefix> created inside the directory where fabfile.py is located.<sup>8</sup>

## D. Host and router information logging

In addition to logging the output of traffic generators and loggers, TEACUP also collects per-host and perrouter information. This section describes the information collected for each host or router participating in an experiment. The following information is gathered *before* an experiment is started (where <testIDprefix> is a test ID prefix and <testID> is a test ID):

- <testID>\_ifconfig.log.gz: This file contains the output of ifconfig (FreeBSD, Linux or MacOSX) or ipconfig (Windows).
- <testID>\_uname.log.gz: This file contains the output of uname -a.
- <testID>\_netstat.log.gz: This file contains information about routing obtained with netstat -r.
- <testID>\_ntp.log.gz: This file contains information about the NTP status based on ntpq -p (FreeBSD, Linux, MacOSX or Windows with NTP daemon installed) or w32tm (Windows).
- <testID>\_procs.log.gz: This file contains the list of all running processes (output of ps).
- <testID>\_sysctl.log.gz: This file contains the output of sysctl -a (FreeBSD, Linux or MacOSX) and various information for Windows.
- <testID>\_config\_vars.log.gz: This file contains information about all the V\_ parameters in config.py (see Section V). It logs the actual parameter values for each experiment. It also provides an indication of whether a variable was actually used or not (caveat: this does not work properly with variables used for TCP parameter configuration, they are always shown as used).
- <testID>\_host\_tcp.log.gz: This file contains information about the TCP congestion control algorithm used on each host, and any TCP parameters specified.
- <testID>\_tcpmod.log.gz: This file contains the TCP congestion control kernel module parameter settings (Linux only).
- <testID>\_ethtool.log.gz: This file contains the network interface configuration information provided by ethtool (Linux only).
- <testIDprefix>\_nameip\_map.log.gz: This file logs host names and IP addresses (control interface IP addresses) of all hosts and routers participating in the experiment or group of experiments.

The following information is gathered from the router *after* an experiment:

• <testID>\_queue\_stats.log.gz: Information about the router queue setup (including all queue discipline parameters) as well as router queue and filtering statistics based on the output of tc (Linux) or ipfw (FreeBSD).

<sup>&</sup>lt;sup>8</sup>Prior to version 0.4.7 TEACUP stored all log files in the directory where fabfile.py was located.

```
# tcpdump file collected on testhost2 for an experiment where two parameters where varied
exp_20131206-170846_dash_1000_tcp_compound_testhost2.dmp.gz
# output of httperf traffic generator (traffic generator 3) executed on testhost2
exp_20131206-170846_dash_1000_tcp_compound_testhost2_3_httperf_dash.log.gz
```

Figure 4: Example file names

# E. Config information logging

TEACUP also logs information about the configuration of each experiment or group of experiments and variables set for each experiment. The following information is gathered *before* an experiment is started (where <testIDprefix> is a test ID prefix and <testID> is a test ID):

- <testID>\_config\_vars.log.gz: This file logs the values of all V\_ variables for each experiment (see Section VII-D).
- <testIDprefix>\_config.tar.gz: This file contains copies of the config file(s) – there can be multiple files if Python's execfile() is used to separate the configuration into multiple files.
- <testIDprefix>\_tpconf\_vars.log.gz: This file lists all TPCONF\_ parameters specified in the config file(s) in a format that can be imported into Python.
- <testIDprefix>\_varying\_params.log.gz: This file contains a list of all V\_ variables varied during the experiment(s) and their short names used in file names (see Section VII-D).

## IV. HOST AND ROUTER CONFIGURATION

This section provides a general description of how the hosts and router are configured for each experiment and test within an experiment. The router implements a bottleneck with configurable one-way delays, rate limits and AQM (active queue management). A Linux-based bottleneck router uses to and netem (section IV-B), while a FreeBSD-based bottleneck router uses ipfw and Dummynet (section IV-C).

# A. Host setup

The setup of hosts other than the router is relatively straight-forward. First:

- Each host is booted into the selected OS
- Hardware offloading, such as TCP segmentation offloading (TSO), is disabled on testbed interfaces (all OS)

- TCP host cache is disabled (Linux) or configured with a very short timeout and purged (FreeBSD)
- TCP receive and send buffers are set to 2 MB or more (FreeBSD, Linux).

#### Next:

- ECN is enabled or disabled depending on the configuration
- TCP congestion control algorithm is configured for FreeBSD and Linux (including loading any necessary kernel modules)
- Parameters for the current TCP congestion control algorithm are configured if specified by the user (FreeBSD, Linux).

Finally, user-specified custom commands are executed on hosts as specified in the configuration (these can overrule the general setup).

# B. Linux-based bottleneck router setup

First, hardware offloading, such as TCP segmentation offloading (TSO) is disabled on the two testbed interfaces. Then, the queuing is configured. In the following two sub sections we first describe our overall approach to setup rate limiting, AQM and delay/loss emulation for the Linux router. Then, we describe an example setup to illustrate the approach in practice.

1) Approach: Shaping, AQM and delay/loss emulation is done on the egress NIC (as usual). To filter packets and direct them into the 'pipes' we use netfilter [26]. The hierarchical token bucket (HTB) queuing discipline is used for rate limiting with the desired AQM queuing discipline (e.g. pfifo, codel) as leaf node (this is similar to a setup mentioned at [27]). After rate shaping and AQM, constant loss and delay is emulated with netem [28]. For each pipe we set up a new to class on the two testbed NICs of the router. If pipes are unidirectional, a class is only used on one of the two interfaces. Otherwise it is used on both interfaces. In future work we could optimise the unidirectional case and omit the creation of unused classes.

The traffic flow is as follows (also see Figure 10):

- Arriving packets are marked at the netfilter mangle table's POSTROUTING hook depending on source and destination IP address with a unique mark for each pipe.<sup>9</sup>
- 2) Marked packets are classified into the appropriate class based on the mark (a one-to-one mapping between marks and classes) and redirected to a pseudo interface. With pseudo device we refer to the so-called intermediate function block (IFB) device [29].
- 3) The traffic control rules on the pseudo interface do the shaping with HTB (bandwidth as per config) and the chosen AQM (as a leaf queuing discipline).
- 4) Packets go back to the actual outgoing interface.
- 5) The traffic control rules on the actual interface do network delay/loss emulation with netem. We still need classes here to allow for pipe specific delay/loss settings. Hence we use a HTB again, but with the bandwidth set to the maximum possible rate (so there is effectively no rate shaping or AQM here) and netem plus pfifo are used as leaf queuing discipline. <sup>10</sup>
- 6) Packets leave the router via the stack and network card driver.

The main reason for this setup with pseudo interfaces is to cleanly separate the rate limiting and AQM from the netem delay/loss emulation. One could combine both on the same interface, but then there are certain limitation, such as netem must be before the AQM and [27] reported that in such a setup netem causes problems. Also, a big advantage with our setup is that it is possible to emulate different delay or loss for different flows that share the same bottleneck/AQM.

2) Example: We now show an example of the setup based on partial (and for convenience reordered) output of a queue\_stats.log.gz file for a scenario with two unidirectional pipes: 8 Mbps downstream and 1 Mbps upstream, both with 30 ms delay and 0% loss.

First, Figure 5 shows the netfilter marking rules. Our upstream direction is 172.16.10.0/24 to 172.16.11.0/24

and all packets are given the mark 0x1. Our downstream direction is 172.16.11.0/24 to 172.16.10.0/24 and all packets are given the mark 0x2.

In the upstream direction our outgoing interface is eth3 and we have the tc filters shown in Figure 6, which put each packet with mark 0x1 in class 1:1 and redirect it to pseudo interface ifb1.

Note that the class setting is effective for eth3, but it will not 'stick' across interfaces. Hence we need to set the class again on ifb1 as shown in Figure 7 (again class 1:1 is set if the mark is 0x1).

On ifb1 we use the queuing discipline setup as shown in Figure 8. The HTB does the rate limiting to 1 Mbps. Here the leaf queuing discipline is a bfifo (byte FIFO) with a buffer size of 18.75 kB.

After packets are through the bfifo, they are passed back to eth3 where we have an HTB with maximum rate and netem as leaf queuing discipline (here netem emulates 30 ms constant delay) as shown in Figure 9.

After leaving netem the packets are passed to the stack which then passes them to the NIC driver. For the sake of brevity we are not describing the downstream direction here, but the principle is exactly the same. The only differences are the interfaces used (eth2 and ifb0 instead of eth3 and ifb1) and the different HTB, AQM and netem parameters.

Figure 10 shows the flow of packets with the different steps carried out in the order of the numbers in parenthesis. The marking/classifying is not shown explicitly, it takes place between step 1 and 2 (netfilter and class on actual interface) and between step 2 and 3 (class on pseudo interface).

We can see that with our setup it is possible to emulate different delay or loss for different flows that share the same bottleneck/AQM. Multiple tc filters on the ifb interface can classify different flows as the same class so they share the same bottleneck. However, on the eth interface we can have one class and one netem queue per flow and the tc filters classify each flow into a different class.

3) Notes: Note that in addition to the buffers mentioned earlier, according to [27] the HTB queuing discipline has a built-in buffer of one packet (that cannot be changed) and the device drivers also have separate buffers.

<sup>&</sup>lt;sup>9</sup>There also is a dummy rule "MARK and 0x0" inserted first, which is used to count all packets going through the POSTROUTING hook. Note that since this dummy rule has 'anywhere' specified for source and destination, it also counts packets going through the router's control interface.

<sup>&</sup>lt;sup>10</sup>The netem queue has a hard-coded size of 1000 packets, which should be large enough for our targeted experimental parameter space.

```
> iptables -t mangle -vL
Chain POSTROUTING (policy ACCEPT 52829 packets, 69M bytes) pkts bytes target prot opt in out
source destination
52988 69M MARK all -- any any anywhere anywhere MARK and 0x0
22774 1202K MARK all -- any any 172.16.10.0/24 172.16.11.0/24 MARK set 0x1
28936 66M MARK all -- any any 172.16.11.0/24 172.16.10.0/24 MARK set 0x2
```

Figure 5: Netfilter marking rules

```
> tc -s filter show dev eth3
filter parent 1: protocol ip pref 49152 fw
filter parent 1: protocol ip pref 49152 fw handle 0x1 classid 1:1
action order 33: mirred (Egress Redirect to device ifb1) stolen
index 3266 ref 1 bind 1 installed 99 sec used 12 sec
Action statistics:
Sent 1520865 bytes 22774 pkt (dropped 0, overlimits 0 requeues 0)
backlog 0b 0p requeues 0
```

Figure 6: tc filter on outgoing network interface

```
> tc -d -s filter show dev ifb1
filter parent 1: protocol ip pref 49152 fw
filter parent 1: protocol ip pref 49152 fw handle 0x1 classid 1:1
```

Figure 7: tc filter on pseudo interface

```
> tc -d -s class show dev ifb1
class htb 1:1 root leaf 1001: prio 0 quantum 12500 rate 1000Kbit ceil 1000Kbit burst 1600b/1
mpu 0b overhead 0b cburst 1600b/1 mpu 0b overhead 0b level 0
Sent 1520865 bytes 22774 pkt (dropped 0, overlimits 0 requeues 0)
rate 62112bit 117pps backlog 0b 0p requeues 0
lended: 22774 borrowed: 0 giants: 0
tokens: 191750 ctokens: 191750
> tc -d -s qdisc show ifb1
qdisc htb 1: dev ifb1 root refcnt 2 r2q 10 default 0 direct_packets_stat 0 ver 3.17
Sent 1520865 bytes 22774 pkt (dropped 0, overlimits 0 requeues 0)
backlog 0b 0p requeues 0
qdisc bfifo 1001: dev ifb1 parent 1:1 limit 18750b
Sent 1520865 bytes 22774 pkt (dropped 0, overlimits 0 requeues 0)
backlog 0b 0p requeues 0
```

Figure 8: Queuing discipline setup on pseudo interface

## C. FreeBSD-based bottleneck router setup

TEACUP can utilise AQM capabilities built into ipfw/dummynet for bottleneck routers based on FreeBSD 10.3 or later (as documented in CAIA-TR-160708A [30]).

Each pipe is realised as one dummynet pipe, which does the rate shaping, queuing, and loss/delay emulation. ipfw rules are used to redirect packets to the pipes based on the specified source and destination IP parameters. If a pipe is unidirectional then there is a single "pipe <num> ip from <source> to <dest> out" rule. If a pipe is bidirectional there

is an additional "pipe <num> ip from <dest> to <source> out" rule. The pipe number <num> is automatically determined by TEACUP.

1) Setting up ipfw/dummynet for AQM experiments: The three main object types (link, queue and scheduler) are required for dummynet to setup a functional pipe. These object provide the following:

- Link object provides traffic shaping, network delay and loss emulation functions.
- Queue object configurable-size buffer that is used to store packets temporarily to absorb net-

```
> tc -d -s class show dev eth3
class htb 1:1 root leaf 1001: prio 0 rate 1000Mbit ceil 1000Mbit burst 1375b cburst 1375b
Sent 1520865 bytes 22774 pkt (dropped 0, overlimits 0 requeues 0)
rate 62184bit 117pps backlog 0b 0p requeues 0
lended: 22774 borrowed: 0 giants: 0
tokens: 178 ctokens: 178
> tc -d -s qdisc show eth3
qdisc htb 1: dev eth3 root refcnt 9 r2q 10 default 0 direct_packets_stat 3 ver 3.17
Sent 1520991 bytes 22777 pkt (dropped 0, overlimits 66602 requeues 0)
backlog 0b 0p requeues 0
qdisc netem 1001: dev eth3 parent 1:1 limit 1000 delay 30.0ms
Sent 1520865 bytes 22774 pkt (dropped 0, overlimits 0 requeues 0)
backlog 0b 0p requeues 0
```

Figure 9: Queuing discipline setup on outgoing interface (netem)




Figure 10: Flow of packets through our queue setup

work bursts, and managed by a queue management scheme (Droptail, RED, CoDel or PIE).

 Scheduler object - responsible for fetching packets from queues and send them through the connected link.

TEACUP directs dummynet to create all three objects and connect them together to form a new pipe, which can then be added to ipfw rules. For a multi-queue scheduler, such as QFQ and RR, they can serve multiple queues depending on the scheduling algorithm. Each queue can be configured with different size and AQM.

For more complex AQM schemes such as FQ-CoDel, the scheduler implements as a single-queue scheduler with multiple internal sub-queue managed by a non FQ AQM (CoDel for FQ-CoDel). To configure a pipe for

FQ-CoDel or FQ-PIE, a queue, scheduler and link should be created separately and be connected together, then the created queue should be added to ipfw rules.

2) Ensuring same delays for all flows in Dummynet pipe: TEACUP generates and runs ipfw commands based on router queues configurations in config.py. For each tuple in a queues configuration, TEACUP creates a dummynet pipe with a specific amount of rate limiting, delay and loss emulation. If queue\_disc argument is a pure queue management name ('fifo', 'codel' or 'pie'), TEACUP sets the queue size limit (if any) to the pipe, and adds it to ipfw rule.

If queue\_disc argument is set to an fq variant ('fq\_codel' or 'fq\_pie'), TEACUP creates a queue and respective scheduler, and sets the queue size limit to the scheduler. This queue size limit is for whole sub-queues that were created by the fq scheduler. The created queue is then added to ipfw rules. For a detailed example and more in depth explanation of how FreeBSD router is setup for TEACUP, see CAIA-TR-160708A [30].

#### V. CONFIG FILE - FORMAT AND FUNCTIONALITY

This section describes TEACUP's top-level **config.py** file that defines the parameters and conditions of an experiment or group of experiments. Available traffic generators are summarised in section VI.

#### A. Location of config.py

By default TEACUP will load the config.py file that is in the directory where fabfile.py is located – the directory from which experiments are started. Since TEACUP version 0.9, alternative config files can be specified using fab's –-set parameter. For example, if we want

to run a series of experiments with the configuration in myconfig.py, we simple need to run TEACUP as follows:

```
> fab --set teacup_config=myconfig.py
run_experiment_multiple
```

# B. V\_variables

TEACUP uses *V\_variables* to support iteratation over a range of parameter values for groups of experiments. These are identifiers of the form V\_<name>, where <name> must consist of only letters, numbers, hyphens (-) or underscores (\_). V\_variables can be used in router queue settings (see Section V-L), traffic generator settings (see Section VI), TCP algorithm settings (see Section V-N) or host setup commands (see Section V-K). Section V-P describes how to define V\_variables.

# C. Fabric configuration

The following settings in the config file are Fabric settings. For a more in-depth description refer to the Fabric documentation [9]. All Fabric settings are part of the Fabric env dictionary and hence are Python variables (and must adhere to the Python syntax).

The user used for the SSH login is specified with env.user. For example:

```
env.user = 'root'
```

The password used for the SSH login is specified with env.password. The password can be empty if public-key authorisation is set up properly, e.g. the public SSH key of the control PC running TEACUP has been added to all hosts <user>/.ssh/authorized\_keys files (and the corresponding private key on the control host is ~/.ssh/id\_rsa or a file <key\_file> specified with fab -i <key\_file> or the env.key\_filename configuration parameter [9]).

```
env.password = 'testroot'
```

Use env.shell to specify the shell used to execute commands. Fabric's default, Bash, is not standard on FreeBSD so TEACUP's default setting is:

```
env.shell = '/bin/sh -c'
```

The timeout for an SSH connection is specified with env.timeout.

```
env.timeout = 5
```

The number of concurrent processes used for parallel execution is specified with env.pool\_size. The number should be at least as high as the number of hosts, unless the number of hosts is large in which case we may want to limit the number of concurrent processes.

```
env.pool\_size = 10
```

#### D. Testbed configuration

All TEACUP config file settings start with the *TPCONF*\_ prefix. They are Python variables and must adhere to the Python syntax.

TPCONF\_script\_path specifies the path to the TEACUP scripts, and is appended to the Python path.

```
TPCONF_script_path = '/home/test/src/teacup'
```

Two lists specify the roles of each testbed host machine. TPCONF\_router specifies the list of machines to be configured as software routers (typically only one in a dumbbell configuration). TPCONF\_hosts specifies the list of machines to be configured as traffic sources and/or sinks (end hosts). Router(s) and end hosts can be specified as IP addresses or human-readable host names (typically for convenience just the name without the domain part).

```
TPCONF_router = [ 'testhost1', ]
TPCONF_hosts = [ 'testhost2', 'testhost3' ]
```

The dictionary TPCONF\_host\_internal\_ip specifies the testbed IP addresses for each host. The hosts (keys) specified must match the entries in the TPCONF\_router and TPCONF\_hosts lists exactly. The current code does simple string matching, it does *not* attempt to resolve host identifiers into some canonical form.

```
TPCONF_host_internal_ip = {
  'testhost1' : ['172.16.10.1','172.16.11.1'],
  'testhost2' : ['172.16.10.2'],
  'testhost3' : ['172.16.10.3'],
}
```

#### E. Sanity checks settings

By default TEACUP checks the connectivity between testbed hosts by performing a ping from each host to each other host that should be reachable (according to the router configuration and IP address configuration of the hosts). This check is carried out before each experiment. During a series of experiments the testbed is likely in

<sup>&</sup>lt;sup>11</sup>Prior to TEACUP version 0.9 the TPCONF\_router list was limited to only one router, but this limitation has been relaxed.

a stable condition and the repeated connectivity check may be unnecessary. It can be turned off by setting the variable TPCONF\_check\_connectivity to '0', i.e. adding the following line to the config file:

```
TPCONF_check_connectivity = '0'
```

#### F. General experiment settings

TPCONF\_test\_id specifies the default test ID **prefix**. Note that if the test ID prefix is specified on the command line, the command line overrules this setting. For example, TEACUP's default test ID prefix can be set by:

```
now = datetime.datetime.today()
TPCONF_test_id =
   'exp_'now.strftime("%Y%m%d-%H%M%S")
```

TPCONF\_remote\_dir specifies the directory on the remote host(s) where the log files (e.g. tcpdump, SIFTR) are temporarily stored during an experiment. These files are copied back to the control host and deleted from the remote host(s) automatically at the end of an experiment.<sup>12</sup>

```
TPCONF_remote_dir = '/tmp/'
```

TEACUP performs a very simple time synchronisation check at the start (after waiting for more than 30 seconds after the hosts were rebooted). It checks the time offset between the control host (the host that executes TEACUP) and each testbed host listed in the config file. TPCONF\_max\_time\_diff specifies the maximum tolerable clock offset, i.e. the maximum allowed time difference in seconds. If the clock offset for one of the testbed hosts is too large, TEACUP will abort the experiment or series of experiments.

```
TPCONF_max_time_diff = 2
```

TPCONF\_debug\_level specifies the debug level for experiments and later analysis. At the default level of 0, no debug information is generated. If set to a higher value debug information is generated. (For example at a debug level of 1, .Rout files are generated when plotting graphs during later analysis.)

```
TPCONF_debug_level = 0
```

The parameter TPCONF\_web10g\_poll\_interval allows specification of the poll interval in milliseconds for

web10g loggers on Linux or Windows. The minimum value is 1 ms and the maximum value is 1000 ms. The default value is 10 ms. Note that the control of the interval length is not very accurate and with small intervals less then 10 ms, the actual interval will likely be larger than the specified interval.

```
TPCONF_web10g_poll_interval = 10
```

# G. tcpdump/pcap snaplen configuration

The variable TPCONF\_pcap\_snaplen sets the *snap length* (number of bytes captured by tcpdump per Ethernet frame). If not specified the default is 80 bytes. Setting TPCONF\_pcap\_snaplen=0 means 'capture all bytes'. The following shows an example where we set the snap length to 128 bytes.

```
TPCONF_pcap_snaplen = 128
```

#### H. Topology configuration

Since version 0.8 TEACUP can automate the assignment of each host into one of the two subnets, given a testbed where the hosts and router are connected via a single VLAN-capable switch. Automatic topology configuration is <u>experimental</u> and based on a number of assumptions around the network setup.<sup>13</sup> For an experiment (or a group of experiments) the topology (re)configuration is (optionally) carried out after the machines haven been rebooted and before any sanity checks are done.

Automatic topology configuration is enabled by setting the variable TPCONF\_config\_topology to '1'. (If this variable is undefined or set to '0' there is no topology configuration.)

```
TPCONF_config_topology = '1'
```

When topology configuration is enabled TEACUP *actively* (*re*)configures each host's test subnet IP address to that specified in TPCONF\_host\_internal\_ip, then *changes* the VLAN configuration of the testbed switch's ports so all hosts are connected to the right subnets.

Automated VLAN (re)configuration requires SSH access to the switch, with the same SSH user name and password as used on all other hosts. As many switches limit the number of concurrent SSH sessions allowed,

<sup>&</sup>lt;sup>12</sup>Files can remain if an experiment is interrupted. There is currently no automatic cleanup of left-over files in the remote directory.

<sup>&</sup>lt;sup>13</sup>The most critical current restriction is that switch reconfiguration has only been tested with Dell 5324 and Dell N3000 series switches.

TEACUP currently performs the configuration of the ports on switch sequentially (host by host). However, after the switch has been configured TEACUP carries out the setup of each host (network interface and routing configuration) in parallel to reduce the overall time for topology configuration.

When mapping switch ports to VLANs, TEACUP assumes we are using /24 subnets and that the third octet of the IP address is identical to the VLAN name configured on the switch. For example, a host being configured with address 172.16.10.2 is mapped to a corresponding VLAN named '10' on the switch.

TEACUP also assumes that all hosts are differentiated by appending consecutive numbers to their hostnames. The lowest number, h, can be chosen arbitrarily. For example, if we have two hosts they could be named 'testhost1' and 'testhost2'. TEACUP further assumes that hosts are connected to consecutive ports of the switch in the same order as their hostname numbering. For example, if we have testhost1 and testhost2, and testhost1 is connected to switch port n then testhost2 must be connected to switch port n+1.

The address or host name of the switch can be configured with the variable TPCONF\_topology\_switch. To map a host to the corresponding port the variables TPCONF\_topology\_switch\_port\_prefix and TPCONF\_topology\_switch\_port\_offset (also called o) can be defined. The name of the switch port used will be the string specified in TPCONF\_topology\_switch\_port\_prefix concatenated with the number h+o. The following shows the default configuration.

```
TPCONF_topology_switch = 'switch2'
TPCONF_topology_switch_port_prefix = 'Gi1/0/'
TPCONF_topology_switch_port_offset = 5
```

The above configuration assumes that testhost1 is connected to switch port 'Gi1/0/6' and testhost2 is connected to switch port 'Gi1/0/7' on a switch with the host name 'switch2' (which has SSH configuration enabled).

Topology configuration works with all supported OS (Linux, FreeBSD, Windows/Cygwin and Mac OS X). However, the switch reconfiguration code has only been tested with Dell 5324 and Dell N3000 series switches.

Note that the network interfaces on the hosts are currently hard-coded inside TEACUP. For example, for

FreeBSD hosts the topology setup method assumes that em1 is the testbed interface. Currently these interface names can only be changed by modifying the Python code.

1) Link speed selection: As of version 0.9, TEACUP can set the link speed of the Ethernet links between the switch and testbed NICs. There are four settings for the speed: '10' (10 Mbps, 10baseT), '100' (100 Mps, 100baseT), '1000' (1000 Mbps, 1000baseT), and 'auto' (default, which should result in 1000baseT if all links use Gigabit Ethernet NICs). The variable TPCONF\_linkspeed allows the configuration of the link speed for all hosts. For example, if all hosts should use a link speed of 100 Mbps (100baseT) we can specify

```
TPCONF_linkspeed = '100'
```

However, we can also configure host-specific link speeds with the dictionary TPCONF\_host\_linkspeed. Each entry must have as index a host name (as defined in TPCONF\_router or TPCONF\_hosts) and as value one of the possible speed settings explained above. For example, if testhost1 should be set 100 Mbps and testhost2 to 1000 Mbps we can define

```
TPCONF_host_linkspeed = {
    'testhost1' : '100',
    'testhost2' : '1000'
```

TPCONF\_host\_linkspeed entries always overrule TP-CONF\_linkspeed. If neither variable is specified the default link speed setting is 'auto'.

Note that the link speed setting is persistent for Linux, FreeBSD and Windows. However, for Mac OS X the speed will reset to 1000baseT after a reboot (normally this should not be an issue as hosts are only rebooted before experiments).

#### I. Rebooting, OS selection and power cycling

With suitable external hardware support, TEACUP supports automated rebooting of testbed hosts into different operating systems and forced power cycling of hosts that have become unresponsive.

1) PXE-based rebooting: TEACUP's PXE-based rebooting process is explained in [7].

The IP address and port of the TFTP or HTTP server that serves the .ipxe configuration files during the

PXE boot process is specified with the parameter TP-CONF\_tftpserver. Both IP address and port number must be specified separated by a colon. For example:

```
TPCONF_tftpserver = '10.1.1.11:8080'
```

The path to the directory that is served by the TFTP or HTTP server is specified with TPCONF\_tftpboot\_dir.

```
TPCONF_tftpboot_dir = '/tftpboot'
```

Omitting TPCONF\_tftpboot\_dir, or setting it to an empty string, disables PXE booting. TPCONF\_host\_os and TP-CONF force reboot (see below) are then ignored.

2) OS and kernel selection: The TPCONF\_host\_os dictionary specifies which OS are booted on the different hosts. The hosts (keys) specified must match the entries in the TPCONF\_router and TPCONF\_hosts lists exactly (any host specified in TPCONF\_host\_os must be specified in either TPCONF\_router or TPCONF\_hosts). The current code does simple string matching, it does not attempt to resolve host identifiers in some canonical form.

TEACUP currently supports selecting from four different types of OS: 'Linux', 'FreeBSD', 'CYGWIN' (Windows) and 'Darwin' (Mac OS X). Selecting the specific Linux kernels to boot is supported with the TPCONF\_linux\_kern\_router and TPCONF\_linux\_kern\_hosts parameters (see below). The OS selection occurs once during reboot, and cannot subsequently be varied during a given experiment.

```
TPCONF_host_os = {
'testhost1' : 'Linux',
'testhost2' : 'FreeBSD',
'testhost3' : 'Linux',
}
```

TPCONF\_linux\_kern\_router specifies the Linux kernel booted on the router, and TPCONF\_linux\_kern\_hosts specifies the Linux kernel booted on all other hosts. The name is the kernel image name minus the starting 'vmlinuz-', so the name starts with the version number. It is also possible to specify the keywords 'running' or 'current' to tell TEACUP to use the same kernel that is currently running on the host (this *requires* that the host is already running Linux).

```
TPCONF_linux_kern_router = '3.14.18-10000hz'
TPCONF_linux_kern_hosts = '3.9.8-web10g'
```

The parameter TPCONF\_os\_partition allows us to specify the partitions for the different operating systems on

the hosts (in GRUB4DOS format since our TEACUP-based testbed uses GRUB4DOS to reboot into the desired OS). For example, if we have the configuration below then TEACUP will attempt to boot from the first partition of the first disk if Windows/Cygwin is selected, boot from the second partition of the first disk if Linux is selected, and boot from the third partition of the first disk if FreeBSD is selected.

```
TPCONF_os_partition = {
'CYGWIN' : '(hd0,0)',
'Linux' : '(hd0,1)',
'FreeBSD' : '(hd0,2)',
```

3) Boot behaviour and timeout: If TP-CONF\_force\_reboot is set to '1' all hosts will be rebooted. If TPCONF\_force\_reboot is set to '0' only hosts where the currently running OS (or kernel in case of Linux) is not the desired OS (or kernel in case of Linux), as specified in TPCONF\_host\_os (and TPCONF\_linux\_kern\_router or TPCONF\_linux\_kern\_hosts), will be rebooted.

```
TPCONF force reboot = '1'
```

TPCONF\_boot\_timeout specifies the maximum time in seconds (as integer) a reboot can take. If the rebooted machine is not up and running the chosen OS after this time, the reboot is deemed a failure and the script aborts, unless TPCONF\_do\_power\_cycle is set to '1' (see below).

```
TPCONF_boot_timeout = 100
```

4) Forced power cycling: If TEACUP-supported power controllers are installed and TPCONF\_do\_power\_cycle is set to '1', a host is power cycled if it does not reboot within TPCONF\_boot\_timeout seconds. If TP-CONF\_do\_power\_cycle is omitted or set to '0' there is no power cycling.

```
TPCONF_do_power_cycle = '0'
```

If TPCONF\_do\_power\_cycle=1 then parameters TP-CONF\_power\_ctrl\_type, TPCONF\_host\_power\_ctrlport, TPCONF\_power\_admin\_name and TP-CONF\_power\_admin\_pw must also be set.

TPCONF\_power\_ctrl\_type must be used to specify the type of power controller – '9258HP' (for an "IP Power 9258HP") or 'SLP-SPP1008' (for a "Serverlink SLP-SPP1008-H"). The default is '9258HP'. A mix of different types of power controllers is currently not supported.

```
TPCONF_power_ctrl_type = '9258HP'
```

TPCONF\_host\_power\_ctrlport is a dictionary that for each host specifies the IP (or host name) of the responsible power controller and the number of the controller's port the host is connected to (as integer starting from 1).

```
TPCONF_host_power_ctrlport = {
'testhost1' : ('192.168.1.178', '1'),
'testhost2' : ('192.168.1.178', '2'),
'testhost3' : ('192.168.1.178', '3'),
}
```

TPCONF\_power\_admin\_name specifies the name of the power controller's admin user.

```
TPCONF_power_admin_name = 'admin'
```

TPCONF\_power\_admin\_pw specifies the password of the power controller's admin user (which in the below example is identical to the SSH password used by Fabric, but in general it can be different).

```
TPCONF_power_admin_pw = env.password
```

#### J. Clock offset measurement (broadcast pings)

All the participating machines should have synchronised clocks (for example by running NTP) so we can accurately compare data measured on different hosts. However, clocks on consumer-grade PC hardware drift even while using NTP. TEACUP provides an additional mechanism to evaluate the quality of the time synchronisation and correct for clock offsets in the post-analysis.

When TPCONF\_bc\_ping\_enable is set to '1', TEACUP configures the router host to send a broadcast or multicast ping over the control network. These ping packets will be multicasted or broadcasted to the control interfaces of all other hosts (almost) simultaneously.

During experiments there is no other traffic on the control network and typically network jitter introduced by the sender (router), the network switch or the receiver is small. Thus one can estimate the offsets of the clocks of different hosts with relatively high accuracy by comparing the arrival times of the broadcast or multicast ping packets. Here we explain how to enable and configure the broadcast pings.

TPCONF\_bc\_ping\_enable must be set to '1' to enable the broadcast/multicast ping (default is '0').

TPCONF\_bc\_ping\_rate controls the rate in ping packets per second (default is one packet per second). TPCONF\_bc\_ping\_address is the address the ping is sent to. This must be either a multicast address (e.g. 224.0.1.199) or a broadcast address (e.g. 192.168.0.255 if the control interfaces are in the 192.168.0.0/24 subnet). The following shows an example configuration for enabled multicast pings.

```
TPCONF_bc_ping_enable = '1'
TPCONF_bc_ping_rate = 1
TPCONF_bc_ping_address = '224.0.1.199'
```

In technical report [8] we explain TEACUP's functions to analyse the clock offsets and use them for the correction of timestamps.

#### K. Custom host init commands

TPCONF\_host\_init\_custom\_cmds allows the execution of custom per-host init commands. This allows changing of the host configuration, for example with sysctls. TPCONF\_host\_init\_custom\_cmds is a dictionary, where the key specifies the host name and the value is a list of commands. The commands are executed in exactly the order specified, after all default build-in host initialisation has been carried out. This means TPCONF\_host\_init\_custom\_cmds makes it possible to override default initialisation. The commands are specified as strings and are executed on the host exactly as specified (with the exception that V\_variables, if present, are substituted with values). V\_variables can be used in commands, with the current limitation of only *one* V\_variable per command.

The custom commands are executed before router-specific configuration. So when using, for example, a FreeBSD host as the router we can use TP-CONF\_host\_init\_custom\_cmds to increase the maximum allowable Dummynet queue length (using sysctl) on the router (as a host) before Dummynet is actually configured (when configuring this particular host as the router).

Note that the custom commands are executed in the foreground, which means that for each command TEACUP will wait until it has been executed on the remote host before executing the next command for the *same* host. It is currently not possible to execute background commands. However, commands on different hosts are executed in parallel (so waiting for a command to finish on host testhost1 does not block executing the next command on host testhost2 or other hosts). In summary, commands on different host are executed in parallel, but commands on the same host are executed sequentially.

The following config file part shows an example where we simply execute the command 'echo TEST' on host testhost1.

```
TPCONF_host_init_custom_cmds = {
'testhost1' : [ 'echo TEST', ],
}
```

#### L. Router queue setup

The variable TPCONF\_router\_queues specifies the router pipes (also referred to as queues here). Each entry is a 2-tuple. The first value specifies a unique integer ID for each queue. The second value is a comma-separated string specifying the queue parameters. The queues do not necessarily need to be defined in the order of queue ID, but it is recommended to do so. The following queue parameters exist:

- **source**: Specifies the source IP/hostname or source network (<ip>[/prefix>]) of traffic that is queued in this queue. If a host name is specified there can be no prefix. One can specify an internal/testbed or external/control IP/hostname. If an external IP/hostname is specified this will be automatically translated into the first internal IP specified for the host in TPCONF\_host\_internal\_ip.
- **dest**: Specifies the destination IP/hostname or source network (<ip>[/fix>]) of traffic that is queued in this queue. If a host name is specified there can be no prefix. One can specify an internal/testbed or external/control IP/hostname. If an external IP/hostname is specified this will be automatically translated into the first internal IP specified for the host in TPCONF\_host\_internal\_ip.
- **delay**: Specifies the emulated constant delay in milliseconds. For example, delay=50 sets the delay to 50 ms.
- **loss**: Specifies the emulated constant loss rate. For example, loss=0.01 sets the loss rate to 1%.
- rate: Specifies the rate limit of the queue. On Linux we can use units such as 'kbit' or 'mbit'. For example, queue\_size='1mbit' sets the rate limit to 1 Mbit/second.
- queue\_size: Specifies the size of the queue. On
  Linux queue size is defined in packets for most
  queuing disciplines, but for some queuing disciplines it needs to be specified in bytes. For example,
  if we have a Linux queue with size specified in

packets, queue\_size=1000 sets the queue size to 1000 packets. On FreeBSD the queue size is also specified in packets typically, but one can specify the size in bytes by adding a 'bytes' or 'kbytes', for example queue\_size='100kbytes' specifies a queue of size 100kbytes. If 'bdp' is specified the queue size will be set to the nominal bandwidth-delay-product (BDP) (this does *only* work for queuing disciplines where TEACUP knows whether the queue size is specified in bytes or packets). The minimum queue size is one packet (if the size is specified in packets) or 2048 bytes (if the size is specified in bytes).

- queue\_size\_mult: The actual queue size is the queue size multiplied with this factor. This should only be used if queue\_size if set to 'bdp'. This allows the variation of the queue size in multiples of the nominal BDP.
- queue\_disc: Specifies the queuing discipline. This can be the name of any of the queuing disciplines supported by Linux, such as 'fq\_codel', 'codel', 'red', 'choke', 'pfifo', 'pie' etc. On FreeBSD 10.3 and later the queuing disciplines available are 'fifo', 'fq\_codel', 'codel', 'fq\_pie', 'pie' and 'red'. For example, queue\_disc='fq\_codel' sets the queuing discipline to the FQ-CoDel (FlowQueuing+CoDel) model. For compatibility with FreeBSD, one can specify 'fifo' on Linux which is mapped to 'pfifo' ('pfifo' is the default for HTB classes, which we use for rate limiting). The queue\_disc parameter must be specified explicitly.
- queue\_disc\_params: This parameter allows passing of parameters to queuing disciplines. For example, if we wanted to turn ECN on for fq\_codel we would specify queue\_disc\_params='ecn' (c.f. fq\_codel man page).
- **bidir**: This allows specification of whether a queue is unidirectional (set to '0') or bidirectional (set to '1'). A unidirectional queue will only get the traffic from source to destination, whereas a bidirectional queue will get the traffic from source to destination *and* from destination to source.
- attach\_to\_queue: This parameter works on Linux only. It allows direct matching of packets into an existing queue referenced by the specified queue ID, but to emulate flow-specific delay/loss (different from the delay and loss of other traffic). If attach\_to\_queue is specified the matching traffic will go through the already existing queue, but the emulated delay or loss is set according to the

current queue specification. This means we can omit the rate, queue\_disc and queue\_size parameters, because they do not have any effect.

• **rtt**: This parameter allows the explicit specification of the emulated RTT in milliseconds. This parameter only needs to be specified if queue\_size is set to 'bdp' and the RTT is not twice the delay of the current TEACUP queue (e.g. if we set up asymmetric delay with attach\_to\_queue).

All parameters must be assigned with either a constant value or a TEACUP V\_variable. V\_variable names must be defined in TPCONF\_parameter\_list and TPCONF\_variable\_defaults (see below). V\_variables are replaced with either the default value specified in TPCONF\_variable\_defaults or the current value from TPCONF\_parameter\_list if we iterate through multiple values for the parameter.

Figure 11 shows an example queue setup with the same delay and loss for every host and the same delay and loss in both directions (all the parameters are variables here).

Figure 12 shows an example that illustrates the attach\_to\_queue parameter. Traffic between 172.16.10.3 and 172.16.11.3 goes through the same queues as traffic between 172.16.10.2 and 172.16.11.2, but in both directions it experiences twice the delay.

Since version 0.9 TEACUP supports multiple routers. If multiple routers are specified in TPCONF\_router, but there is only one TPCONF\_router\_queues specification (for example the one shown above), TEACUP will apply the single TPCONF\_router\_queues specification to all routers. However, in many cases with multiple routers we want to specify router-specific queue setups. This can be done by making TPCONF\_router\_queues a dictionary with the keys being router names (as specified in TPCONF\_router) and the values being TP-CONF\_router\_queues specifications.

As an example let us assume there are two routers: testrouter1 and testrouter2. For each of the routers we need to specify the queue setup (for brevity we use a placeholder here instead of showing the actual queue specifications:

```
testrouter1_queues = [<queue_spec1>]
testrouter2_queues = [<queue_spec2>]
```

Then we need to define TPCONF\_router\_queues as explained above:

# M. Traffic generator setup

Traffic generators are defined with the variable TPCONF\_traffic\_gens. This is a list of 3-tuples. The first value of a tuple is the start time relative to the start time of the experiment. The second value of the tuple is a unique ID. The third value of the tuple is a list of strings with the function name of the start function of the traffic generator as first entry followed by the parameters. The name of the functions and the parameters for each function are described in Section VI.

Client and server parameters can be external (control network) addresses or host names. An external address or host name is replaced by the first internal address specified for a host in TPCONF\_host\_internal\_ip. Client and server parameters can also be internal (testbed network) addresses, which allows specification of any internal address.

Each parameter is defined as:

```
<parameter_name>=<parameter_value>
```

Parameter names must be the parameter names of traffic generator functions (and as such be valid Python variable names). Parameter values can be either constants (string or numeric) or TEACUP V\_variables that are replaced by the actual values depending on the current experiment. The V\_variables must be defined in TP-CONF\_parameter\_list and TPCONF\_variable\_defaults. Numeric V\_variables can be modified using mathematical operations, such as addition or multiplication, with constants. For example, if a variable 'V\_delay' exists one can specify '2\*V\_delay' as parameter value.

Figure 13 shows a simple example. At time zero a web server is started and fake DASH content is created. 0.5 seconds later a httperf DASH-like client is started. The duration and rate of the DASH-like flow are specified by variables that can change for each experiment. In contrast the cycle length and prefetch time are set to fixed values.

The example config files in the source code distribution contain more examples of setting up traffic generators.

Figure 11: Router queue definition example

Figure 12: Router queue definition with attach\_to\_queue example

Figure 13: Traffic generator example

#### N. Mandatory experiment variables

We now describe the mandatory experiment variables that must be in every config file. There are two types: singulars and lists. Singulars are fixed parameters while lists specify the different values used in subsequent experiments based on the definitions of TP-CONF\_parameter\_list and TPCONF\_vary\_parameters (see below).

1) Traffic duration: The duration of the traffic in seconds (must be an integer) is specified with TP-CONF\_duration. Note that currently the actual duration of an experiment is the number of seconds specified by TPCONF\_duration plus the number of seconds until the last traffic generator is started (based on TPCONF\_traffic\_gens) plus some warmup time. TP-CONF\_duration is specified as follows:

```
TPCONF_duration = 30
```

2) Number of repeats (runs): The number of repetitions (runs) carried out for each unique parameter combination is specified with TPCONF\_runs:

```
TPCONF_runs = 1
```

3) Enabling ECN on hosts: TPCONF\_ECN specifies whether ECN is used on the hosts that are the traffic sources/sinks. If set to '1', ECN is enabled for all hosts. If set to '0', ECN is disabled for all hosts. Currently per-host configuration is only possible with custom commands.

```
TPCONF\_ECN = [ '0', '1' ]
```

(Note that TPCONF\_ECN only enables ECN on the hosts. For full ECN support, the AQM mechanism on the router must also be configured to use ECN.)

4) Congestion control algorithms: TP-CONF\_TCP\_algos specifies the TCP congestion algorithms used. The following algorithms can be selected: 'newreno', 'cubic', 'hd', 'htcp', 'cdg', 'compound'.

```
TPCONF_TCP_algos = [ 'newreno', 'cubic', ]
```

However, only some of these are supported depending on the OS a host is running:

- Windows: newreno (default), compound;
- FreeBSD: newreno (default), cubic, hd, htcp, cdg;
- Linux: cubic (default), newreno, htcp;

#### • Mac OS X: newreno (default)

Instead of specifying a particular TCP algorithm one can specify 'default'. This will set the algorithm to the default algorithm depending on the OS the host is running.

Using only TPCONF\_TCP\_algos one is limited to either using the same algorithm on all hosts or the defaults. To run different algorithms on different hosts, one can specify 'host<N>' where <N> is an integer number starting from 0. The <N> refers to the Nth entry for each host in TPCONF\_host\_TCP\_algos.

TPCONF\_host\_TCP\_algos defines the TCP congestion control algorithms used for each host if the 'host<N>' definitions are used in TPCONF\_TCP\_algos. In the following example a 'host0' entry in TPCONF\_TCP\_algos will lead to each host using its default. A 'host1' entry will configure testhost2 to use 'newreno' and testhost3 to use 'cdg'.

```
TPCONF_host_TCP_algos = {
'testhost2' : [ 'default', 'newreno', ],
'testhost3' : [ 'default', 'cdg', ],
}
```

With TPCONF\_host\_TCP\_algo\_params we can specify parameter settings for each host and TCP congestion control algorithm. The settings are passed directly to sysctl on the remote host. We can use V\_variables to iterate over different settings (similar as for pipes and traffic generators) and these are replaced with the actual current value before passing the string to sysctl. For example, we can specify settings for CDG for host testhost2:

```
TPCONF_host_TCP_algo_params = {
  'testhost2' : { 'cdg' : [
  'net.inet.tcp.cc.cdg.beta_delay = V_cdgbdel',
  'net.inet.tcp.cc.cdg.beta_loss = V_cdgbloss',
  'net.inet.tcp.cc.cdg.exp_backoff_scale = 3',
  'net.inet.tcp.cc.cdg.smoothing_factor = 8' ]
}}
```

5) Emulated delays, loss rates and bottleneck bandwidths: TPCONF\_delays specifies the emulated network delays in milliseconds. The numbers must be chosen from [0, max\_delay). For most practical purposes the maximum delay max\_delay is 10 seconds, although it could be more (if supported by the emulator). The following shows an example:

```
TPCONF\_delays = [ 0, 25, 50, 100 ]
```

TPCONF\_loss\_rates specifies the emulated network loss rates. The numbers must be between 0.0 and 1.0. The following shows an example:

```
TPCONF_loss_rates = [ 0, 0.001, 0.01 ]
```

TPCONF\_bandwidths specifies the emulated bandwidths as 2-tuples. The first value in each tuple is the downstream rate and the second value in each tuple is the upstream rate. Note that the values are passed through to the router queues and are not checked by TEACUP. Units can be used if the queue setup allows this, e.g. in the following example we use 'mbit' to specify Mbit/second which Linux tc understands:

```
TPCONF_bandwidths = [
  ('8mbit', '1mbit'),
  ('20mbit', '1.4mbit'),
]
```

6) Selection of bottleneck AQM and buffer sizes: TP-CONF\_aqms specifies the list of AQM/queuing techniques. This is completely dependent on the router OS. Linux supports 'fifo' (mapped to 'pfifo'), 'pfifo', 'bfifo', 'fq\_codel', 'codel', 'pie', 'red' etc. (refer to the tc man page for the full list). FreeBSD support 'fifo', 'fq\_codel', 'codel', 'fq\_pie', 'pie' and 'red'. Default on Linux and FreeBSD are FIFOs (with size in packets). The following shows an example:

```
TPCONF_aqms = [ 'pfifo', 'fq_codel', 'pie' ]
```

Note that all underscores in parameter values used in log file names are changed to hyphens to allow for easier parsing of log file names. For example, 'fq\_codel' will become 'fq-codel' in the file name.

TPCONF\_buffer\_sizes specifies the bottleneck buffer sizes. If the router is Linux this is mostly in packets/slots, but it depends on the AQM technique (e.g. for bfifo it is bytes). If the router is FreeBSD this would be in slots by default, but we can specify byte sizes (e.g. we can specify 4Kbytes). The following example for a Linux router would result in buffers of 100, 200 and 600 packets long:

```
TPCONF_buffer_sizes = [ 100, 200, 600 ]
```

7) Specifying which parameters to vary: TPCONF\_vary\_parameters specifies a list of parameters to vary over a series of experiments, i.e. parameters that will take on multiple values. The listed parameters must be defined in TPCONF\_parameter\_list (see Section V-P). The total number of experiments carried out is the number of unique parameter combinations

(multiplied by the number of TPCONF\_runs if 'runs' is also specified in TPCONF\_vary\_parameters).

The TPCONF\_vary\_parameters specification also defines the order of the parameters in the log file names. While not strictly necessary, if used 'runs' should be last in the list. If 'runs' is not specified, there is a single experiment for each parameter combination. TPCONF\_vary\_parameters is only used for multiple experiments. When we run a single experiment (run\_experiment\_single) all the variables are set to fixed values based on TPCONF\_variable\_defaults. The following shows an example for parameters included in TP-CONF\_parameter\_list in the example config files:

```
TPCONF_vary_parameters = [
    'tcpalgos', 'delays', 'loss',
    'bandwidths', 'aqms', 'bsizes',
    'runs',
]
```

# O. Experiment-specific variables

Some variables defined in the example config file(s) are only used with certain traffic generators.

TPCONF\_dash\_rates specifies the DASH content rates in kbit/second and TPCONF\_dash\_rates\_str is a string with a comma-separated list of rates (the latter is used by the content creation function create\_http\_dash\_content). DASH rates must be integers. The following shows an example:

TPCONF\_inc\_content\_sizes specifies the content sizes in kB (as integer) for the replies sent in an incast scenario. TPCONF\_inc\_periods specifies the length of a period between requests by the querier in seconds (as floating point). The following shows an example:

```
TPCONF_inc_content_sizes= '64, 512, 1024'
TPCONF_inc_periods = [ 10 ]
```

TPCONF\_chunksize\_mpd is used with *start\_dash\_streaming\_dashjs* traffic generator to specify a list of one or more DASH video chunk size and MPD filename pairs. The following shows an example:

```
TPCONF_chunksize_mpd = [
  ('2','BigBuckBunny_2s.mpd'),
  ('10','BigBuckBunny_10s.mpd')
```

# P. Defining parameters to vary

The *keys* in TPCONF\_parameter\_list are names that can be used in TPCONF\_vary\_parameters. The *values* in TPCONF\_parameter\_list are 4-tuples:

- 1st parameter of each tuple is a list of V\_variables that can be used, for example, in the queue configuration or traffic generator configuration
- 2nd parameter of each tuple is a list of 'short names' used in the <testID> (and hence the file names) of created log files
- 3rd parameter of each tuple is the list of parameter values, these are usually references to the lists defined in the previous section
- The last parameter is a dictionary of extra V\_variables to set (this can be empty), where the keys are variable names and the values are the variable values.

The length of the first three tuple parameters (V\_variable identifiers, short names and V\_variable values) must be equal.

When a group of experiments is started with 'fab run\_experiment\_multiple' the following happens: For each parameter combination of the parameters defined in TPCONF\_vary\_parameters, one experiment is run where the parameter name-value pairs (using each parameter's short name) are used to construct the <testID> (and hence various log file names)<sup>14</sup>, and the V\_ variables are set to the parameter combination given by the value lists.

TPCONF\_parameter\_list can handle grouped V\_variables, where in each experiment a specific combination of the grouped V\_variables is used. An example of this is the *bandwidths* parameter which uses TPCONF\_bandwidths for its values.

TPCONF\_variable\_defaults is a dictionary that specifies the defaults for V\_ variables. The keys are V\_ variable

<sup>&</sup>lt;sup>14</sup>The parameters appear in the <testID> in the same (user-defined) order they are listed in TPCONF\_vary\_parameters.

names and the values are the default values (often the first value of the parameter lists). For each parameter that is not varied, the default value specified in TP-CONF variable defaults is used.

We now discuss a simple example where we focus on the variables to vary delay and TCP algorithms. Assume we want to experiment with two delay settings and two different TCP CC algorithms. So we have:

```
TPCONF_delays = [ 0, 50 ]
TPCONF_TCP_algos = [ 'newreno', 'cubic' ]
```

We also need to specify the two parameters to be varied and the default parameters for the variables as shown in Figure 14.

V\_delay can then be used in the router queue settings. V\_tcp\_cc\_algo is passed to the host setup function. When we run 'fab run\_experiment\_multiple' this will run the following experiments, represented by the following test IDs (we assume the test ID prefix is the default from Section V-F):

```
exp_20131206-170846_del_0_tcp_newreno
exp_20131206-170846_del_0_tcp_cubic
exp_20131206-170846_del_50_tcp_newreno
exp_20131206-170846_del_50_tcp_cubic
```

# Q. Adding new V\_ variables

New V\_variables are easy to add. Say we want to create a new V\_variable called V\_varx. We need to do the following:

- Add a new list with parameter values, let's say
   TPCONF\_varx = [x, y]
- 2) Add one line in TPCONF\_parameters\_list: the key is the identifier that can be used in TP-CONF\_vary\_parameters (let's call it varx\_vals), and the value is a 4-tuple: variable name as string 'V\_varx', variable name used in file name (say 'varx'), pointer to value list (here TPCONF\_varx), and optionally a dictionary with related variables (here empty).
- 3) Add one line in TPCONF\_variable\_defaults specifying the default value used (when not iterating over the variable): the key is the V\_variable name as string (here 'V\_varx') and the value is the default value from TPCONF\_varx (say TPCONF\_varx[0]).

Technically, step 1 is not necessary as the list of values can be put directly in TPCONF\_parameters\_list

and the default value can be put directly in TP-CONF\_variable\_defaults. However, defining a separate list improves the readability.

#### VI. AVAILABLE TRAFFIC GENERATORS

This section describes the traffic generators (listed by their start\_\* function names) that can be configured in TPCONF\_traffic\_gens (section V-M).

# A. start\_iperf

This starts an iperf client and server. Note that the client sends data to the server. It has the following parameters:

- **port**: port number to use for client and server (passed to iperf -p option)
- **client**: IP or name of client (passed to iperf -c option)
- **server**: IP or name of server (passed to iperf -B option)
- duration: time in seconds the client transmits (passed to iperf -t option)
- **congestion\_algo**: TCP congestion algorithm to use (works only on Linux)
- **kill**: By default this is '0' and the iperf client will terminate after duration seconds. If this is set to '1', the iperf client will be killed approximately 1 second after duration. This is a work-around for a "feature" in iperf that prevents it from stopping after the specified duration. (If set to '1', the iperf server is also killed approximately 2 seconds after duration.)
- mss: TCP maximum segment size (passed to iperf
   M option)
- **buf\_size**: Send and receive buffer size in bytes (passed to iperf -j and -k, which only exist for iperf with the CAIA patch [7])
- **proto**: Protocol to use, 'tcp' (default) or 'udp' (sets iperf -u option for 'udp')
- rate: The bandwidth used for TCP (passed to iperf -a option) or UDP (passed to iperf -b option). Can end in 'K' or 'M' to indicate kilo bytes or mega bytes.
- extra\_params\_client: Command line parameters passed to iperf client
- extra\_params\_server: Command line parameters passed to iperf server

Figure 14: Specifying the parameters to be varied

#### B. start\_ping

This starts a ping and has the following parameters:

- client: IP or name of machine to run ping on
- dest: IP or name of machine to ping
- duration: Emit pings for this many seconds
- rate: number of pings per second (Windows ping only supports 1 ping/second) (default = 1)
- **extra\_params**: Command line parameters passed to ping

# C. start\_http\_server

This starts a lighttpd-based HTTP server and has the following parameters:

- server: IP or name of HTTP server
- **port**: port to listen on (currently one server can listen on only one port)
- **config\_dir**: directory where the config file (lighttpd.conf) should be copied to
- config in: local template for config file
- docroot: document root on server (FreeBSD default: /usr/local/www/data, MacOSX default: /opt/local/www/htdocs, Linux/CYGWIN default: /srv/www/htdocs)

#### D. start\_nginx\_server

[New in TEACUP 1.1] This starts an nginx-based HTTP server and has the following parameters:

- server: IP or name of HTTP server
- **port**: port to listen on (currently one server can listen on only one port)
- **config\_dir**: directory where the config file (ng-inx.conf) should be copied to
- config\_in: local template for config file

docroot: document root on server (FreeBSD default: /usr/local/www/nginx, Linux default: /var/www/html)

# E. create\_http\_dash\_content

[Deprecated in TEACUP 1.1, but still available] This creates fake content for the DASH-like httperf\_dash client. It has the following parameters:

- server: IP or name of HTTP server
- docroot: document root of HTTP server (FreeBSD default: /usr/local/www/data, MacOSX default: /opt/local/www/htdocs, Linux/CYGWIN default: /srv/www/htdocs)
- duration: number of seconds of fake content
- rates: comma-separated list of DASH rates in kB
- cycles: comma-separated list of cycle lengths in seconds

NOTE: This generator is deprecated in TEACUP 1.1, along with *start\_httperf\_dash*. Users are recommended to launch lighttpd server with genuine DASH content instead, and use *start\_dash\_streaming\_dashjs* to launch a genuine DASH client.

# F. create\_http\_incast\_content

This creates fake content for incast experiments. It has the following parameters:

- server: IP or name of HTTP server
- docroot: document root of HTTP server (FreeBSD default: /usr/local/www/data, MacOSX default: /opt/local/www/htdocs, Linux/CYGWIN default: /srv/www/htdocs)
- duration: number of seconds of fake content
- sizes: comma-separated list of content file sizes

#### G. start\_httperf

This starts an httperf HTTP client. It has the following parameters:

- client: IP or name of client
- **server**: IP or name of HTTP server (passed to httperf --server)
- port: port server is listening on (passed to httperf --port)
- **conns**: total number of connections (passed to httperf --num-conns)
- rate: rate at which connections are created (passed to httperf --rate)
- **timeout**: timeout for each connection; httperf will give up if a HTTP request does not complete within the timeout (passed to httperf --timeout)
- **calls**: number of requests in each connection (passed to httperf --num-calls, default = 1)
- **burst**: length of burst (passed to httperf --burst-length)
- **wsesslog**: session description file (passed to third parameter of httperf --wsesslog)
- wsesslog\_timeout: default timeout for each wsesslog connection (passed to second parameter of httperf --wsesslog)
- **period**: time between creation of connections; equivalent to 1/rate if period is a number, but period can also specify inter-arrival time distributions (see httperf man page)
- **sessions**: number of sessions (passed to first parameter of httperf --wsesslog, default = 1)
- call\_stats: number of entries in call statistics array (passed to httperf --call-stats, default = 1000)
- extra\_params: Command line parameters passed to httperf

# H. start\_httperf\_dash

[Deprecated in TEACUP 1.1, but still available] This starts a simplistic, DASH-like httperf client. It has the following parameters:

- client: IP or name of client
- **server**: IP or name of HTTP server (passed to httperf --server)
- port: port server is listening on (passed to httperf --port)
- duration: duration of DASH flow in seconds
- rate: data rate of DASH-like flow in kbps
- cycle: interval between requests in seconds

- **prefetch**: prefetch time in seconds of content to prefetch (can be fractional number) (default = 0.0)
- **prefetch\_timeout**: like timeout for start\_httperf but only for the prefetch (by default this is set to cycle)
- with\_timeout: if set to '0' there is no timeout for requests (a request may take longer to complete than cycle); if set to '1' httperf will close the connection and terminate the session if the download of a chunk takes longer than cycle
- extra\_params: Command line parameters passed to httperf

The behaviour is as follows:

- 1) The client opens a persistent TCP connection to the server.
- 2) If prefetch is > 0.0 the client will fetch the specified number of seconds of content and right after that send a request for the next block (step 3).
- 3) The client will request a block of content, wait for some time (cycle minus download time) and then request the next block. The size of one block is  $cycle \cdot rate \cdot 1000/8bytes$ .

If prefetch\_timeout is set, the prefetch must be completed within the timeout, or otherwise httperf will close the connection and terminate the session. Similarly, if with\_timeout='1', httperf will close the connection and terminate the session if the download of a chunk takes longer than cycle seconds.

Note that the number of chunks requested by the httperf client is set to floor((duration - prefetch\_timeout) / cycle). This number guarantees that httperf can complete and generate the statistics output within the specified duration, even if the downloading takes the maximum amount of time (downloading always just finishes within the timeouts). However, this also means that if the prefetch is much faster than prefetch\_timeout and/or the download of the last chunk is much faster than cycle seconds, httperf will finish well before duration seconds.

**NOTE:** This generator is deprecated in TEACUP 1.1. Users are recommended to launch lighttpd or nginx server with genuine DASH content instead, and use *start\_dash\_streaming\_dashjs* to launch a genuine DASH client.

#### I. start\_dash\_streaming\_dashjs

[New in TEACUP 1.1] This starts a genuine DASH streaming client (dash.js) inside a web browser on an end host. It has the following parameters:

- client: IP or name of DASH client
- server: IP or name of DASH server
- serv\_port: port server is listening on
- duration: duration of DASH flow in seconds (since version 2.3.0, dash.js supports playback looping, so the specified duration can be longer than the video time)
- **browser**: choose between a Chrome or Firefox browser
- **chunk\_size**: specify the video chunk size (availability depends on the dataset)
- mpd: specify the filename of Media Presentation Description (MPD) (availability depends on the dataset)
- player\_path: specify the path to dash.js player source (which can be located on other hosts)

Note that some additional setup are required for *start\_dash\_streaming\_dashjs* to run successfully::

- 1) Additional packages such as Xorg and Chrome (or Firefox) need to be installed on client host(s). 15
- 2) A DASH-compliant dataset needed to be present and served by the web server host(s).
- 3) The dash.js player's source files need to be available (served) from either the control host or one of the experiment hosts. The location of dash.js source files is supplied via player\_path.

See [31] for more details and configuration examples.

# J. start\_httperf\_incast

This starts an httperf client for the incast scenario. It has the following parameters:

- client: IP or name of client
- **servers**: comma-separated list where each entry specifies one server in the form of '[IPlname]:port'. IP or name is a server's IP address or name and port is the port the server is listening on (a separate session for each server is created via httperf's session log).

- duration: duration of incast session in seconds
- **period**: period between requests in seconds (floating point number)
- burst\_size: number of queries sent at each period start (this is to increase the number of queries in a testbed that only has a few physical responder machines)
- **response\_size**: size of response from each responder in kB
- extra\_params: Command line parameters passed to httperf

Note: If httperf can not complete a request within period time, if will close the connection and terminate the session with the responder (sessions with other responders are unaffected). This may or may not be desirable behaviour.

#### K. start\_nttcp

This starts an nttcp client and an nttcp server for some simple unidirectional UDP VoIP flow emulation. It has the following parameters:

- client: IP or name of client
- server: IP or name of HTTP server
- port: control port server is listening on (passed to nttcp -p)
- **duration**: duration of the flow (based on this and the interval TEACUP computes the number of buffers to send, passed to nttcp -n)
- **interval**: interval between UDP packets in milliseconds (passed to nttcp -g)
- **psize**: UDP payload size (excluding UDP/IP header) (passed to nttcp -1)
- **buf size**: send buffer size (passed to nttcp -w)
- extra\_params\_client: Command line parameters passed to nttcp client
- extra\_params\_server: Command line parameters passed to nttcp server

Note that nttcp also opens a TCP control connection between client and server. However, on this connection only a few packets are exchanged before and after the data flow.

# L. start\_httperf\_incast\_n

This starts an httperf client (querier) and n HTTP servers (responders) for an incast scenario. It also generates the fake content for all n servers. Basically this generator is

<sup>&</sup>lt;sup>15</sup>These client host(s) must also have a functional video card (not an emulated X server) for proper browser-based DASH client behaviour.

a shortcut to setting up n servers with n start\_http\_server and create\_http\_incast\_content. It has the following parameters:

- client: IP or name of client
- servers: comma-separated list of servers, where each entry is either the IP or the host name of an HTTP server (a separate session for each server is created via httperf's session log)
- **server\_port\_start**: the port the first server is listening on. All further servers will be started on consecutive port numbers in the order they are specified in servers
- duration: duration of incast session in seconds
- **period**: period between requests in seconds (floating point number)
- burst\_size: number of queries sent at each period start (this is to increase the number of queries in a testbed that only has a few physical responder machines)
- response\_size: size of response from each responder in kB
- **config\_dir**: directory where the config file (lighttpd.conf) should be copied to
- config\_in: local template for config file
- docroot: document root on server (FreeBSD default: /usr/local/www/data, MacOSX default: /opt/local/www/htdocs, Linux/CYGWIN default: /srv/www/htdocs)
- **sizes**: comma-separated list of content file sizes on the servers
- num\_responders: The querier will only send queries to the first num\_responders servers. This can be used to vary the number of responders in a series of experiments
- **extra\_params**: Command line parameters passed to httperf

Note that for this method the unique ID is the first ID used. The total number of IDs used is one plus the number of server/responders. Each server will be assigned a consecutive ID number starting with the first ID. The client will have an ID one higher than the highest server ID. If further traffic generators are specified after this generator, the user has to make sure there is no ID number clash.

# M. start\_fps\_game

This starts an emulated FPS game traffic session. From a logical viewpoint this starts several game clients and

one game server. This task has the following parameters:

- **clients**: comma-separated list of clients where each client is specified as name/IP followed by a colon and the port number (e.g. client1:10000,client2:10001)
- **server**: server name/IP followed by a colon and the server port number (e.g. server1:27960)
- **game\_type**: the type of game (can be 'q3', 'hl2cs', 'hl2dm', 'hlcs', 'hldm', 'et2pro', 'q4')
- c2s\_interval: time interval between packets send by client (in seconds)
- c2s\_psize: base packet size of packets send by clients (number of bytes of UDP payload); note that pktgen randomly varies the size of packets within a few bytes above the base size)
- **s2c\_interval**: time interval between packets send by server (in seconds)
- duration: duration of the game session (in seconds)
- **client\_start\_delay**: delay between the last serverto-client pktgen process started and the first clientto-server pktgen process started (in seconds)
- extra\_params\_client: extra parameters passed to client pktgen processes
- extra\_params\_server: extra parameters passed to server pktgen processes
- noclients\_games: allows just the declaration of multiple clients without requiring that many clients to be setup, to emulate server behaviour for the specified number of clients.

Note that a pktgen server process will wait for packets from its corresponding client process before starting to send packets. In contrast, a client process will send packets to a corresponding server process immediately. If a client process is started, but the corresponding server process is not listening for packets yet, the server machine will return ICMP port unreachable messages to the client machine, which in turn will terminate the client process. The parameter client\_start\_delay must be set large enough so that all server processes are started and listen for packets before any client processes are started. The delay must be chosen based on the number of game clients (as each game client results in one pktgen process started on the server). By default client\_start\_delay is set to three seconds, which is sufficient for up 8 game clients.

Note that pktgen only supports emulating games with 4–32 clients. Fewer actual clients may be specified if

noclients\_game is specified to be between 4 and 32, in which case fewer instances of pktgen will be launched and the server-to-client traffic will emulate that of a game with noclients\_game clients.. If noclients\_game is not specified, then the number of separate clients must be at least 4, and no larger than 32.

Also note that for this method the unique ID is the first ID used. In total the number of IDs used is twice the number of clients. Each server-to-client pktgen will be assigned a consecutive ID number starting with the first ID. Each client-to-server pktgen will be assigned a consecutive ID number starting with an ID one higher than the highest server-to-client pktgen ID. If further traffic generators are specified after this generator, the user has to make sure there is no ID number clash.

#### VII. RUNNING EXPERIMENTS

This section describes how to run experiments. First, we describe the initial steps needed. Then we outline a simple example config file. Finally, we describe how to run the experiments.

#### A. Initial steps

First you should create a new directory for the experiment or series of experiments. Copy the files fabfile.py and run.sh (and run\_resume.sh) from the TEACUP distribution into that new directory. Then create a config.py file in the directory. An easy way to get a config.py file is to start with one of the provided example config files as basis and modify it as necessary.

# B. Example config

Listing 1 shows a minimal but complete config.py file. The testbed consists of three machines, two hosts (192.168.1.2, 192.168.1.3) connected by a router (192.168.1.4). The two hosts will run FreeBSD for the experiment, while the router will run Linux. On the router we configure two pipes, one in each direction, with different rates but the same AQM mechanism, buffer size, and emulated delay and loss. The test traffic consists of two parallel TCP sessions generated with iperf, both start at the start of the experiment (time 0.0). With iperf the client sends data to the server, so the data is sent from 192.168.1.2 to 192.168.1.3. Each experiment lasts 30 seconds and we run a series of experiments varying the TCP congestion control algorithm, network delay and loss, upstream and downstream bandwidths, AQM

technique, and buffer size. There is one experiment for each combination of parameters (one run).

#### C. Running experiments

There are two Fabric tasks to start experiments:  $run\_experiment\_single$  and  $run\_experiment\_multiple$ .

To run a single experiment with the default test ID prefix (TPCONF\_test\_id), type:

```
> fab run_experiment_single
```

To run a group of experiment based on the TP-CONF\_vary\_parameters settings with the default test ID prefix (TPCONF\_test\_id), type:

```
> fab run_experiment_multiple
```

In both cases the Fabric log output will be printed out on the current terminal (stdout) and can be redirected with the usual means. The default test ID prefix (TP-CONF\_test\_id) is specified in the config file. However, the test ID prefix can also be specified on the command line (overruling the config setting):

```
> fab run_experiment_multiple:test_id=exp_'date
+"%Y%m%d-%H%M%S"'
```

The last command will run a series of experiments where the test ID prefix is exp\_YYYYMMDD-HHMMSS (using the actual date and time when the fab command is run). For convenience TEACUP provides a shell script (run.sh) that logs the Fabric output in a <testIDprefix>.log file inside the <testIDprefix> sub directory, and is started with:

#### > run.sh

The shell script generates a test ID prefix and then executes the command:

```
> fab run_experiment_multiple:test_id=
<testIDprefix> > <testIDprefix>.log 2>&1
```

The test ID prefix is set to exp\_'date +"%Y%m%d-%H%M%S"'. The output is unbuffered, so one can use tail -f on the <testIDprefix>.log file and get timely output. The fabfile to be used can be specified, i.e. to use the fabfile myfabfile.py instead of fabfile.py run:

# > run.sh myfabfile.py

TEACUP keeps track of experiments using two files in the current directory:

```
import datetime
 from fabric.api import env
 env.password = 'password'
env.shell = '/bin/sh -c'
env.timeout = 5
 env.pool_size = 10
TPCONF_script_path = '/home/test/src/teacup'
sys.path.append(TPCONF_script_path)
TPCONF_tftpboot_dir = '/tftpboot'
TPCONF_touter = [ '192.168.1.4', ]
TPCONF_hosts = [ '192.168.1.2', '192.168.1.3', ]
TPCONF_host_internal_ip = {
  '192.168.1.4' : [ '172.16.10.1', '172.16.11.1' ],
  '192.168.1.2' : [ '172.16.10.2' ],
  '192.168.1.3' : [ '172.16.11.2' ], }
 TPCONF_script_path = '/home/test/src/teacup'
 now = datetime.datetime.today()
TPCONF_test_id = 'exp_' + now.strftime("%Y%m%d-%H%M%S")
TPCONF_remote_dir = '/tmp/'
TPCONF_remote_dir = '/tmp/'
TPCONF_host_os = {
  '192.168.1.4' : 'Linux',
  '192.168.1.2' : 'FreeBSD',
  '192.168.1.3' : 'FreeBSD', }
TPCONF_linux_kern_router = '3.14.18-10000hz'
TPCONF_force_reboot = '1'
TPCONF_boot_timeout = 100
TPCONF_do nower_cycle = '0'
 TPCONF_host_power_ctrlport =
TPCONF_nower_admin_name = ''
 TPCONF_power_admin_name =
TPCONF_power_admin_pw = ''
 TPCONF_max_time_diff = 2
 TPCONF_router_queues = [
 ('1', "source='172.16.10.0/24', dest='172.16.11.0/24', delay=V_delay, loss=V_loss, rate=V_urate, queue_disc=V_aqm, queue_size=V_bsize"), ('2', "source='172.16.11.0/24', dest='172.16.10.0/24', delay=V_delay, loss=V_loss, rate=V_drate, queue_disc=V_aqm, queue_size=V_bsize"), ]
traffic_iperf = [
  ('0.0', '1', "start_iperf, client='192.168.1.2', server='192.168.1.3', port=5000, duration=V_duration"),
  ('0.0', '2', "start_iperf, client='192.168.1.2', server='192.168.1.3', port=5001, duration=V_duration"), ]
TPCONF_traffic_gens = traffic_iperf;
TPCONF_duration = 30
TPCONF_runs = 1
TPCONF_ECN = [ '0', '1' ]
TPCONF_TCP_algos = [ 'newreno', 'cubic', 'http', ]
 TPCONF_host_TCP_algos = { }
TPCONF_host_TCP_algo_params = { }
 TPCONF_host_init_oustom_comds = { }

TPCONF_host_init_oustom_comds = { }

TPCONF_delays = [ 0, 25, 50, 100 ]

TPCONF_loss_rates = [ 0, 0.001, 0.01 ]

TPCONF_bandwidths = [ ('8mbit', '1mbit'), ('20mbit', '1.4mbit'), ]

TPCONF_aqms = [ 'pfifo', 'codel', 'pie' ]

TPCONF_buffer_sizes = [ 1000, 1 ]
TPCONF_parameter_list = {
  'delays' : ( [ 'V_delay' ], [ 'del' ], TPCONF_delays, {} ),
  'loss' : ( [ 'V_loss' ], [ 'loss' ], TPCONF_loss_rates, {} ),
  'tcpalgos' : ( [ 'V_tcp_cc_algo' ], [ 'tcp' ], TPCONF_TCP_algos, {} ),
  'aqms' : ( [ 'V_aqm' ], [ 'aqm' ], TPCONF_aqms, {} ),
  'bsizes' : ( [ 'V_bsize' ], [ 'bs' ], TPCONF_buffer_sizes, {} ),
  'runs' : ( [ 'V_runs' ], [ 'run' ], range(TPCONF_runs), {} ),
  'bandwidths' : ( [ 'V_drate', 'V_urate' ], [ 'down', 'up' ], TPCONF_bandwidths, {} ), }
  TPCONF_variable defaults = {
'bandwidths' : ( [ 'V_drate', 'V_urate
TPCONF_variable_defaults = {
'V_ecn' : TPCONF_ECN[0],
'V_duration' : TPCONF_duration,
'V_delay' : TPCONF_delays[0],
'V_loss' : TPCONF_loss_rates[0],
'V_tcp_cc_algo' : TPCONF_TCP_algos[0],
'V_drate' : TPCONF_bandwidths[0][0],
'V_urate' : TPCONF_bandwidths[0][1],
'V_arm' : TPCONF_arms[0]
 'V_drate : TPCONF_Bandwidths[0][1],
'V_aqm' : TPCONF_aqms[0],
'V_bsize' : TPCONF_buffer_sizes[0], }
 TPCONF_vary_parameters = [ 'topalgos', 'delays', 'loss', 'bandwidths', 'aqms', 'bsizes', 'runs', ]
```

Listing 1: Example config.py file

- The file experiment\_started.txt logs the test IDs of all experiments started.
- The file experiment\_completed.txt logs the test IDs of all experiments *successfully completed*.

Note that TEACUP never resets either of these files – new test IDs are simply appended to the files (which are created if they don't already exist). <sup>16</sup>

A run\_experiment\_multiple task that was interrupted part-way through may be restarted with the resume parameter. TEACUP will perform all experiments of the series that were not previously completed (not logged in experiments\_completed.txt).

For example, the following command resumes a series of experiments with test ID prefix exp\_20131218-113431 (and appends the log output to the existing log file):

```
> fab run_experiment_multiple:
test_id=exp_20131218-113431,resume=1 >>
exp_20131218-113431.log 2>&1
```

The resume parameter also enables redoing of previously completed experiments, by first editing them out of experiments\_completed.txt.

If a series of experiments is interrupted by nondeterministic errors, i.e. each experiment may fail with some small probability, the run\_resume.sh shell script can be used to ensure the whole series of experiments is completed. The script runs the experiments using the run\_experiment\_multiple task and uses the resume option to automatically restart and continue each time an experiment was not successfully completed. The script is used by executing:

```
> run_resume.sh
```

## D. TEACUP variable information logged

TEACUP logs configuration information for conducted experiments in two files. In the following <testID> is a test ID and <testIDprefix> is the corresponding test ID prefix. For each experiment, TEACUP logs all V\_ variables and their values (in alphabetical order of variable names) in a file <testID>\_config\_vars.log.gz. The following is an example (with header and legend lines omitted for brevity):

```
U V_aqm: pfifo
U V_bsize: 1000
U V_delay: 100
```

Each line starts with an 'U' or an 'N' indicating whether a variable is Used or Not used. After the use indicator follows the variable name and the value the variable was set to in the particular experiment.

TEACUP also logs all varying parameters for a series of experiments in a file named <testIDpre-fix>\_varying\_params.log.gz. The following shows a file as example (excluding the header line):

```
V_aqm aqm aqms
V_bsize bs bsizes
V_delay del delays
```

In each line, the first column is the V\_ variable name, the second column is the short name used in the test ID (in the file names), and the last column is the identifier that is used in TPCONF\_vary\_parameters (and links to an entry in TPCONF\_parameter\_list).

# VIII. HOST CONTROL UTILITY FUNCTIONS

This section describes a number of utility functions available as Fabric tasks. As mentioned previously, the fab utility has an option to list all available tasks:

```
> fab -l
```

# A. Remote command execution

The exec\_cmd task can be used to execute one command on one or more testbed hosts. For example, the following command executes the command uname -s on a number of hosts:

```
> fab -H testhost1,testhost2,testhost3
exec_cmd:cmd="uname -s"
```

If no hosts are specified on the command line, the exec\_cmd command is executed on all hosts listed in the config file (the union set of TPCONF\_router and TPCONF\_hosts). For example, the following command is executed on all testbed hosts:

```
> fab exec_cmd:cmd="uname -s"
```

#### B. Copying files to testbed hosts

The copy\_file task can be used to copy a local file to one or more testbed hosts. For example, the following command copies the web10g-logger executable to all

<sup>&</sup>lt;sup>16</sup>The user must manually delete or edit these files if actual experiment results are later deleted.

testbed hosts except the router (this assumes all the hosts run Linux when the command is executed):

```
> fab -H testhost2,testhost3
copy_file:file_name=/usr/bin/web10g-logger,
remote_path=/usr/bin
```

If no hosts are specified on the command line, the command is executed for all hosts listed in the config file (the union set of TPCONF\_router and TPCONF\_hosts). For example, the following command copies the file to all testbed hosts:

```
> fab copy_file:file_name=
/usr/bin/web10g-logger,remote_path=/usr/bin
```

The parameter method controls the method used for copying. By default (method='put') copy\_file will use the Fabric put function to copy the file. However, the Fabric put function is slow. For large files setting method='scp' provides much better performance using the scp command. While scp is faster, it may prompt for the password if public key authentication has not been configured.

# C. Installing ssh keys

The authorize\_key task can be used to append the current user's public SSH key to the ~./ssh/authorized\_keys file of the remote user. The user can then login via SSH without having to enter a password. For example, the following command enables password-less access for the user on three testbed hosts:

```
> fab -H testhost1,testhost2,testhost3
authorize_key
```

Note: the authorize\_key task assumes the user has a ~/.ssh/id\_rsa.pub key file. This can be created with ssh-keygen -t rsa. Also note that this task does not check if the public key is already in the remote user's authorized\_keys file, so executing this task multiple times may lead to duplicate entries in the remote user's authorized\_keys file.

#### D. Topology configuration

Where the testbed meets the requirements described in Section V-H, the init\_topology task can be used to "move" hosts from one test subnet to the other by configuring the VLAN membership of the switch ports in conjunction with IP addresses and static routes on each host. This task uses the config.py file to get the testbed IP addresses of the hosts to

be configured (from TPCONF\_host\_internal\_ip). It also uses the values of TPCONF\_topology\_switch, TPCONF\_topology\_switch\_port\_prefix, and TPCONF\_topology\_switch\_port\_offset specified in config.py to reconfigure the switch. The last three parameters can also be overridden by the task's parameters switch, port\_prefix, and port\_offset. Limitations of the current implementation are described in Section V-H.

The following shows an example where we configure the hosts testhost1 and testhost2 using the task's parameters to specify the switch-relevant settings:

```
> fab -H testhost1,testhost2
init_topology:switch="switch2",
port_prefix="Gi1/0/",port_offset="5"
```

#### E. Initialise hosts to a specific operating system

The init\_os task can be used to reboot hosts into specific operating systems (OSs). For example, the following command reboots the hosts testhost1 and testhost2 into the OSs Linux and FreeBSD respectively:

```
> fab -H testhost1,testhost2
init_os:os_list="Linux\,FreeBSD",
force_reboot=1
```

Note that the commas in os\_list need to be escaped with backslashes (\), since otherwise Fabric interprets the commas as parameter delimiters. Note that os\_list can be shorter than the number of specified hosts, in which case it will be padded to the length of the number of hosts by duplicating the last entry. This allows the rebooting of a large number of hosts into the same OS while specifying an os\_list with only a single entry (the desired OS).

For Linux the kernel to boot can be chosen with the parameters <code>linux\_kern\_hosts</code> and <code>linux\_kern\_router</code>. <code>linux\_kern\_hosts</code> specifies the kernel for normal hosts (not routers) and <code>linux\_kern\_router</code> specifies the kernel for routers. Please refer to the description in Section V-I2 on how to specify the kernel name.

By default force\_reboot is 0, which means hosts that are already running the desired OS are not rebooted. Setting force\_reboot to 1 enforces a reboot. By default the script waits 100 seconds for a host to reboot. If the host is not responsive after this time, the script will give up unless the do\_power\_cycle parameter is set to

1. This timeout can be changed with the boot\_timeout parameter, which specifies the timeout in seconds (as integer). A minimum boot timeout of 60 seconds will be enforced.

The do\_power\_cycle parameter can be set to 1 to force a power cycle if a host does not respond after the boot timeout (assuming TEACUP-compatible power controller(s) are configured). The script will then wait for boot\_timeout seconds again for the host to come up. If the host is still unresponsive after the timeout the script will give up (there are no further automatic power cycles). The following command shows an example with do\_power\_cycle set to 1:

```
> fab -H testhost1,testhost2
init_os:os_list="Linux\,FreeBSD",
force_reboot=1,do_power_cycle=1
```

Since version 0.9.3 TEACUP can reboot unresponsive hosts (i.e. hosts to which TEACUP cannot establish an SSH connection), if the user specifies the MAC addresses of the control interface and a power controller is configured for the hosts. The MAC address(es) are specified with the mac\_list parameter (comma-separated list of MAC addresses, one for each host to be rebooted).

The following command shows an example of rebooting the unresposive host testhost1 (with control network interface MAC of 01:02:03:04:05:06) into Linux:

```
> fab -H testhost1 init_os:os_list="Linux",
mac_list="01:02:03:04:05:06"
```

# F. Power cycling

The power\_cycle task can be used to power cycle hosts, i.e. if hosts become unresponsive (assuming TEACUP-compatible power controller are configured). After the power cycle the hosts will boot the last selected OS. For example, the following command power cycles the hosts testhost1 and testhost2:

```
> fab -H testhost1,testhost2 power_cycle
```

#### G. Check software installations on testbed hosts

The check\_host command can be used to check if the required software is installed on the hosts. This task only checks for the presence of necessary tools, but it does not check if the tools actually work. For example, the following command checks all testbed hosts:

```
> fab -H testhost1,testhost2,testhost3
check_host
```

#### H. Check testbed host connectivity

The check\_connectivity task can be used to check connectivity between testbed hosts with ping. This task only checks the connectivity of the internal testbed network, not the reachability of hosts on their control interface. For example, the following command checks whether each host can reach each other host across the testbed network:

```
> fab -H testhost1,testhost2,testhost3
check_connectivity
```

# I. Check TEACUP config file

The check\_config task can be used to check the TEACUP config file. This task will perform a number of checks and abort with an error message if it finds any errors in the config file. (This task is automatically run at the start of each experiment or series of experiments.)

#### > fab check\_config

1) Print version information: The get\_version task prints out the TEACUP version number, revision number and data, and the copyright:

```
> fab get_version
```

The output will look like:

```
TEACUP Version 0.9
Revision: 1175
Date: 2015-04-01 11:00:50 +1100 (Wed, 01
Apr 2015)
Copyright (c) 2013-2015 Centre for
Advanced Internet Architectures
Swinburne University of Technology. All
rights reserved.
```

#### IX. EXPERIMENT EXAMPLES

#### A. Overview

Here we provide a few example scenarios of how TEACUP can be used. Each scenario involves traffic senders and receivers distributed across two subnets (subnet A and subnet B) connected by a bottleneck router. All hosts and the router are time synchronised using NTP. We have the following scenarios.

• Scenario 1: We have two TCP flows with data flowing from a source in subnet A to a destination

- in subnet B. We emulate different delays on the router. In this scenario the rebooting functionality of TEACUP is not used, which means the experimenter has to boot all three machines into the desired OS before the experiment is started.
- Scenario 2: As with scenario 1, with TEACUP also automatically booting the desired OS.
- Scenario 3: As with scenario 2, with TEACUP using a power controller to power cycle hosts if they don't respond after the reboot.
- Scenario 4: As with scenario 1, with each TCP flow between a different sender/receiver pair and different network path delay emulated for each flow (both flows still go through the same bottleneck).
- Scenario 5: We have three staggered bulk-transfer flows going through the router, each between a different sender/receiver pair. We use different emulated delay for each sender/receiver pair and also vary the bandwidths. We now also vary the TCP congestion control algorithm.
- Scenario 6: We have two hosts plus the router.
   One host acts as web server. The other host acts as a client to retrieve video content from the web server. We emulate different network delays and AQM mechanisms.
- Scenario 7: Investigating the incast problem. On host in subnet A queries 10 responders in subnet B. Again, we emulate different network delays, AQM mechanisms and TCP algorithms. We also vary the size of the responses.
- B. Scenario 1: Two TCP flows from data sender to receiver
- 1) Topology: In this scenario we have two hosts: newtcp20 connected to the 172.16.10.0/24 network and newtcp27 connected to the 172.16.11.0/24 network. The machine newtcpt3 connects the two experiment subnets. All three machines also have a second network interface that is used to control the experiment via TEACUP. newtcp20 and newtcp27 must run Linux, FreeBSD, Windows 7 or Mac OS X and newtcpt3 must run FreeBSD or Linux. newtcp20 and newtcp27 must have the traffic generator and logging tools installed as described in [7]. However, PXE booting or a multi-OS installation is not needed for this scenario.
- 2) Test Traffic: Two TCP bulk transfer flows are created using iperf.

- 3) Variable Parameters: We emulate three different delays and two different bandwidth settings – six different experiments in total. We do also define a variable parameter for AQM, but define only one AQM (default pfifo). This causes the used AQM to be logged as part of the experiment ID.
- 4) TEACUP Config File: You can download the configuration file from [32]. To use the configuration rename it to config.py. In the following we explain the configuration file.

Note that TEACUP configuration files can be split across multiple files (using Python's execfile()). This allows the splitting of a large config file into multiple files for better readability. It also allows the inclusion of parts of configuration files into multiple different config files, which makes it possible to reuse parts of the config that is not changed across multiple experiments. An example of a this is this config file, which is functionally identical to the above config file. Only here the main config file includes separate files to specify the testbed machines, the router setup and the traffic generated.

At the top of the configuration file we need to import the Fabric env structure and we also need to import any other Python functionality used (see Listing 2). First we need to configure the user and password used by Fabric via Fabrics env parameters. A password is not required if public key authentication is set up. We also need to tell Fabric how to execute commands on the remote machines. TEACUP uses Bourne shell (/bin/sh) by default.

The next part of the config file defines the path to the TEACUP scripts and the testbed hosts (see Listing ??). TPCONF\_router is used to define the router and TPCONF\_hosts is used to define the list of hosts. For each host and the router the testbed network interfaces need to be defined with TPCONF\_host\_internal\_ip. The router obviously has two testbed network interfaces, whereas the hosts have only one.

In the next part of the configuration file we need to define some general experiment settings (see Listing ??). TEACUP\_max\_time\_diff specifies (in seconds) the maximum clock offset allowed between all participating hosts. This is a very coarse threshold as the offset estimation performed by TEACUP is not very accurate. Currently, TEACUP simply attempts to find out if the synchronisation is very bad and if yes it will abort; it does not try to enforce high accuracy for

```
# User and password
env.user = 'root'
env.password = 'rootpw'
# Set shell used to execute commands
env.shell = '/bin/sh -c'
```

Listing 2: Scenario 1, Fabric configuration

```
# Path to teacup scripts
TPCONF_script_path = '/home/test/src/teacup'
# DO NOT remove the following line
sys.path.append(TPCONF_script_path)
# Set debugging level (0 = no debugging info output)
TPCONF_debug_level = 0
# Host lists
TPCONF_router = ['newtcprt3', ]
TPCONF_hosts = [ 'newtcp20', 'newtcp27', ]
# Map external IPs to internal IPs
TPCONF_host_internal_ip = {
        'newtcprt3': ['172.16.10.1', '172.16.11.1'],
        'newtcp20': ['172.16.10.60'],
        'newtcp27': ['172.16.11.67'],
}
```

Listing 3: Scenario 1, general settings and host

the time synchronisation. Despite the historical name, TPCONF\_test\_id defines the test ID <u>prefix</u> for an experiment or a group of experiments. TPCONF\_remote\_dir specifies where on the hosts the log files are stored until they are moved to the control host running TEACUP after each experiment.

Then we define the router queues/pipes using TP-CONF\_router\_queues (see Listing 5). Each entry of this list is a tuple. The first value is the queue number and the second value is a comma separated list of parameters. The queue numbers must be unique. Note that variable parameters must be either constants or variable names defined by the experimenter. Variables are evaluated during run-time. Variable names must start with a 'V\_'. Parameter names can only contain numbers, letter (upper and lower case), underscores (\_), and hyphen/minus (-). All V\_variables must be defined in TPCONF variable list (see below).

Next we need to define the traffic generated during the experiments (see Listing 6). TEACUP implements a number of traffic generators. In this example we use iperf to generate TCP bulk transfer flows. TP-CONF\_traffic\_gens defines the traffic generator, but here we use a temporary variable as well, which allows multiple traffic generator definitions and being able to

switch between them by changing the variable assigned to TPCONF\_traffic\_gens.

Each entry in is a 3-tuple. The first value of the tuple must be a float and is the time relative to the start of the experiment when tasks are executed. If two tasks have the same start time their start order is arbitrary. The second entry of the tuple is the task number and must be a unique integer (used as ID for the process). The last value of the tuple is a comma separated list of parameters. The first parameter of this list must be the task name. The TEACUP manual lists the task name and possible parameters. Client and server can be specified using the external/control IP addresses or host names. In this case the actual interface used is the first internal address (according to TPCONF\_host\_internal\_ip). Alternatively, client and server can be specified as internal addresses, which allows the use of any internal interfaces configured.

Next, we define all the parameter values used in the experiments (see Listing ??). TPCONF\_duration defines the duration of the traffic. TPCONF\_runs specifies the number of runs carried out for each unique combination of parameters. TPCONF\_TCP\_algos specifies the congestion control algorithms. Here we only use Newreno.

```
# Maximum allowed time difference between machines in seconds
# otherwise experiment will abort cause synchronisation problems
TPCONF_max_time_diff = 2
# Experiment name prefix used if not set on the command line
# The command line setting will overrule this config setting
now = datetime.datetime.today()
TPCONF_test_id = 'exp_' + now.strftime("%Y%m%d-%H%M%S")
# Directory to store log files on remote host
TPCONF_remote_dir = '/tmp/'
```

Listing 4: Scenario 1, test ID prefix and

Listing 5: Scenario 1, router queue configuration

Listing 6: Scenario 1, traffic configuration

In this simple case all hosts use the same TCP congestion control algorithm, but TEACUP allows the specification of per-host algorithms with TP-CONF\_host\_TCP\_algos. Parameter settings for TCP congestion control algorithms can be specified with TPCONF\_host\_TCP\_algo\_params (assuming parameters can be controlled with sysctl), but here we do not make use of that and simply use the default settings.

TPCONF\_delays specifies the delay values (delay in each direction), TPCONF\_loss\_rates specifies the possible packet loss rates and TPCONF\_bandwidths specifies the emulated bandwidths (in downstream and upstream directions). TPCONF\_aqms specifies the AQM mechanism to use (here pfifo which is the default). TPCONF\_buffer\_sizes specifies the size of the queue. This is normally specified in packets, but it depends on

the type of AQM. For example, if bfifo was used the size would need to be specified in bytes.

Finally, we need to specify which parameters will be varied and which parameters will be fixed for a series of experiments, and we also need to define how our parameter ranges above map to V\_variables used for the queue setup and traffic generators and the log file names generated by TEACUP (see Listing ??).

TPCONF\_parameter\_list is a map of the parameters we potentially want to vary. The key of each item is the identifier that can be used in TPCONF\_vary\_parameters (see below). The value of each item is a 4-tuple containing the following things. First, a list of variable names. Second, a list of short names uses for the file names. For each parameter varied a string '\_<short\_name>\_<value>'

```
# Duration in seconds of traffic
TPCONF_duration = 30
# Number of runs for each setting
TPCONF\_runs = 1
# TCP congestion control algorithm used
TPCONF_TCP_algos = ['newreno', ]
# Emulated delays in ms
TPCONF\_delays = [0, 25, 50]
# Emulated loss rates
TPCONF_loss_rates = [0]
# Emulated bandwidths (downstream, upstream)
TPCONF_bandwidths = [ ('8mbit', '1mbit'), ('20mbit', '1.4mbit'), ]
# AOM
TPCONF_aqms = ['pfifo', ]
# Buffer size
TPCONF_buffer_sizes = [100]
```

Listing 7: Scenario 1, experiment parameter

is appended to the log file names (appended to chosen prefix). Note, short names should only be letters from a–z or A–Z, do not use underscores or hyphens. Third, the list of parameters values. If there is more than one variable this must be a list of tuples, each tuple having the same number of items as the number of variables. Fourth, an optional dictionary with additional variables, where the keys are the variable names and the values are the variable values.

The parameters that are actually varied are specified with TPCONF\_vary\_parameters. Only parameters listed in TPCONF\_vary\_parameters will appear in the name of TEACUP output files. So it can make sense to add a parameter in TPCONF\_vary\_parameters that only has a single value, because only then will the parameter short name and value be part of the file names.

TPCONF\_variable\_defaults specifies the default value for each variable, which is used for variables that are not varied. The key of each item is the parameter name. The value of each item is the default parameter value used if the variable is not varied.

5) Running Experiment: Create a directory with the above config.py and copy fabfile.py and run.sh from the TEACUP code distribution into this directory. To run the series of experiments with all parameter combinations go into the experiment directory (that contains fabfile.py and run.sh) and execute:

```
> ./run.sh
```

This will create a sub directory with the name of the test ID prefix and store all output files in this sub directory.

6) Analysing Results: TEACUP provides a range of tasks for analysing the results of a given experiment, described in an accompanying technical report [8]. Here we briefly summarise how to extract some key results.

TEACUP will create a <testIDprefix>.log file in the experiment data sub directory. It will also create a file experiments\_started.txt and experiments\_completed.txt in the parent directory. The file experiments\_started.txt contains the names of all experiments started and the file experiments completed.txt contains the names of all experiments successfully completed. If some experiments were not completed, check the log file for errors.

Assuming all experiments of a series completed successfully, we can now start to analyse the data. To create time series of CWND, RTT as estimated by TCP, RTT as estimated using SPP and the throughput over time for each experiment of the series, use the following command which creates intermediate files and the .pdf plot files in a sub directory named results inside the test data directory (the command needs to be executed in the directory where fabfile.py is).

```
> fab analyse_all:out_dir="../results"
```

Figure 15 shows the throughput and TCP's smoothed RTT estimates produced by TEACUP for the experiment with an emulated RTT of 50 ms, a bandwidth of 8 mbit/s downstream and 1 mbit/s upstream, and a buffer size of 100 packets. The hosts and the router ran Linux kernel 3.17.4. The throughput graph shows that both flows share the downstream link equally, while the upstream link carrying only ACKs is not fully utilised. The RTT graph shows that the total RTT reaches almost 100 ms due to

```
TPCONF_parameter_list = {
        # Vary name V_ variable file name values extra vars
        'delays' : (['V_delay'], ['del'], TPCONF_delays, {}),
        'loss' : (['V_loss'], ['loss'], TPCONF_loss_rates, {}),
        'tcpalgos' : (['V_tcp_cc_algo'],['tcp'], TPCONF_TCP_algos, {}),
        'aqms' : (['V_aqm'], ['aqm'], TPCONF_aqms, {}),
        'bsizes' : (['V_bsize'], ['bs'], TPCONF_buffer_sizes, {}),
        'runs' : (['V_runs'], ['run'], range(TPCONF_runs), {}),
        'bandwidths' : (['V_down_rate', 'V_up_rate'], ['down', 'up'], TPCONF_bandwidths, {}),
TPCONF_variable_defaults = {
        # V_ variable value
        'V_duration' : TPCONF_duration,
        'V_delay' : TPCONF_delays[0],
'V_loss' : TPCONF_loss_rates[0],
        'V tcp cc algo' : TPCONF TCP algos[0],
        'V_down_rate' : TPCONF_bandwidths[0][0],
        'V_up_rate' : TPCONF_bandwidths[0][1],
        'V_aqm' : TPCONF_aqms[0],
        'V_bsize' : TPCONF_buffer_sizes[0],
# Specify the parameters we vary through all values, all others will be fixed
# according to TPCONF_variable_defaults
TPCONF_vary_parameters = ['delays', 'bandwidths', 'aqms', 'runs',]
```

Listing 8: Scenario 1, variable parameters

the buffering (the plotted RTT estimates for the ACK streams are useless).

C. Scenario 2: Scenario 1 plus automatic booting of hosts

- 1) Topology: Like in scenario 1 we have two hosts: newtcp20 connected to the 172.16.10.0/24 network and newtcp27 connected to the 172.16.11.0/24 network. The machine newtcprt3 connects the two experiment subnets. All three machines also have a second network interface that is used to control the experiment via TEACUP. In this scenario we assume that the hosts have been installed according to [7] including PXE booting and a multi-OS installation on each host as described in the tech report.
- 2) *Test Traffic:* Like in scenario 1 two TCP bulk transfer flows are created using iperf.
- 3) Variable Parameters: Like in scenario 1 we emulate three different delays and two different bandwidth settings six different experiments in total. We do also define a variable parameter for AQM, but define only one AQM (default pfifo). This causes the used AQM to be logged as part of the experiment ID.
- 4) TEACUP Config File: You can download the configuration file from [32]. To use the configuration rename

it to config.py. In the following we explain the configuration file.

Most of the configuration is identical to the configuration used in scenario 1. The only difference is that now TEACUP will reboot the machines automatically into the specified OS, which is very useful if machines have a multi-boot setup, i.e. can run different OS. The automatic rebooting of multi-OS machines requires that machines are configured with PXE+GRUB as described in the tech report. If machines have only a single OS the reboot function is still useful to put machines into a clean state before an experiment and in this case PXE booting is not needed.

Listing 9 shows the additional configuration needed, compared to scenario 1. TPCONF\_tftpboot\_dir specifies the directory where TEACUP will put the files that GRUB will read (after loaded via PXE) which specify from which hard disk partition to boot from. TPCONF\_host\_os specifies the operating for each host and router. For Linux TEACUP allows the specification of the kernel that is booted. TPCONF\_linux\_kern\_router specifies the kernel booted on the router and TP-CONF\_linux\_kern\_hosts specifies the kernel booted on the other hosts. If TPCONF\_force\_reboot is not set to '0', TEACUP will only reboot a host if the currently running OS is different from the OS specified




Figure 15: Throughput and TCP RTT estimate measured in Scenario 1

in TPCONF\_host\_os (Linux hosts will also be rebooted if the currently running kernel is different from the kernel specified in TPCONF\_linux\_kern\_router or TP-CONF\_linux\_kern\_hosts). TPCONF\_boot\_timeout specifies the amount of time TEACUP will wait for a host to be rebooted and accessible via SSH again. If a host is not rebooted and running the desired OS within this time TEACUP will abort with an error.

Currently, by default TEACUP expects Windows on partition 1, Linux on partition 2, FreeBSD on partition 3 on the first hard disk. However, the variable TP-CONF\_os\_partition can be used to specify the partitions in GRUB4DOS format. PXE booting of MacOS is not supported currently.

5) Run and analyse experiment: See scenario 1.

### D. Scenario 3: Scenario 1 plus power control

1) Topology: Like in scenario 1 we have two hosts: newtcp20 connected to the 172.16.10.0/24 network and newtcp27 connected to the 172.16.11.0/24 network. The machine newtcprt3 connects the two experiment subnets. All three machines also have a second network interface that is used to control the experiment via TEACUP. We assume that the hosts have been installed according to [7]. Furthermore, this scenario only works with installed TEACUP-compatible power controllers that are set up to control the power of the three hosts.

2) *Test Traffic:* Like in scenario 1 two TCP bulk transfer flows are created using iperf.

3) Variable Parameters: Like in scenario 1 we emulate three different delays and two different bandwidth settings – six different experiments in total. We do also define a variable parameter for AQM, but define only one AQM (default pfifo). This causes the used AQM to be logged as part of the experiment ID.

4) TEACUP Config File: You can download the configuration file from [32]. To use the configuration rename it to config.py. In the following we explain the configuration file.

Most of the configuration is identical to the configuration used in scenario 2. The only difference is that now TEACUP will automatically power cycle machines that to not come up within the reboot timeout. TEACUP will only power cycle machines once. If after a power cycle and reboot the machines are still unresponsive TEACUP will give up. Power cycling can only used if the machines are connected via a power controller supported by TEACUP. Currently, TEACUP supports two power controllers: IP Power 9258HP (9258HP) and Serverlink SLP-SPP1008-H (SLP-SPP1008).

Listing 10 shows the additional configuration needed, compared to scenario 1. TPCONF\_do\_power\_cycle must be set to '1' to perform power cycling. If power cycling is used TPCONF\_host\_power\_ctrlport must define the IP address of the responsible power controller for each machine as well as the power controller's port the machine is connected to. TPCONF\_power\_admin\_name and TPCONF\_power\_admin\_pw must specify the admin user's name and password required to login to the power

```
# Path to tftp server handling the pxe boot
# Setting this to an empty string '' means no PXE booting, and TPCONF_host_os
# and TPCONF_force_reboot are simply ignored
TPCONF_tftpboot_dir = '/tftpboot'
# Operating system config, machines that are not explicitly listed are
# left as they are (OS can be 'Linux', 'FreeBSD', 'CYGWIN', 'Darwin')
TPCONF_host_os = {
        'newtcprt3': 'Linux',
        'newtcp20': 'Linux',
        'newtcp27': 'Linux',
# Specify the Linux kernel to use, only used for machines running Linux
# (basically the full name without the vmlinuz-)
TPCONF_linux_kern_router = '3.17.4-vanilla-10000hz'
TPCONF_linux_kern_hosts = '3.17.4-vanilla-web10g'
# Force reboot
# If set to '1' will force a reboot of all hosts
\# If set to '0' only hosts where OS is not the desired OS will be rebooted
TPCONF_force_reboot = '0'
# Time to wait for reboot in seconds (integer)
# Minimum timeout is 60 seconds
TPCONF_boot_timeout = 120
# Map OS to partition on hard disk (note the partition must be specified
# in the GRUB4DOS format, _not_ GRUB2 format)
TPCONF_os_partition = {
        'CYGWIN': '(hd0,0)',
        'Linux': '(hd0,1)',
        'FreeBSD': '(hd0,2)',
}
```

Listing 9: Scenario 2, OS and reboot configuration

controller's web interface. TPCONF\_power\_ctrl\_type specifies the type of power controller.

- 5) Run and analyse experiment: See scenario 1.
- E. Scenario 4: TCP flows with same bottleneck queue but different delay
- 1) Topology: We now have two hosts in each subnet: newtcp20 and newtcp21 connected to the 172.16.10.0/24 network, newtcp27 and newtcp28 connected to the 172.16.11.0/24 network. The machine newtcpt3 connects the two experiment subnets. All three machines also have a second network interface that is used to control the experiment via TEACUP. Like scenario 1 this scenario requires that hosts have the traffic generator and logging tools installed as described in [7], but PXE booting or a multi-OS installation is not needed.
- 2) Test Traffic: Two TCP bulk transfer flows are created using iperf. One flow is between newtcp20 and newtcp27 and the second flow is between newtcp21 and newtcp28.

- 3) Variable Parameters: Like in scenario 1 we emulate two different bandwidth settings. However, we setup different delays for each flow. Since each flow can have two different values, we have eight different experiments in total. We do also define a variable parameter for AQM, but define only one AQM (default pfifo). This causes the used AQM to be logged as part of the experiment ID.
- 4) TEACUP Config File: You can download the configuration file from [32]. To use the configuration rename it to config.py. In the following we explain the parts of the configuration file that have changed compared to scenario 1.

Our host configuration now looks as in Listing 11.

To configure different delays for each flow we also need to change the router setup (see Listing 12).

We also need to define both of the  $V_{-}$  variables and make sure we iterate over both in the experiments (see Listing  $\ref{eq:condition}$ ).

```
# If host does not come up within timeout force power cycle
# If set to '1' force power cycle if host not up within timeout
# If set to '0' never force power cycle
TPCONF_do_power_cycle = '1'
# Maps host to power controller IP (or name) and power controller port number
TPCONF_host_power_ctrlport = {
       'newtcprt3': ('10.0.0.100', '1'),
        'newtcp20': ('10.0.0.100', '2'),
        'newtcp27': ('10.0.0.100', '3'),
# Power controller admin user name
TPCONF_power_admin_name = 'admin'
# Power controller admin user password
TPCONF_power_admin_pw = env.password
# Type of power controller. Currently supported are only:
# IP Power 9258HP (9258HP) and Serverlink SLP-SPP1008-H (SLP-SPP1008)
TPCONF_power_ctrl_type = 'SLP-SPP1008'
```

Listing 10: Scenario 3, power controller configuration

```
TPCONF_router = ['newtcprt3', ]
TPCONF_hosts = [ 'newtcp20', 'newtcp21', 'newtcp27', 'newtcp28', ]
TPCONF_host_internal_ip = {
        'newtcprt3': ['172.16.10.1', '172.16.11.1'],
        'newtcp20': ['172.16.10.60'],
        'newtcp21': ['172.16.10.61'],
        'newtcp27': ['172.16.11.67'],
        'newtcp28': ['172.16.11.68'],
}
```

Listing 11: Scenario 4, host configuration

```
TPCONF_router_queues = [
        ('1', " source='172.16.10.60', dest='172.16.11.67', delay=V_delay, "
         " loss=V_loss, rate=V_up_rate, queue_disc=V_aqm, queue_size=V_bsize "),
        ('2', " source='172.16.11.67', dest='172.16.10.60', delay=V_delay, "
          " loss=V_loss, rate=V_down_rate, queue_disc=V_aqm, queue_size=V_bsize "),
        ('3', " source='172.16.10.61', dest='172.16.11.68', delay=V_delay2, "
          " loss=V_loss, rate=V_up_rate, queue_disc=V_aqm, queue_size=V_bsize, "
          " attach_to_queue='1' "),
        ('4', " source='172.16.11.68', dest='172.16.10.61', delay=V_delay2, "
          " loss=V_loss, rate=V_down_rate, queue_disc=V_aqm, queue_size=V_bsize, "
          " attach_to_queue='2' "),
]
```

Listing 12: Scenario 4, router queue configuration

one TCP bulk transfer flow for each host pair as shown in Listing 14.

5) Run and analyse experiment: See scenario 1.

- Finally, we need to define the traffic generators to create F. Scenario 5: Partially overlapping TCP flows with different TCP CC
  - 1) Topology: We now have three hosts in each subnet: newtcp20, newtcp21 and newtcp22 connected to the 172.16.10.0/24 network, and newtcp27, newtcp28 and newtcp29 connected to the 172.16.11.0/24 network. The machine newtcprt3 connects the two experiment subnets. All three machines also have a second network interface

```
TPCONF\_delays = [5, 50]
TPCONF\_delays2 = [5, 50]
TPCONF_parameter_list = {
        # Vary name V_ variable file name values extra vars
        'delays' : (['V_delay'], ['del1'], TPCONF_delays, {}),
        'delays2' : (['V_delay2'], ['del2'], TPCONF_delays2, {}),
        'loss' : (['V_loss'], ['loss'], TPCONF_loss_rates, {}),
        'tcpalgos' : (['V_tcp_cc_algo'],['tcp'], TPCONF_TCP_algos, {}),
        'aqms' : (['V_aqm'], ['aqm'], TPCONF_aqms, {}),
        'bsizes' : (['V_bsize'], ['bs'], TPCONF_buffer_sizes, {}),
        'runs' : (['V_runs'], ['run'], range(TPCONF_runs), {}),
        'bandwidths' : (['V_down_rate', 'V_up_rate'], ['down', 'up'], TPCONF_bandwidths, {}),
TPCONF_variable_defaults = {
        # V_ variable value
        'V duration' : TPCONF duration,
        'V_delay' : TPCONF_delays[0],
        'V_delay2' : TPCONF_delays2[0],
        'V_loss' : TPCONF_loss_rates[0],
        'V_tcp_cc_algo' : TPCONF_TCP_algos[0],
'V_down_rate' : TPCONF_bandwidths[0][0],
        'V_up_rate' : TPCONF_bandwidths[0][1],
        'V_aqm' : TPCONF_aqms[0],
        'V_bsize' : TPCONF_buffer_sizes[0],
TPCONF_vary_parameters = ['delays', 'delays2', 'bandwidths', 'aqms', 'runs',]
                              Listing 13: Scenario 4, experiment parameter
traffic_iperf = [
        ('0.0', '1', " start_iperf, client='newtcp27', server='newtcp20', port=5000, "
                 " duration=V_duration "),
        ('0.0', '2', " start_iperf, client='newtcp28', server='newtcp21', port=5001, "
                 " duration=V_duration "),
TPCONF_traffic_gens = traffic_iperf
```

Listing 14: Scenario 4, traffic configuration

that is used to control the experiment via TEACUP. Like scenario 1 this scenario requires that hosts have the traffic generator and logging tools installed as described in [7], but PXE booting or a multi-OS installation is not needed.

- 2) Test Traffic: Three TCP bulk transfer flows are created using iperf. One flow is between newtcp20 and newtcp27, the second flow is between newtcp21 and newtcp28, and the third flow is between newtcp22 and newtcp29. The flows do not longer start at the same time. Flow one start at the start of the experiment, while flow 2 starts 10 seconds after the first flow and flow 3 starts 10 seconds after flow 2. All flows have a duration of 30 seconds as in scenario 1.
- 3) Variable Parameters: Like in scenario 1 we emulate three different delays (same delays for all flows) and two different bandwidth settings. However, we now also vary the used TCP congestion control algorithm between Newreno and Cubic. This means we have 12 different experiments in total. We do also define a variable parameter for AQM, but define only one AQM (default pfifo). This causes the used AQM to be logged as part of the experiment ID.
- 4) TEACUP Config File: You can download the configuration file from [32]. To use the configuration rename it to config.py. In the following we explain the parts of the configuration file that have changed compared to scenario 1.

Our host configuration now looks as shown in Listing 15.

The traffic generator setup now creates three staggered flows as shown in Listing 16.

We also need to configure the different TCP congestion control algorithms and instruct TEACUP to vary this parameter (see Listing 17).

- 5) Run and analyse experiment: See scenario 1.
- G. Scenario 6: One HTTP-based (DASH) video streaming client
- 1) Topology: We now have host newtcp20 connected to the 172.16.10.0/24 network and host newtcp33 connected to the 172.16.11.0/24 network. The machine newtcprt3 connects the two experiment subnets. All three machines also have a second network interface that is used to control the experiment via TEACUP. Like scenario 1 this scenario requires that hosts have the traffic generator and logging tools installed as described in [7], but PXE booting or a multi-OS installation is not needed.
- 2) Test Traffic: In this scenario we generate DASH video streaming traffic. Host newtcp33 runs a web server. Host newtcp20 is a client that uses dash.js player inside Firefox browser to retrieve video content there is one DASH flow between the client and the server. In this scenario we use 10-sec chunks with a MPD that supplies 20 different video encoding rates (representation rates).
- 3) Variable Parameters: Like in scenario 1 we emulate three different delays and two different bandwidth settings. We now also vary the AQM mechanism used on the router between FIFO, CoDel and FQ CoDel. This means we have 18 experiments in total.
- 4) TEACUP Config File: To use the configuration rename it to config.py. In the following we explain the parts of the configuration file that have changed compared to scenario 1.

Our host configuration now looks as in Listing 18.

The traffic generator setup now starts a web server on newtcp33 before starting the DASH flow as shown in Listing 19.

We need to add one additional DASH-specific parameter to TPCONF\_chunksize\_mpd and

TPCONF\_parameter\_list, and two variables to TPCONF\_variable\_defaults as shown in Listing 20.

Finally, we need to configure the different AQM mechanisms used (see Listing 20) with TPCONF\_aqms. In order to permutate across different video chunk sizes and MPDs, the variable 'chunksize\_mpd' needs to be added to TPCONF\_vary\_parameters.

- 5) Run and analyse experiment: See scenario 1.
- H. Scenario 7: Incast problem scenario
- 1) Topology: We now have the host newtcp20 connected to the 172.16.10.0/24 network and hosts newtcp22–30 connected to the 172.16.11.0/24 network. The machine newtcprt3 connects the two experiment subnets. All three machines also have a second network interface that is used to control the experiment via TEACUP. Like scenario 1 this scenario requires that hosts have the traffic generator and logging tools installed as described in [7], but PXE booting or a multi-OS installation is not needed.
- 2) Test Traffic: In this scenario we emulate traffic to investigate the incast problem. The host newtcp20 is the querier and in regular intervals sends simultaneous queries to hosts newtcp21, newtcp22, newtcp23, newtcp24, newtcp25, newtcp26, newtcp27, newtcp28, newtcp29 and newtcp30 which then respond simultaneously. The querier uses httperf to send the queries to web servers running on all of the responders.
- 3) Variable Parameters: Like in scenario 6 we emulate three different delays (same delays for all flows), two different bandwidth settings, and three different AQM mechanism (FIFO, CoDel and FQ CoDel). We now also vary the size of the response between six different values. This means we have 108 experiments in total.
- 4) TEACUP Config File: You can download the configuration file from [32]. To use the configuration rename it to config.py. In the following we explain the parts of the configuration file that have changed compared to scenario 6.

Our host configuration now looks as in Listing 21.

The traffic generator setup now starts a web server and generates fake streaming content on each responder. Then after a delay of one second it starts the querier. Listing 22 shows the configuration. Setting up each

```
TPCONF_router = ['newtcpt3', ]
TPCONF_hosts = [ 'newtcp20', 'newtcp21', 'newtcp22', 'newtcp27', 'newtcp28', 'newtcp29', ]
TPCONF_host_internal_ip = {
        'newtcprt3': ['172.16.10.1', '172.16.11.1'],
        'newtcp20': ['172.16.10.60'],
        'newtcp21': ['172.16.10.61'],
        'newtcp22': ['172.16.10.62'],
        'newtcp27': ['172.16.11.67'],
        'newtcp28': ['172.16.11.68'],
        'newtcp29': ['172.16.11.69'],
}
```

Listing 15: Scenario 5, host configuration

Listing 16: Scenario 5, traffic configuration

server individually requires a large number of entries in the traffic configuration. Since version 0.9 TEACUP supports the start\_httperf\_incast\_n traffic generator that will setup the n servers and the querier with a single entry

Next, we need to configure the value ranges for response sizes and the time period between sending queries (see Listing ??).

Finally, we need to configure TEACUP to make sure the V\_ variables used in the traffic generator setup are defined and we vary the response sizes (see Listing ??).

5) Run and analyse experiment: See scenario 1.

# X. EXTENDING TEACUP FUNCTIONALITY

This section contains some notes on extending the current implementation. We refer to Python functions (which can be Fabric tasks) using the notation of <python\_file>.py:<function>().

### A. Additional host setup

Any general host setup (e.g. sysctl settings for all experiments) should be added in hostsetup.py:init\_host(). Note that in this function there are different sections,

one for each OS (FreeBSD, Linux, Windows/Cygwin, Mac OS X). Commands that shall only be executed in certain experiments can be set in the config (TP-CONF host init custom cmds).

## B. New TCP congestion control algorithm

Adding support for a new TCP congestion control algorithm requires modifying hostsetup.py:init\_cc\_algo(). The new algorithm needs to be added to the list of supported algorithms and in the OS-specific sections code need to be added to load the corresponding kernel module (if any).

#### C. New traffic generator

Adding a new traffic generator requires adding a new start task in trafficgens.py. The current start tasks always consist of two methods, the actual start method is a wrapper around an internal \_start method. This allows having the host on which the generator is started as explicit parameter (and not as Fabric hosts parameter) and having multiple traffic generators that actually use the same underlying tool (for example this is the case for httperf). The new start method must be added to the imports in experiment.py.

```
TPCONF_TCP_algos = ['newreno', 'cubic', ]
TPCONF_parameter_list = {
        'delays' : (['V_delay'], ['del'], TPCONF_delays, {}),
        'loss' : (['V_loss'], ['loss'], TPCONF_loss_rates, {}),
        'tcpalgos' : (['V_tcp_cc_algo'],['tcp'], TPCONF_TCP_algos, {}),
        'aqms' : (['V_aqm'], ['aqm'], TPCONF_aqms, {}),
        'bsizes' : (['V_bsize'], ['bs'], TPCONF_buffer_sizes, {}),
        'runs' : (['V_runs'], ['run'], range(TPCONF_runs), {}),
        'bandwidths' : (['V_down_rate', 'V_up_rate'], ['down', 'up'], TPCONF_bandwidths, {}),
TPCONF_variable_defaults = {
        'V_duration' : TPCONF_duration,
        'V_delay' : TPCONF_delays[0],
'V_loss' : TPCONF_loss_rates[0],
        'V_tcp_cc_algo' : TPCONF_TCP_algos[0],
        'V_down_rate' : TPCONF_bandwidths[0][0],
        'V_up_rate' : TPCONF_bandwidths[0][1],
        'V_aqm' : TPCONF_aqms[0],
        'V_bsize' : TPCONF_buffer_sizes[0],
TPCONF_vary_parameters = ['tcpalgos', 'delays', 'bandwidths', 'aqms', 'runs',]
                         Listing 17: Scenario 5, variable parameter configuration
TPCONF_router = ['newtcprt3', ]
TPCONF_hosts = [ 'newtcp20', 'newtcp33', ]
TPCONF_host_internal_ip = {
        'newtcprt3': ['172.16.10.1', '172.16.11.1'],
        'newtcp20': ['172.16.10.60'],
        'newtcp33': ['172.16.11.73'],
```

Listing 18: Scenario 6, host configuration

The traffic generator start function must, after the traffic generator process has been started, register the started process with its process ID by calling <code>bgproc.register\_proc()</code>. This ensures that the process will be stopped at the end of the experiment and the traffic generator's log file is collected when <code>runbg.py:stop\_processes()</code> is called. A current limitation is that there can only be one log file per traffic generator process.

Some traffic generators also have stop methods. Initially, the idea was that traffic generators could be started and stopped from the command line directly, but this is not supported at the moment, i.e. some stop methods are not implemented (empty).

### D. New data logger

}

To add a new data logger a start method and possibly a stop method need to be added in loggers.py. The new logger's start method should

be called from <code>loggers.py:start\_loggers()</code> via Fabric's execute(), but could also be called from <code>experiment.py:run\_experiment()</code> if required (in the latter case it must be added to the imports in <code>experiment.py</code>).

If the logger is a userspace process, such as tcpdump, at the end of the start function it should register itself (including its process ID) using bgproc.register\_proc\_later(). Then it is ensured that the logging process will be stopped at the end of the experiment and the log file is collected when runbg.py:stop\_processes() is called. In this case no stop method needs to be implemented.

If the logger is not a userspace process, for example SIFTR on FreeBSD, start *and* stop methods need to be implemented. The start method must still call bgproc.register\_proc\_later(), but the process ID must be set to zero. The stop method must be called from runbg.py:stop\_processes() if the process ID is

```
traffic_dash_streaming = [
        # Start server (server must be started first)
        ( '0.0', '1', " start_http_server, server='newtcp33', port='8000',
          docroot='/data/dash_dataset' "),
        # Create DASH flows
        ('0.1', '2', "start_dash_streaming_dashjs, client='newtcp20', serv='newtcp33',
          serv_port='8000', browser='firefox', chunk_size=V_chunksize, mpd=V_mpd,
          player_path='136.186.229.181:8080/dashjs-v2.4.1/samples/dash-if-reference-player',
          duration=V_duration "),
]
TPCONF_traffic_gens = traffic_dash_streaming
                              Listing 19: Scenario 6, traffic configuration
# Video chunk size and MPD pair
TPCONF_chunksize_mpd = [
    ('10','BigBuckBunny_10s.mpd'),
1
TPCONF_parameter_list = {
    Vary name V_ variable file name values extra vars
    'chunksize_mpd' : (['V_chunksize','V_mpd'], ['chunksize','mpd'], TPCONF_chunksize_mpd, {}),
}
TPCONF_variable_defaults = {
    V_ variable
                                value
    'V_chunksize'
                                TPCONF_chunksize_mpd[0][0],
    'V_mpd'
                                TPCONF_chunksize_mpd[0][1],
```

Listing 20: Scenario 6, parameter configuration

zero and the internal TEACUP name of the process is the name of the new logger.

TPCONF\_aqms = ['pfifo', 'codel', 'fq\_codel', ]

TPCONF\_vary\_parameters = ['delays', 'bandwidths', 'aqms', 'runs',]

### E. New analysis method

To add a new analysis method add an analysis task in analysis.py. If the new analysis should be carried out as part of the analyse\_all task, the new task must be called from analysis.py:analyse\_all() via Fabrics execute() function. The new task should implement the common parameters test\_id, out\_dir, pdf\_dir, out\_name, replot\_only, source\_filter, min\_values, etime, stime, ymin, ymax (see existing analyse tasks as examples). The new task must be added to the imports in fabfile.py.

# XI. KNOWN ISSUES

During the host setup phase TEACUP enables and disables NICs. On Windows the enable and disable NIC commands have permanent effect. If TEACUP is interrupted or aborts between a disable and enable command, the NIC will stay disabled. TEACUP will automatically enable all testbed NICs on Windows prior to each experiment, however in the unlikely event that the previous aborted NIC configuration left the NIC in an inconsistent state, it may be necessary to reconfigure the NIC manually.

TEACUP logs all output from traffic generators, such as iperf or httperf. Some of the tools used only generate output after they completed. If an experiment ends *before* a tool completed its task, the resulting log file may be empty. Possibly this issue could be mitigated by turning

```
TPCONF_router = ['newtcprt3', ]
TPCONF_hosts = [
       'newtcp20', 'newtcp21', 'newtcp22', 'newtcp23', 'newtcp24',
    'newtcp25', 'newtcp26', 'newtcp27', 'newtcp28', 'newtcp29', 'newtcp30',
TPCONF_host_internal_ip = {
        'newtcprt3': ['172.16.10.1', '172.16.11.1'],
        'newtcp20': ['172.16.10.60'], # querier
        'newtcp21': ['172.16.11.61'], # responders...
        'newtcp22': ['172.16.11.62'],
        'newtcp23': ['172.16.11.63'],
        'newtcp24': ['172.16.11.64'],
        'newtcp25': ['172.16.11.65'],
        'newtcp26': ['172.16.11.66'],
        'newtcp27': ['172.16.11.67'],
        'newtcp28': ['172.16.11.68'],
        'newtcp29': ['172.16.11.69'],
        'newtcp30': ['172.16.11.70'],
}
```

Listing 21: Scenario 7, host configuration

the stdout and stderr buffering off for these tools in future CAIA, Swinburne University of Technology. The original was released in June 2016 under a Creative Commons

#### XII. CONCLUSIONS AND FUTURE WORK

This report describes TEACUP version 1.1, a Python-based software developed to run automated TCP performance tests in a controlled testbed. In the future we will continue to extend TEACUP with more features.

### ACKNOWLEDGEMENTS

TEACUP versions prior to 1.0 were developed as part of a project funded by Cisco Systems and titled "Study in TCP Congestion Control Performance In A Data Centre". This was a collaborative effort between Swinburne University of Technology's Centre for Advanced Internet Architectures and Fred Baker of Cisco Systems. These may be found at http://caia.swin.edu.au/tools/teacup/downloads.html.

Starting with TEACUP v1.0, development will be community supported and publicly hosted at http://sourceforge.net/projects/teacup/.

Russell Collom and Jonathan Kua contributed additional text in 2017 for version 1.1 of this document.

### COPYRIGHT AND LICENSE

This document is based on "TEACUP v1.0 – A System for Automated TCP Testbed Experiments" by Sebastian Zander and Grenville Armitage, © 2015 – 2016

CAIA, Swinburne University of Technology. The original was released in June 2016 under a Creative Commons Attribution-ShareAlike 4.0 International License (CC BY-SA 4.0, http://creativecommons.org/licenses/by-sa/4. 0). Based on a work at http://caia.swin.edu.au/reports/150529A/CAIA-TR-150529A.pdf

#### REFERENCES

- [1] A. Finamore, M. Mellia, M. M. Munafò, R. Torres, and S. G. Rao, "Youtube everywhere: Impact of device and infrastructure synergies on user experience," in *Proceedings of the 2011 ACM SIGCOMM Conference on Internet Measurement Conference*, ser. IMC '11, 2011, pp. 345–360.
- [2] A. Rao, A. Legout, Y.-s. Lim, D. Towsley, C. Barakat, and W. Dabbous, "Network characteristics of video streaming traffic," in *Proceedings of the Seventh Conference on Emerging Networking Experiments and Technologies*, ser. CoNEXT '11, 2011, pp. 25:1–25:12.
- [3] "Dynamic adaptive streaming over HTTP (DASH) Part 1: Media presentation description and segment formats," ISO, 2012, iSO/IEC 23009-1:2012. http://www.iso.org/iso/iso\_catalogue/catalogue\_tc/catalogue\_detail.htm?csnumber=57623.
- [4] S. Zander and G. Armitage, "TEACUP v1.0 A System for Automated TCP Testbed Experiments," Centre for Advanced Internet Architectures, Swinburne University of Technology, Melbourne, Australia, Tech. Rep. 150529A, 29 May 2015. [Online]. Available: http://caia.swin.edu.au/reports/150529A/ CAIA-TR-150529A.pdf
- [5] L. Stewart, "SIFTR Statistical Information For TCP Research." [Online]. Available: http://caia.swin.edu.au/urp/ newtcp/tools.html
- [6] "The Web10G Project." [Online]. Available: http://web10g.org/

```
traffic_incast = [
            # Start servers and create contents (server must be started first)
            ('0.0', '1', " start_http_server, server='newtcp21', port=80 "), ('0.0', '2', " start_http_server, server='newtcp22', port=80 "),
            ('0.0', '3', " start_http_server, server='newtcp23', port=80 "),
            ('0.0', '4', " start_http_server, server='newtcp24', port=80 "),
            ('0.0', '5', " start_http_server, server='newtcp25', port=80 "), ('0.0', '6', " start_http_server, server='newtcp26', port=80 "),
            ('0.0', '7', " start_http_server, server='newtcp27', port=80 "),
            ('0.0', '8', " start_http_server, server='newtcp28', port=80 "),
            ('0.0', '9', " start_http_server, server='newtcp29', port=80 "),
            ('0.0', '10', " start_http_server, server='newtcp30', port=80 "),
            ('0.0', '11', " create_http_incast_content, server='newtcp21', duration=2*V_duration, " sizes=V_inc_content_sizes_str "),
            ('0.0', '12', " create_http_incast_content, server='newtcp22', duration=<math>2*V_duration, server='newtcp22', duration=<math>2*V_duration, server='newtcp22', duration=<math>2*V_duration=0
                           " sizes=V_inc_content_sizes_str "),
            ('0.0', '13', " create_http_incast_content, server='newtcp23', duration=2 \times V_duration,
                            " sizes=V_inc_content_sizes_str "),
            ('0.0', '15', " create_http_incast_content, server='newtcp25', duration=2*V_duration, "
                            sizes=V_inc_content_sizes_str "),
            ('0.0', '16', " create_http_incast_content, server='newtcp26', duration=2*V_duration, "
                            " sizes=V_inc_content_sizes_str "),
            ('0.0', '18', " create_http_incast_content, server='newtcp28', duration=2*V_duration, "
                            ' sizes=V_inc_content_sizes_str "),
            ('0.0', '19', " create_http_incast_content, server='newtcp29', duration=2*V_duration, " sizes=V_inc_content_sizes_str "),
            ('0.0', '20', " create_http_incast_content, server='newtcp30', duration=2*V_duration, "
                           " sizes=V_inc_content_sizes_str "),
            # Start querier
            ('1.0', '30', " start_httperf_incast, client='newtcp20', "
               " servers='newtcp21:80,newtcp22:80,newtcp23:80,newtcp24:80,newtcp25:80,newtcp26:80, "
         " newtcp27:80, newtcp28:80, newtcp29:80, newtcp30:80', "
         " duration=V_duration, period=V_inc_period, response_size=V_inc_size"),
TPCONF_traffic_gens = traffic_incast
```

Listing 22: Scenario 7, traffic configuration

```
TPCONF_inc_content_sizes = [8, 16, 32, 64, 128, 256]
TPCONF_inc_content_sizes_str = ','.join( str(x) for x in TPCONF_inc_content_sizes)
TPCONF_inc_periods = [10]
```

Listing 23: Scenario 7, incast content parameter

- [7] S. Zander, G. Armitage, "CAIA Testbed for TCP Experiments Version 2," Centre for Advanced Internet Architectures, Swinburne University of Technology, Tech. Rep. 150210C, 2015. [Online]. Available: http://caia.swin.edu.au/ reports/150210C/CAIA-TR-150210C.pdf
- [8] —, "TEACUP v1.1 Data Analysis Functions," Tech. Rep., Feb 2018. [Online]. Available: https://sourceforge.net/projects/ teacup/files/TEACUP-Analysis-v1.1.pdf
- [9] "Fabric 1.8 documentation." [Online]. Available: http://docs. fabfile.org/en/1.8/
- [10] "Fabric 1.8 documentation Installation." [Online]. Available: http://docs.fabfile.org/en/1.8/installation.html
- [11] "iperf Web Page." [Online]. Available: http://iperf.fr/

- [12] "LIGHTTPD Web Server." [Online]. Available: http://www.lighttpd.net/
- [13] "NGINX Web Server." [Online]. Available: https://nginx.org/
- [14] HP Labs, "httperf homepage." [Online]. Available: http://www.hpl.hp.com/research/linux/httperf/
- [15] DASH-IF, "dash.js Player," 2016. [Online]. Available: https://github.com/Dash-Industry-Forum/dash.js/wiki
- [16] T. Stockhammer, "Dynamic Adaptive Streaming over HTTP: Standards and Design Principles," in *Proceedings of the Second Annual ACM Conference on Multimedia Systems*, ser. MMSys '11. New York, NY, USA: ACM, 2011, pp. 133–144. [Online]. Available: http://doi.acm.org/10.1145/1943552.1943572

```
TPCONF_parameter_list = {
    'delays' : (['V_delay'], ['del'], TPCONF_delays, {}),
    'loss' : (['V_loss'], ['loss'], TPCONF_loss_rates, {}),
    'tcpalgos' : (['V_tcp_cc_algo'], ['tcp'], TPCONF_TCP_algos, {}),
    'aqms' : (['V_aqm'], ['aqm'], TPCONF_aqms, {}),
    'bsizes' : (['V_bsize'], ['bs'], TPCONF_buffer_sizes, {}),
    'runs' : (['V_runs'], ['run'], range(TPCONF_runs), {}),
    'bandwidths' : (['V_down_rate', 'V_up_rate'], ['down', 'up'], TPCONF_bandwidths, {}),
    'incast_periods': (['V_inc_period'], ['incper'], TPCONF_inc_periods, {}),
    'incast_sizes' : (['V_inc_size'], ['incsz'], TPCONF_inc_content_sizes, {}),
}

TPCONF_variable_defaults = {
    'V_duration' : TPCONF_duration,
    'V_delay' : TPCONF_delays[0],
    'V_loss' : TPCONF_loss_rates[0],
    'V_tcp_cc_algo' : TPCONF_TCP_algos[0],
    'V_down_rate' : TPCONF_bandwidths[0][0],
    'V_up_rate' : TPCONF_bandwidths[0][1],
    'V_aqm' : TPCONF_apms[0],
    'V_bsize' : TPCONF_bandwidths[0][1],
    'V_bsize' : TPCONF_inc_periods[0],
    'V_inc_period' : TPCONF_inc_periods[0],
    'V_inc_size' : TPCONF_inc_content_sizes_str,
}

TPCONF_vary_parameters = ['incast_sizes', 'delays', 'bandwidths', 'aqms', 'runs',]
```

Listing 24: Scenario 7, variable parameter

- [17] J. Kua, G. Armitage, and P. Branch, "A Survey of Rate Adaptation Techniques for Dynamic Adaptive Streaming Over HTTP," *IEEE Communications Surveys Tutorials*, vol. 19, no. 3, pp. 1842–1866, thirdquarter 2017. [Online]. Available: https://doi.org/10.1109/COMST.2017.2685630
- [18] J. Summers, T. Brecht, D. Eager, B. Wong, "Modified version of httperf," 2012. [Online]. Available: https://cs.uwaterloo.ca/ ~brecht/papers/nossdav-2012/httperf.tgz
- [19] "nttcp-1.47 An improved version of the popular ttcp program." [Online]. Available: http://hpux.connect.org.uk/hppd/hpux/Networking/Admin/nttcp-1.47/
- [20] C. Javier, "Broadband Internet Traffic Simulation & Synthesis (BITSS)," http://caia.swin.edu.au/bitss/.
- [21] R. Al-Saadi, G. Armitage, and J. But, "ttprobe v0.1: Packet-Driven TCP Stack Statistics Gathering for TEACUP," Centre for Advanced Internet Architectures, Swinburne University of Technology, Melbourne, Australia, Tech. Rep. 150911A, 11 September 2015. [Online]. Available: http://caia.swin.edu.au/reports/150911A/CAIA-TR-150911A.pdf
- [22] M. Mathis, J. Heffner, and R. Raghunarayan, "TCP Extended Statistics MIB," RFC 4898 (Proposed Standard), Internet Engineering Task Force, May 2007. [Online]. Available: http://www.ietf.org/rfc/rfc4898.txt
- [23] Wikipedia, "DTrace," http://en.wikipedia.org/w/index.php? title=DTrace&oldid=637195163.
- [24] L. Stewart, "SIFTR v1.2.3 README," July 2010. [Online]. Available: http://caia.swin.edu.au/urp/newtcp/tools/ siftr-readme-1.2.3.txt
- [25] M. Mathis, J. Semke, R. Reddy, J. Heffner, "Documentation of variables for the Web100 TCP Kernel Instrumentation Set

- (KIS) project." [Online]. Available: http://www.web100.org/download/kernel/tcp-kis.txt
- [26] "netfilter firewalling, NAT, and packet mangling for Linux."
  [Online]. Available: http://www.netfilter.org/
- [27] J. Gettys, "Best practices for benchmarking bufferbloat." [Online]. Available: http://www.bufferbloat.net/projects/codel/wiki/Best\_practices\_for\_benchmarking\_Codel\_and\_FQ\_Codel
- [28] Linux Foundation, "netem Network Emulation Functionality," November 2009. [Online]. Available: http://www.linuxfoundation.org/collaborate/workgroups/networking/netem
- [29] —, "IFB Intermediate Functional Block device," November 2009. [Online]. Available: http://www.linuxfoundation.org/ collaborate/workgroups/networking/ifb
- [30] J. Kua, R. Al-saadi, G. Armitage, "Using Dummynet AQM - FreeBSD's CoDel, PIE, FQ-CoDel and FQ-PIE with TEACUP v1.0 testbed," Centre for Advanced Internet Architectures, Swinburne University of Technology, Tech. Rep. 160708A, 2016. [Online]. Available: http://caia.swin.edu.au/ reports/160708A/CAIA-TR-160708A.pdf
- [31] J. Kua and G. Armitage, "Generating Dynamic Adaptive Streaming over HTTP Traffic Flows with TEACUP Testbed," Centre for Advanced Internet Architectures, Swinburne University of Technology, Melbourne, Australia, Tech. Rep. 161216A, 16 December 2016. [Online]. Available: http://caia.swin.edu.au/reports/161216A/CAIA-TR-161216A.pdf
- [32] S. Zander, "TCP Experiment Automation Controlled Using Python (TEACUP) – Usage Examples," 2014. [Online]. Available: http://caia.swin.edu.au/tools/teacup/usageexamples.