

**F** C Decisions

This material is the confidential, proprietary, and unpublished property of Fair Isaac Corporation. Receipt or possession of this material does not convey rights to divulge, reproduce, use, or allow others to use it without the specific written authorization of Fair Isaac Corporation and use must conform strictly to the license agreement.

The information in this document is subject to change without notice. If you find any problems in this documentation, please report them to us in writing. Neither Fair Isaac Corporation nor its affiliates warrant that this documentation is error-free, nor are there any other warranties with respect to the documentation except as may be provided in the license agreement.

©1983–2018 Fair Isaac Corporation. All rights reserved. Permission to use this software and its documentation is governed by the software license agreement between the licensee and Fair Isaac Corporation (or its affiliate). Portions of the program may contain copyright of various authors and may be licensed under certain third-party licenses identified in the software, documentation, or both.

In no event shall Fair Isaac Corporation or its affiliates be liable to any person for direct, indirect, special, incidental, or consequential damages, including lost profits, arising out of the use of this software and its documentation, even if Fair Isaac Corporation or its affiliates have been advised of the possibility of such damage. The rights and allocation of risk between the licensee and Fair Isaac Corporation (or its affiliates) are governed by the respective identified licenses in the software, documentation, or both.

Fair Isaac Corporation and its affiliates specifically disclaim any warranties, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. The software and accompanying documentation, if any, provided hereunder is provided solely to users licensed under the Fair Isaac Software License Agreement. Fair Isaac Corporation and its affiliates have no obligation to provide maintenance, support, updates, enhancements, or modifications except as required to licensed users under the Fair Isaac Software License Agreement.

FICO and Fair Isaac are trademarks or registered trademarks of Fair Isaac Corporation in the United States and may be trademarks or registered trademarks of Fair Isaac Corporation in other countries. Other product and company names herein may be trademarks of their respective owners.

**Xpress Optimizer** 

Deliverable Version: A

Last Revised: 25 April 2018

Version 33.01

# **Contents**

1	Introduction	1
	1.1 Outline	1
	1.2 Installing the Python Xpress module	1
	1.2.1 Installation from the Xpress Optimizer distribution	1
	1.2.2 Installation from Conda	2
	1.2.3 Troubleshooting the installation	2
		_
2		3
		3
		3
		3
		4
	•	5
		6
		6
		6
		8
		8
	2.11 Reading and writing a problem	
	2.12 Hints for building models efficiently	0
2	Haling Braham managarian Bharatan	^
3	Using Python numerical libraries  1	
	3.1 Using NumPy in the Xpress Python interface	
	3.2 Products of NumPy arrays	J
4	Controls and Attributes 1	5
	4.1 Controls	
	4.2 Examples	
	4.3 Attributes	
	4.4 Examples	
	4.5 Accessing controls and attributes as object members	
	4.6 Accessing controls and attributes as object members	′
5	Using Callbacks 2	0
	5.1 Introduction	0
		_
6	Examples of use 2	
	6.1 Creating simple problems	
	6.1.1 Generating a small Linear Programming problem	
	6.1.2 A Mixed Integer Linear Programming problem	
	6.2 Modeling examples	
	6.2.1 A simple model	
	6.2.2 Using IIS to investigate an infeasible problem	
	6.2.3 Modeling a problem using Python lists and vectors	
	6.2.4 A knapsack problem	
	6.2.5 A Min-cost-flow problem using NumPy	
	6.2.6 A nonlinear model	7

		6.2.7	Finding the maximum-area <i>n</i> -gon
		6.2.8	Solving the <i>n</i> -queens problem
		6.2.9	Solving Sudoku problems
	6.3		oles using NumPy
		6.3.1	Using NumPy multidimensional arrays to create variables
		6.3.2	Using the dot product to create arrays of expressions
		6.3.3	Using the Dot product to create constraints and quadratic functions
		6.3.4	Using NumPy to create quadratic optimization problems
	6.4		aced examples: callbacks and problem querying, modifying, and analysis
		6.4.1	Visualize the branch-and-bound tree of a problem
		6.4.2	Query and modify a simple problem
		6.4.3	Change a problem after solution
		6.4.4	Comparing the coefficients of two equally sized problems
		6.4.5	Combining modeling and API functions
		6.4.6	A simple Traveling Salesman Problem (TSP) solver
7			Manual 40
	7.1		this chapter
			at of the reference
	7.2		I methods of the Xpress module
	7.3		ods of the class problem 42
	7.4		ods for branching objects
	7.5		ods for adding/removing callbacks of a problem object
	7.6		ods to be used within a callback of a problem object
			46
			panner 47
			checkedmode
			<mark>laysleft</mark>
			asterror
			icerrmsg
			r <mark>ersion</mark>
			checkedmode
			lefaults
			lefaultcontrol
			1
			58
			d
			61
		_	
		_	0
			65
			1
			s68
			1
			· · · · · · · · · · · · · · · · · · ·
			71
		_	73
			75
			76
	xpre	ess.usei	r

xpress.addcbmsghandler	78
xpress.removecbmsghandler	79
problem.addcbbariteration	80
problem.addcbbarlog	
problem.addcbchgbranchobject	
problem.addcbcutlog	84
problem.addcbdestroymt	85
problem.addcbgapnotify	86
problem.addcbgloballog	88
problem.addcbinfnode	89
problem.addcbintsol	90
problem.addcblplog	91
problem.addcbmessage	
problem.addcbmipthread	93
problem.addcbnewnode	94
problem.addcbnodecutoff	
problem.addcboptnode	
problem.addcbpreintsol	
problem.addcbprenode	98
problem.addcbusersolnotify	
problem.addcoefs	
problem.addcols	
problem.addConstraint	
problem.addcuts	
problem.adddfs	
problem.addIndicator	
problem.addmipsol	
problem.addgmatrix	
problem.addrows	
problem.addSOS	
problem.addtolsets	
problem.addVariable	
problem.addvars	
problem.basisstability	
problem.btran	
problem.calcobjective	
·	
problem.calcslacks	
problem.calcsolinfo	119
problem.cascade	120
problem.cascadeorder	
problem.chgbounds	122
problem.chgcoef	123
problem.chgcoltype	124
problem.chgcascadenlimit	125
problem.chgccoef	
problem.chgdeltatype	
problem.chgdf	128
problem.chgglblimit	129
problem.chgmcoef	130
problem.chgmqobj	
problem.chgnlcoef	132
problem.chgobj	133
problem.chgobjsense	134
problem.chgqobj	135

problem.chgqrowcoeff	
problem.chgrhs	
problem.chgrhsrange	
problem.chgrowstatus	139
problem.chgrowtype	
problem.chgrowwt	141
problem.chgtolset	142
problem.chgvar	143
problem.construct	145
problem.copy	146
problem.copycallbacks	147
problem.copycontrols	148
problem.delcoefs	
problem.delConstraint	
problem.delcpcuts	
problem.delcuts	
problem.delqmatrix	
problem.delSOS	
problem.deltolsets	
problem.delVariable	
problem.delvars	
problem.dumpcontrols	
problem.estimaterowdualranges	
problem.evaluatecoef	
problem.evaluateformula	
problem.filesol	
problem.fixglobals	
problem.fixpenalties	
problem.ftran	
problem.getAttrib	
problem.getattribinfo	
problem.getbasis	
problem.getccoef	
problem.getcoef	
problem.getcoefformula	
problem.getcoefs	
problem.getcolinfo	
problem.getcols	
problem.getcoltype	175
problem.getConstraint	176
problem.getControl	177
problem.getcontrolinfo	178
problem.getcpcutlist	179
problem.getcpcuts	180
problem.getcutlist	181
problem.getcutmap	182
problem.getcutslack	183
problem.getdirs	184
problem.getdf	185
problem.getdtime	186
problem.getDual	187
problem.getdualray	188
problem.getglobal	189
problem.getiisdata	190
problem getIndex	192

problem.getIndexFromName	193
problem.getindicators	194
problem.getinfeas	195
problem.getlasterror	196
problem.getlb	197
problem.getlpsol	198
problem.getmessagestatus	
problem.getmessagetype	
problem.getmipsol	
problem.getmqobj	
problem.getobj	
problem.getObjVal	
problem.getpivotorder	
problem.getpivots	
problem.getpresolvebasis	
problem.getpresolvemap	
problem.getpresolvesol	
problem.getprimalray	
problem.getProbStatus	
problem.getProbStatusString	
problem.getqobj	
problem.getqrowcoeff	
problem.getqrowgmatrix	
problem.getqrowqmatrixtriplets	
problem.getqrows	
problem.getRCost	
problem.getrhs	
problem.getrhsrange	
problem.getrowinfo	
problem.getrows	
problem.getrowstatus	
problem.getrowtype	
problem.getrowwt	
problem.getscaledinfeas	
problem.getSlack	
problem.getslpsol	
problem.getSolution	
	230
1	231
production of the contract of	232
	232
1 5	234
1 3	236
	237
1	238
,	239
	240
	241
•	242
•	243
	244
·	245
	246
problem.interrupt	
problem.loadbasis	248

problem.loadbranchdirs	249
problem.loadcoefs	250
problem.loadcuts	252
problem.loaddelayedrows	253
problem.loaddfs	254
problem.loaddirs	255
problem.loadlpsol	
problem.loadmipsol	
problem.loadmodelcuts	
problem.loadpresolvebasis	
problem.loadpresolvedirs	
problem.loadproblem	
problem.loadsecurevecs	
problem.loadtolsets	
problem.loadvars	
problem.lpoptimize	
problem.mipoptimize	
problem.msaddcustompreset	
problem.msaddjob	
problem.msaddpreset	
problem.msclear	
problem.name	
problem.nlpoptimize	
problem.objsa	
problem.parsecformula	
problem.parseformula	
problem.postsolve	
problem.preparseformula	
problem.presolve	
problem.presolverow	
problem.printmemory	
problem.printevalinfo	
problem.printmsg	
problem.read	
problem.readbasis	
problem.readbinsol	
problem.readdirs	
problem.readslxsol	289
problem.refinemipsol	
problem.reinitialize	
problem.removecbbariteration	
problem.removecbbarlog	293
problem.removecbcutlog	
problem.removecbdestroymt	
problem.removecbgapnotify	
problem.removecbgloballog	
problem.removecbinfnode	
problem.removecbintsol	
problem.removecblplog	
problem.removechmessage	
problem.removecbmipthread	
problem.removecbnewnode	
problem.removecbnodecutoff	
problem.removecboptnode	306

problem.removecbpreintsol	
problem.removecbprenode	
problem.removecbusersolnotify	
problem.repairinfeas	
problem.repairweightedinfeas	
problem.repairweightedinfeasbounds	
problem.reset	316
problem.restore	317
problem.rhssa	318
problem.save	319
problem.scale	320
problem.scaling	321
problem.setbranchbounds	322
problem.setbranchcuts	323
problem.setcbcascadeend	324
problem.setcbcascadestart	325
problem.setcbcascadevar	
problem.setcbcascadevarfail	
problem.setcbcoefevalerror	
problem.setcbconstruct	
problem.setcbdestroy	
problem.setcbdrcol	
problem.setcbformula	
problem.setcbiterend	
problem.setcbiterstart	
problem.setcbitervar	
problem.setcbmessage	
problem.setcbmsjobend	
problem.setcbmsjobstart	
problem.setcbmswinner	
problem.setcbslpend	
problem.setcbslpnode	
problem.setcbslpstart	
problem.setControl	
problem.setcurrentiv	
problem.setdefaultcontrol	
problem.setdefaults	
problem.setindicators	
problem.setlogfile	349
problem.setmessagestatus	•
problem.setObjective	
problem.setprobname	
problem.setuniqueprefix	
problem.solve	
problem.storebounds	
problem.storecuts	
problem.strongbranch	357
problem.strongbranchcb	358
problem.tokencount	359
problem.tune	
problem.tunerreadmethod	361
problem.tunerwritemethod	
problem.unconstruct	
problem.updatelinearization	
The state of the s	365
problem validate	่อบถ

	problem.validatekkt	. 366
	problem.validaterow	. 367
	problem.validatevector	. 368
	problem.validformula	. 369
	problem.write	. 370
	problem.writebasis	. 371
	problem.writebinsol	. 372
	problem.writedirs	. 373
	problem.writeprtsol	. 374
	problem.writeslxsol	. 375
	problem.writesol	. 376
	branchobj.addbounds	. 377
	branchobj.addbranches	. 378
	branchobj.addcuts	. 379
	branchobj.addrows	. 380
	branchobj.getbounds	
	branchobj.getbranches	
	branchobj.getid	. 383
	branchobj.getlasterror	. 384
	branchobj.getrows	. 385
	branchobj.setpreferredbranch	. 386
	branchobj.setpriority	
	branchobj.store	. 388
	branchobj.validate	. 389
Αŗ	pendix	390
Δ	Contacting FICO	390
^	Product support	
	Product education	
	Product documentation	
	Sales and maintenance	
	Related services	
	About FICO	
		. 05.
In	dex	392

# Introduction

The Xpress Python interface allows for creating and solving optimization problems using the Python programming language and the FICO Xpress Optimizer library. This manual describes how to use the Xpress Python interface.

#### 1.1 Outline

The following chapters cover:

- Creating, handling, solving, and querying optimization problems (Chapter 2);
- Using Python numerical libraries such as NumPy to create optimization problems (Chapter 3);
- Setting and getting the value of parameters (controls and attributes) of a problem (Chapter 4);
- Using Python functions as callbacks for the Xpress Optimizer and the Xpress Nonlinear solver (Chapter 5);
- Several examples of usage of the Xpress Python interface (Chapter 6);
- A reference with all functions and parameters in the Python interface (Chapter 7).

It is assumed here that the reader has basic understanding of the Python programming language. Ample documentation on Python is available at <a href="http://docs.python.org">http://docs.python.org</a>, including a tutorial and a reference manual. Unless specified otherwise, Python 3 is used in all of the examples and code samples throughout this manual. The current version of the Xpress Python interface works on Python 2.7, Python 3.4, and subsequent versions.

# 1.2 Installing the Python Xpress module

#### 1.2.1 Installation from the Xpress Optimizer distribution

Using the Xpress Optimizer suite, the module is automatically installed by the installation script. If  $xpress\_dir$  is the directory where the Xpress Optimizer suite was installed (for example c:\xpressmp for Windows users or /opt/xpressmp for \*nix users), then the Python module is at  $xpress\_dir/lib$  for \*nix users and  $xpress\_dir/lib$  for Windows users.

Documentation is available in PDF form in the installation: see xpress\_dir/docs/python/xpress\_python\_interface.pdf.

#### 1.2.2 Installation from Conda

A Conda package is available for download with the following command:

```
conda install -c fico-xpress xpress
```

Conda packages for Python 2.7 and 3.4 and subsequent versions are available, for Windows, Linux, and MacOS. The Conda package contains the Python interface module and its documentation, but not the Xpress Optimizer's libraries, its documentation, or a license. Please refer to the FICO Xpress Optimizer web pages for instructions on how to obtain a full installation of the Xpress optimization suite, which also contains an installation package that is compatible with Conda.

#### 1.2.3 Troubleshooting the installation

Whether the Xpress Python module is downloaded from the Conda server or used from the Xpress installation, there are a few remarks that might help ensure that the installation works right away. The advice below is independent of the Python platform (PyCharm, Spyder, etc.) that may be in use.

The Xpress Python interface uses the Python package NumPy for some operation, hence NumPy must be installed. It is usually installed if a Conda installation is used, nevertheless ensure that version 1.13 or later is installed for Python versions 2.7, 3.5, and 3.6, and version 1.11 is installed for Python 3.4.

As a general note, always ensure that the PATH environment variable (for Windows; for Linux, it is LD\_LIBRARY\_PATH, and for MacOS there is the additional variable DYLD\_LIBRARY\_PATH) contains the location of the libraries of the Xpress installation, which is C:\xpressmp\bin (for Windows, or /opt/xpressmp/lib for Linux and MacOS). When using a Conda installation and installing the Xpress Python interface from Conda, if the Conda-located Xpress packages are preferred then the PATH should contain the Conda library directories before C:\xpressmp\bin.

For MacOS users, it might be useful to alter the linking settings of the Python modules. All such modules (named xpress.\*.so) depend on libxprs.dylib, and the modules are given the correct absolute path of the installation directory containing libxprs.dylib. Should the location of this library change, the dependency has to be updated on the modules as well with the command

install\_name\_tool -change libxprs.dylib /path/to/libxprs.dylib xpress.so

# Modeling an optimization problem

This chapter illustrates the modeling capabilities of the Xpress Python interface. It shows how to create variables, constraints of different types, add an objective function, and solving and retrieving a problem's solution. It also shows how to read or write a problem from/to a file.

# 2.1 Getting started

The Xpress Python module is imported as follows:

```
import xpress
```

A complete list of methods and constants available in the module is obtained by running the Python command dir(xpress). Because all types and methods must be called by prepending "xpress.", it is advisable to alias the module name upon import:

```
import xpress as xp
```

We assume that this is the way the module is imported from now on. It is also possible to import all methods and types to avoid prepending the module name or its alias, but this practice is usually advised against:

```
from xpress import *
```

# 2.2 Creating a problem

Create an empty optimization problem myproblem as follows:

```
myproblem = xp.problem ()
```

A name can be assigned to a problem upon creation:

```
myproblem = xp.problem (name = "My first problem")
```

The problem has no variables or constraint at this point.

#### 2.3 Variables

The Xpress type var allows for creating optimization variables. Note that variables are **not** tied to a problem but may exist globally in a Python program. In order for them to be included into a problem,

they have to be explicitly added to that problem. Below is the complete declaration with the list of all parameters (all of them are optional):

```
var (name, lb, ub, threshold, vartype)
```

The parameters are:

- 1. name is a Python UTF-8 string containing the name of the variable (its ASCII version will be saved if written onto a file); a default name is assigned if the user does not specify it;
- 2. 1b is the lower bound (0 by default);
- 3. ub is the upper bound (+inf is the default);
- 4. threshold is the threshold for semi-continuous, semi-integer, and partially integer variables; it must be between its lower and its upper bound; it has no default, so if a variable is defined as partially integer the threshold must be specified;
- 5. vartype is the variable type, one of the six following types:
  - xpress.continuous for continuous variables;
  - xpress.binary for binary variables (lower and upper bound are further restricted to 0 and
    1);
  - xpress.integer for integer variables;
  - xpress.semicontinuous for semi-continuous variables;
  - xpress.semiinteger for semi-integer variables;
  - xpress.partiallyinteger for partially integer variables.

The features of each variable are accessible as members of the associated object: after declaring a variable with x = xpress.var(), its name, lower and upper bound can be accessed via x.name, x.lb, and x.ub. Note that, after a variable x has been added to one or more problems, a change in its feature will not be reflected in these problems, but only in the problems to which this variable is added subsequently.

One or more variables (or vectors of variables) can be added to a problem with the addVariable method:

```
v = xp.var (lb = -1, ub = 2)
m.addVariable (v)

x = [xp.var (ub = 10) for i in range (10)]
y = [xp.var (ub = 10, vartype = xp.integer) for i in range (10)]
m.addVariable (x,y)
```

By default, variables added to an Xpress problems are constrained to be nonnegative. In order to add a free variable, one must specify its lower bound to be  $-\infty$  as follows:

```
v = xp.var (lb = -xp.infinity)
```

#### 2.4 Constraints

Linear, quadratic, and nonlinear constraints can be specified as follows:

```
constraint (constraint, body, lb, ub, sense, rhs, name)
```

The parameters are:

- 1. constraint is the full-form constraint, such as x1 + 2 \* x2 <= 4;
- 2. body is the body of the constraint, such as 3 \* x1 + x2 (it may contain constants);
- 3. 1b is the lower bound on the body of the constraint;
- 4. ub is the upper bound on the body of the constraint;
- 5. sense is the sense of the constraint, one among xpress.leq, xpress.geq, xpress.eq, and xpress.range; in the first three cases, the parameter rhs must be specified; only in the fourth case must lb and ub be specified;
- 6. rhs is the right-hand side of the constraint;
- 7. name is the name of the constraint. Parameters 1b, ub, and rhs must be constant.

A constraint can be specified more naturally as a condition on an expression:

One or more constraints (or vectors of constraints) can be added to a problem via the addConstraint method:

In order to help formulate compact problems, the Sum operator of the xpress module can be used to express sums of expressions. Its argument is a list of expressions:

```
m.addConstraint (xp.Sum ([y[i] for i in range (10)]) \leq 1) m.addConstraint (xp.Sum ([x[i]**5 for i in range (9)]) \leq x[9])
```

When handling variables or expressions, it is advised to use the Sum operator in the Xpress module rather than the native Python operator, for reasons of efficiency.

As for variables, an object of type constraint allows for read/write access of its features via its members name, body, 1b, and ub. The same caveat for variables holds here: any change to an object's members will only have an effect in the problems to which a constraint is added after the change.

# 2.5 Objective function

The objective function is any expression, so it can be constructed as for constraints. The method problem.setObjective can be used to set (or replace if one has been specified before) the objective function of a problem. The definition of setObjective is as follows:

```
setObjective (objective, sense)
```

where objective is the expression defining the new objective and sense is either xpress.minimize or xpress.maximize. Examples follows (in the first, the objective function is to be minimized as per default, while the second example specifies the optimization sense as maximization).

```
m.setObjective (xp.Sum ([y[i]**2 for i in range (10)])) m.setObjective (v1 + 3 * v2, sense = xp.maximize)
```

# 2.6 Special Ordered Sets (SOSs)

A Special Order Set (SOS) is a modeling tool for constraining a small number of consecutive variables in a vector to be nonzero. The Xpress Python interface allows for defining a SOS as follows:

```
sos (indices, weights, type, name)
```

The first argument, indices, is a list of variables, while weights is a list of floating point numbers. The type of SOS (either 1 or 2) is specified by type. While indices and weights are mandatory parameters, type and name are not; type is set to a default of 1 when not specified. Examples follow:

```
set1 = xp.sos (x, [0.5 + i*0.1 for i in range(10)], type = 2)

set2 = xp.sos ([y[i] for i in range(5)], [i+1 for i in range(5)])

set3 = xp.sos ([v1, v2], [2, 5], 2)
```

One or more SOS can be added to a problem via the problem.addSOS method:

The name member of a SOS object can be read and written by the user.

#### 2.7 Indicator constraints

Indicator constraints are defined by a binary variable, called the *indicator*, and a constraint. Depending on the value of the indicator, the constraint is enforced or relaxed.

For instance, if the constraint  $x + y \ge 3$  should only be enforced if the binary variable u is equal to 1, then  $(u = 1 \rightarrow x + y \ge 3)$  is an indicator constraint.

An indicator constraint in Python can be added to a problem with the addIndicator as follows (note the "==" as the symbol for equality):

```
m.addIndicator (vb == 1, v1 + v2 >= 4)
```

# 2.8 Modeling and solving nonlinear problems

Version 8.3 of the Xpress Optimizer suite introduces nonlinear modeling in the Python interface. It allows for creating and solving nonlinear, possibly nonconvex problems with similar functions as for linear, quadratic, and conic problems and their mixed integer counterpart.

A nonlinear problem can be defined by creating one or more variables and then adding constraints and an objective function. This can be done using the same Python calls as one would do for other problems. The available operators are +, -, \*, /, \*\* (which is the Python equivalent for the power operator, "^"). Univariate functions can also be used from the following list: sin, cos, tan, asin, acos, atan, exp, log, log10, abs, sign, and sqrt. Multivariate functions are min and max, which can receive an arbitrary number of arguments.

Examples of nonlinear constraints are as follows:

```
import xpress as xp
import math

x = xp.var ()
p = xp.problem ()

p.addVariable (x)

# polynomial constraint
p.addConstraint (x**4 + 2 * x**2 - 5 >= 0)

# A terrible way to constrain x to be integer
p.addConstraint (xp.sin (math.pi * x) == 0)

p.addConstraint (x**2 * xp.sign (x) <= 4)</pre>
```

Note that non-native mathematical functions such as log and sin must be prefixed with xpress or its alias, xp in this case. This can be avoided by importing all symbols from xpress using the import \* command as follows

```
from xpress import *
x = var()
a = sin(x)
```

but this hides namespaces and is usually frowned upon.

User functions are also accepted in the Python interface, and must be specified with the keyword user and the function as the first argument. They are handled in the Nonlinear solver in a transparent way, so all is needed is to define a Python function to be run as the user function and specify it in the problem with user, as in the following example:

```
import xpress as xp
import math

def mynorm (x1, x2):
   return math.sqrt (x1**2 + x2**2)

def myfun (v1, v2, v3):
   return v1 / v2 + math.cos (v3)

x,y = xp.var (), xp.var ()

p = xp.problem ()

p.addVariables (x,y)

p.setObjective (user (mynorm, x, y))

p.addConstraint (x+y >= 2)
p.addConstraint (user (myfun, x**2, x**3, 1/y) <= 3)</pre>
```

As a final word of caution, solving nonlinear problem requires a preprocessing step that is transparent to the user except for two steps: first, if the objective function has a nonlinear component f(x) then a new constraint (called *objective transfer row* or *objtransrow*) and a new variable, the *objective transfer column* or *objtranscol*) are called that are defined as follows:

```
objtransrow: -objtranscol + f(x) = 0
```

The resulting problem is equivalent in that the set of optimal (resp. feasible) solutions of this problem will be the same as those of the original problem. The user, however, will notice an increase by one of both the number of rows and of columns when a nonlinear objective function is set.

The second caveat is about yet another variable that may be added to the problem for reasons having to do with one of the Xpress Nonlinear solvers. This variable is called *equalscol* and it is fixed to 1. Its existence and value are therefore of no interest to the user.

The reader can find more information on this in the Xpress Nonlinear reference manual.

# 2.9 Solving a problem

Simply call <code>solve()</code> to solve an optimization problem that was either built or read from a file. The type of solver is determined based on the type of problem: if at least one integer variable was declared, then the problem will be solved as a mixed integer (linear, quadratically constrained, or nonlinear) problem, while if all variables are continuous the problem is solved as a continuous optimization problem. If the problem is nonlinear in that it contains non-quadratic, non-conic nonlinear constraints, then the appropriate nonlinear solver of the Xpress Optimization suite will be called. Note that in case of a nonconvex quadratic problem, the Xpress Nonlinear solver will be applied as the Xpress Optimizer solver cannot handle such problems.

```
m.solve ()
```

The status of a problem after solution can be inquired via the functions <code>getProbStatus()</code> and <code>getProbStatusString()</code> as follows:

The meaning of the returned value is explained in the Optimizer's reference manual. Note that the value and string returned by the above functions reflect the type of problem as input by the user, not the way the problem was last solved. If the user creates a MILP and then solves it as an LP with the flag "1", then both getProbStatus() and getProbStatusString() yield the status of the MILP rather than the LP relaxation. At all effects, the call p.getProbStatus() returns p.attributes.lpstatus if p has continuous variables and p.attributes.mipstatus if p has integer variables.

The output of the solver when reading and solving a problem is the same as with other interfaces of the Xpress Optimizer. The verbosity level is determined by the control outputlog, which is 1 by default. To turn off the solver's output, it should be set to zero (see Chapter 4 for how to set a control).

# 2.10 Querying a problem

It is useful, after solving a problem, to obtain the value of an optimal solution. After solving a continuous or mixed integer problem, the two methods <code>getSolution</code> and <code>getSlack</code> return the vector (of portions thereof) of an optimal solution or the slack of the constraints. If an optimal solution was not found but a feasible solution is available, these methods will return data based on this solution. They can be used in multiple ways as shown in the following examples:

```
import xpress as xp
v1 = xp.var (name = 'Var1')
x = [xp.var (lb = -1, ub = 1, vartype = xp.integer) for i in range(10)]
m = xp.problem ()
```

```
m.addVariable (v1, x)
[...] # add constraints and objective

m.solve()

print (m.getSolution ())  # prints a list with an optimal solution
print ("v1 is", m.getSolution (v1)) # only prints the value of v1
a = m.getSolution (x)  # gets the values of all variables in the vector x
b = m.getSolution (0:4)  # gets the value of v1 and x[0], x[1], x[2]
c = m.getSolution ('Var1')  # gets the value of v1 by its name
```

Consider the last five lines. The first of them returns a list of ncol floating point scalars, where ncol is the number of variables of the problem (nrow is the number of constraints, the size of the vector returned by getSlack) containing the full solution. The second example retrieves the value of the single variable v1. The third example returns an array of the same size as x with the value of all variables of the list x. The fourth example shows that a range of indices can be specified in order to obtain a vector of values without specifying the corresponding variables. Recall that the column and row indices begin at 0. Finally, the last line shows that a variable can be passed by name.

The method getSlack works similarly, except constraints, integer indices, or constraint names must be passed. The following examples illustrate a few possible uses.

```
import xpress as xp
N = 10
x = [xp.var (vartype = xp.binary) for i in range(N)]
m = xp.problem ()
m.addVariable (x)
con1 = xp.Sum (x[i] * i for i in range (N)) <= N)
con2 = (x[i] >= x[i+1]  for i in range (N-1))
m.addConstraints (con1, con2)
m.setObjective (xp.Sum (x[i] for i in range (N))
m.solve ()
print (m.getSlack ())
                                        # prints a list of slacks for all N constraints
print ("slack_1 is", m.getSlack (con1)) # only prints the slack of con1
a = m.getSlack (con2)
                                     # gets the slack of N-1 constraints con2
b = m.getSlack (0:2)
                                     # gets the slack of con1 and con2[0]
```

In addition, for problems with only continuous variables, the two methods getDual and getRCost return the the vector (or a portion thereof) of dual variables and reduced costs, respectively. Their usage is similar to that for getSolution and getSlack.

Note that the inner workings of the Python interface obtain a copy of the *whole* solution, slack, dual, or reduced cost vectors, even if only one element is requested. It is therefore advisable that instead of repeated calls (for instance, in a loop) to <code>getSolution</code>, <code>getSlack</code>, etc. only one call is made and the result is stored in a list to be consulted in the loop. Hence, in the following example:

```
import xpress as xp
n = 10000
N = range (n)
x = [xp.var () for i in N]
p = xp.problem ()
```

```
p.addVariable (x)
m.addConstraints (xp.Sum (x[i] * i for i in N) <= n))
m.setObjective (xp.Sum (x[i] for i in N)
m.solve ()

for i in N:
    if m.getSolution (x[i]) > 1e-3:
        print (i)
```

the last three lines should be substituted as follows, as this will prevent repeatedly copying a large (10,000) vector:

```
sol = m.getSolution ()
for i in N:
    if sol[i] > 1e-3:
        print (i)
```

# 2.11 Reading and writing a problem

After creating an empty problem, one can read a problem from a file via the read method, which only takes the file name as its argument. An already-built problem can be written to a file with the write method. Its arguments are similar to those in the Xpress Optimizer API function XPRSwriteprob, to which we refer.

```
import xpress as xp

m = xp.problem ()
m.read ("example2.lp")
m.solve ()

print (m.getSolution ())

m2 = xp.problem ()
v1 = xp.var ()
v2 = xp.var (vartype = xp.integer)

m2.addVariable (v1, v2)
m2.addConstraint (v1 + v2 <= 4)
m2.setObjective (v1**2 + v2)

m2.write ("twovarsproblem", "lp")</pre>
```

# 2.12 Hints for building models efficiently

The Xpress Python interface allows for creating optimization models using methods described in this and other sections. As happens with other interpreted languages, using explicit loops may result in a slow Python script. When using the Xpress Python interface, this can be noticeable in large optimization models if multiple calls to addVariable, addConstraint, or addSOS are made. For this reason, the Xpress module allows for *generators* and list, dictionaries, and sequences as arguments to these methods, to ensure faster execution.

Let us consider an example:

```
import xpress as xp
N = 100000
S = range(N)
x = [xp.var() for i in S]
```

```
y = [xp.var(vartype = xp.binary) for i in S]
for i in S:
    m.addVariable (x[i])
    m.addVariable (y[i])

for i in S:
    m.addConstraint (x[i] <= y[i])

m.solve()</pre>
```

While the declaration of x and y is correct and efficient, the two subsequent loops are very inefficient: they imply 2N calls to addVariable and N calls to addConstraint. Both methods add some overhead due to the conversion of Python object into data that can be read by the Optimizer, and the total overhead can be large.

Most methods of the Xpress Python interface allow for passing sequences (lists, dictionaries, NumPy arrays, etc.) as parameters, and are automatically recognized as such. Hence the first loop can be replaced by two calls to addVariable:

```
m.addVariable (x)
m.addVariable (y)
```

or, more compact and slightly more efficient:

```
m.addVariable (x,y)
```

The largest gain in performance, though, comes from replacing the second loop with a single call to addConstraint:

```
m.addConstraint (x[i] \le y[i] for i in S)
```

This line is equivalent to the second loop above, and it is much faster and more elegant.

When declaring  ${\bf x}$  and  ${\bf y}$  as NumPy vectors, an equally efficient and even more compact model can be written:

```
import xpress as xp
import numpy as np

N = 100000
S = range(N)

x = np.array ([xp.var () for i in S])
y = np.array ([xp.var (vartype = xp.binary) for i in S])

m.addVariable (x,y)
m.addConstraint (x <= y)

m.solve()</pre>
```

See Chapter 3 for more information on how to use NumPy arrays in the Xpress Python interface.

# **Using Python numerical libraries**

The NumPy library allows for creating and using arrays of any order and size for efficiency and compactness purposes. This chapter shows how to take advantage of the features of NumPy in the creation of optimization problems. The Xpress Python interface works with NumPy versions 1.10 and above.

# 3.1 Using NumPy in the Xpress Python interface

NumPy arrays can be used as usual when creating variables, functions (linear and quadratic) of variables, and constraints. All functions described in this manual that take lists or tuples as arguments can take array's, i.e., NumPy array objects, as well, as in the following example:

```
import numpy as np
import xpress as xp
N = 20
S = range (N)
x = np.array ([xp.var () for i in S])
y = np.array ([xp.var (vartype = xp.binary) for i in S])
constr1 = x <= y
p = xp.problem ()
p.addVariable (x, y)
p.addConstraint (constr1)</pre>
```

The above script imports both NumPy and the Xpress Python interface, then declares two arrays of variables and creates the set of constraints  $x_i \le y_i$  for all i in the set S.

As happens for all NumPy operations, all operations are replicated on each element of an array, taking into account all *broadcasting* features. For example, the following script "broadcasts" the right-hand side 1 to all elements of the array, thus creating the set of constraints  $x_i + y_i \le 1$  for all i in the set S.

```
constr2 = x + y <= 1
```

All these operations can be carried out on arrays of any number of dimensions, and can be aggregated at any level. The following example shows two three-dimensional array of variables involved in two systems of constraints: the first has two variables per each of the 200 constraints, while the second has 10 constraints and 20 variables in each constraint.

Finally, a note on sums of multi-dimensional NumPy arrays: in keeping with the way NumPy arrays are handled, the sum of a bi-dimensional array results in a one-dimensional array with the xpress. Sum operator. The result of such a sum is exemplified by the following code:

For the casual NumPy user, suffice it to say that the sum is done on the *first* dimension. Similarly, when creating a NumPy array of dimensions k of expressions, xpress. Sum returns a (k-1)-array resulting from the sum across the first dimension.

It is important to note the following: NumPy does **not** use the <u>\_\_iadd\_\_</u> operator when computing these sums, but rather the <u>\_\_add\_\_</u> operator. For reasons discussed above and in the entry regarding the <u>xpress.Sum</u> operator, this can have a huge impact on performance. Consider the following example:

```
m,n = 1000,10
a = np.random.random((m,n))
x = np.array ([xp.var () for i in range (m*n)]).reshape(m,n)
sum_0d = xp.Sum (xp.Sum (a*x))
sum_1d = xp.Sum (a*x)
```

The above example has a poor performance, and it is advised to avoid using xpress.Sum as such on a multi-dimensional array. If a scalar sum of all elements of the array is sought, such as sum(sum(a)) for the numerical array above, we strongly advise to flatten the array first, and run instead xpress.Sum(b.flatten()) if b is a multiarray of expressions. If only one pass is required, then it is better to explicitly create a vector whose elements are defined with a call to xpress.Sum:

```
prod = a*x
sum_0d = xp.Sum (prod.flatten())
sum_1d = np.array ([xp.Sum (prod[i,j] for i in range(m)) for i in range(n)])
```

# 3.2 Products of NumPy arrays

The dot product is a useful operator for carrying out aggregate operations on vectors, matrices, and tensors. The dot operator in NumPy allows for reducing, along one axis of a multi-dimensional arrays, data such as floating points or integer values.

The application of the dot product of NumPy of two multi-dimensional arrays of dimensions  $(i_1, i_2, ..., i_{k'})$  and  $(j_1, j_2, ..., j_{k''})$ , respectively, requires that  $i_{k'} = j_{k''-1}$ , i.e., the size of the last dimension of the first array must match the size of the penultimate dimension of the second vector. For instance, the following dot product is valid:

```
import numpy as np
a = np.random.random (4,6)
b = np.random.random (6,2)
c = np.dot (a,b)
```

and the result is a 4x2 matrix. The Xpress Python interface has its own dot product operator, which can be used for all similar operations on variables and expression. The rules for applying the Xpress dot operator are the same as for the native Python dot product, with one extra feature: there is no limit on the number of arguments, hence the following example is correct as per the restrictions on the dimensions, albeit it yields a nonconvex constraint.

```
coeff_pre = np.random.random ((6,3,7))
x = np.array ([xp.var () for i in range(140)]).reshape (4,7,5)
y = np.array ([xp.var () for i in range(80)]).reshape (2,5,8)
coeff_post = np.random.random ((6,8,7))
p.addConstraint (xp.Dot (coeff_pre, x, y, coeff_post) >= 0)
```

Similar to the NumPy dot product, the Xpress dot product has an *out* parameter for defining the output in which to store the product.

The following script defines two constraints: the first restricts the squared norm  $||z|| = z \cdot z$  of the vector z of variables to be at most one. It does so by applying the dot operator on the vector itself. The second constraint  $(t - z)'Q(t - z) \le 1$  restricts the quadratic form on the left-hand side to be at most 1.

```
p.addConstraint (xp.Dot (z,z) <= 1) # restrict norm of z to 1 Q = \text{np.random.random (N,N)} \qquad \text{# create a random 20x20 matrix p.addConstraint (xp.Dot ((t-z), Q, (t-z)) <= 1)}
```

As for the Sum operator, when handling variables or expressions, it is advised to use the Dot operator in the Xpress module rather than the native Python operator, for reasons of efficiency.

# **Controls and Attributes**

A *control* is a parameter that can influence the performance and behavior of the Xpress Optimizer. For example, the MIP gap, the feasibility tolerance, or the type of root LP algorithms are controls that can be set. Controls can both be read from and written to an optimization problem.

An *attribute* is a feature of an optimization problem, such as the number of rows and columns or the number of quadratic elements of the objective function. They are read-only parameters in that they can only be modified, for example, by functions for adding constraints or variables, or functions for setting and modifying the objective function.

Both controls and attributes are of three types: integer, floating point, or string. The Xpress Python interface allows for setting and retrieving the value of all controls of an optimization problem, as well as getting the value of all of a problem's attributes.

This reference manual does *not* describe the meaning of controls and attributes in the Xpress Optimizer; for a detailed description of each, please refer to the Optimizer's reference manual.

Following Python's philosophy, one can set and obtain multiple controls/attributes with one function call. In other words, one can set either (i) a single control and its value; or (ii) a Python dictionary coupling a list of control names and their respective value. Similarly, with one function call one can obtain (i) the value of a single attribute or control by specifying it as a parameter; or (ii) a dictionary associating names to values for each of a list of controls or attributes given as an argument. See the examples below for more information.

#### 4.1 Controls

Use problem.setControl to set the value of one or more controls. Its synopsis is as follows:

```
setControl (ctrl, value)
setControl ({ctrl1: value1, ctrl2: value2, ..., ctrlk: valuek})
```

The first form is for setting the value of the control ctrl to value. The second form is for setting ctrl1 to value1, ctrl2 to value2, ..., and ctrlk to valuek.

A list of all controls can be found on the Xpress Optimizer's reference manual. The control parameters to be passed in setControl are lower-case strings:

```
p.setControl ('miprelstop', 1e-9)
p.setControl ({'miprelstop': 1e-3, 'feastol': 1e-6})
```

Use the method getControl to retrieve the value of one or more controls. Its synopsis is one of the following:

```
getControl (ctrl)
```

```
getControl ([ctrl1, ctrl2, ..., ctrlk])
getControl (ctrl1, ctrl2, ..., ctrlk)
getControl ()
```

The first form is for obtaining the value of the control ctrl. The output will be the value of the control. The second and third forms are for retrieving ctrll, ctrl2, ..., and ctrlk. Whether the controls are declared in a list or a tuple does not matter. The result will be a dictionary coupling each control with its value. The last form is to obtain all controls; the result is a dictionary coupling all controls with their respective value.

The control parameters to be passed in <code>getControl</code> are lower-case strings. For a problem p the call will be as follows:

```
mrs = p.getControl ('miprelstop')
someattr = p.getControl ('miprelstop', 'feastol')
```

## 4.2 Examples

```
import xpress as xp
p = xp.problem ()
p.setControl ({'miprelstop': 1e-5, 'feastol': 1e-4})
p.setControl ('miprelstop', 1e-5)
print (p.getControl ('miprelstop') )
                                               # print the current value of miprelstop
print (p.getControl ('maxtime', 'feastol'))
                                               # print a dictionary with the current
                                               # value of miprelstop and feastol
print (p.getControl (['presolve', 'miplog'])) # Same output
print (p.getControl ())
                                               # print a dictionary with ALL control
# Initialize a dictionary with two controls and their value. Then
# change their value conditionally and set their new (possibly
# changed) value.
myctrl = p.getControl (['miprelstop', 'feastol'])
if (myctrl['miprelstop'] <= 1e-4):</pre>
   myctrl['miprelstop'] = 1e-3
   myctrl['feastol']
                       = 1e-3
else:
   myctrl['feastol']
                         = 1e-4
p.setControl (myctrl)
```

#### 4.3 Attributes

Use the method getAttrib to retrieve the value of one or more controls. Its synopsis is one of the following:

```
getAttrib (attr)
getAttrib ([attr1, attr2, ..., attrk])
getAttrib (attr1, attr2, ..., attrk)
getAttrib ()
```

The first form is for obtaining the value of the attribute attr. The output will be the value of the attribute. The second and third forms are for retrieving attr1, attr2, ..., and attrk. Whether the attributes are declared in a list or a tuple does not matter. The result will be a dictionary coupling each attribute with its value. The last form is to obtain all attributes; the result is a dictionary coupling all attributes with their respective value.

A list of all attributes can be found on the Xpress Optimizer's reference manual. As for controls, the attribute parameters to be passed in getAttrib are lower-case strings. For a problem p the call will be as follows:

```
nrows = p.getAttrib ('nrow')
problemsize = p.getAttrib ('nrow', 'ncol')
```

# 4.4 Examples

# 4.5 Accessing controls and attributes as object members

An alternative, more "prompt-friendly" way to get controls and attributes is through their direct access in a problem or, in the case of controls, the Xpress module itself.

The Xpress module has an object, called <code>controls</code>, containing all controls of the Optimizer. Upon importing the Xpress module, these controls are initialized at their default value. The user can obtain their value at any point and can also set their value; this new value will be inherited by all problems created *after* the modification. They can be read and written as follows:

```
xpress.controls.<controlname> 
xpress.controls.<controlname> = <new value>
```

For example, the object xpress.controls.miprelstop contains the value of the control miprelstop. Controls can be read (and, for example, printed) and set as follows:

```
import xpress as xp
print (xp.controls.heurstrategy)
xp.controls.feastol = 1e-4 # Set new default to 1e-4
```

These "global" controls are maintained throughout while the Xpress module is loaded. Note that the controls object of the Xpress module does not refer to any specific problem.

In addition, every problem has a controls object that stores the controls related to the problem itself. This is the object the functions getControl and setControl refer to. Similar to the Xpress module's controls object, all members of a problem's object can be read and written. For a problem p, the following shows how to read and write a problem's control:

```
p.controls.<controlname>
```

```
p.controls.<controlname> = <new value>
```

A problem's controls are independent of the global controls object of the Xpress module. However, when a new problem is created its controls are copied from the current values in the global object. Note that after creating a new problem, changing the members in xpress.controls does not affect the problem's controls. The following examples should clarify this:

```
import xpress as xp
# create a new problem whose MIPRELSTOP is ten times smaller
# than the default value
p1 = xp.problem ("problem1")
p1.controls.miprelstop = 0.1 * xp.controls.miprelstop
p1.controls.feastol = 1e-5
p1.read ("example1.lp")
xp.controls.miprelstop = 1e-8 # Set new default
# The new problem will have a MIPRELSTOP of 1e-8
p2 = xp.problem ("problem2")
p2.read ("example2.lp")
# The next problem has a less restrictive feasibility tolerance
\# (i.e. 1e-6) than problem 2
p2v = xp.problem ("problem2 variant")
p2v.read ("example2.1p")
p2v.controls.feastol = 100 * p2.controls.feastol
p1.solve ()
p2.solve ()
p2v.solve () # solve "example2.lp" with a less restrictive
             # feasibility tolerance
```

Attributes can be handled similar as above through a member of the class problem, called attributes, with two exceptions: first, there is no "global" attribute object, as a set of attributes only makes sense when associated with a problem; second, an attribute cannot be set.

Once a problem p has been created (or read from a file), its attributes are available as p.attribute.attribute\_name. The example in the previous section can be modified as follows:

When using the Python prompt in creating problems with the Xpress module, the name of controls and attributes can be auto-completed by pressing TAB (note: this only works in Python 3.4 and subsequent versions). For instance,

```
>>> import xpress
>>> p = xp.problem ()
>>> p.read ("example.lp")
>>> p.attributes.n<TAB>
p.attributes.namelength p.attributes.nodedepth p.attributes.nodes p.attributes.numiis
>>> p.attributes.nodedepth
0
>>> p.attributes.ma<TAB>
p.attributes.matrixname p.attributes.maxabsdualinfeas
p.attributes.maxabsprimalinfeas p.attributes.maxprobnamelength
```

p.attributes.maxreldualinfeas
>>> p.attributes.matrixname
'noname'
>>>> xp.controls.o<TAB>
xp.controls.oldnames
xp.controls.optimalitytol
xp.controls.outputlog
xp.controls.outputtol
>>> xp.controls.omniformat

p.attributes.maxrelprimalinfeas

xp.controls.omniformat
xp.controls.optimalitytoltarget
xp.controls.outputmask

# **Using Callbacks**

This chapter shows how to define and use callback functions from the Xpress Python interface. The design of this part of the interface reflects as closely as possible the design of the callback functions defined in the C API of the Xpress Optimizer.

#### 5.1 Introduction

Callback functions are a useful tool for adapting the Xpress Optimizer to the solution of various classes of problems, in particular Mixed Integer Programming (MIP) problems, with linear or nonlinear constraints. Their main purpose is to provide the user with a point of entry into the branch-and-bound, which is the workhorse algorithm for MIPs.

Using callback functions is simple: the user first defines a function (say myfunction) that is to be run every time the branch-and-bound reaches a well-specified point; second, the user calls a function (such as addcbpreintsol) with myfunction as its argument. Finally, the user runs the solve command that launches the branch-and-bound, the simplex solver, or the barrier solver; it is while these are run that myfunction is called.

A callback function, hence, is passed once as an argument and used possibly many times. It is called while a solver is running, and it is passed the following:

- a problem object, of the same class as an object declared with p = xpress.problem();
- a data object.

The data object is user-defined and is given to the problem when adding the callback function. It can be used to store information that the user can read and/or modify within the callback. For instance, the following code shows how to add a callback function, preintsolcb, that is called every time a new integer solution is found.

```
import xpress as xp

class foo:
    "Simple class"
    bar = 0
    def __init__ (self):
        self.bar = 1
    def update (self):
        self.bar += 1

def preintsolcb (prob, data, isheuristic, cutoff):
    """
    Callback to be used when an integer solution is found. The
    "data" parameter is of class foo
    """
```

```
p = xp.problem ()
p.read ('myprob.lp') # reads in a problem, let's say a MIP
baz = foo ()
p.addcbpreintsol (preintsolcb, baz, 3)
p.solve ()
```

While the function argument is necessary for all addcb\* functions, the data object can be specified as None. In that case, the callback will be run with None as its data argument. The call also specifies a priority with which the callback should be called: the larger the (positive) priority, the more urgently it is called.

Any call to an addcb\* function, as the names imply, only adds a function to a list of callback functions for that specific point of the BB algorithm. For instance, two calls to addcbpreintsol with two functions preint1 and preint2, respectively with priority 3 and 5, puts the two functions in a list. The two functions will be called (preint2 first) whenever the BB algorithm finds an integer solution.

In order to remove a callback function that was added with addcb\*, a corresponding removecb\* function is provided, for instance removecbpreintsol. This function takes two arguments, i.e., the callback function and the data object, and deletes all elements of the list of callbacks that were added with the corresponding addcb function that match the function and the data.

The None keyword acts as a wildcard that matches any function/data object: if removecb\* is called with None as the function, then all callbacks matching the data will be deleted. If the data is also None, all callback functions of that type are deleted; this can be obtained by passing no argument to removecb\*.

The arguments and return value of the callback functions reflect those in the C API, and this holds for parameter names as well. As for the other API functions of the Python interface, there are a few exceptions:

- If a function in the C API requires a parameter *n* to indicate the size of an array argument to follow, *n* is not required in the corresponding Python function;
- If a function in the C API uses passing by reference as a means to allow for modifying a value and returning it as an output, the Python counterpart will have this as the return value of the function. Where multiple output values are comprised in the list of parameters, the return value is a *tuple* composed of the returned values. Elements of this tuple can be None if no change was made to that output value.

Most callback functions refer to a problem, therefore the addcb\* method is called from a problem object. The only exception is the function xpress.addcbmsghandler(), which is called on the Xpress module itself and allows for providing a function that is called every time *any* output is produced within the Optimizer.

We refer to the Reference chapter of this manual for all information regarding callback functions and how to add/remove them from a problem.

# **Examples of use**

This chapter discusses some example Python scripts that are part of the Xpress Optimizer's Python interface. Most of them are well commented so the user can refer directly to the source for guidance.

Most of these scripts have an initial part in common, which we reproduce here but omit in all explanations below for compactness. These initial lines import the Xpress module itself and the NumPy module, which is used in some of the examples. The last line is to make the print statements, which are in Python 3 style here, work in Python 2.7 as well.

```
from __future__ import print_function
import xpress as xp
import numpy as np
```

# 6.1 Creating simple problems

Below are a few examples on how to create simple LP, MIP, MIQP, and similar problems. Note that they make use of API functions that resemble the C API functions for creating problems, and are used similarly here.

### 6.1.1 Generating a small Linear Programming problem

In this example, we create a problem and load a matrix of coefficients, a rhs, and an objective coefficient vector with the loadproblem function. We also assign names to both rows and columns (both are optional). These data correspond to the following problem with three variables and four constraints:

```
[3,4,5], # obj
[0,2,4,8], # mstart
None, # mnel
[0,1,2,3,0,1,2,3], # mrwind
[1,2,2,1,1,3,3,1], # dmatval
[-1,-1,-1], # lb
[3,5,8], # ub
colnames = ['X1','X2','X3'], # column names
rownames = ['row1','row2','row3','constr_04']) # row names

p.write ("loadlp", "lp")
p.solve ()
```

We then create another variable and add it to the problem, then modify the objective function. Note that the objective function is replaced by, not amended with, the new expression. After solving the problem, it saves it into a file called update.1p.

```
x = xp.var()
p.addVariable (x)
p.setObjective (x**2 + 2*x + 444)
p.solve()
p.write ("updated", "lp")
```

#### **6.1.2** A Mixed Integer Linear Programming problem

This example uses <code>loadproblem</code> to create a Mixed Integer Quadratically Constrained Quadratic Programming problem with two Special Ordered Sets. Note that data that is not needed is simply set as <code>None</code>.

The Examples directory provides similar examples for different types of problems.

```
p = xp.problem ()
p.loadproblem ("",
                                      # probname
                ['G','G','L', 'L'], # qrtypes
                [-2.4, -3, 4, 5], # rhs
                None,
                                     # range
                [3,4,5],
                                    # obj
                                   # mstart
                [0,2,4,8],
                None,
                                     # mnel
                [0,1,2,3,0,1,2,3], # mrwind
[1,1,1,1,1,1,1], # dmatval
                [-1,-1,-1],
                                     # lb
                                    # ub
                [3,5,8],
                [0,0,0,1,1,2], # mqobj1
[0,1,2,1,2,2], # mqobj1
[2,1,1,2,1,2], # dqe
                [2,3],
                                    # qcrows
                                     # qcnquads
                [2,3],
                [1,2,0,0,2],
                                     # qcmqcol1
                                    # qcmqcol2
                [1,2,0,2,2],
                [3,4,1,1,1],
                                    # qcdqval
                ['I','S'],
                                    # qgtype
                [0,1],
                                     # mgcols
                [0,2],
                                     # dlim
                ['1','1'],
                                    # qstype
                [0,1,0,2], " msstart
                [1.1,1.2,1.3,1.4]) # dref
p.solve ()
```

## 6.2 Modeling examples

#### 6.2.1 A simple model

This example demonstrates how variables and constraints, or arrays thereof, can be added into a problem. The script then prints the solution and all attributes/controls of the problem.

```
N = 4
S = range (N)
v = [xp.var (name = "y{0}]".format (i)) for i in S] # set name of a variable as <math>m = xp.problem ()
v1 = xp.var (name = "v1", lb=0, ub=10, threshold=5, vartype = xp.continuous)
v2 = xp.var (name = "v2", lb=1, ub=7, threshold=3, vartype = xp.continuous)
v3 = xp.var (name = "v5", vartype = xp.continuous)
v4 = xp.var (name = "v5", vartype = xp.binary)
v5 = xp.var (name = "v5", vartype = xp.binary)
v6 = xp.var (name = "y6", vartype = xp.binary)
```

The call below adds both v, a vector (list) of variables, and v1 and v2, two scalar variables.

#### 6.2.2 Using IIS to investigate an infeasible problem

The problem modeled below is infeasible,

```
x0 = xp.var()

x1 = xp.var()

x2 = xp.var(vartype = xp.binary)

c1 = x0 + 2 * x1 >= 1

c2 = 2 * x0 + x1 >= 1

c3 = x0 + x1 <= .5

c4 = 2 * x0 + 3 * x1 >= 0.1
```

The three constraints c1, c2, and c3 above are incompatible as can be easily verified. Adding all of them to a problem will make it infeasible. We use the functions to retrieve the Irreducible Infeasible Subsystems (IIS).

```
minf = xp.problem ("ex-infeas")
minf.addVariable (x0, x1, x2)
minf.addConstraint (c1,c2,c3,c4)
minf.solve()
minf.iisall()
print ("there are ", minf.attributes.numiis, " iis's")
misrow = []
miscol = []
constrainttype = []
colbndtype = []
duals = []
rdcs = []
isolationrows = []
isolationcols = []
# get data for the first IIS
minf.getiisdata (1, miisrow, miiscol, constrainttype, colbndtype,
                 duals, rdcs, isolationrows, isolationcols)
print ("iis data:", miisrow, miiscol, constrainttype, colbndtype,
       duals, rdcs, isolationrows, isolationcols)
# Another way to check IIS isolations
print ("iis isolations:", minf.iisisolations (1))
rowsizes = []
colsizes = []
suminfeas = []
numinfeas = []
print ("iisstatus:", minf.iisstatus (rowsizes, colsizes, suminfeas, numinfeas))
print ("vectors:", rowsizes, colsizes, suminfeas, numinfeas)
```

### 6.2.3 Modeling a problem using Python lists and vectors

We create a convex QCQP problem. We use a vector of N=5 variables and sets constraints and objective. We define all constraints and the objective function using a Python aggregate type.

```
N = 5
S = range (N)
v = [xp.var (name = "y{0}".format (i)) for i in S]
m = xp.problem ("problem 1")
print ("variable:", v)
m.addVariable (v)
m.addConstraint (v[i] + v[j] >= 1 for i in range (N-4) for j in range (i,i+4))
m.addConstraint (xp.Sum([v[i]**2 for i in range (N-1)]) <= N**2 * v[N-1]**2)
m.setObjective (xp.Sum ([i*v[i] for i in S]) * (xp.Sum ([i*v[i] for i in S])))
m.solve ()
print ("solution: ", m.getSolution ())</pre>
```

#### 6.2.4 A knapsack problem

Here follows an example of a knapsack problem formulated using lists of numbers. All data in the problem are lists, and so are the variables.

```
S = range (5)  # that's the set {0,1,2,3,4}
value = [102, 512, 218, 332, 41] # or just read them from file
weight = [ 21, 98, 44, 59, 9]

x = [xp.var (vartype = xp.binary) for i in S]
profit = xp.Sum (value[i] * x[i] for i in S)

p = xp.problem ("knapsack")
p.addVariable (x)
p.addConstraint (xp.Sum (weight[i] * x[i] for i in S) <= 130)
p.setObjective (profit, sense = xp.maximize)
p.solve ()</pre>
```

Note that the same result could have been achieved using NumPy arrays and the Xpress module's dot product as follows:

```
value = np.array ([102, 512, 218, 332, 41])
weight = np.array ([21, 98, 44, 59, 9])

x = np.array ([xp.var (vartype = xp.binary) for i in S])
profit = xp.Dot (value, x)

p = xp.problem ("knapsack")
p.addVariable (x)
p.addConstraint (xp.Dot (weight, x) <= 130)
p.setObjective (profit, sense = xp.maximize)
p.solve ()</pre>
```

#### 6.2.5 A Min-cost-flow problem using NumPy

This example solves a min-cost-flow problem using NumPy and the incidence matrix of the graph. It uses the networkx package, which might have to be installed using, for example, pip.

```
import networkx as netx
# digraph definition

V = [1,2,3,4,5]  # vertices
E = [[1,2], [1,4], [2,3], [3,4], [4,5], [5,1]] # arcs

n = len (V) # number of nodes
m = len (E) # number of arcs

G = netx.DiGraph (E)

# Get NumPy representation
A = (netx.incidence_matrix (G, oriented = True).toarray())
```

We use NumPy vectors and the Xpress interface's dot product, the xpress. Dot operator. Note that although NumPy has a dot operator, especially for large models it is strongly advised to use the Xpress interface's Dot function for reasons of efficiency.

```
demand = np.array ([3, -5, 7, -2, -3])
cost = np.array ([23, 62, 90, 5, 6, 8])
flow = np.array ([xp.var () for i in E]) # flow variables declared on arcs
p = xp.problem ('network flow')
p.addVariable (flow)
p.addConstraint (xp.Dot (A, flow) == - demand)
p.setObjective (xp.Dot (cost, flow))
p.solve ()
```

```
for i in range (m):
    print ('flow on', E[i], ':', p.getSolution (flow [i]))
```

## 6.2.6 A nonlinear model

Let's solve a classical nonlinear problem: finding the minimum of the Rosenbrock function. For parameters a and b, minimize  $(a - x)^2 + b(y - x^2)^2$ .

```
a,b = 1,100

x = xp.var (lb = -xp.infinity)
y = xp.var (lb = -xp.infinity)

p = xp.problem ()
p.addVariable (x,y)
p.setObjective ((a-x)**2 + b*(y-x**2)**2)
p.controls.xslp_solver = 0 # solve it with SLP, not Knitro
p.solve ()

print ("status: ", p.getProbStatus ())
print ("string: ", p.getProbStatusString ())

print ("solution:", p.getSolution ())
```

## 6.2.7 Finding the maximum-area *n*-gon

The problem asks, given n, to find the n-sided polygon of largest area inscribed in the unit circle.

While it is natural to prove that all vertices of a global optimum reside on the unit circle, the problem is formulated so that every vertex i is at distance  $rho_i$  from the center, and at angle  $theta_i$ . We would expect that the local optimum found has all rho's are equal to 1. The example file contains instructions for drawing the resulting polygon using matplotlib.

The objective function is the total area of the polygon. Considering the segment S[i] joining the center to the i-th vertex and A(i,j) the area of the triangle defined by the two segments S[i] and S[j], the objective function is  $A_{(0,1)} + A_{(1,2)} + ... + A_{(N-1,0)}$ , where  $A_{(i,j)} = 1/2 * rho_i * rho_j * sin(theta_i - theta_j)$ . We first define the set Vertices as the set of integers from 0 to n-1.

We establish that the angles must be increasing in order to obtain a sensible solution:

```
p.addConstraint (theta[i] >= theta[i-1] + 1e-4 for i in Vertices if i != 0)
```

Note also that we enforce that the angles be different as otherwise they might form a local optimum where all of them are equal.

## 6.2.8 Solving the *n*-queens problem

In chess, the queen can move in all directions (even diagonally) and travel any distance. The problem of the n queens consists in placing n queens on an  $n \times n$  chessboard so that none of them can be eaten in one move.

We first create a dictionary of variables, mapping each cell of the chessboard to one variable so that we can refer to it later. All variables are clearly binary as they indicate whether a given cell has a queen or not

```
n = 10 \#  the size of the chessboard
N = range (n)
x = \{(i,j): xp.var (vartype = xp.binary, name='q\{0\}_{1}'.format (i,j))\}
     for i in N for j in N}
vertical = [xp.Sum (x[i,j] for i in N) \le 1 for j in N]
horizontal = [xp.Sum (x[i,j] for j in N) \le 1 for i in N]
diagonal1 = [xp.Sum (x[k-j,j] for j in range (max(0,k-n+1), min(k+1,n))) \le 1
             for k in range (1,2*n-2)]
diagonal2 = [xp.Sum (x[k+j,j] for j in range (max(0,-k),
                                                           min(n-k,n)) <= 1
             for k in range (2-n, n-1)]
p = xp.problem()
p.addVariable
                (x)
p.addConstraint (vertical, horizontal, diagonal1, diagonal2)
# Objective, to be maximized: number of queens on the chessboard
p.setObjective (xp.Sum (x), sense = xp.maximize)
p.solve ()
```

As a rudimentary form of visualization, we print the solution on the chessboard with different symbols for variables at one or zero.

```
for i in N:
    for j in N:
        if p.getSolution (x[i,j]) == 1:
            print ('@', sep='', end='')
        else:
            print ('.', sep='', end='')
    print ('')
```

## 6.2.9 Solving Sudoku problems

The well-known Sudoku puzzles ask one to place numbers from 1 to 9 into a 9  $\times$  9 grid such that no number repeats in any row, in any column, and in any 3x3 sub-grid. For a more general version of the game, replace 3 with q and 9 with  $q^2$ .

We model this problem as an assignment problem where certain conditions must be met for all numbers in the columns, rows, and sub-grids.

These subgrids are lists of tuples with the coordinates of each subgrid. In a 9  $\times$  9 sudoku, for instance, subgrids[0,1] has the 9 elements in the middle top square.

The input is a starting grid where the unknown numbers are replaced by zero. The example file contains a relatively hard  $9 \times 9$  sudoku, which we show below, and also a  $16 \times 16$  variant of the same game.

```
q = 3
starting_grid = \
```

```
[[8,0,0,0,0,0,0,0,0],
  [0,0,3,6,0,0,0,0,0],
  [0,7,0,0,9,0,2,0,0],
  [0,5,0,0,0,7,0,0,0],
  [0,0,0,0,4,5,7,0,0],
  [0,0,0,1,0,0,0,3,0],
  [0,0,1,0,0,0,0,6,8],
  [0,0,8,5,0,0,0,1,0],
  [0,9,0,0,0,0,4,0,0]]
n = q**2  # the size must be the square of the size of the subgrids
N = range (n)
x = \{(i,j,k): xp.var (vartype = xp.binary, name='x{0}_{1}_{2}'.format(i,j,k))\}
     for i in N for j in N for k in N}
# define all q^2 subgrids
subgrids = \{(h,l): [(i,j) \text{ for } i \text{ in range } (q*h, q*h + q)\}
                           for j in range (q*l, q*l + q)]
                    for h in range (q) for l in range (q) }
vertical = [xp.Sum (x[i,j,k] for i in N) == 1 for j in N for k in N]
horizontal = [xp.Sum (x[i,j,k] for j in N) == 1 for i in N for k in N]
subgrid = [xp.Sum (x[i,j,k] for (i,j) in subgrids[h,l]) == 1
                                for (h,l) in subgrids.keys() for k in N]
# Assign exactly one number to each cell
assign = [xp.Sum (x[i,j,k] for k in N) == 1 for i in N for j in N]
```

Then we fix those variables that are non-zero in the input grid. We don't need an objective function as this is a feasibility problem. After computing the solution, we print it to the screen.

## 6.3 Examples using NumPy

## 6.3.1 Using NumPy multidimensional arrays to create variables

Use NumPy arrays for creating a 3-dimensional array of variables, then use it to create a mode.

```
S1 = range (2)
S2 = range (3)
S3 = range (4)
m = xp.problem ()
```

The final part of the code retrieves the matrix representation of the quadratic part of the only constraint

```
mstart1=[]
mclind1=[]
dqe1=[]
m.getqrowqmatrix (cons00, mstart1, mclind1, dqe1, 29, h[0][0][0], h[3][2][1])
print ("row 0:", mstart1, mclind1, dqe1)
```

## 6.3.2 Using the dot product to create arrays of expressions

Here we use NumPy arrays to print the product of a matrix by a random vector, and the xpress. Dot function on a matrix and a vector. Note that the NumPy dot operator works perfectly fine here, but should be avoided for reasons of performance, especially when handling large arrays where at least one contains optimization variables or expressions.

```
x = np.array ([xp.var() for i in range(5)])

p = xp.problem ()
p.addVariable (x)
p.addConstraint (xp.Sum (x) >= 2)

p.setObjective (xp.Sum (x[i]**2 for i in range (5)))
p.solve()

A = np.array (range(30)).reshape(6,5) # A is a 6x5 matrix
sol = np.array (p.getSolution ()) # a vector of size 5
columns = A*sol # not a matrix-vector product!
v = np.dot (A,sol) # an array: matrix-vector product A*sol
w = xp.Dot (A,x) # an array of expressions

print (v,w)
```

## 6.3.3 Using the Dot product to create constraints and quadratic functions

This is an example of a problem formulation that uses the xpress. Dot operator to formulate constraints in a concise fashion. Note that the NumPy dot operator is not suitable here as the result is an expression in the Xpress variables.

```
A = np.random.random(30).reshape(6,5) # A is a 6x5 matrix
Q = np.random.random(25).reshape(5,5) # Q is a 5x5 matrix
x = np.array ([xp.var() for i in range(5)]) # vector of variables
x0 = np.random.random (5) # random vector
```

```
Q += 4 * np.eye (5) # add 5 * the identity matrix
Lin_sys = xp.Dot (A,x) <= np.array([3,4,1,4,8,7]) # 6 constraints (rows of A)
Conv_c = xp.Dot (x,Q,x) <= 1 # one quadratic constraint

p = xp.problem ()
p.addVariable (x)
p.addConstraint (Lin_sys, Conv_c)
p.setObjective (xp.Dot (x-x0, x-x0)) # minimize distance from x0
p.solve ()</pre>
```

## 6.3.4 Using NumPy to create quadratic optimization problems

This example creates and solves a simple quadratic optimization problem. Given an  $n \times n$  matrix Q and a point  $x_0$ , minimize the quadratic function  $x^T(Q + n^3I)x$  subject to the linear system  $(x - x_0)^TQ + e = 0$ , where e is the vector of all ones, the inequalities  $Qx \ge 0$ , and nonnegativity on all variables. Report solution if available.

```
n = 10

Q = np.arange (1, n**2 + 1).reshape (n, n)
x = np.array ([xp.var () for i in range (n)])
x0 = np.random.random (n)

p = xp.problem ()

p.addVariable (x)

c1 = xp.Dot ((x - x0), Q) + 1 == 0
c2 = xp.Dot (Q, x) >= 0

p.addConstraint (c1,c2)
p.setObjective (xp.Dot (x, Q + N**3 * np.eye (N), x))

p.solve ('')

print ("nrows, ncols:", p.attributes.rows, p.attributes.cols)
print ("solution:", p.getSolution ())

p.write ("test5-qp", "lp")
```

# 6.4 Advanced examples: callbacks and problem querying, modifying, and analysis

## 6.4.1 Visualize the branch-and-bound tree of a problem

This example shows how to visualize the BB tree of a problem after (partially) solving it. It is assumed here that all branches are binary.

We first define a recursive function that computes the cardinality of a subtree rooted at a node i. This is necessary as the visualization of the BB tree is more balanced when the subtree size is taken into account. The card\_subtree array, which is filled here, is used then for computing the width of each visualized subtree.

```
import networkx as netx
from matplotlib import pyplot as plt
def postorder_count (node):
```

We also define a function that determines the position of each node depending on the cardinality of the subtree rooted at the node.

```
def setpos (T, node, curpos, st_width, depth):
   Set position depending on cardinality of each subtree
    # Special condition: we are at the root
    if node == 1:
       T.add\_node (node, pos = (0.5, 1))
    alpha = .1 # use a convex combination of subtree comparison and
               # depth to assign a width to each subtree
    if node in left.keys ():
        # X position in the graph should not just depend on depth,
        # otherwise we'd see a long and thin subtree and it would just
        # look like a path
       leftwidth = st_width * (alpha * .5 + (1 - alpha) * card_subtree [left [node]]
                    / card_subtree [node])
       leftpos = curpos - (st_width - leftwidth) / 2
       T.add_node (left [node], pos = (leftpos, - depth))
       T.add_edge (node, left [node])
        setpos (T, left [node], leftpos, leftwidth, depth + 1)
    if node in right.keys ():
        rightwidth = st_width * (alpha * .5 + (1 - alpha) * card_subtree [right [node]]
                    / card_subtree [node])
        rightpos = curpos + (st_width - rightwidth) / 2
       T.add_node (right [node], pos = (rightpos, - depth))
        T.add_edge (node, right [node])
        setpos (T, right [node], rightpos, rightwidth, depth + 1)
```

This is the only operation we need to be carried out at every node: given a node number, newnode, and its parent, we store the information in the left and right arrays so that at the end of the BB we have an explicit BB tree stored in these arrays.

```
def storeBBnode (prob, Tree, parent, newnode, branch):
    # Tree is the callback data, and it's equal to T

if branch == 0:
    left [parent] = newnode
else:
```

```
right [parent] = newnode
```

We now set up the BB tree data and create a problem. We read it from a local file, but any user problem can be read and analyzed. We set the node callback with addcbnewnode so that we can collect information at each new node.

```
T = nx.Graph()
left = {}
right = {}
card_subtree = {}
pos = \{\}
p = xp.problem ()
p.read ('sampleprob.mps.gz')
p.addcbnewnode (storeBBnode, T, 100)
p.controls.maxnode=40000 \# Limit the number of nodes inserted in the graph
p.solve ()
postorder_count (1)
                         # assign card_subtree to each node
setpos (T, 1, 0.5, 1, 0) \# determine the position of each node
                         # depending on subtree cardinalities
pos = nx.get_node_attributes (T, 'pos')
nx.draw (T, pos) # create BB tree representation
               # display it; you can zoom indefinitely and see all subtrees
plt.show ()
```

## 6.4.2 Query and modify a simple problem

This example shows how to change an optimization problem using the Xpress Python interface.

```
x = xp.var ()
y = xp.var ()

cons1 = x + y >= 2
upperlim = 2*x + y <= 3

p = xp.problem ()
p.addVariable (x,y)
p.setObjective ((x-4)**2 + (y-1)**2)
p.addConstraint (cons1, upperlim)
p.write ('original', 'lp')</pre>
```

After saving the problem to a file, we change two of its coefficients. Note that the same operations can be carried out with a single call to p.chgmcoef ([cons1,1], [x,0], [3,4]).

```
p.chgcoef (cons1, x, 3) # coefficient of x in cons1 becomes 3
p.chgcoef (1, 0, 4) # coefficient of y in upperlim becomes 4
p.write ('changed', 'lp')
```

## 6.4.3 Change a problem after solution

Construct a problem using addVariable and addConstraint, then use the Xpress API routines to amend the problem with rows and quadratic terms.

```
p = xp.problem ()
N = 5
S = range (N)
```

```
x = [xp.var (vartype = xp.binary) for i in S]
p.addVariable (x)

# vectors can be used whole or addressed with their index

c0 = xp.Sum (x) <= 10
cc = [x[i]/1.1 <= x[i+1]*2 for i in range (N-1)]
p.addConstraint (c0, cc)
p.setObjective (3 - x[0])
mysol = [0, 0, 1, 1, 1, 1.4]

# add a variable with its coefficients
p.addcols ([4], [0,3], [c0,4,2], [-3, 2.4, 1.4], [0], [2], ['Y'], ['B'])
p.write ("problem1", "lp")

# load a MIP solution
p.loadmipsol ([0,0,1,1,1,1.4])</pre>
```

We now add a quadratic term  $x_0^2 - 2x_0x_3 + x_1^3$  to the second constraint. Note that the -2 coefficient for an off-diagonal element must be passed divided by two.

```
\texttt{p.addqmatrix} \ (\texttt{cc[0]}, \ [\texttt{x[0]}, \texttt{x[3]}, \texttt{x[3]}], \ [\texttt{x[0]}, \texttt{x[0]}, \texttt{x[3]}], \ [\texttt{1,-1,1]})
```

As constraint vector cc was added after c0, it is the latter which has index 0 in the problem, while cc[0] has index 1.

We then add the seventh and eighth constraints:

```
subject to: x_0 + 2x_1 + 3x_2 \ge 4
4x_0 + 5x_1 + 6x_2 + 7x_3 + 8x_4 + y \le 4.4
```

Note the new column named 'Y' is added with its index 5 (variables' indices begin at 0). The same would happen if 5 were substituted by Y.

The code below add five columns, then solves the problem and prints the solution, if one has been found.

```
p.addcols ([4], [0,3], [c0,4,2], [-3, -2, 1], [0], [2], ['p1'], ['I'])
p.addcols ([4], [0,3], [c0,4,2], [-3, 2.4, 1.4], [0], [10], ['p2'], ['C'])
p.addcols ([4], [0,3], [c0,4,2], [-3, 2, 1], [0], [1], ['p3'], ['S'])
```

```
p.addcols ([4], [0,3], [c0,4,2], [-3, 2.4, 4], [0], [2], ['p4'], ['P'])
p.addcols ([4], [0,3], [c0,4,2], [-3, 2, 1], [0], [2], ['p5'], ['R'])

p.solve ()

try:
    print ("new solution:", p.getSolution ())
except:
    print ("could not get solution, perhaps problem is infeasible")
```

Note that the single command below has the same effect as the four addcols calls above, and is to be preferred when adding a large number of columns for reasons of efficiency.

## 6.4.4 Comparing the coefficients of two equally sized problems

Given two problems with the same number of variables, we read their coefficient matrices into Scipy so as to compare each row for discrepancies in the coefficients. We begin by creating two Xpress problems and reading them from two files, probl.lp and probl.lp, though p1 and p2 might have been created with the module's modeling features.

```
import xpress as xp
import scipy.sparse

p1 = xp.problem()
p2 = xp.problem()

p1.read ('prob1.lp')
p2.read ('prob2.lp')
```

Next we obtain the matrix representation of the coefficient matrix for both problems. Let us suppose that, for memory reasons, we can only retrieve one million coefficients.

```
coef1, ind1, beg1 = [], [], []
coef2, ind2, beg2 = [], [], []
p1.getrows (beg1, ind1, coef1, 1000000, 0, p1.attributes.rows - 1)
p2.getrows (beg2, ind2, coef2, 1000000, 0, p2.attributes.rows - 1)
```

The function problem.getrows provides a richer output by filling up ind1 and ind2 with the Python objects (i.e. Xpress variables) corresponding to the variable indices rather than the numerical indices. We need to convert them to numerical indices using the problem.getIndex function.

```
indln = [p1.getIndex (v) for v in indl]
ind2n = [p2.getIndex (v) for v in ind2]
```

The next step is to create a Compressed Sparse Row (CSR) format matrix, defined in the scipy.sparse module, using the data from problem.getrows plus the numerical indices.

Then we convert the CSR matrix to a NumPy array of arrays, so that each row is a (non-compressed) array to be compared in the loop below.

```
A1 = scipy.sparse.csr_matrix ((coef1, ind1n, beg1))
```

```
A2 = scipy.sparse.csr_matrix ((coef2, ind2n, beg2))
M1 = A1.toarray()
M2 = A2.toarray()
for i in range (min (p1.attributes.rows, p2.attributes.rows)):
    print (M1[i] != M2[i])
```

The result is a few vector of size COLS with an element-wise comparison of the coefficient vector of each row, with True indicating discrepancies. A more meaningful representation can be given using other functions in NumPy.

```
[False False True False False]
[False False False False False]
[False False False False True]
[ True True False False False]
[False False False False False]
```

## 6.4.5 Combining modeling and API functions

This is an example where a problem is loaded from a file, solved, then modified by adding a Global Upper Bound (GUB) constraint. Note that we do not know the structure of the problem when reading it, yet we can simply extract the list of variables and use them to add a constraint.

```
p = xpress.problem ()
p.read ("example.lp")
p.solve ()
print ("solution of the original problem: ", p.getVariable(), "==>", p.getSolution())
```

After solving the problem, we obtain its variables through getVariable and add a constraints so that their sum cannot be more than 1.1.

```
x = p.getVariable ()
p.addConstraint (xpress.Sum (x) <= 1.1)
p.solve()
print ("New solution: ", p.getSolution ())</pre>
```

## 6.4.6 A simple Traveling Salesman Problem (TSP) solver

A classical example of use of callbacks is the development of a simple solver for the well-known TSP problem. The aim here is not to create an efficient solver (there are far better implementations), but rather a simple solver where the user only needs to specify two callbacks: one for checking whether a given solution forms a Hamiltonian tour and one for separating a subtour elimination constraint from the current node solution.

After a successful solve (or an interrupted one with a feasible solution), the best Hamiltonian tour is displayed. Note that this section omits unnecessary details (checks of return values, exceptions, etc.) of the actual code, which can be found in the Examples/ directory.

```
import networkx as nx
import xpress as xp
import re, math, sys

from matplotlib import pyplot as plt
import urllib.request as ul
filename = 'dj38.tsp'
```

```
ul.urlretrieve ('http://www.math.uwaterloo.ca/tsp/world/' + filename, filename)
instance = open (filename, 'r')
coord_section = False
points = {}
G = nx.Graph ()
```

We have downloaded an instance of the TSP and now it must be read and interpreted as it does not have a format that we know. We save in cx and cy the coordinates of all nodes in the graph, which is assumed to be *complete*, i.e., all nodes are connected to one another.

```
for line in instance.readlines ():
    if re.match ('NODE_COORD_SECTION.*', line):
        coord_section = True
        continue
    elif re.match ('EOF.*', line):
        break

if coord_section:
        coord = line.split (' ')
        index = int (coord [0])
        cx = float (coord [1])
        cy = float (coord [2])
        points [index] = (cx, cy)
        G.add_node (index, pos = (cx, cy))
```

The next step is to define a callback function for checking if the solution forms a Hamiltonian tour, i.e., if it connects all nodes of the graph. The callback will be passed with the method addcbpreintsol, therefore it needs to return a tuple of two values: the first value is True if the solution should be rejected, and the second is the new cutoff in case it has to be changed. This is not the case here, so None can be safely returned.

After obtaining the integer solution to be checked, the function scans the graph from node 1 to see if the solutions at one form a tour.

The second callback to be defined is a separator for subtour elimination constraints. It must return a nonzero value if the node is deemed infeasible by the function, zero otherwise. The function addcuts is used to insert a subtour elimination constraint.

The function works as follows: Starting from node 1, gather all connected nodes of a loop in connset. If this set contains all nodes, then the solution is valid if integer, otherwise the function adds a subtour elimination constraint in the form of a clique constraint with all arcs (i,j) for all i,j in connset.

```
def eliminate_subtour (prob, G):
    s = [] # initialize s to an empty string to provide it as an output parameter
    prob.getlpsol (s, None, None, None)
    orignode = 1
    nextnode = 1
    connset = []
    while nextnode != orignode or len (connset) == 0:
        connset.append (nextnode)
        FS = [j for j in V if j != nextnode
              and s [prob.getIndex (x [nextnode, j])] == 1] # forward star
        if len (FS) < 1:
            return 0
        nextnode = FS [0]
    if len (connset) < n:
        # Add a subtour elimination using the nodes in connset (or, if
        \# card (connset) > n/2, its complement)
        if len (connset) <= n/2:
            columns = [x[i,j] for i in connset for j in connset
                      if i != j]
            nArcs = len (connset)
        else:
            columns = [x[i,j] for i in
                                             V for j in
                                                              V
                      if not i in connset and not j in connset and i != j]
            nArcs = n - len (connset)
        nTerms = len (columns)
        prob.addcuts ([1], ['L'], [nArcs - 1], [0, nTerms], columns, [1] \star nTerms)
    return 0
```

We now formulate the problem with the degree constraints on each node and the objective function (the cost of each arc (i,j) is assumed to be the Euclidean distance between i and j).

```
n = len (points)  # number of nodes
V = range (1, n+1)  # set of nodes
A = [(i,j) for i in V for j in V if i != j] # set of arcs (i.e. all pairs)

x = {(i,j): xp.var (name = 'x_{0}_{1}'.format (i,j), vartype = xp.binary) for (i,j) in A}

conservation_in = [xp.Sum (x[i,j] for j in V if j != i) == 1 for i in V]

conservation_out = [xp.Sum (x[j,i] for j in V if j != i) == 1 for i in V]

p = xp.problem ()

p.addVariable (x)
p.addConstraint (conservation_in, conservation_out)

xind = {(i,j): p.getIndex (x[i,j]) for (i,j) in x.keys ()}
```

We now solve the problem, and if a solution is found it is displayed using the Python library matplotlib.

```
p.solve ()
sol = p.getSolution ()
# Read solution and store it in the graph
for (i,j) in A:
    if sol [p.getIndex (x[i,j])] > 0.5:
        G.add_edge (i,j)
# Display best tour found
pos = nx.get_node_attributes (G, 'pos')
nx.draw (G, points) # create a graph with the tour plt.show () # display it interactively
```

## CHAPTER 7

## **Reference Manual**

## 7.1 Using this chapter

This chapter provides a list of functions available through the Xpress Python interface. For each function, the synopsis and an example are given.

In keeping with the Xpress Optimizer's C API, the name and order of the parameters used in these functions has been retained. However, in order to make optimal use of the greater flexibility provided by Python, the argument lists and the return value of some functions has been modified so as to obtain a more compact notation.

For example, for functions with a list as an argument, the number of elements of the list is not part of the arguments. Compare the call to the C function XPRSaddrows, where the parameters newrow and newnz must be passed, to its Python counterpart:

In the Python version, the prob pointer is not provided as obviously addrows is a method of the problem class. The C variables n and nnz, which are assigned to arguments newrow and newnz, respectively, of the call to XPRSaddrows, are not necessary in the Python call as the length of rhs, mstart, etc. is inferred from the passed lists. If the lengths of all lists passed as arguments are not consistent with one another, an error will be returned.

Because Python lists (or tuples, generators, iterators, sequences) can be used as parameters of all functions in this manual, their size does not need to be passed explicitly as it is detected from the parameter itself. The interface will check the consistency and the content if the vector is referred to the variables or constraints, and will return an error in case of a mismatch.

When passing (lists, arrays, dictionaries of) variables, constraints, or SOSs, there are three ways of referring to these entities: by numerical index, by Python object, and by name. For instance, consider the problem.getSolution method, which admits both an empty argument and one or a list of variables. If we define a variable with a name as follows

```
x = xpress.var (name = 'myvar')
p = xpress.problem()
p.addVariable (x)
```

then we can refer to its index (which will be 0 here as it is the first variable added to the problem), by its object name, i.e., x, and by its given name "myvar", in the three following (equivalent) ways:

```
print ('x is ', p.getSolution (x))
```

```
print ('x is ', p.getSolution (0))
print ('x is ', p.getSolution ('myvar'))
```

Another difference between the Python methods and their C API counterpart is that some *output* arguments are no longer passed (by reference) as arguments to the Python functions but rather are (part of) the value returned by the function. Where multiple scalar output parameters are returned by the C API function, some Python functions return a *tuple* containing all such output values.

The non-scalar parameters can instead be specified as Python lists, NumPy arrays, sequences, or generators when applicable. The output non-scalar parameters are stored as Python lists.

Optional parameters can be specified as None or skipped, provided the subsequent arguments are explicitly declared with their parameter name as Python allows:

Because the Python interface relies on the Xpress Optimizer C Application Program Interface, it is advisable to complement the knowledge in this reference manual with that of the Xpress Optimizer reference manual.

## Format of the reference

The descriptions in the following pages report, for each function:

- Name;
- A short description of its purpose;
- Its synopsis, i.e., how it must be called. If it returns a value, then it will be presented as an assignment Python command, otherwise it will be just shown as a call without a returned value; also, if it is a module function rather than a problem-specific function, it will be prefixed by xpress;
- A description of its arguments and whether each argument is optional;
- Error values;
- Associated controls;
- A sample usage of the function;
- Further useful information about the function;
- Related functions, parameters.

Note that all arguments defined in the following as "array" can be many other Python non-scalar objects: lists, generators, and NumPy arrays are admissible as parameters, except when specified (e.g. getControl). However, for simplicity we refer to non-scalar arguments as array.

Finally, some attributes and controls are referred to as uppercase words for clarity. For example, ROWS indicates the attribute "rows" of a problem, hence it is equivalent to problem.attributes.rows.

## 7.2 Global methods of the Xpress module

Below is a list of functions that are invoked from the Xpress module, i.e., they are not methods of the problem or the branchobj class and can be invoked after the import command. The invocation is therefore as in the example that follows:

```
import xpress as xp
print (xp.getlasterror ())
```

```
xpress.initxpress.freexpress.addcbmsghandlerxpress.getbannerxpress.getcheckedmodexpress.getdaysleftxpress.getlasterrorxpress.getlicerrmsgxpress.getversionxpress.Sumxpress.Dotxpress.setcheckedmodexpress.removecbmsghandlerxpress.setdefaultcontrolxpress.setdefaults
```

## 7.3 Methods of the class problem

The tables below show all methods of the class problem of the Xpress Python interface, with the exception of callbacks, which are listed separately. Their invocation is therefore to be preceded by a problem object (the class prefix problem. is omitted in the table for compactness), as follows:

```
import xpress as xp
x = xp.var ()
p = xp.problem ()
p.setObjective (x + 3 * x**2 + 2)
```

addcols	addConstraint	addIndicator	addmipsol
addqmatrix	addrows	addSOS	addVariable
basisstability	btran	calcobjective	calcreducedcosts
calcslacks	calcsolinfo	chgbounds	chgcoef
chgcoltype	chgglblimit	chgmcoef	chgmqobj
chgobj	chgobjsense	chgqobj	chgqrowcoeff
chgrhs	chgrhsrange	chgrowtype	сору
copycontrols	delConstraint	delqmatrix	delSOS
delVariable	dumpcontrols	estimaterowdualranges	fixglobals
ftran			

getAttrib	getbasis	getcoef	getcols
getcoltype	getConstraint	getControl	getdirs
getDual	getdualray	getglobal	getiisdata
getIndex	getIndexFromName	getindicators	getinfeas
getlasterror	getlb	getlpsol	getmessagestatus
getmipsol	getmqobj	getobj	getObjVal
getpivotorder	getpivots	getpresolvebasis	getpresolvemap
getpresolvesol	getprimalray	getProbStatus	getProbStatusString
getqobj	getqrowcoeff	getqrowqmatrix	getqrowqmatrixtriplets
getqrows	getRCost	getrhs	getrhsrange
getrows	getrowtype	getscaledinfeas	getSlack
getSolution	getSOS	getub	getunbvec
getVariable	hasdualray	hasprimalray	

iisall	iisclear	iisfirst
iisisolations	iisnext	iisstatus
iiswrite	loadbasis	loadbranchdirs
loaddelayedrows	loaddirs	loadlpsol
loadmipsol	loadmodelcuts	loadpresolvebasis
loadpresolvedirs	loadproblem	loadsecurevecs
lpoptimize	mipoptimize	name
objsa	postsolve	presolverow
read	readbasis	readbinsol
readdirs	readslxsol	refinemipsol
repairinfeas	repairweightedinfeas	repairweightedinfeasbounds
restore	reset	rhssa
save	scale	setControl
setdefaults	setindicators	setlogfile
setmessagestatus	setObjective	setprobname
solve	strongbranch	write
writebasis	writebinsol	writedirs
writeprtsol	writeslxsol	writesol

## The following table contains the problem functions to be called for nonlinear problems.

addcoefs	adddfs	addtolsets
addvars	cascade	cascadeorder
chgcascadenlimit	chgccoef	chgnlcoef
chgdeltatype	chgdf	chgrowstatus
chgrowwt	chgtolset	chgvar
construct	delcoefs	deltolsets
delvars	evaluatecoef	evaluateformula
filesol	fixpenalties	getccoef
getcoefformula	getcoefs	getcolinfo
getdf	getdtime	getmessagetype
getrowinfo	getrowstatus	getrowwt
getslpsol	gettolset	getvar
globalsol	loadcoefs	loaddfs
loadtolsets	loadvars	msaddcustompreset
msaddjob	msaddpreset	msclear
parsecformula	parseformula	preparseformula
presolve	printmemory	printevalinfo
printmsg	reinitialize	scaling
setcurrentiv	setuniqueprefix	tokencount
unconstruct	updatelinearization	validformula
validate	validatekkt	validaterow
validatevector		

## 7.4 Methods for branching objects

The following pages present the methods of the branchobj class, i.e., the methods used when creating and manipulating branching objects. Their invocation can be as follows:

```
import xpress as xp
b = xp.branchobj ()
b.addbranches (3)
```

```
branchobj.addbounds branchobj.addbranches branchobj.addcuts
branchobj.addrows branchobj.getbounds branchobj.getid branchobj.getlasterror branchobj.getrows
branchobj.setpreferredbranch branchobj.setpriority branchobj.store
branchobj.validate
```

## 7.5 Methods for adding/removing callbacks of a problem object

The following pages present methods that can be called from a problem **before** optimization has started, to add or remove callbacks. All these methods are part of the problem class and have to be instantiated from a problem object.

```
addcbbariteration
                      removecbbariteration
addcbbarlog
                      removecbbarlog
                      removecbchqbranchobject
addcbchqbranchobject
addcbcutlog
                      removecbcutlog
addcbdestroymt
                      removecbdestroymt
addcbgapnotify
                      removecbgapnotify
addcbgloballog
                      removecbgloballog
addcbinfnode
                      removecbinfnode
addcbintsol
                      removecbintsol
addcblplog
                      removecblplog
addcbmessage
                      removecbmessage
addcbmipthread
                      removecbmipthread
addcbnewnode
                      removecbnewnode
addcbnodecutoff
                      removecbnodecutoff
addcboptnode
                      removecboptnode
addcbpreintsol
                      removecbpreintsol
addcbprenode
                      removecbprenode
addcbusersolnotify
                      removecbusersolnotify
```

## 7.6 Methods to be used within a callback of a problem object

The following methods can be called from within a callback function that has been passed in one of the problem.addcb\* methods. Calling these functions outside of a callback may result in an error and

trigger termination of the optimization process. We provide two tables: one is for the Optimizer and another for the nonlinear solvers.

copycallbacks	delcpcuts	delcuts
getcpcutlist	getcpcuts	getcutlist
getcutmap	getcutslack	interrupt
loadcuts	setbranchbounds	setbranchcuts
storebounds	storecuts	strongbranchcb
addcuts		

setcbcascadeend	setcbcascadestart	setcbcascadevar
setcbcascadevarfail	setcbcoefevalerror	setcbconstruct
setcbdestroy	setcbdrcol	setcbformula
setcbiterend	setcbiterstart	setcbitervar
setcbmsjobend	setcbmsjobstart	setcbmswinner
setcbslpend	setcbslpnode	setcbslpstart

## xpress.free

#### **Purpose**

Releases the Xpress environment, thus freeing up one license. The subsequent creation of a problem automatically triggers a call to xpress.init.

Note that it is **unnecessary** to call this function upon exiting a block that uses the Xpress module, or when the optimizer is no longer used, as Python will release the Xpress environment when freeing the Xpress module. This function might be useful when a license is needed by another user or program, and one wishes to release the license.

#### **Synopsis**

```
xpress.free ()
```

### **Example**

The following example shows how to call xpress.free and a possible use:

Note that xpress.init is only useful when the user wants to claim a license that might be used by another program or user.

#### **Further information**

Similar to a call to XPRSfree () of the C API, calling xpress.free cleans the Xpress environment. Any problem created prior to a call to xpress.free is no longer available, and referring to it may lead to errors. For instance, the following code results in an aborted run:

```
import xpress
p = xpress.problem ()
xpress.free()
xpress.init()
p.solve ()
```

#### **Related topics**

```
xpress.init
```

## xpress.getbanner

## **Purpose**

Returns the banner and copyright message.

## **Synopsis**

```
i = xpress.getbanner ()
```

## Example

print (xpress.getbanner ())

## xpress.getcheckedmode

## **Purpose**

Returns whether checking & validation of all Optimizer function calls is enabled for the current process. Checking & validation is enabled by default but can be disabled by <a href="mailto:xpress.setcheckedmode">xpress.setcheckedmode</a>.

## **Synopsis**

i = xpress.getcheckedmode ()

## **Related topics**

xpress.setcheckedmode.

## xpress.getdaysleft

#### **Purpose**

Returns the number of days left until an evaluation license expires.

## **Synopsis**

```
d = xpress.getdaysleft ()
```

#### **Example**

The following calls getdaysleft to print information about the license:

```
try:
   ndays = xpress.getdaysleft ()
except RuntimeError:
   print ("Not an evaluation license")
else
   print ("Evaluation license expires in {0} days".format (ndays))
```

#### **Further information**

This function can only be used with evaluation licenses, and, if called when a normal license is in use, it returns an error. The expiry information for evaluation licenses is also included in the Optimizer banner message.

## xpress.getlasterror

## **Purpose**

Returns the last error encountered during a call to the Xpress global environment.

## **Synopsis**

```
(i,s) = xpress.getlasterror ()
```

## **Arguments**

- i Error code
- s Error message relating to the global environment will be returned.

## **Example**

```
import xpress as xp
# last error referring to the global environment
print (xp.getlasterror ())
```

## xpress.getlicerrmsg

## **Purpose**

Returns the error message string describing the last licensing error, if any occurred.

## **Synopsis**

```
m = xpress.getlicerrmsg ()
```

## **Example**

The following calls getlicerrmsg to find out why the import of the Xpress Python module failed:

```
try:
    import xpress
except RuntimeError:
    print (xpress.getlicerrmsg ())
else:
    print ("all good")
```

## xpress.getversion

## **Purpose**

Returns the full Optimizer version number as a string of the form 15.10.03, where 15 is the major release, 10 is the minor release, and 03 is the build number.

## **Synopsis**

```
v = xpress.getversion ()
```

## **Example**

print ("Using Xpress Optimizer version", xpress.getversion ())

## xpress.init

#### **Purpose**

Initializes the Xpress environment prior to creating or reading a problem.

Note that it is **not** necessary to call this function after importing the Xpress module and before creating or solving a problem, as Python will claim a license automatically. This function might be useful when the user wants to reserve a license and prevent that it is claimed by another user or program.

#### **Synopsis**

```
xpress.init ()
```

## **Example**

The following example shows how to call xpress.init and why it could be useful:

```
xp.init () # reserves the license before creating variables
x = xp.var ()
y = xp.var ()
p = xp.problem () # This would imply a call to xp.init()
p.addVariable (x, y)
p.addConstraint (x+y <= 1)
p.setObjective (x+2*y, sense=xp.maximize)
p.solve ()</pre>
```

Note that the call to xpress.init is not necessary and should only be made when the user wants to claim a license that might be used by another program or user before the call to xpress.problem.

#### **Related topics**

```
xpress.free
```

## xpress.setcheckedmode

### **Purpose**

Disable/enable some of the checking & validation of function calls & function call parameters for calls to the Xpress Optimizer API. This checking is relatively lightweight but disabling it can improve performance in cases where non-intensive Xpress Optimizer functions are called repeatedly in a short space of time.

Please note: after disabling checking and validation for function calls, invalid usage of Xpress Optimizer functions may not be detected and may cause the Xpress Optimizer process to behave unexpectedly or crash. It is not recommended to disable function call checking & validation during application development.

#### **Synopsis**

xpress.setcheckedmode (checked\_mode)

## **Argument**

checked\_mode

Pass as False or 0 to disable much of the validation for all Xpress function calls from the current process. Pass True or 1 to re-enable validation. By default, validation is enabled.

#### Related topics

xpress.getcheckedmode.

## xpress.setdefaults

### **Purpose**

Sets the module's controls to their default values. This affects all problems created after calling setdefaults, not before.

## **Synopsis**

```
xpress.setdefaults ()
```

## **Example**

The following creates two problems, one before and one after calling setdefaults():

## **Related topics**

xpress.setdefaultcontrol, problem.setdefaults, problem.setdefaultcontrol.

## xpress.setdefaultcontrol

#### **Purpose**

Sets one of the module's controls to its default values. This affects all problems created after calling setdefaults, not before.

#### **Synopsis**

```
xpress.setdefaultcontrol (control)
```

## **Argument**

control Name of the control to be set to default.

#### **Example**

The following creates two problems, one before and one after calling setdefaultcontrol (xpress.presolve):

## **Related topics**

xpress.setdefaults,problem.setdefaults,problem.setdefaultcontrol.

## xpress.Sum

### **Purpose**

Alternative sum operator for an arbitrary number of objects created by a Python list, tuple, generator, NumPy array, dictionary, etc.

#### **Synopsis**

```
a = xpress.Sum (t1, t2, ...)
```

#### **Example**

The following are allowed uses of the Sum operator:

#### **Further information**

The Sum operator is functionally equivalent to Python's native sum operator. However, it is strongly advised to use the Xpress' Sum operator when constructing large expressions involving variables, as doing otherwise might slow down the execution significantly.

## xpress.Dot

#### **Purpose**

Alternative dot-product operator for an arbitrary number of NumPy single- or multi-dimensional arrays. Following the convention for dot-product, the result of Dot for a list of k objects  $T_1, T_2, ..., T_k$  of  $d_1, d_2, ..., d_k$  dimensions is an object of  $d_1 + d_2 + ... + d_k - 2(k-1)$  dimensions. For each i-th factor in [1,2,...,k-1], the arity of the last dimension of  $T_i$  must match the arity of the penultimate dimension of  $T_{i+1}$  (or its arity if  $T_{i+1}$  is single-dimensional, i.e., a vector).

### **Synopsis**

```
a = xpress.Dot (t1, t2, ..., out)
```

#### **Argument**

out (optional) NumPy array of the correct dimension and arity where the result is stored. If not provided, the dot product is returned.

## **Example**

The following code shows some possible uses of the Dot operator:

```
import numpy as np
import xpress as xp
N = 10
M = 20
S = range(N)
x = np.array ([xp.var () for i in S])
x0 = np.random.random (N) # creates an N-vector of random numbers
p = xp.problem ()
# objective function is the squared Euclidean distance of the
# variable vector x from a fixed point x0
p.setObjective (xp.Dot ((x-x0), (x-x0)))
A = np.random.random ((M, N))
b = np.random.random (M)
\# constraint Ax = b, random MxN matrix A and M-vector b
p.addConstraint (xp.Dot (A, x) == b)
# Create a single quadratic constraint with
# a positive semidefinite matrix Q + N^3 * I
Q = np.random.random ((N,N))
p.addConstraint (xp.Dot (x, Q + N**3 * np.eye (N), x) \leq 1)
# Create four quadratic constraints using an order-three
# tensor, i.e., a three-dimensional array.
k = 4
T = np.random.random ((k, N, N))
q = np.random.random (k)
p.addConstraint (xp.Dot (x, T, x) \leq q)
```

#### **Further information**

From an operational standpoint, the dot product of k multi-dimensional arrays is the result of k-1 dot products of two factors each, and proceeds as in the following Python code:

```
result = T[0]
for i in range (1,k):
    result = xpress.Dot (result, T[i])
```

The dot product of two multi-dimensional array T' and T'' of dimensions d' and d'' and of arities  $(n_1, n_2, ..., n_{d'})$  and  $(m_1, m_2, ..., m_{d''})$ , respectively, is a multi-dimensional array of dimension d' + d'' - 2, whose arity vector is  $(n_1, n_2, ..., n_{d'-1}, m_1, m_2, ..., m_{d''-2}, m_{d''})$  and whose generic element is

$$v_{i_1,i_2,\dots,i_{d'-1},j_1,j_2,\dots,j_{d''-2},j_{d''}} = \sum\nolimits_{1 \le h \le n_{d'}} t'_{i_1,i_2,\dots,i_{d'-1},h} \cdot t''_{j_1,j_2,\dots,j_{d''-2},h,j_{d''}}.$$

It is assumed here that  $n_{d'} = m_{d''-1}$ . Two simple cases may help understand the behavior of the operator: for two single-dimensional arrays v' and v'' of size n, the result is the inner product

$$\sum_{1 \leq h \leq n} v'_h \cdot v''_h$$
.

For two matrices A and B of sizes  $m \times n$  and  $n \times p$  respectively, the result is the  $m \times p$  matrix C whose generic element is

$$C_{ij} = \sum_{1 \le h \le n} A_{ih} \cdot B_{hj}$$

The Dot operator is functionally equivalent to Python's dot operator from the NumPy package. However, the Xpress Dot operator is the only one that can work on variables and expressions containing variables.

## xpress.Prod

## **Purpose**

Returns the product of a sequence of one or more expressions.

## **Synopsis**

```
a = xpress.Prod (t1, t2, ...)
```

#### **Example**

The following are allowed uses of the Prod operator:

```
n = 10
x = [xp.var() for i in range (n)]
prod = xp.Prod(x)
polynomial = xp.Sum (i * xp.Prod (x[i:i+4]) for i in range (n-4))
```

## **Further information**

While n-ary product operators may exist in Python and/or NumPy, it is advisable to use xpress.Prod when creating products of many expressions as it is the most efficient alternative.

## xpress.exp

## **Purpose**

Returns the exponential of a given expression.

## **Synopsis**

```
a = xpress.exp (t)
```

## **Argument**

t Exponent.

## **Further information**

Using Python's math library operator math.exp is only advisable when the argument is not an expression that depends on variables.

## xpress.log

## **Purpose**

Returns the natural logarithm of a given expression.

## **Synopsis**

$$a = xpress.log (t)$$

## **Argument**

t Argument of the log function.

## **Further information**

Using Python's math library operator math.log is only advisable when the argument is not an expression that depends on variables.

# xpress.log10

### **Purpose**

Returns the base-10 logarithm of a given expression.

## **Synopsis**

```
a = xpress.log10 (t1)
```

## **Argument**

t Argument.

#### **Further information**

Using Python's math library operator math.log10 is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.log.

## xpress.sin

### **Purpose**

Returns the sine of a given expression.

## **Synopsis**

```
a = xpress.sin (t)
```

#### **Argument**

t Argument of the sine function.

#### **Further information**

Using Python's math library operator math.sin is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.cos, xpress.tan, xpress.asin, xpress.acos, xpress.atan.

## xpress.cos

### **Purpose**

Returns the cosine of a given expression.

## **Synopsis**

```
a = xpress.cos(t)
```

#### **Argument**

t Argument of the cosine function.

#### **Further information**

Using Python's math library operator math.cos is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.sin, xpress.tan, xpress.asin, xpress.acos, xpress.atan.

## xpress.tan

#### **Purpose**

Returns the tangent of a given expression.

## **Synopsis**

```
a = xpress.tan (t)
```

#### **Argument**

t Argument of the tangent function.

#### **Further information**

Using Python's math library operator math.tan is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.sin, xpress.cos, xpress.asin, xpress.acos, xpress.atan.

## xpress.asin

### **Purpose**

Returns the arcsine of a given expression.

## **Synopsis**

```
a = xpress.asin (t)
```

#### **Argument**

t Argument of the arcsine function.

#### **Further information**

Using Python's math library operator math.asin is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.sin, xpress.cos, xpress.tan, xpress.acos, xpress.atan.

## xpress.acos

### **Purpose**

Returns the arccosine of a given expression.

## **Synopsis**

```
a = xpress.acos (t)
```

#### **Argument**

t Argument of the arccosine function.

#### **Further information**

Using Python's math library operator math.acos is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.sin, xpress.cos, xpress.tan, xpress.asin, xpress.atan.

## xpress.atan

### **Purpose**

Returns the arctangent of a given expression.

## **Synopsis**

```
a = xpress.atan (t)
```

#### **Argument**

t Argument of the arctangent function.

#### **Further information**

Using Python's math library operator math. atan is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.sin, xpress.cos, xpress.tan, xpress.asin, xpress.acos.

## xpress.max

### **Purpose**

Returns the maximum of one or more expressions.

## **Synopsis**

```
a = xpress.max (t1, t2, ..., tn)
```

## **Argument**

```
t1, t2... Arguments.
```

## **Further information**

Using Python's operator max is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.min.

# xpress.min

### **Purpose**

Returns the minimum of one or more expressions.

## **Synopsis**

```
a = xpress.min (t1, t2, ..., tn)
```

## **Argument**

```
t1, t2... Arguments.
```

## **Further information**

Using Python's operator  $\min$  is only advisable when the argument is not an expression that depends on variables.

## **Related topics**

xpress.max.

# xpress.abs

### **Purpose**

Returns the absolute value of a given expression

## **Synopsis**

```
a = xpress.abs (t)
```

## **Argument**

t Argument of the abs() function.

## **Further information**

Python's native abs operator is equivalent to xpress.abs for arguments that are functions of variables.

# xpress.sign

## **Purpose**

Returns the sign of an expression: 1 if positive, -1 if negative, 0 if zero.

## **Synopsis**

$$a = xpress.sign (t)$$

## **Argument**

t Argument of the sign function.

## xpress.erf

#### **Purpose**

Returns the error function with an expression as its argument.

## **Synopsis**

```
a = xpress.erf (t)
```

## **Argument**

t Argument of the function.

#### **Further information**

For reasons related to compilers and math libraries, on Windows machines this function can only be used with Python 3.

## **Related topics**

xpress.erfc.

# xpress.erfc

### **Purpose**

Returns the complementary error function with an expression as its argument.

## **Synopsis**

```
a = xpress.erfc (t)
```

## Argument

t Argument of the function.

#### **Further information**

For reasons related to compilers and math libraries, on Windows machines this function can only be used with Python 3.

## **Related topics**

xpress.erf.

## xpress.sqrt

### **Purpose**

Returns the square root of an expression.

## **Synopsis**

```
a = xpress.sqrt (t)
```

## **Argument**

t Radicand of the function.

#### **Further information**

Using Python's math library operator math.sqrt is only advisable when the argument is not an expression that depends on variables.

## xpress.user

#### **Purpose**

Creates an expression that is computed by means of a user-specified function.

#### **Synopsis**

```
def f (a1, a2, ..., an):
[...]
a = xpress.user (f, t1, t2, ..., tn)
```

#### **Arguments**

```
    User function; must be a Python function with as many (possibly optional) arguments as specified in the declaration.
    t1,...,tn
    Arguments of the user function.
```

#### **Example**

The following code shows how to define user functions:

```
import math
def mynorm (v):
    return math.sqrt (sum (v[i] for i in range (len (v)))

def weighted_sum (t1, t2, t3 = 0):
    return 2*t1 + 3*t2 + 4*t3

x = [xp.var() for i in range (20)]

f1 = xp.user (mynorm, x)
f2 = xp.user (weighted_sum, x[0], x[1], x[2])

# doesn't use optional arg
f3 = xp.user (weighted_sum, x[0], x[1])
```

#### **Further information**

User functions must return a Float, as the behaviour is otherwise undefined.

## xpress.addcbmsghandler

#### **Purpose**

Declares an output callback function in the global environment, called every time a line of message text is output by any object in the library. This callback function will be called in addition to any output callbacks already added by xpress.addcbmsghandler.

#### **Synopsis**

#### **Arguments**

msghandler The callback function which takes six arguments, vObject, vUserContext,

vSystemThreadId, sMsg, iMsgType and iMsgNumber. Use None to cancel a

callback function.

vObject The object sending the message.

vUserContext The user-defined object passed to the callback function.

vSystemThreadId The system id of the thread sending the message cast to a void \*.

sMsq A string containing the message, which may simply be a new line. When the callback is

called for the first time sMsq will be empty.

iMsgType Indicates the type of output message:

1 information messages;

2 (not used);

3 warning messages;

4 error messages.

When the callback is called for the first time iMsqType will be a negative value.

iMsqNumber The number associated with the message. If the message is an error or a warning then

you can look up the number in the section Optimizer Error and Warning Messages for

advice on what it means and how to resolve the associated issue.

data A user-defined object to be passed to the callback function.

priority An integer that determines the order in which multiple message handler callbacks will

be invoked. The callback added with a higher priority will be called before a callback

with a lower priority. Set to 0 if not required.

#### **Further information**

To send all messages to a log file the built in message handler logfilehandler can be used. This can be done with:

```
xpress.addcbmsghandler (logfilehandler,
'log.txt', 0)
```

#### **Related topics**

xpress.removecbmsghandler.

## xpress.removecbmsghandler

#### **Purpose**

Removes a message callback function previously added by xpress.addcbmsghandler. The specified callback function will no longer be called after it has been removed.

### **Synopsis**

xpress.removecbmsghandler (msghandler, data)

#### **Arguments**

 ${\tt msghandler} \quad {\tt The\ callback\ function\ to\ remove.\ If\ None\ then\ all\ message\ callback\ functions\ added}$ 

with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all message callbacks with the function msghandler will be removed.

#### **Related topics**

xpress.addcbmsghandler.

## problem.addcbbariteration

#### **Purpose**

Declares a barrier iteration callback function, called after each iteration during the interior point algorithm, with the ability to access the current barrier solution/slack/duals or reduced cost values, and to ask barrier to stop. This callback function will be called in addition to any callbacks already added by addebbariteration.

#### **Synopsis**

```
problem.addcbbariteration (callback, data, priority)
barrier_action = callback (my_prob, my_object)
```

Set to 0 if not required.

#### **Arguments**

The callback function itself. This takes two arguments, my\_prob and my\_object, and callback returns an integer return value. This function is called at every barrier iteration. The problem passed to the callback function, fubi. my\_prob my\_object The user-defined object passed as object when setting up the callback with addcbbariteration. barrier\_action Defines a return value controlling barrier: continue with the next iteration; <0 =0let barrier decide (use default stopping criteria) barrier stops with status not defined; 1 2 barrier stops with optimal status; 3 barrier stops with dual infeasible status; barrier stops wih primal infeasible status; A user-defined object to be passed to the callback function, f\_bariteration. data An integer that determines the order in which callbacks of this type will be invoked. The priority callback added with a higher priority will be called before a callback with a lower priority.

#### Example

This simple example demonstrates how the solution might be retrieved for each barrier iteration.

```
# Barrier iteration callback
def BarrierIterCallback (my_prob, my_object):
   current_iteration = my_prob.attributes.bariter
   PrimalObj = my_prob.attributes.barprimalobj
             = my_prob.attributes.bardualobj
   Gap = DualObj - PrimalObj
   PrimalInf
                     = my_prob.attributes.barprimalinf
   DualInf
                     = my_prob.attributes.bardualinf
   ComplementaryGap = my_prob.attributes.barcgap
    # decide if stop or continue
   barrier_action = 0
    if (current_iteration >= 50 or
        Gap \le 0.1 * max (abs (PrimalObj), abs (DualObj))):
       barrier_action = 2
   return barrier_action
```

```
# To set callback:
xprob.addcbbariteration (BarrierIterCallback, myobj, 0)
```

#### **Further information**

- 1. Only the following functions are expected to be called from the callback: <a href="mailto:problem.getlpsol">problem.getlpsol</a> and the attribute/control value retrieving and setting routines.
- 2. Please note that these values refer to the scaled and presolved problem used by barrier, and may differ from the ones calculated from the postsolved solution returned by problem.getlpsol.

## **Related topics**

problem.removecbbariteration.

## problem.addcbbarlog

#### **Purpose**

Declares a barrier log callback function, called at each iteration during the interior point algorithm. This callback function will be called in addition to any barrier log callbacks already added by addcbbarlog.

#### **Synopsis**

```
problem.addcbbarlog (callback, data, priority)
ret = callback (my_prob, my_object)
```

#### **Arguments**

callback The callback function itself. This takes two arguments, my\_prob and my\_object, and

has an integer return value. If the value returned by callback is nonzero, the solution

process will be interrupted. This function is called at every barrier iteration.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcbbarlog.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple barrier log callbacks will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Example**

This simple example prints a line to the screen for each iteration of the algorithm.

```
prob.addcbbarlog (barLog, None, 0)
prob.lpoptimize ('b')
```

The callback function might resemble:

```
def barLog (prob, object):
    print ('Next barrier iteration')
```

#### **Further information**

If the callback function returns a nonzero value, the Optimizer run will be interrupted.

#### **Related topics**

problem.removecbbarlog,problem.addcbgloballog,problem.addcblplog, problem.addcbmessage.

## problem.addcbchgbranchobject

#### **Purpose**

Declares a callback function that will be called every time the Optimizer has selected a global entity for branching. Allows the user to inspect and override the Optimizer's branching choice. This callback function will be called in addition to any callbacks already added by

problem.addcbchgbranchobject.

#### **Synopsis**

problem.addcbchgbranchobject (callback, data, priority)
newobject = callback (my\_prob, my\_object, obranch)

#### **Arguments**

callback The callback function, which takes three arguments: my\_prob, my\_object, and

obranch. This function is called every time the Optimizer has selected a candidate

entity for branching.

my\_prob The problem passed to the callback function, callback.

my\_object The user defined object passed as object when setting up the callback with

addcbchgbranchobject.

obranch The candidate branching object selected by the Optimizer.

newobject New branching object to replace the Optimizer's selection. Can be None.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple callbacks of this type will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Further information**

- 1. The branching object given by the Optimizer provides a linear description of how the Optimizer intends to branch on the selected candidate. This will often be one of standard global entities of the current problem, but can also be e.g. a split disjunction or a structural branch, if those features are turned on.
- 2. The functions branchobj.getbranches, branchobj.getbounds and branchobj.getrows can be used to inspect the given branching object.
- 3. Refer to the branchobj class to learn how to create a new branching object to replace the Optimizer's selection. Note that the new branching object should be created with a priority value no higher than the current object to guarantee it will be used for branching.

#### **Related topics**

problem.removecbchgbranchobject.

## problem.addcbcutlog

#### **Purpose**

Declares a cut log callback function, called each time the cut log is printed. This callback function will be called in addition to any callbacks already added by <a href="mailto:problem.addcbcutlog">problem.addcbcutlog</a>.

### **Synopsis**

```
problem.addcbcutlog (callback, data, priority)
ret = callback (my_prob, my_object)
```

## **Arguments**

callback The callback function which takes two arguments, my\_prob and my\_object, and has

an integer return value.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcbcutlog.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple cut log callbacks will be invoked.

The callback added with a higher priority will be called before a callback with a lower

priority. Set to 0 if not required.

#### **Further information**

The callback callback should return a non-zero value to stop cutting on the current node.

#### **Related topics**

problem.removecbcutlog.

## problem.addcbdestroymt

#### **Purpose**

Declares a callback function that is called every time a MIP thread is destroyed by the parallel MIP code. This callback function will be called in addition to any callbacks already added by addcbdestroymt.

### **Synopsis**

```
problem.addcbdestroymt (callback, data, priority)
callback (my_prob, my_object)
```

## **Arguments**

callback The callback function which takes two arguments, my\_prob and my\_object, and has

no return value.

my\_prob The thread problem passed to the callback function.

my\_object The user-defined object passed as object when setting up the callback with

addcbdestroymt.

data A user-defined object to be passed to the callback function.

priority An integer that determines the order in which multiple callbacks of this type will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Further information**

This callback is useful for freeing up any user data created in the MIP thread callback.

#### **Related topics**

problem.removecbdestroymt,problem.addcbmipthread.

## problem.addcbgapnotify

#### **Purpose**

Declares a gap notification callback, to be called when a MIP solve reaches a predefined target, set using the miprelgapnotify, mipabsgapnotify, mipabsgapnotifyobj, and/or mipabsgapnotifybound controls.

#### **Synopsis**

#### **Arguments**

callback The callback function.

object A user-defined object that wil be passed into the callback callback.

priority An integer that determines the order in which multiple gap notification callbacks will be

invoked. The callback added with the higher priority will be called before a callback with

a lower priority. Set to 0 if not required.

my\_prob The current problem.

my\_object The user-defined object passed as object when setting up the callback with

addcbgapnotify.

RelGapNotify The value the miprelgapnotify control will be set to after this callback. May be modified within the callback in order to set a new notification target.

AbsGapNotify The value the mipabsgapnotify control will be set to after this callback. May be modified within the callback in order to set a new notification target.

AbsGapNotifyObj The value the mipabsgapnotifyobj control will be set to after this callback.

May be modified within the callback in order to set a new notification target.

AbsGapNotifyBound The value the mipabsgapnotifybound control will be set to after this callback. May be modified within the callback in order to set a new notification target.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple estimate callbacks will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

### Example

The following example prints a message when the gap reaches 10% and 1%

```
def gapnotify (prob, object):
    obj = prob.attributes.mipobjval
    bound = prob.attributes.bestbound
    relgap = abs ((obj - bound) / obj)

    newRelGapNotifyTarget = -1

if relgap <= 0.1:
    print ('Gap reached 10%')
    newRelGapNotifyTarget = 0.1

if relgap <= 0.01:
    print ('Gap reached 1%')
    newRelGapNotifyTarget = -1 # Don't call gapnotify again</pre>
```

```
# return a quadruple with new values, or
# None for those that should not be set
return (newRelGapNotifyTarget, None, None, None)

prob.controls.miprelgapnotify = 0.1
prob.addcbgapnotify (gapnotify, None, 0)
prob.mipoptimize ('')
```

## **Further information**

The target values that caused the callback to be triggered will automatically be reset to prevent the same callback from being fired again.

#### **Related topics**

MIPRELGAPNOTIFY, MIPABSGAPNOTIFY, MIPABSGAPNOTIFYOBJ, MIPABSGAPNOTIFYBOUND, problem.removecbgapnotify.

## problem.addcbgloballog

#### **Purpose**

Declares a global log callback function, called each time the global log is printed. This callback function will be called in addition to any callbacks already added by addebgloballog.

#### **Synopsis**

```
problem.addcbgloballog (callback, data, priority)
ret = callback (my_prob, my_object)
```

#### Arguments

callback The callback function which takes two arguments, my\_prob and my\_object, and has

an integer return value. This function is called whenever the global log is printed as

determined by the MIPLOG control.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcbgloballog.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple global log callbacks will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Example**

The following example prints at each node of the global search the node number and its depth:

```
prob.controls.miplog = 3
prob.addcbgloballog (globalLog, None, 0)
prob.mipoptimize ('')
```

The callback function may resemble:

#### **Further information**

If the callback function returns a nonzero value, the global search will be interrupted.

#### **Related topics**

```
problem.removecbgloballog, problem.addcbbarlog, problem.addcblplog, problem.addcbmessage.
```

## problem.addcbinfnode

#### **Purpose**

Declares a user infeasible node callback function, called after the current node has been found to be infeasible during the Branch and Bound search. This callback function will be called in addition to any callbacks already added by addcbinfnode.

#### **Synopsis**

```
problem.addcbinfnode (callback, data, priority)
callback (my_prob, my_object)
```

#### **Arguments**

callback The callback function which takes two arguments, my\_prob and my\_object, and has

no return value. This function is called after the current node has been found to be

infeasible.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcbinfnode.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple user infeasible node callbacks

will be invoked. The callback added with a higher priority will be called before a callback

with a lower priority. Set to 0 if not required.

### **Example**

The following notifies the user whenever an infeasible node is found during the global search:

```
prob.addcbinfnode (nodeInfeasible, None, 0)
prob.mipoptimize ("")
```

The callback function may resemble:

```
def nodeInfeasible (prob, object):
   node = prob.attributes.currentnode
   print ("Node {0} infeasible".format (node))
```

#### **Related topics**

problem.removecbinfnode,problem.addcboptnode,problem.addcbintsol, problem.addcbnodecutoff.

## problem.addcbintsol

#### **Purpose**

Declares a user integer solution callback function, called every time an integer solution is found by heuristics or during the Branch and Bound search. This callback function will be called in addition to any callbacks already added by addcbintsol.

#### **Synopsis**

```
problem.addcbintsol (callback, data, priority)
callback (my_prob, my_object)
```

#### **Arguments**

callback The callback function which takes two arguments, my\_prob and my\_object, and has no return value. This function is called if the current node is found to have an integer

feasible solution, i.e. every time an integer feasible solution is found.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcbintsol.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple integer solution callbacks will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Example**

The following example prints integer solutions as they are discovered in the global search:

```
prob.addcbintsol (printsol, None, 0)
prob.mipoptimize ("")
```

The callback function might resemble:

```
def printsol (my_prob, object):
    cols = my_prob.attributes.originalcols
    objval = my_prob.attributes.lpobjval
    x = []
    my_prob.getlpsol (x, None, None, None)
    print ("Integer solution found:", objval, "; values:")
    print (x)
```

#### **Further information**

- 1. This callback is useful if the user wants to retrieve the integer solution when it is found.
- 2. To retrieve the integer solution, use either problem.getlpsol or problem.getmipsol always returns the last integer solution found and, if called from the intsol callback, it will not necessarily return the solution that caused the invocation of the callback (for example, it is possible that when solving with multiple MP threads, another thread finds a new integer solution before the user calls problem.getmipsol).
- 3. This callback is called after a new integer solution was found by the Optimizer. Use a callback set by problem.addcbpreintsol in order to be notified before a new integer solution is accepted by the Optimizer, which allows for the new solution to be rejected.

#### Related topics

problem.removecbintsol, problem.addcbpreintsol.

## problem.addcblplog

#### **Purpose**

Declares a simplex log callback function which is called after every LPLOG iterations of the simplex algorithm. This callback function will be called in addition to any callbacks already added by addeblplog.

#### **Synopsis**

```
problem.addcblplog (callback, data, priority)
ret = callback (my_prob, my_object)
```

#### **Arguments**

callback The callback function which takes two arguments, my\_prob and my\_object, and has

an integer return value. This function is called every LPLOG simplex iterations including

iteration 0 and the final iteration.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcblplog.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple lplog callbacks will be invoked.

The callback added with a higher priority will be called before a callback with a lower

priority. Set to 0 if not required.

### **Example**

The following code sets a callback function, lpLog, to be called every 10 iterations of the optimization:

```
prob.controls.lplog = 10
prob.addcblplog (lpLog, None, 0)
prob.read ("problem", "")
prob.mipoptimize ("")
```

The callback function may resemble:

```
def lpLog (my_prob, object):
    iter = my_prob.attributes.simplexiter
    obj = my_prob.attributes.lpobjval
    print ("At iteration {0} objval is {1}".format (iter, obj))
    return 0
```

#### **Further information**

If the callback function returns a nonzero value, the solution process will be interrupted.

#### Related topics

```
problem.removecblplog,problem.addcbbarlog,problem.addcbgloballog,
problem.addcbmessage.
```

## problem.addcbmessage

#### **Purpose**

Declares an output callback function, called every time a text line relating to the given prob is output by the Optimizer. This callback function will be called in addition to any callbacks already added by addcbmessage.

#### **Synopsis**

```
problem.addcbmessage (callback, data, priority)
callback (my_prob, my_object, msq, msqtype)
```

#### **Arguments**

 $\verb|callback| & \textbf{The callback function which takes five arguments}, \verb|my_prob|, my_object|, \verb|msg|, \verb|len and | \\$ 

msgtype, and has no return value. Use a None value to cancel a callback function.

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as object when setting up the callback with

addcbmessage.

msq A null terminated character array (string) containing the message, which may simply be

a new line.

msgtype Indicates the type of output message:

information messages;

2 (not used)

3 warning messages;

4 error messages.

A negative value indicates that the Optimizer is about to finish and the buffers should be

flushed at this time if the output is being redirected to a file.

data A user-defined object to be passed to the callback function.

priority An integer that determines the order in which callbacks of this type will be invoked. The

callback added with a higher priority will be called before a callback with a lower priority.

Set to 0 if not required.

#### **Example**

The following example simply sends all output to the screen (stdout):

```
prob.addcbmessage (Message, None, 0)
```

The callback function might resemble:

```
def Message (my_prob, object, msg, msgtype):
    print ('{0}: {1}'.format (msgtype, msg))
```

#### **Further information**

- Screen output is automatically created by the Optimizer Console only. To produce output when using the Optimizer library, it is necessary to define this callback function and use it to print the messages to the screen (stdout).
- 2. This function offers one method of handling the messages which describe any warnings and errors that may occur during execution. Other methods are to check the return values of functions and then get the error code using the ERRORCODE attribute, obtain the last error message directly using <a href="mailto:problem.getlasterror">problem.getlasterror</a>, or send messages direct to a log file using <a href="problem.setlogfile">problem.setlogfile</a>.

#### **Related topics**

problem.removecbmessage, problem.addcbbarlog, problem.addcbgloballog, problem.addcblplog, problem.setlogfile.

## problem.addcbmipthread

#### **Purpose**

Declares a MIP thread callback function, called every time a MIP worker problem is created by the parallel MIP code. This callback function will be called in addition to any callbacks already added by addcbmipthread.

#### **Synopsis**

```
problem.addcbmipthread (callback, data, priority)
callback (my_prob, my_object, thread_prob)
```

#### **Arguments**

callback The callback function which takes three arguments, my\_prob, my\_object and

thread\_prob, and has no return value.

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed to the callback function.

thread\_prob The problem for the MIP thread

data A user-defined object to be passed to the callback function.

priority An integer that determines the order in which multiple callbacks of this type will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Example**

The following example clears the message callback for each of the MIP threads:

```
prob.addcbmipthread (mipthread, None, 0)

def mipthread (my_prob, my_object, mipthread):
    my_prob.removecbmessage (mipthread, None)
```

#### **Further information**

This function will be called when a new MIP worker problem is created. Each worker problem receives a unique identifier that can be obtained through the MIPTHREADID attribute. Worker problems can be matched with different system threads at different points of a solve, so the system thread that is responsible for executing the callback is not necessarily the same thread used for all subsequent callbacks for the same worker problem. On the other hand, worker problems are always assigned to a single thread at a time and the same nodes are always solved on the same worker problem in repeated runs of a deterministic MIP solve. A worker problem therefore acts as a virtual thread through the node solves.

#### **Related topics**

problem.removecbmipthread, problem.addcbdestroymt.

## problem.addcbnewnode

#### **Purpose**

Declares a callback function that will be called every time a new node is created during the branch and bound search. This callback function will be called in addition to any callbacks already added by addebnewnode.

#### **Synopsis**

```
problem.addcbnewnode (callback, data, priority)
callback (my_prob, my_object, parentnode, newnode, branch)
```

#### **Arguments**

callback The callback function, which takes five arguments: myprob, my\_object, parentnode,

newnode and branch. This function is called every time a new node is created through

branching.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcbnewnode.

parentnode Unique identifier for the parent of the new node.

newnode Unique identifier assigned to the new node.

branch The sequence number of the new node amongst the child nodes of parentnode. For

regular branches on a global entity this will be either 0 or 1.

data A user-defined object to be passed to the callback function.

priority An integer that determines the order in which callbacks of this type will be invoked. The

callback added with a higher priority will be called before a callback with a lower priority.

Set to 0 if not required.

#### **Further information**

- 1. For regular branches on a global entity, branch will be either zero or one, depending on whether the new node corresponds to branching the global entity up or down.
- 2. When branching on a branchobject, branch refers to the given branch index of the object.

#### **Related topics**

problem.removecbnewnode.

# problem.addcbnodecutoff

#### **Purpose**

Declares a user node cutoff callback function, called every time a node is cut off as a result of an improved integer solution being found during the branch and bound search. This callback function will be called in addition to any callbacks already added by addcbnodecutoff.

#### **Synopsis**

```
problem.addcbnodecutoff (callback, data, priority)
callback (my_prob, my_object, node)
```

#### **Arguments**

callback The callback function, which takes three arguments, my\_prob, my\_object and node,

and has no return value. This function is called every time a node is cut off as the result

of an improved integer solution being found.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcbnodecutoff.

node The number of the node that is cut off.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple node-optimal callbacks will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Example**

The following notifies the user whenever a node is cutoff during the global search:

```
prob.addcbnodecutoff (Cutoff, None, 0)
mipoptimize (prob, "")
```

The callback function might resemble:

```
def Cutoff (prob, object, node):
    print ("Node {0} cutoff".format (node))
```

#### **Further information**

This function allows the user to keep track of the eligible nodes. Note that the LP solution will not be available from this callback.

#### **Related topics**

problem.removecbnodecutoff,problem.addcboptnode,problem.addcbinfnode, problem.addcbintsol.

## problem.addcboptnode

#### **Purpose**

Declares an optimal node callback function, called during the branch and bound search, after the LP relaxation has been solved for the current node, and after any internal cuts and heuristics have been applied, but before the Optimizer checks if the current node should be branched. This callback function will be called in addition to any callbacks already added by addcboptnode.

#### **Synopsis**

```
problem.addcboptnode (callback, data, priority)
feas = callback (my_prob, my_object)
```

#### **Arguments**

callback The callback function which takes three arguments, my\_prob, my\_object and feas,

and has no return value.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcboptnode.

feas The feasibility status. If set to a nonzero value by the user, the current node will be

declared infeasible.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple node-optimal callbacks will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Example**

The following prints the optimal objective value of the node LP relaxations:

```
prob.addcboptnode (nodeOptimal, None, 0)
prob.mipoptimize ("")
```

The callback function might resemble:

```
def nodeOptimal (prob, object):
   node = prob.attributes.currentnode
   print ("NodeOptimal: node number", node)
   objval = prob.attributes.lpobjval
   print ("Objective function value =", objval)
   return 0
```

### **Related topics**

```
problem.removecboptnode, problem.addcbinfnode, problem.addcbintsol,
problem.addcbnodecutoff, CALLBACKCOUNT_OPTNODE.
```

## problem.addcbpreintsol

#### **Purpose**

Declares a user integer solution callback function, called when an integer solution is found by heuristics or during the branch and bound search, but before it is accepted by the Optimizer. This callback function will be called in addition to any integer solution callbacks already added by addcbpreintsol.

#### **Synopsis**

```
problem.addcbpreintsol (callback, data, priority)
(ifreject, newcutoff) = callback (my_prob, my_object, soltype, cutoff)
```

#### **Arguments**

The callback function which takes five arguments, my\_prob, my\_object, callback

> isheuristic, ifreject and cutoff, and has no return value. This function is called when an integer solution is found, but before the solution is accepted by the Optimizer, allowing the user to reject the solution.

The problem passed to the callback function, callback. my\_prob

The user-defined object passed as object when setting up the callback with my\_object

addcbpreintsol.

soltype The type of MIP solution that has been found: Set to 1 if the solution was found using a

heuristic. Otherwise, it will be the global feasible solution to the current node of the

global search.

The continuous relaxation solution to the current node of the global search, 0

which has been found to be global feasible.

A MIP solution found by a heuristic. 1

2 A MIP solution provided by the user.

A solution resulting from refinement of primal or dual violations of a previous 3

MIP solution.

Set this to 1 if the solution should be rejected. ifreject

The current cutoff value. cutoff

newcutoff The new cutoff value, to be used by the Optimizer if the solution is accepted. The

returned newcutoff value will not be updated if the solution is rejected.

data A user-defined object to be passed to the callback function, callback.

An integer that determines the order in which callbacks of this type will be invoked. The priority

callback added with a higher priority will be called before a callback with a lower priority.

Set to 0 if not required.

#### **Further information**

- 1. If a solution is rejected, the Optimizer will drop the found solution without updating any attributes, including the cutoff value. To change the cutoff value when rejecting a solution, the control MIPABSCUTOFF should be set instead.
- 2. When a node solution is rejected (isheuristic = 0), the node itself will be dropped without further branching.
- 3. To retrieve the integer solution, use either problem.getlpsol or problem.getpresolvesol. problem.getmipsol will not return the newly found solution because it has not been saved at this point.

#### **Related topics**

problem.removecbpreintsol, problem.addcbintsol.

## problem.addcbprenode

#### **Purpose**

Declares a preprocess node callback function, called before the LP relaxation of a node has been optimized, so the solution at the node will not be available. This callback function will be called in addition to any callbacks already added by addcbprenode.

#### **Synopsis**

```
problem.addcbprenode (callback, data, priority)
nodinfeas = callback (my_prob, my_object)
```

#### **Arguments**

The callback function, which takes three arguments, my\_prob, my\_object and nodinfeas, and has no return value. This function is called before a node is reoptimized and the node may be made infeasible by setting \*nodinfeas to 1.

my\_prob The problem passed to the callback function, callback.

my\_object The user-defined object passed as object when setting up the callback with

addcbprenode.

nodinfeas The feasibility status. If set to a nonzero value by the user, the current node will be

declared infeasible by the Optimizer.

data A user-defined object to be passed to the callback function, callback.

priority An integer that determines the order in which multiple preprocess node callbacks will be

invoked. The callback added with a higher priority will be called before a callback with a

lower priority. Set to 0 if not required.

#### **Example**

The following example notifies the user before each node is processed:

```
prob.addcbprenode (preNode, None, 0)
prob.mipoptimize ("")
```

The callback function might resemble:

```
def preNode (prob, object):
    return 0 # set to 1 if node is infeasible
```

#### Related topics

problem.removecbprenode, problem.addcbinfnode, problem.addcbintsol, problem.addcbnodecutoff, problem.addcboptnode.

# problem.addcbusersolnotify

#### **Purpose**

Declares a callback function to be called each time a solution added by problem.addmipsol has been processed. This callback function will be called in addition to any callbacks already added by addcbusersolnotify.

#### **Synopsis**

```
problem.addcbusersolnotify (callback, data, priority)
callback (my_prob, my_object, solname, status)
```

#### **Arguments**

The callback function which takes four arguments, my\_prob, my\_object, id and callback

status and has no return value.

The problem passed to the callback function, callback. my\_prob

my\_object The user-defined object passed as object when setting up the callback with

addcbusersolnotify.

The string name assigned to the solution when it was loaded into the Optimizer using solname

problem.addmipsol.

One of the following status values: status

An error occured while processing the solution.

Solution is feasible. 1

2 Solution is feasible after reoptimizing with fixed globals.

A local search heuristic was applied and a feasible solution discovered. 3

A local search heuristic was applied but a feasible solution was not found. 4

Solution is infeasible and a local search could not be applied. 5

Solution is partial and a local search could not be applied. 6

Failed to reoptimize the problem with globals fixed to the provided solution. 7 Likely because a time or iteration limit was reached.

Solution is dropped. This can happen if the MIP problem is changed or solved

to completion before the solution could be processed.

A user-defined object to be passed to the callback function, callback. data

An integer that determines the order in which multiple callbacks will be invoked. The priority

callback added with a higher priority will be called before a callback with a lower priority.

Set to 0 if not required.

8

#### **Further information**

If presolve is turned on, any solution added with problem.addmipsol will first be presolved before it can be checked. The value returned in status refers to the presolved solution, which might have had values adjusted due to bound changes, fixing of variables, etc.

#### **Related topics**

problem.removecbusersolnotify, problem.addmipsol.

# problem.addcoefs

#### **Purpose**

Add non-linear coefficients to the SLP problem

#### **Synopsis**

```
problem.addcoefs (rowindex, colindex, factor, fstart, parsed, type, value)
```

#### **Arguments**

rowindex Array holding the indices of rows for the coefficient.

colindex Array holding the indices of columns for the coefficient.

factor Array holding factor by which formula is scaled. If None, a value of 1.0 will be used.

FormulaStart Integer array holding the start position in the arrays Type and Value of the formula for the coefficients. FormulaStart should have an extra entry containing the next position after the end of the last formula.

parsed Integer indicating whether the token arrays are formatted as internal unparsed (parsed = False) or internal parsed reverse Polish (parsed = True).

type Array of token types providing the formula for each coefficient.

value Array of values corresponding to the types in Type.

## **Example**

Assume that the rows and columns of Prob are named Row1, Row2 ..., Col1, Col2 ..., respectively. The following example adds coefficients representing:

```
Col2 * Col3 + Col6 * Col2^2 into Row1 and
Col2 ^ 2 into Row3.
      rowindex = [Row1, Row1, Row3]
      colindex = [Col2, Col6, Col2]
      formulastart = []
      n = 0
      ncoef = 0
      formulastart[ncoef], ncoef = n, ncoef + 1
      Type[n], Value[n], n = xslp_op_col, 3, n+1
      Type[n],
                          n = xslp_op_eof,
      formulastart[ncoef], ncoef = n, ncoef + 1
      Type[n], Value[n], n = xslp_op_col, 2,
                                                           n+1
      Type[n], Value[n], n = xslp_op_col, 2,
                                                           n+1
      Type[n], Value[n], n = xslp_op_op, xslp_MULTIPLY, n+1
                          n = xslp_op_eof,
      Type[n],
                                                           n+1
      formulastart[ncoef], ncoef = n, ncoef + 1
      Type[n], Value[n], n = xslp_op_col, 2, n+1
      Type[n],
                          n = xslp_op_eof,
      formulastart [ncoef] = n
      p.addcoefs (rowindex, colindex, None, formulastart, 1, Type, Value)
```

The first coefficient in Row1 is in Co12 and has the formula Co13, so it represents Co12 \* Co13.

The second coefficient in Row1 is in Col6 and has the formula Col2 \* Col2 so it represents Col6 \* Col2^2. The formulae are described as parsed (Parsed=1), so the formula is written as Col2 Col2 \*

rather than the unparsed form

Col2 \* Col2

The last coefficient, in Row3, is in Col2 and has the formula Col2, so it represents Col2 \* Col2.

#### **Further information**

The j<sup>th</sup> coefficient is made up of two parts: Factor and Formula. Factor is a constant multiplier, which can be provided in the Factor array. If Xpress Nonlinear can identify a constant factor in Formula, then it will use that as well, to minimize the size of the formula which has to be calculated. Formula is made up of a list of tokens in Type and Value starting at formulastart [j]. The tokens follow the rules for parsed or unparsed formulae as indicated by the setting of Parsed. The formula must be terminated with an  $xslp_op_eof$  token. If several coefficients share the same formula, they can have the same value in FormulaStart. For possible token types and values see the chapter on "Formula Parsing".

The addcoef function loads additional items into the SLP problem. The corresponding loadcoefs function deletes any existing items first.

The behaviour for existing coefficients is additive: the formula defined in the parameters are added to any existing formula coefficients. However, due to performance considerations, such duplications should be avoided when possible.

## **Related topics**

problem.chgnlcoef,problem.chgccoef,problem.delcoefs,problem.getcoefformula, problem.getccoef,problem.loadcoefs

# problem.addcols

#### **Purpose**

Add columns to the problem after passing it to the Optimizer using the input routines.

## **Synopsis**

```
problem.addcols (objx, mstart, mrwind, dmatval, bdl, bdu, names, types)
```

#### **Arguments**

Array containing the objective function coefficients of the new columns.					
Array containing the offsets in the mrwind and dmatval arrays of the start of the elements for each column.					
Array containing the row indices for the elements in each column.					
Array containing the element values.					
Array containing the lower bounds on the added columns.					
Array containing the upper bounds on the added columns.					
(optional) Array containing the names of the columns added.					
<ul> <li>(optional) Array of characters containing the types of the newly added columns:</li> <li>c indicates a continuous variable (default);</li> <li>I indicates an integer variable;</li> <li>B indicates a binary variable;</li> <li>S indicates a semi-continuous variable;</li> <li>R indicates a semi-continuous integer variable;</li> <li>P indicates a partial integer variable.</li> </ul>					

#### Example

In this example, we consider the two problems:

(a)	maximize:	2x + y			(b)	maximize:	2x + y + 3z		
	subject to:	x + 4y	$\leq$	24		subject to:	x + 4y + 2z	$\leq$	24
		у	$\leq$	5			y + z	$\leq$	5
		3x + y	$\leq$	20			3x + y	$\leq$	20
		x + y	$\leq$	9			x + y + 3z	$\leq$	9
							Z	$\leq$	12

Using addcols, the following transforms (a) into (b):

## **Further information**

- 1. The constant xpress.infinity can be used to represent infinite bounds.
- 2. If the columns are added to a MIP problem, then they will be continuous variables unless types is specified. Use problem.chgcoltype to impose integrality conditions on such new columns.

#### **Related topics**

problem.addrows, problem.chgcoltype.

# problem.addConstraint

#### **Purpose**

Adds one or more constraints to the problem.

#### **Synopsis**

```
problem.addConstraint (c1, c2, ...)
```

## **Argument**

c1, c2... Constraints or list/tuples/array of constraints created with the xpress.constraint() call.

# **Example**

```
N = 20

x = [xpress.var () for i in range (N)]

c = [x[i] \le x[i+1] for i in range (N-1)]

c2 = x[0] >= x[19]

p = xpress.problem ()

p.addVariable (x)

p.addConstraint (x[2] == x[4])

p.addConstraint (c, c2)
```

#### **Further information**

All arguments can be single constraints or lists, tuples, or NumPy arrays of constraints created as xpress.constraint objects. Arguments do not need to be declared prior to the call.

# problem.addcuts

#### **Purpose**

Adds cuts directly to the matrix at the current node. Any cuts added to the matrix at the current node and not deleted at the current node will be automatically added to the cut pool. The cuts added to the cut pool will be automatically restored at descendant nodes.

#### **Synopsis**

problem.addcuts (mtype, rtype, rhs, mstart, mcols, dmatval)

#### **Arguments**

mtype Array containing the user assigned cut types. The cut types can be any integer chosen by the user, and are used to identify the cuts in other cut manager routines using user

supplied parameters. The cut type can be interpreted as an integer or a bitmap - see

problem.delcuts.

rtype Character array containing the row types:

 $\begin{array}{ll} L & \text{indicates a} \leq \text{row;} \\ \text{G} & \text{indicates} \geq \text{row;} \\ \text{E} & \text{indicates an = row.} \end{array}$ 

rhs Array containing the right hand side elements for the cuts.

mstart Array containing offset into the mcols and dmatval arrays indicating the start of each

cut. This array is of length ncuts+1 with the last element, mstart[ncuts], being

where cut ncuts+1 would start.

mcols Array containing the column indices in the cuts.

dmatval Array containing the matrix values for the cuts.

#### **Further information**

- 1. The columns and elements of the cuts must be stored contiguously in the mcols and dmatval arrays passed to addcuts. The starting point of each cut must be stored in the mstart array. To determine the length of the final cut, the mstart array must be of length ncuts+1 with the last element of this array containing the position in mcols and dmatval where the cut ncuts+1 would start. mstart[ncuts] denotes the number of nonzeros in the added cuts.
- 2. The cuts added to the matrix are always added at the end of the matrix and the number of rows is always set to the original number of cuts added. If ncuts have been added, then the rows 0,...,ROWS-ncuts-1 are the original rows, whilst the rows ROWS-ncuts,...,ROWS-1 are the added cuts. The number of cuts can be found by consulting the CUTS problem attribute.

#### **Related topics**

problem.addrows, problem.delcpcuts, problem.delcuts, problem.getcpcutlist, problem.getcutlist, problem.loadcuts, problem.storecuts, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

# problem.adddfs

#### **Purpose**

Add a set of distribution factors

#### **Synopsis**

```
problem.adddfs (colindex, rowindex, value)
```

#### **Arguments**

colindex Array of indices of columns whose distribution factor is to be changed.

rowindex Array of indices of the rows where each distribution factor applies.

value Array holding the new values of the distribution factors.

#### **Example**

The following example adds distribution factors as follows:

```
column 282 in row 134 = 0.1
column 282 in row 136 = 0.15
column 285 in row 133 = 1.0.

colindex = [282, 282, 285]
    rowindex = [134, 136, 133]
    value = [0.1, 0.15, 1]
    p.adddfs (colindex, rowindex, value)
```

#### **Further information**

The distribution factor of a column in a row is the matrix coefficient of the corresponding delta vector in the row. Distribution factors are used in conventional recursion models, and are essentially normalized first-order derivatives. Xpress SLP can accept distribution factors instead of initial values, provided that the values of the variables involved can all be calculated after optimization using determining rows, or by a callback.

The problem.adddfs functions load additional items into the SLP problem. The corresponding problem.loaddfs functions delete any existing items first.

```
problem.chgdf,problem.getdf,problem.loaddfs
```

# problem.addIndicator

#### **Purpose**

Adds one or more indicator constraints to the problem.

#### **Synopsis**

```
problem.addIndicator (c1, c2, ...)
```

#### **Argument**

c1, c2... Tuples containing an indicator constraints, or list/tuples/array of tuples containing a binary condition and a constraint.

# **Example**

```
x = xpress.var (vartype = xpress.binary)
y = xpress.var (lb = 10, ub = 20)
z = xpress.var ()
ind1 = (x==1, y+z <= 40)
p = xpress.problem ()
p.addVariable (x,y,z)
p.addIndicator (ind1)</pre>
```

#### **Further information**

All arguments can be single indicator constraints or lists, tuples, or NumPy arrays created as indicator constraints. An indicator constraint is a tuple of two elements, the first being a condition (i.e. a binary variable being 0 or 1) and the second being the constraint.

# problem.addmipsol

#### **Purpose**

Adds a new feasible, infeasible or partial MIP solution for the problem to the Optimizer.

## **Synopsis**

problem.addmipsol (mipsolval, mipsolcol, solname)

#### **Arguments**

mipsolval Array containing solution values.

mipsolcol Optional integer array containing the column indices for the solution values provided in

mipsolval. It is optional when the length of mipsolval is equal to COLS, in which case

it is assumed that mipsolval provides a complete solution vector.

solname An optional name to associate with the solution.

#### **Further information**

- 1. The function returns immediately after passing the solution to the Optimizer. The solution is placed in a pool until the Optimizer is able to analyze the solution during a MIP solve.
- 2. If the provided solution is found to be infeasible, a limited local search heuristic will be run in an attempt to find a close feasible integer solution.
- 3. If a partial solution is provided, global columns will be fixed to any provided values and a limited local search will be run in an attempt to find integer feasible values for the remaining unspecified columns. Values provided for continuous column in partial solutions are currently ignored.
- 4. The problem.addcbusersolnotify callback function can be used to discover the outcome of a loaded solution. The optional name provided as solname will be returned in the callback function.
- 5. If one or more solutions are loaded during the problem.addcboptnode callback, the Optimizer will process all loaded solutions and fire the callback again. This will be repeated as long as new solutions are loaded during the callback.

## **Related topics**

problem.addcbusersolnotify, problem.addcboptnode.

# problem.addqmatrix

#### **Purpose**

Adds a new quadratic matrix into a row defined by triplets.

#### **Synopsis**

```
problem.addqmatrix (irow, mqc1, mqc2, dqe)
```

## **Arguments**

irow Index of the row where the quadratic matrix is to be added.

mqc1 First index in the triplets.
mqc2 Second index in the triplets.
dqe Coefficients in the triplets.

#### **Further information**

- 1. The triplets should define the whole quadratic expression. This means that to add  $x^2$  + 4xy the dge arrays shall contain the coefficients 1 and 4.
- 2. The matrix defined by mqc1, mqc2 and dqe should be positive semi-definite for  $\leq$  and negative semi-definite for  $\geq$  rows.
- 3. The row must not be an equality or a ranged row.

```
problem.loadproblem.problem.getqrowcoeff,problem.chgqrowcoeff,problem.getqrowqmatrix,problem.getqrowqmatrixtriplets,problem.getqrows,problem.chgqobj,problem.chgqobj,problem.getqobj.
```

# problem.addrows

#### **Purpose**

Adds rows and their coefficient to the problem.

#### **Synopsis**

# **Arguments**

qrtype	Character array containing the row types:
	L indicates a $\leq$ row;
	G indicates $\geq$ row;
	E indicates an = row.
	R indicates a range constraint;
	N indicates a nonbinding constraint.
rhs	Array containing the right hand side elements.
mstart	Array containing the offsets in the mclind and dmatval arrays of the start of the elements for each row.
mclind	Array containing the (contiguous) column indices for the elements in each row.
dmatval	Array containing the (contiguous) element values.
range	(optional) Array containing the row range elements. Optional. The values in the range array will only be read for $\tt R$ type rows. The entries for other type rows will be ignored.
names	(optional) Array of names to be assigned to each new row.

#### **Example**

Suppose the current problem is:

```
maximize: 2x + y + 3z

subject to: x + 4y + 2z \le 24

y + z \le 5

3x + y \le 20

x + y + 3z \le 9
```

Then the following adds the row  $8x + 9y + 10z \le 25$  to the problem and names it NewRow:

#### **Further information**

Range rows are automatically converted to type L, with an upper bound in the slack. This must be taken into consideration, when retrieving row type, right-hand side values or range information for rows.

#### **Related topics**

problem.addcols,problem.addcuts.

# problem.addSOS

#### **Purpose**

Adds one or more Special Ordered Set (SOS) to the problem.

#### **Synopsis**

```
problem.addSOS (s1, s2, ...)
```

#### **Argument**

s1, s2... Special Ordered Sets defined prior to the call or (see example below) defined directly in the call.

#### **Example**

```
N = 20
x = [xpress.var () for i in range (N)]
p = xpress.problem ()
p.addVariable (x)
s = xpress.sos ([x], [i+2 for i in range (N)])
p.addSOS (s)
p.addSOS ([x[0], x[2]], [4,6])
```

#### **Further information**

All arguments can be single SOSs or lists, tuples, or NumPy arrays of SOSs created as xpress.sos objects. As for constraints, a SOS does not need to be declared prior to being added as an argument.

# problem.addtolsets

#### **Purpose**

Add sets of standard tolerance values to an SLP problem

#### **Synopsis**

```
problem.addtolsets (tol)
```

#### **Argument**

slptol Array of 9h elements containing the 9 tolerance values for each set in order.

#### **Example**

The following example creates two tolerance sets: the first has values of 0.005 for all tolerances; the second has values of 0.001 for relative tolerances (numbers 2,4,6,8), values of 0.01 for absolute tolerances (numbers 1,3,5,7) and zero for the closure tolerance (number 0).

tol = 
$$9*[0.005]+[0]+[0.01,0.001]*4$$
  
p.addtolsets (tol)

#### **Further information**

A tolerance set is an array of 9 values containing the following tolerances:

Entry / Bit	Tolerance	XSLP constant	XSLP bit constant
0	Closure tolerance (TC)	xslp_TOLSET_TC	xslp_TOLSETBIT_TC
1	Absolute delta tolerance (TA)	xslp_TOLSET_TA	xslp_TOLSETBIT_TA
2	Relative delta tolerance (RA)	xslp_TOLSET_RA	xslp_TOLSETBIT_RA
3	Absolute coefficient tolerance (TM)	xslp_TOLSET_TM	xslp_TOLSETBIT_TM
4	Relative coefficient tolerance (RM)	xslp_TOLSET_RM	xslp_TOLSETBIT_RM
5	Absolute impact tolerance (TI)	xslp_TOLSET_TI	xslp_TOLSETBIT_TI
6	Relative impact tolerance (RI)	xslp_TOLSET_RI	xslp_TOLSETBIT_RI
7	Absolute slack tolerance (TS)	xslp_TOLSET_TS	xslp_TOLSETBIT_TS
8	Relative slack tolerance (RS)	xslp_TOLSET_RS	xslp_TOLSETBIT_RS

The xslp\_TOLSET constants can be used to access the corresponding entry in the value arrays, while the xslp\_TOLSETBIT constants are used to set or retrieve which tolerance values are used for a given SLP variable. Once created, a tolerance set can be used to set the tolerances for any SLP variable. If a tolerance value is zero, then the default tolerance will be used instead. To force the use of a zero tolerance, use the problem.chgtolset function and set the Status variable appropriately. See the section "Convergence criteria" of the SLP Reference Manual for a fuller description of tolerances and their uses. The problem.addtolsets functions load additional items into the SLP problem. The corresponding problem.loadtolsets functions delete any existing items first.

#### **Related topics**

problem.chgtolset,problem.deltolsets,problem.gettolset,problem.loadtolsets

# problem.addVariable

## **Purpose**

Adds one or more variables to the problem.

#### **Synopsis**

```
problem.addVariable (v1, v2, ...)
```

## **Argument**

v1, v2... Variables or list/tuples/array of variables created with the xpress.var() call.

# **Example**

```
x = xpress.var (vartype = xpress.binary)
Y = [xpress.var () for i in range (20)]
p = xpress.problem ()
p.addVariable (x, Y)
```

#### **Further information**

All arguments can be single variables or lists, tuples, or NumPy arrays of variables created as xpress.var objects.

# problem.addvars

#### **Purpose**

Add SLP variables defined as matrix columns to an SLP problem

#### **Synopsis**

#### **Arguments**

colindex Integer array holding the index of the matrix column corresponding to each SLP variable.

vartype Bitmap giving information about the SLP variable as follows:

Bit 1 Variable has a delta vector;
Bit 2 Variable has an initial value;
Bit 14 Variable is the reserved "=" column;

May be None if not required.

detrow Integer array holding the index of the determining row for each SLP variable (a negative

value means there is no determining row)

May be None if not required.

segnum Integer array holding the index sequence number for cascading for each SLP variable (a

zero value means there is no pre-defined order for this variable)

May be None if not required.

tolindex Integer array holding the index of the tolerance set for each SLP variable (a zero value

means the default tolerances are used)

May be None if not required.

initvalue Double array holding the initial value for each SLP variable (use the VarType bit map to

indicate if a value is being provided)

May be None if not required.

stepbound Double array holding the initial step bound size for each SLP variable (a zero value

means that no initial step bound size has been specified). If a value of

xpress.infinity is used for a value in stepbound, the delta will never have step

bounds applied, and will almost always be regarded as converged.

May be None if not required.

#### Example

The following example loads two SLP variables into the problem. They correspond to columns 23 and 25 of the underlying LP problem. Column 25 has an initial value of 1.42; column 23 has no specific initial value

```
colindex = [23,25]
vartype = [0,2]
initvalue = [0,1.42]
```

```
p.addvars (colindex, vartype, None, None, None, initvalue, None)
```

initvalue is not set for the first variable, because it is not used (vartype = 0). Bit 1 of vartype is set for the second variable to indicate that the initial value has been set. The arrays for determining rows, sequence numbers, tolerance sets and step bounds are not used at all, and so have been passed to the function as None.

## **Further information**

The addvars functions load additional items into the SLP problem. The corresponding loadvars functions delete any existing items first.

#### **Related topics**

problem.chgvar,problem.delvars,problem.getvar,problem.loadvars

# problem.basisstability

#### **Purpose**

Returns various measures for the stability of the current basis, including the basis condition number.

#### **Synopsis**

```
x = problem.basisstability (type, norm, ifscaled)
```

#### **Arguments**

type	0 Condition number of the basis.
	1 Stability measure for the solution relative to the current basis.
	2 Stability measure for the duals relative to the current basis.
	3 Stability measure for the right hand side relative to the current basis.
	4 Stability measure for the basic part of the objective relative to the current basis.
norm	0 Use the infinity norm.
	1 Use the 1 norm.
	2 Use the Euclidian norm for vectors and the Frobenius norm for matrices.
ifscaled	If the stability values are to be calculated in the scaled or the unscaled matrix.

#### **Further information**

- 1. The condition number (type = 0) of an invertible matrix is the norm of the matrix multiplied with the norm of its inverse. This number is an indication of how accurate the solution can be calculated and how sensitive it is to small changes in the data. The larger the condition number is, the less accurate the solution is likely to become.
- 2. The stability measures (type = 1...4) are using the original matrix and the basis to recalculate the various vectors related to the solution and the duals. The returned stability measure is the norm of the difference of the recalculated vector to the original one.

# problem.btran

#### **Purpose**

Post-multiplies a (row) vector provided by the user by the inverse of the current basis.

#### **Synopsis**

```
problem.btran (vec)
```

#### **Argument**

vec

Array of length problem.attributes.rows containing the values by which the basis inverse is to be multiplied. The transformed values will also be returned in this array.

## **Example**

Get the (unscaled) tableau row  ${\tt z}$  of constraint number  ${\tt irow}$ , assuming that all arrays have been dimensioned.

```
y = [0,1,0,0]
p.btran (y)
print ("btran result:", y)
```

#### **Further information**

If the problem is in a presolved state, btran works with the basis for the presolved problem.

```
problem.ftran.
```

# problem.calcobjective

#### **Purpose**

Returns the objective value of a given solution.

## **Synopsis**

```
objval = problem.calcobjective (solution)
```

# **Argument**

solution Array of length problem.attributes.cols that holds the solution.

#### **Further information**

The calculations are always carried out in the original problem, even if the problem is currently presolved.

# **Related topics**

 $\verb|problem.calcs| a cks, \verb|problem.calcreducedcosts|.$ 

# problem.calcreducedcosts

#### **Purpose**

Returns the reduced cost values for a given (row) dual solution.

#### **Synopsis**

```
problem.calcreducedcosts (duals, solution, calculateddjs)
```

## **Arguments**

duals Array of length problem.attributes.rows that holds the dual solution to calculate

the reduced costs for.

solution Optional array of length problem.attributes.cols that holds the primal solution.

This is necessary for quadratic problems.

calculateddjs Array of length problem.attributes.cols in which the calculated reduced costs are returned.

## **Example**

```
p = xpress.problem ()
p.read ("silly_walks.lp") # assume problem has 4 constraints
dj = []
p.calcreducedcosts ([0,1,1,1], None, dj)
print ("red. cost:", dj)
```

#### **Further information**

- 1. The calculations are always carried out in the original problem, even if the problem is currently presolved.
- 2. If using the function during a solve (e.g. from a callback), use ORIGINALCOLS and ORIGINALROWS to retrieve the non-presolved dimensions of the problem.

#### **Related topics**

problem.calcslacks, problem.calcobjective.

# problem.calcslacks

#### **Purpose**

Calculates the row slack values for a given solution.

#### **Synopsis**

problem.calcslacks (solution, calculatedslacks)

## **Arguments**

solution Array of length problem.attributes.cols that holds the solution to calculate the slacks for.

calculatedslacks Array of length problem.attributes.rows in which the calculated row slacks are returned.

#### **Further information**

- 1. The calculations are always carried out in the original problem, even if the problem is currently presolved.
- 2. If using the function during a solve (e.g. from a callback), use ORIGINALCOLS and ORIGINALROWS to retrieve the non-presolved dimensions of the problem.

# **Related topics**

problem.calcreducedcosts, problem.calcobjective.

# problem.calcsolinfo

#### **Purpose**

Returns the required property of a solution, like maximum infeasibility of a given primal and dual solution.

#### **Synopsis**

```
val = problem.calcsolinfo (solution, dual, property)
```

#### **Arguments**

Array of length problem.attributes.cols that holds the solution.

Array of length problem.attributes.rows that holds the dual solution.

property xpress.solinfo\_absprimalinfeas absolute primal infeasibility.

xpress.solinfo\_relprimalinfeas relative primal infeasibility.

xpress.solinfo\_absdualinfeas absolute dual infeasibility.

xpress.solinfo\_reldualinfeas relative dual infeasibility.

xpress.solinfo\_maxmipfractional absolute MIP infeasibility (fractionality).

#### **Further information**

The calculations are always carried out in the original problem, even if the problem is currently presolved.

#### **Related topics**

problem.calcslacks, problem.calcobjective, problem.calcreducedcosts.

# problem.cascade

#### **Purpose**

Re-calculate consistent values for SLP variables. based on the current values of the remaining variables

#### **Synopsis**

```
problem.cascade ()
```

#### **Example**

The following example changes the solution value for column 91, and then re-calculates the values of those dependent on it.

```
colnum = 91
(a,b,c,d,e,f,value,h,i,j,k,l,m,n,o) = p.getvar (colnum)
value += 1.42
p.chgvar (colnum, None, None, None, None, None, None, None, None)
p.cascade ()
```

problem.getvar and problem.chgvar are being used to get and change the current value of a single variable. Provided no other values have been changed since the last execution of cascade, values will be changed only for variables which depend on column 91.

#### **Further information**

See the section on cascading for an extended discussion of the types of cascading which can be performed.

cascade is called automatically during the SLP iteration process and so it is not normally necessary to perform an explicit cascade calculation.

The variables are re-calculated in accordance with the order generated by <a href="mailto:problem.cascadeorder">problem.cascadeorder</a>.

#### Related topics

problem.cascadeorder

# problem.cascadeorder

#### **Purpose**

Establish a re-calculation sequence for SLP variables with determining rows.

#### **Synopsis**

```
problem.cascadeorder ()
```

## **Example**

Assuming that all variables are SLP variables, the following example sets default values for the variables, creates the re-calculation order and then calls problem.cascade to calculate consistent values for the dependent variables.

#### **Further information**

cascadeorder is called automatically at the start of the SLP iteration process and so it is not normally necessary to perform an explicit cascade ordering.

#### **Related topics**

problem.cascade

# problem.chgbounds

#### **Purpose**

Changes the bounds on columns in the problem.

#### **Synopsis**

```
problem.chgbounds (mindex, qbtype, bnd)
```

#### **Arguments**

mindex Array containing the indices of the columns on which the bounds will change.

gbtype Character array indicating the type of bound to change:

U indicates a change in the upper bound;L indicates a change in the lower bound;

B indicates a change in both bounds, i.e. the column is fixed.

bnd Array giving the new bound values.

# **Example**

The following changes the lower bound of variable v1 to 2, upper bound of variable v2 to 5, and fixes variable v3 to 3:

```
p.chgbounds ([v1, v2, v3], ['L', 'U', 'B'], [2, 5, 3])
```

#### **Further information**

- 1. A column may appear twice in the mindex array so it is possible to change both the upper and lower bounds on a variable in one go.
- 2. chgbounds may be applied to the problem in a presolved state, in which case it expects references to the presolved problem.
- 3. The double constant xpress.infinity can be used to represent plus and minus infinity in the bound (bnd) array.
- 4. If the upper bound on a binary variable is changed to be greater than 1 or the lower bound is changed to be less than 0 then the variable will become an integer variable.

## **Related topics**

problem.getlb, problem.getub.

# problem.chgcoef

#### **Purpose**

Changes a single coefficient in the problem. If the coefficient does not already exist, a new coefficient will be added to the problem. If many coefficients are being added to a row of the problem, it may be more efficient to delete the old row and add a new row.

#### **Synopsis**

```
problem.chgcoef (irow, icol, dval)
```

#### **Arguments**

irow Row index for the coefficient.

icol Column index for the coefficient.

dval New value for the coefficient. If dval is zero, any existing coefficient will be deleted.

#### **Example**

In the following, the constraint is introduced in the problem and then its linear coefficient for  ${\bf x}$  is changed to 3:

```
p = xpress.problem ()
x = xpress.var ()
c = x + x**2 <= 3
p.addVariable (x)
p.addConstraint (c)
p.chgcoef (c,x,3)</pre>
```

#### **Further information**

problem.chgmcoef is more efficient than multiple calls to chgcoef and should be used in its place in such circumstances.

```
problem.addcols,problem.addrows,problem.chgmcoef,problem.chgmqobj,problem.chgobj,problem.chgqobj,problem.chgrhs,problem.getcols,problem.getrows.
```

# problem.chgcoltype

#### **Purpose**

Changes the type of a column in the problem.

#### **Synopsis**

```
problem.chgcoltype (mindex, qctype)
```

#### **Arguments**

mindex Array containing the indices of the columns. Character array giving the new column types: qctype

- С indicates a continuous column;
- В indicates a binary column;
- indicates an integer column. Ι
- indicates a semi-continuous column. The semi-continuous lower bound will S be set to 1.0.
- indicates a semi-integer column. The semi-integer lower bound will be set to R
- Ρ indicates a partial integer column. The partial integer bound will be set to 1.0.

#### **Example**

The following changes the type of variable x from binary to integer:

```
p = xpress.problem ()
x = xpress.var (vartype = xp.binary)
p.addVariable (x)
p.chgcoltype ([x],['I'])
```

#### **Further information**

- 1. The column types can only be changed before the global search is started.
- 2. Calling chgcoltype to change any variable into a binary variable causes the bounds previously defined for the variable to be deleted and replaced by bounds of 0 and 1.
- 3. Calling chgcoltype to change a continuous variable into an integer variable cause its lower bound to be rounded up to the nearest integer value and its upper bound to be rounded down to the nearest integer value.

#### **Related topics**

problem.addcols, problem.chgrowtype, problem.getcoltype.

# problem.chgcascadenlimit

#### **Purpose**

Set a variable specific cascade iteration limit

#### **Synopsis**

problem.chgcascadenlimit (icol, cascadenlimit)

#### **Arguments**

icol The index of the column corresponding to the SLP variable for which the cascading limit is to be imposed.

cascadenlimit The new cascading iteration limit.

#### **Further information**

A value set by this function will overwrite the value of the control  $xslp\_cascadenlimit$  for this variable. To remove any previous value set by this function, use an iteration limit of 0.

#### **Related topics**

problem.cascadeorder

# problem.chgccoef

#### **Purpose**

Add or change a single matrix coefficient using a character string for the formula

#### **Synopsis**

```
problem.chgccoef (rowindex, colindex, factor, formula)
```

#### **Arguments**

rowindex The index of the matrix row for the coefficient.

Colindex The index of the matrix column for the coefficient.

factor Constant multiplier for the formula. If factor is None, a value of 1.0 will be used.

Formula Character string holding the formula, with the tokens separated by spaces.

#### **Example**

Assuming that the columns of the matrix are named Coll, Col2, etc, the following example puts the formula 2.5\*sin(Coll) into the coefficient in row 1, column 3.

```
Formula = "sin ( Col1 ) "
Factor = 2.5
p.chgccoef (1, 3, Factor, Formula)
```

Note that all the tokens in the formula (including mathematical operators and separators) are separated by one or more spaces.

#### **Further information**

If the coefficient already exists as a constant or formula, it will be changed into the new coefficient. If it does not exist, it will be added to the problem.

A coefficient is made up of two parts: Factor and Formula. Factor is a constant multiplier which can be provided in the Factor variable. If Xpress Nonlinear can identify a constant factor in the Formula, then it will use that as well, to minimize the size of the formula which has to be calculated.

This function can only be used if all the operands in the formula can be correctly identified as constants, existing columns, character variables or functions. Therefore, if a formula refers to a new column, that new item must be added to the Xpress Nonlinear problem first.

#### **Related topics**

 $\verb|problem.addcoefs,problem.delcoefs,problem.chgnlcoef,problem.getcoefformula,problem.loadcoefs|$ 

# problem.chgdeltatype

#### **Purpose**

Changes the type of the delta assigned to a nonlinear variable

# **Synopsis**

```
problem.chgdeltatype (vars, deltatypes, values)
```

#### **Arguments**

Vars Indices of the variables to change the deltas for.

DeltaTypes Type if the delta variable:

O Differentiable variable, default.

1 Variable defined over the grid size given in values.

Variable where a minimum perturbation size given in values may be required before a significant change in the problem is achieved.

3 Variable where a meaningful step size should automatically be detected,

with an upper limit given in values.

Values Grid or minimum step sizes for the variables.

#### **Further information**

Changing the delta type of a variables makes the variable nonlinear.

# problem.chgdf

#### **Purpose**

Set or change a distribution factor

#### **Synopsis**

```
problem.chgdf (colindex, rowindex, value)
```

## **Arguments**

colindex The index of the column whose distribution factor is to be set or changed.

rowindex The index of the row where the distribution applies.

value Address of a double precision variable holding the new value of the distribution factor.

May be None if not required.

# **Example**

The following example retrieves the value of the distribution factor for column 282 in row 134 and changes it to be twice as large.

```
value = p.getdf (282,134)
value *= 2
p.chgdf (282,134,value)
```

#### **Further information**

The distribution factor of a column in a row is the matrix coefficient of the corresponding delta vector in the row. Distribution factors are used in conventional recursion models, and are essentially normalized first-order derivatives. Xpress Nonlinear can accept distribution factors instead of initial values, provided that the values of the variables involved can all be calculated after optimization using determining rows, or by a callback.

#### **Related topics**

problem.adddfs,problem.getdf,problem.loaddfs

# problem.chgglblimit

#### **Purpose**

Changes semi-continuous or semi-integer lower bounds, or upper limits on partial integers.

## **Synopsis**

```
problem.chgglblimit (mindex, dlimit)
```

## **Arguments**

mindex Array containing the indices of the semi-continuous, semi-integer or partial integer

columns that should have their limits changed.

dlimit Array giving the new limit values.

## **Further information**

1. The new limits are not allowed to be negative.

2. Partial integer limits can be at most 2<sup>28</sup>.

# **Related topics**

problem.chgcoltype,problem.getglobal.

# problem.chgmcoef

#### **Purpose**

Change multiple coefficients in the problem. The coefficients that do not exist yet will be added to the problem. If many coefficients are being added to a row of the matrix, it may be more efficient to delete the old row of the matrix and add a new one.

#### **Synopsis**

```
problem.chgmcoef (mrow, mcol, dval)
```

#### **Arguments**

mrow Array containing the row indices of the coefficients to be changed.

mcol Array containing the column indices of the coefficients to be changed.

dval Array containing the new coefficient values. If an element of dval is zero, the coefficient will be deleted.

# **Example**

```
con1 = x + y + z <= 2
con2 = x + y >= 1
con3 = x + 3*y = 1
p.addVariable (x,y,z)
p.addConstraint (con1, con2, con3)
p.chgmcoef ([con1,con1,con1,con2,con3], [x,y,z,x,x], [-2, -3, -3.2, 1, 3])
```

This changes five coefficients, three of which in the first constraint and one in each of the second and third constraints.

#### **Further information**

chgmcoef is more efficient than repeated calls to problem.chgcoef and should be used in its place if many coefficients are to be changed.

```
problem.chgcoef,problem.chgmqobj,problem.chgobj,problem.chgrobj,problem.chgrhs,problem.getcols,problem.getrhs.
```

# problem.chgmqobj

#### **Purpose**

Change multiple quadratic coefficients in the objective function. If any of the coefficients does not exist already, new coefficients will be added to the objective function.

#### **Synopsis**

```
problem.chgmqobj (mqcol1, mqcol2, dval)
```

#### **Arguments**

mqcoll Array containing the column index of the first variable in each quadratic term.

mqcoll Array containing the column index of the second variable in each quadratic term.

New values for the coefficients. If an entry in dval is 0, the corresponding entry will be deleted. These are the coefficients of the lower triangular part of the Hessian of the objective function.

## **Example**

The following code results in an objective function with terms:  $[4x_1^2 + 6x_1x_2]$ 

```
p.chgmqobj ([x1,x1], [x1,x2], [4,3])
```

#### **Further information**

- 1. The columns in the arrays mqcol1 and mqcol2 must already exist in the matrix. If the columns do not exist, they must be added.
- 2. chgmqobj is more efficient than repeated calls to problem.chgqobj and should be used in its place when several coefficients are to be changed.

```
problem.chgcoef, problem.chgmcoef, problem.chgobj, problem.chgqobj,
problem.getqobj.
```

# problem.chgnlcoef

#### **Purpose**

Add or change a single matrix coefficient using a parsed or unparsed formula

Array of values corresponding to the types in type.

#### **Synopsis**

```
problem.chgnlcoef (rowindex, colindex, factor, parsed, type, value)
```

#### **Arguments**

rowindex The index of the matrix row for the coefficient.

The index of the matrix column for the coefficient.

Address of a double precision variable holding the constant multiplier for the formula. If Factor is None, a value of 1.0 will be used.

parsed Integer indicating the whether the token arrays are formatted as internal unparsed (parsed=False) or internal parsed reverse Polish (parsed=True).

type Array of token types providing the description and formula for each item.

#### **Example**

value

Assuming that the columns of the matrix are named Coll, Col2, etc, the following example puts the formula 2.5\*sin (Coll) into the coefficient in row 1, column 3.

```
type = [xp.xslp_op_ifun, xp.xslp_op_var, xp.xslp_op_rb, xp.xslp_op_eof]
value = [xp.xslp_ifun_sin, 1, 0, 0]

Factor = 2.5
p.chgnlcoef (1, 3, Factor, 0, type, value)
```

problem.getIndex is used to retrieve the index for the internal function sin. The "nocase" version
matches the function name regardless of the (upper or lower) case of the name. Tokens of type
xpress.xslp\_op\_var always count from 1, so Coll is 1. The formula is written in unparsed form
(parsed = 0) and so it is provided as tokens in the same order as they would appear if the formula
were written in character form.

#### **Further information**

If the coefficient already exists as a constant or formula, it will be changed into the new coefficient. If it does not exist, it will be added to the problem.

A coefficient is made up of two parts: Factor and Formula. Factor is a constant multiplier which can be provided in the factor variable. If Xpress Nonlinear can identify a constant factor in the Formula, then it will use that as well, to minimize the size of the formula which has to be calculated.

```
problem.addcoefs,problem.chgccoef,problem.delcoefs,problem.getcoefformula,
problem.loadcoefs
```

# problem.chgobj

#### **Purpose**

Change the objective function coefficients.

#### **Synopsis**

```
problem.chgobj (mindex, obj)
```

#### **Arguments**

mindex Arraycontaining the indices of the columns on which the range elements will change. An

index of -1 indicates that the fixed part of the objective function on the right hand side

should change.

obj Array giving the new objective function coefficient.

## **Example**

Changing three coefficients of the objective function with chgobj:

```
p.chgobj ([x1, x2, x3, -1], [3.5, -2, 0, 224])
```

#### **Further information**

The value of the fixed part of the objective function can be obtained using the <code>OBJRHS</code> problem attribute.

```
problem.chgcoef,problem.chgmcoef,problem.chgmqobj,problem.chgqobj,
problem.getobj.
```

# problem.chgobjsense

#### **Purpose**

Changes the problem's objective function sense to minimize or maximize.

#### **Synopsis**

```
problem.chgobjsense (sense)
```

#### **Argument**

objsense xpress.minimize or xpress.maximize to change into a minimization or maximization problem, respectively.

## **Example**

Changing three coefficients of the objective function with chgobj:

```
p.chgobjsense (xpress.maximize) # optimize in this general direction
```

# **Related topics**

problem.lpoptimize, problem.mipoptimize.

# problem.chgqobj

#### **Purpose**

Change a single quadratic coefficient in the objective function corresponding to the variable pair (icol, jcol) of the Hessian matrix.

#### **Synopsis**

```
problem.chgqobj (icol, jcol, dval)
```

#### **Arguments**

icol Column index for the first variable in the quadratic term.
 jcol Column index for the second variable in the quadratic term.
 dval New value for the coefficient in the quadratic Hessian matrix. If an entry in dval is 0, the corresponding entry will be deleted.

#### **Example**

The following code adds the terms  $[6x_1^2 + 3x_1x_2 + 3x_2x_1]/2$  to the objective function:

```
p.chgqobj (x1, x1, 6)
p.chgqobj (x1, x2, 3)
```

#### **Further information**

- 1. The columns icol and jcol must already exist in the matrix..
- 2. If icol is not equal to jcol, then both the matrix elements (icol, jcol) and (jcol, icol) are changed to leave the Hessian symmetric.

### **Related topics**

```
problem.chgcoef,problem.chgmcoef,problem.chgmdobj,problem.chgobj,
problem.getqobj.
```

# problem.chgqrowcoeff

#### **Purpose**

Changes a single quadratic coefficient in a row.

### **Synopsis**

```
problem.chgqrowcoeff (irow, icol, jcol, dval)
```

#### **Arguments**

irow Index of the row where the quadratic matrix is to be changed.
icol First index of the coefficient to be changed.
jcol Second index of the coefficient to be changed.
dval The new coefficient.

#### **Further information**

- 1. This function may be used to add new nonzero coefficients, or even to define the whole quadratic expression with it. Doing that, however, is significantly less efficient than adding the whole expression with problem.addqmatrix.
- 2. The row must not be an equality or a ranged row.

### **Related topics**

```
problem.loadproblem.getqrowcoeff,problem.addqmatrix,problem.chgqrowcoeff,problem.getqrowqmatrix,problem.getqrowqmatrixtriplets,problem.getqrows,problem.chgqobj,problem.chgmqobj,problem.getqobj.
```

# problem.chgrhs

### **Purpose**

Changes right-hand side values of the problem.

### **Synopsis**

```
problem.chgrhs (mindex, rhs)
```

#### **Arguments**

mindex Array containing the indices of the rows whose right hand side will change.

rhs Array containing the right hand side values.

# **Example**

Here we change the three right hand sides in rows 2, 6, and 8 to new values:

```
p.chgrhs ([2,8,6], [5, 3.8, 5.7])
```

# **Related topics**

problem.chgcoef,problem.chgmcoef,problem.chgrhsrange,problem.getrhs, problem.getrhsrange.

# problem.chgrhsrange

#### **Purpose**

Change the range for one or more rows of the problem.

# **Synopsis**

```
problem.chgrhsrange (mindex, rng)
```

#### **Arguments**

mindex Array containing the indices of the rows on which the range elements will change.

Array containing the range values.

### **Example**

Here, the constraint cons1 x + y  $\leq$  10 is changed to 8  $\leq$  x + y  $\leq$  10:

#### **Further information**

If the range specified on the row is *r*, what happens depends on the row type and value of *r*. It is possible to convert non-range rows using this routine.

Value of r	Row type	Effect
$r \geq 0$	= $b$ , $\leq b$	$b-r\leq\sum a_jx_j\leq b$
$r \geq 0$	$\geq b$	$b \leq \sum a_j x_j \leq b + r$
<i>r</i> < 0	= $b$ , $\leq b$	$b \leq \sum a_j x_j \leq b - r$
r < 0	$\geq b$	$b+r \leq \sum a_j x_j \leq b$

### **Related topics**

problem.chgcoef, problem.chgmcoef, problem.chgrhs, problem.getrhsrange.

# problem.chgrowstatus

#### **Purpose**

Change the status setting of a constraint

### **Synopsis**

```
problem.chgrowstatus (rowindex, status)
```

### **Arguments**

rowindex The index of the matrix row to be changed.

status The bitmap with the new status settings. If the status is to be changed, always get the

current status first (use problem.getrowstatus) and then change settings as

required. The only settings likely to be changed are:

 ${\tt Bit\ 11}$   ${\tt\ Set\ if\ row\ must\ not\ have\ a\ penalty\ error\ vector.\ This\ is\ the\ equivalent\ of\ an}$ 

enforced constraint (SLPDATA type EC).

#### **Example**

The following example changes the status of row 9 to be an enforced constraint.

```
status = p.getrowstatus (9)
status = status | (1<<11)
p.chgrowstatus (9, status)</pre>
```

#### **Further information**

If status is None the current status will remain unchanged.

### **Related topics**

problem.getrowstatus

# problem.chgrowtype

#### **Purpose**

Changes the type of a row in the problem.

# **Synopsis**

```
problem.chgrowtype (mindex, qrtype)
```

#### **Arguments**

mindex Array containing the indices of the rows.

qrtype Character array giving the new row types:

L indicates  $a \le row$ ; E indicates an = row; G indicates  $a \ge row$ ; R indicates a range row; N indicates a free row.

# **Example**

Here two rows are changed to an equality and a free row, respectively:

```
p.chgrowtype ([con1, con2], ['E', 'N'])
```

#### **Further information**

A row can be changed to a range type row by first changing the row to an R or L type row and then changing the range on the row using problem.chgrhsrange.

### **Related topics**

 $\verb|problem.addrows,problem.chgcoltype,problem.chgrhs,problem.chgrhsrange,problem.getrowtype.\\$ 

# problem.chgrowwt

#### **Purpose**

Set or change the initial penalty error weight for a row

### **Synopsis**

```
problem.chgrowwt (rowindex, value)
```

### **Arguments**

RowIndex The index of the row whose weight is to be set or changed.

Value The new value of the weight. May be None if not required.

# Example

The following example sets the initial weight of row number 2 to a fixed value of 3.6 and the initial weight of row 4 to a value twice the calculated default value.

```
p.chgrowwt (2, -3.6)
p.chgrowwt (4,2)
```

#### **Further information**

A positive value is interpreted as a multiplier of the default row weight calculated by Xpress SLP.

A negative value is interpreted as a fixed value: the absolute value is used directly as the row weight.

The initial row weight is used only when the augmented structure is created. After that, the current weighting can be accessed and changed using problem.getrowinfo.

#### **Related topics**

problem.getrowwt,problem.getrowinfo

# problem.chgtolset

#### **Purpose**

Add or change a set of convergence tolerances used for SLP variables

# **Synopsis**

```
problem.chgtolset (ntol, status, tols)
```

#### **Arguments**

ntol	Tolerance set for which values are to be changed. A zero value for nSLPTo1 will create a new set.
status	Address of an integer holding a bitmap describing which tolerances are active in this set. See below for the settings.
tols	Array of 9 double precision values holding the values for the corresponding tolerances.

### **Example**

The following example creates a new tolerance set with the default values for all tolerances except the relative delta tolerance, which is set to 0.005. It then changes the value of the absolute delta and absolute impact tolerances in tolerance set 6 to 0.015

```
Tols = 9*[0]

Tols[2] = 0.005

Status = 1<<2

p.chgtolset (0, 1<<2, Tols)

Tols[1] = 0.015

Tols[5] = 0.015

Status = 1<<1 | 1<<5

p.chgtolset (6, Status, Tols)
```

### **Further information**

The bits in status are set to indicate that the corresponding tolerance is to be changed in the tolerance set. The meaning of the bits is as follows:

Entry / Bit	Tolerance	XSLP constant	XSLP bit constant
0	Closure tolerance (TC)	xslp_TOLSET_TC	xslp_TOLSETBIT_TC
1	Absolute delta tolerance (TA)	xslp_TOLSET_TA	xslp_TOLSETBIT_TA
2	Relative delta tolerance (RA)	xslp_TOLSET_RA	xslp_TOLSETBIT_RA
3	Absolute coefficient tolerance (TM)	xslp_TOLSET_TM	xslp_TOLSETBIT_TM
4	Relative coefficient tolerance (RM)	xslp_TOLSET_RM	xslp_TOLSETBIT_RM
5	Absolute impact tolerance (TI)	xslp_TOLSET_TI	xslp_TOLSETBIT_TI
6	Relative impact tolerance (RI)	xslp_TOLSET_RI	xslp_TOLSETBIT_RI
7	Absolute slack tolerance (TS)	xslp_TOLSET_TS	xslp_TOLSETBIT_TS
8	Relative slack tolerance (RS)	xslp_TOLSET_RS	xslp_TOLSETBIT_RS

The xslp\_TOLSET constants can be used to access the corresponding entry in the value arrays, while the xslp\_TOLSETBIT constants are used to set or retrieve which tolerance values are used for a given SLP variable. The members of the Tols array corresponding to nonzero bit settings in Status will be used to change the tolerance set. So, for example, if bit 3 is set in Status, then Tols[3] will replace the current value of the absolute coefficient tolerance. If a bit is not set in Status, the value of the corresponding element of Tols is unimportant.

#### Related topics

problem.addtolsets, problem.deltolsets, problem.gettolset, problem.loadtolsets

# problem.chgvar

#### **Purpose**

Define a column as an SLP variable or change the characteristics and values of an existing SLP variable

# **Synopsis**

### **Arguments**

colindex	The index of the matrix column.		
detrow	Address of an integer holding the index of the determining row. Use -1 if there is no determining row. May be None if not required.		
initstepbou	and Address of a double precision variable holding the initial step bound size. May be None if not required.		
stepbound	Address of a double precision variable holding the current step bound size. Use zero to disable the step bounds. May be None if not required.		
penalty	Address of a double precision variable holding the weighting of the penalty cost for exceeding the step bounds. May be None if not required.		
damp	Address of a double precision variable holding the damping factor for the variable. May be None if not required.		
initvalue	Address of a double precision variable holding the initial value for the variable. May be None if not required.		
value	Address of a double precision variable holding the current value for the variable. May be None if not required.		
tolset	Address of an integer holding the index of the tolerance set for this variable. Use zero if there is no specific tolerance set. May be None if not required.		
history	Address of an integer holding the history value for this variable. May be None if not required.		
converged	Address of an integer holding the convergence status for this variable. May be None if not required.		
vartype	Address of an integer holding a bitmap defining the existence of certain properties for this variable:  Bit 1: Variable has a delta vector		
	Bit 2: Variable has an initial value Bit 14: Variable is the reserved "=" column		

#### **Example**

The following example sets an initial value of 1.42 and tolerance set 2 for column 25 in the matrix.

May be None if not required.

Note that bits 1 and 2 of vartype are set, indicating that the variable has a delta vector and an initial value. For columns already defined as SLP variables, use problem.getvar to obtain the current value of vartype because other bits may already have been set by the system.

#### **Further information**

If any of the arguments is None then the corresponding information for the variable will be left unaltered. If the information is new (i.e. the column was not previously defined as an SLP variable) then the default values will be used.

Changing Value, History or Converged is only effective during SLP iterations.

Changing initvalue and initstepbound is only effective before problem.construct. If a value of xpress.infinity is used in the value for stepbound or initstepbound, the delta will never have step bounds applied, and will almost always be regarded as converged.

# **Related topics**

problem.addvars,problem.delvars,problem.getvar,problem.loadvars

# problem.construct

#### **Purpose**

Create the full augmented SLP matrix and data structures, ready for optimization

### **Synopsis**

```
problem.construct ()
```

#### **Example**

The following example constructs the augmented matrix and then outputs the result in MPS format to a file called augment.mat

```
# creation and/or loading of data
# precedes this segment of code
p.construct ()
p.write ("augment","1")
```

The "I" flag causes output of the current linear problem (which is now the augmented structure and the current linearization) rather than the original nonlinear problem.

#### **Further information**

construct adds new rows and columns to the SLP matrix and calculates initial values for the non-linear coefficients. Which rows and columns are added will depend on the setting of xslp\_augmentation. Names for the new rows and columns are generated automatically, based on the existing names and the string control variables xslp\_xxxformat.

Once construct has been called, no new rows, columns or non-linear coefficients can be added to the problem. Any rows or columns which will be required must be added first. Non-linear coefficients must not be changed; constant matrix elements can generally be changed after construct, but not after problem.presolve if used.

construct is called automatically by the SLP optimization procedure, and so only needs to be called explicitly if changes need to be made between the augmentation and the optimization.

#### **Related topics**

problem.presolve

# problem.copy

#### **Purpose**

Obtains a copy of a problem.

#### **Synopsis**

```
p = problem.copy ()
```

### **Example**

```
p = xpress.problem () 
 x = [xpress.var () for _ in range (10)] 
 p.addVariable (x) 
 p.addConstraint (xpress.Sum (x) <= 10) 
 p2 = p.copy () # add a constraint that won't be in p 
 p2.addConstraint (xpress.Sum (x) >= 6) # x[0] is deleted from p2 
 p2.delVariable (x[0])
```

# **Further information**

The objects of the copied problem (variables, constraints, SOSs) are the same as the source problem, i.e., the one of which a copy was created. Therefore, any object that existed in the source problem can be addressed and used in the copy problem.

# **Related topics**

problem.copycallbacks.

# problem.copycallbacks

### **Purpose**

Copies callback functions defined for one problem to another.

# **Synopsis**

```
problem.copycallbacks (src)
```

#### **Argument**

src

The problem from which the callbacks are copied.

### **Example**

The following sets up a message callback function callback for problem prob1 and then copies this to the problem prob2.

```
prob1 = xp.problem ()
prob1.addcbmessage (callback, None, 0)
prob2 = xp.problem ()
prob2.copycallbacks (prob1)
```

### **Related topics**

problem.copycontrols.problem.copy.

# problem.copycontrols

### **Purpose**

Copies controls defined for one problem to another.

# **Synopsis**

```
problem.copycontrols (src)
```

#### **Argument**

src

The problem from which the controls are copied.

### **Example**

The following turns off presolve for problem prob1 and then copies this and other control values to the problem prob2:

```
prob1 = xpress.problem ()
prob2 = xpress.problem ()
prob1.controls.presolve = 0
prob2.copycontrols (prob1)
```

### **Related topics**

problem.copycallbacks.

# problem.delcoefs

# **Purpose**

Delete coefficients from the current problem

### **Synopsis**

```
problem.delcoefs (rowindex, colindex)
```

### **Arguments**

rowindex Row indices of the SLP coefficients to delete.

colindex Column indices of the SLP coefficients to delete.

# **Related topics**

 $\verb|problem.addcoefs,problem.chgnlcoef,problem.chgccoef,problem.getcoefformula,problem.getcoef,problem.loadcoefs|$ 

# problem.delConstraint

#### **Purpose**

Delete one or more constraints from the problem.

#### **Synopsis**

```
problem.delConstraint (c1, c2, ...)
```

#### **Example**

```
N = 20
x = [xpress.var () for i in range (N)]
p = xpress.problem ()
p.addVariable (x)
p.addConstraint (x[i] >= x[i+1] for i in range (N-1))
p.delConstraint (2) # deletes x[2] >= x[3]
```

#### **Further information**

- 1. All arguments can be single constraints or lists, tuples, or NumPy arrays of variables. They can also be constraint indices (from 0 to ROWS-1). The index of variables, constraints, and SOSs can be obtained with problem.getIndex.
- 2. Indicator constraints are indexed as constraints, hence they can also be deleted with this function.

# problem.delcpcuts

#### **Purpose**

During the branch and bound search, cuts are stored in the cut pool to be applied at descendant nodes. These cuts may be removed from a given node using problem.delcuts, but if this is to be applied in a large number of cases, it may be preferable to remove the cut completely from the cut pool. This is achieved using delcpcuts.

### **Synopsis**

problem.delcpcuts (itype, interp, cutind)

### **Arguments**

itype User defined cut type to match against.
interp Way in which the cut itype is interpreted:

-1 match all cut types;

1 treat cut types as numbers;

treat cut types as bit maps - delete if any bit matches any bit set in itype;

3 treat cut types as bit maps - delete if all bits match those set in itype.

cutind Array containing the cuts which are to be deleted.

#### **Related topics**

problem.addcuts, problem.delcuts, problem.loadcuts, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

# problem.delcuts

#### **Purpose**

Deletes cuts from the matrix at the current node. Cuts from the parent node which have been automatically restored may be deleted as well as cuts added to the current node using problem.addcuts or problem.loadcuts. The cuts to be deleted can be specified in a number of ways. If a cut is ruled out by any one of the criteria it will not be deleted.

#### **Synopsis**

problem.delcuts (ibasis, itype, interp, delta, cutind)

### **Arguments**

ibasis	Ensures the basis will be valid if set to 1. If set to 0, cuts with non-basic slacks may be deleted.
itype	User defined type of the cut to be deleted.
interp	Way in which the cut itype is interpreted:  -1 match all cut types;  1 treat cut types as numbers;  2 treat cut types as bit maps - delete if any bit matches any bit set in itype;  3 treat cut types as bit maps - delete if all bits match those set in itype.
delta	Only delete cuts with an absolute slack value greater than delta. To delete all the cuts, this argument should be set to -xpress.infinity.
cutind	Array containing the cuts which are to be deleted.

#### **Further information**

- 1. It is usually best to drop only those cuts with basic slacks, otherwise the basis will no longer be valid and it may take many iterations to recover an optimal basis. If the ibasis parameter is set to 1, this will ensure that cuts with non-basic slacks will not be deleted even if the other parameters specify that these cuts should be deleted. It is highly recommended that the ibasis parameter is always set to 1.
- 2. The cuts to be deleted can also be specified by the size of the slack variable for the cut. Only those cuts with a slack value greater than the delta parameter will be deleted.
- 3. A list of indices of the cuts to be deleted can also be provided. The list of active cuts at a node can be obtained with the problem.getcutlist command.

#### **Related topics**

problem.addcuts, problem.delcpcuts, problem.getcutlist, problem.loadcuts, Section
"Working with the cut manager" of the Xpress Optimizer reference manual.

# problem.delqmatrix

# **Purpose**

Deletes the quadratic part of a row or of the objective function.

# **Synopsis**

problem.delqmatrix (row)

# **Argument**

row

Index of row from which the quadratic part is to be deleted.

### **Further information**

If a row index of -1 is used, the function deletes the quadratic coefficients from the objective function.

#### Related topics

problem.addrows.

# problem.delSOS

#### **Purpose**

Delete one or more SOSs from the problem.

# **Synopsis**

```
problem.delSOS (s1, s2, ...)
```

### **Example**

```
N = 20
x = [xpress.var () for i in range (N)]
p = xpress.problem ()
p.addVariable (x)
s = xpress.sos (x, i+1 for i in range (N))
p.addSOS (s)
p.delSOS (s)
```

#### **Further information**

All arguments can be single SOSs or lists, tuples, or NumPy arrays of SOSs. They can also be constraint indices (from 0 to ROWS-1). The index of variables, constraints, and SOSs can be obtained with problem.getIndex.

# problem.deltolsets

# **Purpose**

Delete tolerance sets from the current problem

# **Synopsis**

problem.deltolsets (index)

# **Argument**

tolsetindex Indices of tolerance sets to delete.

# **Related topics**

problem.addtolsets,problem.chgtolset,problem.gettolset,problem.loadtolsets

# problem.delVariable

# **Purpose**

Delete one or more variables from the problem.

### **Synopsis**

```
problem.delVariable (x1, x2, ...)
```

#### **Example**

```
N = 20

x = [xpress.var () for i in range (N)]
p = xpress.problem ()
p.addVariable (x)
p.addConstraint (x[i] >= x[i+1] for i in range (N-1))

# deletes x[2], x[3], i.e., third and fourth variable
p.delVariable (x[2:4])
```

### **Further information**

All arguments can be single variables or lists, tuples, or NumPy arrays of variables. They can also be variable indices (from 0 to COLS-1). The index of variables, constraints, and SOSs can be obtained with problem.getIndex.

# problem.delvars

# **Purpose**

Convert SLP variables to normal columns. Variables must not appear in SLP structures

### **Synopsis**

problem.delvars (index)

### **Argument**

colindex Columns to be converted to linear ones.

### **Further information**

The SLP variables to be converted to linear, non SLP columns must not be in use by any other SLP structure (coefficients, initial value formulae, delayed columns). Use the appropriate deletion or change functions to remove them first.

### **Related topics**

problem.addvars,problem.chgvar,problem.getvar,problem.loadvars

# problem.dumpcontrols

# **Purpose**

Displays the list of controls and their current value for those controls that have been set to a non default value.

# **Synopsis**

problem.dumpcontrols ()

# **Related topics**

 ${\tt problem.setdefaults}$ 

# problem.estimaterowdualranges

#### **Purpose**

Performs a dual side range sensitivity analysis, i.e. calculates estimates for the possible ranges for dual values.

#### **Synopsis**

#### **Arguments**

```
rowIndices Row indices to analyze.

iterationLimit Effort limit expressed as simplex iterations per row.

minDualActivity Estimated lower bounds on the possible dual ranges.

maxDualActivity Estimated upper bounds on the possible dual ranges.
```

#### **Further information**

This function may provide better results for individual row dual ranges when called for a larger number of rows

# **Related topics**

problem.lpoptimize,problem.strongbranch

# problem.evaluatecoef

#### **Purpose**

Evaluate a coefficient using the current values of the variables

### **Synopsis**

```
value = problem.evaluatecoef (rowindex, colindex)
```

### **Arguments**

```
rowindex Integer index of the row.

colindex Integer index of the column.

value The result of the calculation.
```

#### **Example**

The following example sets the value of column 5 to 1.42 and then calculates the coefficient in row 2, column 3. If the coefficient depends on column 5, then a value of 1.42 will be used in the calculation.

### **Further information**

The values of the variables are obtained from the solution, or from the Value setting of an SLP variable (see problem.chgvar and problem.getvar).

# **Related topics**

problem.chgvar,problem.evaluateformulaproblem.getvar

# problem.evaluateformula

#### **Purpose**

Evaluate a formula using the current values of the variables

### **Synopsis**

```
result = problem.evaluateformula (parsed, type, value)
```

### **Arguments**

parsed integer indicating whether the formula of the item is in internal unparsed format

(Parsed=0) or parsed (reverse Polish) format (Parsed=1).

type Integer array of token types for the formula.
value Double array of values corresponding to Type.

result The result of the calculation.

#### **Example**

The following example calculates the value of column 3 divided by column 6.

```
type = [xp.xslp_op_var, xp.xslp_op_var, xp.xslp_op_op, xp.xslp_op_eof]
value = [3, 6, xp.xslp_ifun_divide, 0]

value = p.evaluateformula (1, type, value)
```

#### **Further information**

The formula in Type and Value must be terminated by an xslp\_op\_eof token.

The formula cannot include "complicated" functions, such as user functions which return more than one value.

#### **Related topics**

problem.evaluatecoef

# problem.filesol

### **Purpose**

Prints the last SLP iteration's solution to file

# **Synopsis**

problem.filesol (filename)

# **Argument**

filename Name of the file to write the solution into

### **Further information**

For SLP variables, the initial values are also printed.

# **Related topics**

problem.write

# problem.fixglobals

#### **Purpose**

Fixes all the global entities to the values of the last found MIP solution. This is useful for finding the reduced costs for the continuous variables after the global variables have been fixed to their optimal values.

### **Synopsis**

```
problem.fixglobals (ifround)
```

#### **Argument**

ifround

If all global entities should be rounded to the nearest discrete value in the solution before being fixed.

### **Example**

This example performs a global search on problem myprob and then uses fixglobals before solving the remaining linear problem:

```
p.read ("myprob", "")
p.mipoptimize ()
p.fixglobals (1)
p.lpoptimize ()
p.writeprtsol ()
```

#### **Further information**

- 1. Because of tolerances, it is possible for e.g. a binary variable to be slightly fractional in the MIP solution, where it might have the value 0.999999 instead of being at exactly 1.0. With ifround = 0, such a binary will be fixed at 0.999999, but with ifround = 1, it will be fixed at 1.0.
- 2. This command is useful for inspecting the reduced costs of the continuous variables in a problem after the global entities have been fixed. Sensitivity analysis can also be performed on the continuous variables in a MIP problem using problem.rhssa or problem.objsa after calling fixglobals.

#### **Related topics**

problem.mipoptimize.

# problem.fixpenalties

#### **Purpose**

Fixe the values of the error vectors

#### **Synopsis**

```
status = problem.fixpenalties ()
```

#### **Argument**

status Return status after fixing the penalty variables: 0 is successful, nonzero otherwise.

### **Further information**

The function fixes the values of all error vectors on their current values. It also removes their objective cost contribution.

The function is intended to support post optimization analysis, by removing any possible direct effect of the error vectors from the dual and reduced cost values.

The fixpenalties function will automatically reoptimize the linearization. However, as the XSLP convergence and infeasibility checks (regarding the original non-linear problem) will not be carried out, this function will not update the SLP solution itself. The updated values will be accessible using getlpsolution instead.

# problem.ftran

#### **Purpose**

Pre-multiplies a (column) vector provided by the user by the inverse of the current matrix.

### **Synopsis**

```
problem.ftran (vec)
```

### **Argument**

vec

Array of length problem.attributes.rows containing the values which are to be multiplied by the basis inverse. The transformed values appear in the array.

#### **Example**

To get the (unscaled) tableau column of structural variable number <code>jcol</code>, assuming that all arrays have been dimensioned, do the following:

```
y = [0,1,0,0]
p.ftran (y)
print ("ftran result:", y)
```

#### **Further information**

If the problem is in a presolved state, the function will work with the basis for the presolved problem.

# **Related topics**

```
problem.btran.
```

# problem.getAttrib

#### **Purpose**

Retrieves one or more attributes of a problem.

# **Synopsis**

attr\_subset = p.getAttrib (['cols', 'rows'])

#### **Further information**

This function can be passed either a single attribute name, whose value will be returned, or a list of attribute names, in which case the return value is a dictionary associating each key in the list with its value. If no argument is provided, a dictionary containing all attributes of the problem will be returned.

# problem.getattribinfo

### **Purpose**

Accesses the id number and the type information of an attribute given its name. An attribute name may be for example 'rows'. The function will return an id number of 0 and a type value of notdefined if the name is not recognized as an attribute name. Note that this will occur if the name is a control name and not an attribute name.

# **Synopsis**

(id, type) = problem.getattribinfo (name)

### **Argument**

name

The name of the attribute to be queried. Names are case-insensitive. A full list of all attributes may be found in the Xpress Optimizer reference manual.

# **Related topics**

problem.getcontrolinfo.

# problem.getbasis

#### **Purpose**

Returns the current basis into the user's data arrays.

#### **Synopsis**

```
problem.getbasis (rstatus, cstatus)
```

#### **Arguments**

rstatus

Array of length problem.attributes.rows to the basis status of the slack, surplus or artificial variable associated with each row. The status will be one of:

- o slack, surplus or artificial is non-basic at lower bound;
- 1 slack, surplus or artificial is basic;
- 2 slack or surplus is non-basic at upper bound.
- 3 slack or surplus is super-basic.

May be None if not required.

cstatus

Array of length problem.attributes.cols to hold the basis status of the columns in the constraint matrix. The status will be one of:

- variable is non-basic at lower bound, or superbasic at zero if the variable has no lower bound:
- 1 variable is basic;
- variable is non-basic at upper bound;
- 3 variable is super-basic.

May be None if not required.

### **Example**

The following example minimizes a problem before saving the basis for later:

```
rstatus = []
cstatus = []
p.lpoptimize ()
p.getbasis (rstatus, cstatus)
```

#### **Related topics**

problem.getpresolvebasis, problem.loadbasis, problem.loadpresolvebasis.

# problem.getccoef

#### **Purpose**

Retrieve a single matrix coefficient as a formula in a character string

### **Synopsis**

```
(factor, formula) = problem.getccoef (rowindex, colindex, flen)
```

### **Arguments**

RowIndex Integer holding the row index for the coefficient.

ColIndex Integer holding the column index for the coefficient.

Factor Address of a double precision variable to receive the value of the constant factor

multiplying the formula in the coefficient.

Formula Character buffer in which the formula will be placed in the same format as used for

input from a file. The formula will be null terminated.

fLen Maximum length of returned formula.

#### Return value

0 Normal return.

1 Formula is too long for the buffer and has been truncated.

other Error.

### **Example**

The following example displays the formula for the coefficient in row 2, column 3:

```
(factor, formula) = p.getccoef (2, 3, 60)
```

#### **Further information**

If the requested coefficient is constant, then factor will be set to 1.0 and the value will be formatted in formula.

If the length of the formula would exceed flen - 1, the formula is truncated to the last token that will fit, and the (partial) formula is terminated with a null character.

#### **Related topics**

problem.chgccoef,problem.chgnlcoef,problem.getcoefformula

# problem.getcoef

### **Purpose**

Returns a single coefficient in the constraint matrix.

# **Synopsis**

```
coef = problem.getcoef (irow, icol)
```

# **Arguments**

irow Row of the constraint matrix.

icol Column of the constraint matrix.

# **Further information**

It is quite inefficient to get several coefficients with the <code>getcoef</code> function. It is better to use <code>getcols</code> or <code>getrows</code>.

### **Related topics**

problem.getcols,problem.getrows.

## problem.getcoefformula

#### **Purpose**

Retrieve a single matrix coefficient as a formula split into tokens

#### **Synopsis**

#### **Arguments**

rowindex The row index for the coefficient.

colindex The column index for the coefficient.

factor The value of the constant factor multiplying the formula in the coefficient.

parsed Integer indicating whether the formula of the item is to be returned in internal unparsed

format (Parsed=0) or parsed (reverse Polish) format (Parsed=1).

bufsize Maximum number of tokens to return, i.e. length of the Type and Value arrays.

tokencount Number of tokens returned in Type and Value.

type Array to hold the token types for the formula.

value Array of values corresponding to Type.

### **Example**

The following example displays the formula for the coefficient in row 2, column 3 in unparsed form:

```
(fac, tc, type, value) = p.getcoefformula (2, 3, 0, 10)
```

#### **Further information**

The type and value arrays are terminated by an xslp\_op\_eof token.

If the requested coefficient is constant, then factor will be set to 1.0 and the value will be returned with token type xslp\_op\_con.

#### **Related topics**

problem.chgccoef,problem.chgnlcoef,problem.getccoef

# problem.getcoefs

#### **Purpose**

Retrieve the list of positions of the nonlinear coefficients in the problem

## **Synopsis**

```
problem.getcoefs (rowindex, colindex)
```

## **Arguments**

rowindices Row positions of the coefficients. May be None if not required. colindices Column positions of the coefficients. May be None if not required.

## **Related topics**

problem.getccoef, problem.getcoefformula

## problem.getcolinfo

#### **Purpose**

Get current column information.

## **Synopsis**

```
problem.getcolinfo (infotype, colindex);
```

#### **Arguments**

InfoType Type of information (see below)

Colindex Index of the column whose information is to be handled

Info Address of information to be set or retrieved

#### **Further information**

If the data is not available, the type of the returned Info is set to None. The following constants are provided for column information handling:

xpress.colinfo\_value Get the current value of the column

xpress.colinfo\_rdj Get the current reduced cost of the column

xpress.colinfo\_deltaindex Get the delta variable index associated to the column

xpress.colinfo\_delta Get the delta value (change since previous value) of the column

xpress.colinfo\_deltadj Get the delta variables reduced cost

xpress.colinfo\_updaterow Get the index of the update (or step bound) row associated to the

column

xpress.colinfo\_sb Get the step bound on the variable

xpress.colinfo\_sbdual Get the dual multiplier of the step bound row for the variable

## problem.getcols

#### **Purpose**

Returns the nonzeros in the constraint matrix for the columns in a given range.

#### **Synopsis**

```
problem.getcols (mstart, mrwind, dmatval, size, first, last)
```

#### **Arguments**

mstart	Array which will be filled with the indices indicating the starting offsets in the mrwind and dmatval arrays for each requested column. It must be of length at least last-first+2. Column i starts at position mstart[i] in the mrwind and dmatval arrays, and has mstart[i+1]-mstart[i] elements in it. May be None if not required.
mrwind	Array of length size which will be filled with the row indices of the nonzero coefficents for each column. May be None if not required.
dmatval	Array of length size which will be filled with the nonzero coefficient values. May be None if not required.
size	The size of the mrwind and dmatval arrays. This is the maximum number of nonzero coefficients that the Optimizer is allowed to return.
first	First column in the range.
last	Last column in the range.

### **Example**

The following examples retrieves the mstart vector of the problem:

```
p = xpress.problem ()
p.read ("example", "l")
mstart = []
p.getcols (mstart, first = 0, last = p.attributes.cols - 1)
```

#### **Further information**

It is possible to obtain just the number of elements in the range of columns by replacing mstart, mrwind and dmatval by None, as in the example. In this case, size must be set to 0 to indicate that the length of arrays passed is zero. This is demonstrated in the example above.

```
problem.getrows.
```

## problem.getcoltype

#### **Purpose**

Returns the column types for the columns in a given range.

#### **Synopsis**

```
problem.getcoltype (coltype, first, last)
```

#### **Arguments**

coltype Character array of length last-first+1 where the column types will be returned: C indicates a continuous variable;

I indicates an integer variable;

B indicates a binary variable;

s indicates a semi-continuous variable;

R indicates a semi-continuous integer variable;

P indicates a partial integer variable.

first First column in the range.

last Last column in the range.

#### **Example**

This example finds the types for all columns in the matrix and prints them:

```
coltype = []
p.getcoltype (coltype, 0, p.attributes.cols - 1)
print ("coltypes:", coltype)
```

```
problem.chgcoltype, problem.getrowtype.
```

## problem.getConstraint

#### **Purpose**

Returns one or more constraint of a problem corresponding to one or more indices passed as arguments. These constraints are returned as Python objects and can be used to access and manipulate the problem.

#### **Synopsis**

```
r = problem.getConstraint (index, first, last)
```

#### **Arguments**

first (optional) The first index of the constraints to be returned. It must be between 0 and

ROWS - 1.

last (optional) The last index of the constraints to be returned. It must be between 0 and

ROWS - 1.

index (optional) Either an integer or a list of integers (not necessarily sorted) with the

index/indices of all constraints to be returned, all between 0 and ROWS - 1

#### **Further information**

All arguments are optional. If neither of them is provided, the return value is a list with all constraints of the problem. Otherwise, either first and last or just index can be passed.

#### **Related topics**

problem.getVariable,problem.getSOS.

## problem.getControl

#### **Purpose**

Retrieves one or more controls of a problem.

## **Synopsis**

```
c = problem.getControl (ctrl1, ctrl2, ...)
```

#### **Example**

```
p = xpress.problem ()
[...]
print ("tolerance for feasibility and optimality: ",
   p.getControl ('feastol'), p.getControl ('miprelstop'))
all_ctrls = p.getControl ()
ctrl_subset = p.getControl (['presolve', 'miprelstop', 'feastol'])
```

#### **Further information**

This function can be passed either a single control name, whose value will be returned, or a list of control names, in which case the return value is a dictionary associating each key in the list with its value. If no argument is provided, a dictionary containing all controls of the problem will be returned.

```
problem.setControl.
```

# problem.getcontrolinfo

### **Purpose**

Accesses the id number and the type information of a control given its name. A control name may be for example 'presolve'. The function will return an id number of 0 and a type value of notdefined if the name is not recognized as a control name. Note that this will occur if the name is an attribute name rather than a control name.

## **Synopsis**

(id,type) = problem.getcontrolinfo (name)

#### **Argument**

name

The name of the control to be queried. Names are case-insensitive. A full list of all control may be found in the Xpress Optimizer reference manual.

### **Related topics**

problem.getattribinfo.

## problem.getcpcutlist

#### **Purpose**

Returns a list of cut indices from the cut pool.

#### **Synopsis**

```
ncuts = problem.getcpcutlist (itype, interp, delta, size, cutind, viol)
```

#### **Arguments**

The user defined type of the cuts to be returned. itype Way in which the cut type is interpreted: interp -1 get all cuts; 1 treat cut types as numbers; treat cut types as bit maps - get cut if any bit matches any bit set in itype; 2 treat cut types as bit maps - get cut if all bits match those set in itype. delta Only those cuts with a signed violation greater than delta will be returned. Maximum number of cuts to be returned. size Array of length size where the cuts will be returned. mcutind Array of length size where the values of the signed violations of the cuts will be dviol returned.

#### **Further information**

- 1. The violated cuts can be obtained by setting the delta parameter to the size of the (signed) violation required. If unviolated cuts are required as well, delta may be set to \_MINUSINFINITY which is defined in the library header file.
- 2. If the number of active cuts is greater than size, only size cuts will be returned. Otherwise only the existing cuts will be used to fill in the positions of mcutind.
- 3. In case of a cut of type 'L', the violation equals the negative of the slack associated with the row of the cut. In case of a cut of type 'G', the violation equals the slack associated with the row of the cut. For cuts of type 'E', the violation equals the absolute value of the slack.
- 4. Please note that the violations returned are absolute violations, while feasibility is checked by the Optimizer in the scaled problem.

#### **Related topics**

problem.delcpcuts, problem.getcpcuts, problem.getcutlist, problem.loadcuts, problem.getcutmap, problem.getcutslack, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

## problem.getcpcuts

#### **Purpose**

Returns cuts from the cut pool. A list of cuts in the array mindex must be passed to the routine. The columns and elements of the cut will be returned in the regions pointed to by the mcols and dmatval parameters. The columns and elements will be stored contiguously and the starting point of each cut will be returned in the region pointed to by the mstart parameter.

#### **Synopsis**

problem.getcpcuts (mindex, size, type, rtype, mstart, mcols, dmatval, drhs)

#### **Arguments**

mindex List containing the cuts.

size Maximum number of column indices of the cuts to be returned.

type List where the cut types will be returned.

rtype Character list where the sense of the cuts (L, G, or E) will be returned.

mstart Array containing the offsets into the mcols and dmatval arrays. The last element

indicates the total number of elements.

cols Array where the column indices of the cuts will be returned.

matval Array where the matrix values will be returned.

rhs Array where the right hand side elements for the cuts will be returned.

#### **Related topics**

problem.getcpcutlist, problem.getcutlist, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

## problem.getcutlist

#### **Purpose**

Retrieves a list of cuts for the cuts active at the current node.

#### **Synopsis**

```
problem.getcutlist (itype, interp, size, cutind)
```

#### **Arguments**

#### **Further information**

If the number of active cuts is greater than size, then size cuts will be returned. Otherwise only the positions corresponding to the number of active cuts will be filled in cutind.

### **Related topics**

problem.getcpcutlist, problem.getcpcuts, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

## problem.getcutmap

#### **Purpose**

Returns in which rows a list of cuts are currently loaded into the Optimizer. This is useful for example to retrieve the duals associated with active cuts.

### **Synopsis**

```
problem.getcutmap (cuts, cutmap)
```

#### **Arguments**

cuts Array with the cuts for which the row index is requested.

cutmap Array where the row indices are returned.

#### **Further information**

For cuts currently not loaded into the problem, a row index of -1 is returned.

#### **Related topics**

problem.getcpcutlist, problem.delcpcuts, problem.getcutlist, problem.loadcuts, problem.getcutslack, problem.getcpcuts, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

# problem.getcutslack

#### **Purpose**

Used to calculate the slack value of a cut with respect to the current LP relaxation solution. The slack is calculated from the cut itself, and might be requested for any cut (even if it is not currently loaded into the problem).

#### **Synopsis**

```
slack = problem.getcutslack (cut)
```

### **Arguments**

cuts Cut object for which the slack is to be calculated.

slack Value of the slack.

## **Related topics**

problem.getcpcutlist, problem.delcpcuts, problem.getcutlist, problem.loadcuts, problem.getcutmap, problem.getcpcuts, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

## problem.getdirs

#### **Purpose**

Returns the directives that have been loaded into a problem. Priorities, forced branching directions and pseudo costs can be returned. If called after presolve, getdirs will get the directives for the presolved problem.

#### **Synopsis**

problem.getdirs (mcols, mpri, qbr, dupc, ddpc)

#### **Arguments**

Array containing the column numbers (0, 1, 2,...) or negative values corresponding to special ordered sets (the first set numbered -1, the second numbered -2,...). May be None if not required.

Array containing the priorities for the columns and sets. May be None if not required.

Character array with the branching direction for each column or set:

U the entity is to be forced up;

D the entity is to be forced down;

N not specified.

dupc

Array containing the up pseudo costs for the columns and sets. May be None if not required.

ddpc Array containing the down pseudo costs for the columns and sets. May be None if not

required.

#### **Further information**

The size of all lists is at most MIPENTS, obtainable from xproblem.attributes.mipents.

#### **Related topics**

problem.loaddirs.problem.loadpresolvedirs.

## problem.getdf

#### **Purpose**

Get a distribution factor

#### **Synopsis**

```
value = problem.getdf (colindex, rowindex)
```

#### **Arguments**

rowindex
The index of the column whose distribution factor is to be retrieved.

The index of the row from which the distribution factor is to be taken.

The value of the distribution factor.

#### **Example**

The following example retrieves the value of the distribution factor for column 282 in row 134 and changes it to be twice as large.

```
value = p.getdf (282,134)
value *= 2
p.chgdf (282,134,calue)
```

#### **Further information**

The distribution factor of a column in a row is the matrix coefficient of the corresponding delta vector in the row. Distribution factors are used in conventional recursion models, and are essentially normalized first-order derivatives. Xpress SLP can accept distribution factors instead of initial values, provided that the values of the variables involved can all be calculated after optimization using determining rows, or by a callback.

#### **Related topics**

problem.adddfs,problem.chgdf,problem.loaddfs

## problem.getdtime

#### **Purpose**

Retrieve a double precision time stamp in seconds

#### **Synopsis**

```
seconds = problem.getdtime ()
```

#### **Argument**

seconds

Address of double precision variable of the time in seconds.

#### **Example**

The following example measures the elapsed time to read a problem:

```
start = p.getdtime ()
p.read ("NewMat","")
finish = p.getdtime ()
print ("Elapsed time to read = {0} secs".format (finish - start))
```

#### **Further information**

The timing information returned is provided by the operating system and is typically accurate to no more than 1 millisecond.

The clock is not initialized when Xpress Nonlinear starts, so it is necessary to save an initial time and then measure all times by difference.

# problem.getDual

### **Purpose**

Return the dual for all constraints of the problem w.r.t. the solution found by solve(); this only works on continuous optimization problems.

## **Synopsis**

```
d = problem.getDual ()
```

## **Example**

```
p.solve ()
print ("duals:", p.getDual ())
```

## **Related topics**

 $\verb|problem.getlpsol,problem.getSlack,problem.getRCost,problem.getProbStatus,problem.getProbStatusString|$ 

## problem.getdualray

#### **Purpose**

Retrieves a dual ray (dual unbounded direction) for the current problem, if the problem is found to be infeasible.

#### **Synopsis**

```
problem.getdualray (dray)
```

#### **Argument**

dray

Array of length problem.attributes.rows to hold the ray. May be None if not required.

### **Example**

The following code tries to retrieve a dual ray:

```
if not p.hasdualray ():
    print ("Could not retrieve a dual ray")
else:
    dray = []
    p.getdualray (dray)
    print ("dual ray:", dray)
```

#### **Further information**

- 1. It is possible to retrieve a dual ray only when, after solving an LP problem, the final status is xpress.lp\_infeas.
- 2. Dual rays are not post-solved. If the problem is in a presolved state, the dual ray that is returned will be for the presolved problem. If the problem was solved with presolve on and has been restored to the original state (the default behavior), this function will not be able to return a ray. To ensure that a dual ray can be obtained, it is recommended to solve a problem with presolve turned off (presolve = 0).

```
problem.getprimalray.
```

## problem.getglobal

#### **Purpose**

Retrieves global information about a problem. It must be called before problem.mipoptimize if the presolve option is used.

### **Synopsis**

```
problem.getglobal (qgtype, mgcols, dlim, qstype, msstart, mscols, dref)
```

## **Arguments**

qgtype	Character array where the entity types will be returned. The types will be one of:  B binary variables;
	I integer variables;
	P partial integer variables;
	s semi-continuous variables;
	R semi-continuous integer variables.
mgcols	Array where the column indices of the global entities will be returned.
dlim	Array where the limits for the partial integer variables and lower bounds for the semi-continuous and semi-continuous integer variables will be returned (any entries in the positions corresponding to binary and integer variables will be meaningless).
qstype	Character array where the set types will be returned. The set types will be one of:  SOS1 type sets; SOS2 type sets.
msstart	Array where the offsets into the mscols and dref arrays indicating the start of the sets will be returned. This array must be of length SETMEMBERS+1: the final element contains the length of the mscols and dref arrays.
mscols	Array of length problem.attributes.setmembers where the columns in each set will be returned.
dref	Array of length problem.attributes.setmembers where the reference row entries for each member of the sets will be returned.

### **Example**

The following obtains the SOS information:

```
qstype = []
mstart = []
mscols = []
dref = []
p.getglobal (None, None, None, qstype, mstart, mscols, dref)
```

## **Further information**

All arguments may be None if not required.

## **Related topics**

problem.loadproblem.

## problem.getiisdata

#### **Purpose**

Returns information for an Irreducible Infeasible Set: size, variables (row and column vectors) and conflicting sides of the variables, duals and reduced costs.

#### **Synopsis**

#### **Arguments**

```
The ordinal number of the IIS to get data for.
num
               Indices of rows in the IIS. Can be None if not required.
miisrow
               Indices of bounds (columns) in the IIS. Can be None if not required.
miiscol
                     Sense of rows in the IIS:
constrainttype
                      for less or equal row;
               L
                      for greater or equal row.
               G
               Ε
                       for an equality row (for a non LP IIS);
                      for a SOS1 row:
               1
                      for a SOS2 row:
               2
                      for an indicator row.
               Т
               Can be None if not required.
               Sense of bound in the IIS:
colbndtype
               U
                       for upper bound;
                       for lower bound.
               Τ.
               F
                      for fixed columns (for a non LP IIS);
                      for a binary column;
               В
                      for an integer column;
               Ι
                      for a partial integer columns;
               Ρ
                       for a semi-continuous column;
               S
                      for a semi-continuous integer column.
               Can be None if not required.
               The >dual multipliers associated with the rows. Can be None if not required.
duals
               The dual multipliers (reduced costs) associated with the bounds. Can be None if not
rdcs
               required.
isolationrows
                    The isolation status of the rows:
               _1
                      if isolation information is not available for row (run iis isolations);
               0
                      if row is not in isolation;
                      if row is in isolation.
               1
               Can be None if not required.
isolationcols
                   The isolation status of the bounds:
                       if isolation information is not available for column (run iisisolations);
               -1
               0
                      if column is not in isolation;
                      if column is in isolation. Can be None if not required.
```

#### **Example**

This example first retrieves the size of IIS 1, then gets the detailed information for the IIS.

```
miisrow = []
miiscol = []
constrainttype = []
colbndtype = []
duals = []
rdcs = []
```

#### **Further information**

- 1. IISs are numbered from 1 to NUMIIS. Index number 0 refers to the IIS approximation.
- 2. If miisrow and miiscol both are None, only the rownumber and colnumber are returned.
- 3. The arrays may be None if not required. However, arrays constrainttype, duals and isolationrows are only returned if miisrow is not None. Similarly, arrays colbndtype, rdcs and isolationcols are only returned if miiscol is not None.
- 4. For the initial IIS approximation (num = 0) the number of rows and columns with a nonzero Lagrange multiplier (dual/reduced cost respectively) are returned. Please note that in such cases, it might be necessary to call problem.iisstatus to retrieve the necessary size of the return arrays.
- 5. If there are Special Ordered Sets in the IIS, their number is included in the miisrow array.
- 6. For non-LP IISs, some column indices may appear more than once in the miiscol array, for example an integrality and a bound restriction for the same column.
- 7. Duals, reduced cost and isolation information is not available for nonlinear IIS problems, and for those the arrays are filled with zero values in case they are provided.

```
problem.iisall, problem.iisclear, problem.iisfirst, problem.iisisolations,
problem.iisnext, problem.iisstatus, problem.iiswrite.
```

## problem.getIndex

#### **Purpose**

Returns the numerical index for a specified row, column, or set of the optimizer.

#### **Synopsis**

```
ind = problem.getIndex (obj)
```

#### **Argument**

obj

Python object with the column, row, or SOS

#### **Example**

The following example adds a constraint to a problem and then retrieves its index:

```
x = xpress.var ()
c = x**2 + 2*x >= 5
p.addVariable (x)
p.addConstraint (c)
print ("c has index", p.getIndex (c))
```

#### **Related topics**

problem.getIndexFromName,problem.getVariable,problem.getConstraint.

# problem.getIndexFromName

#### **Purpose**

Returns the index for a specified row or column name.

#### **Synopsis**

```
ind = problem.getIndexFromName (type, name)
```

#### **Arguments**

```
type 1 if a row index is required;
2 if a column index is required.
name String containing name of the item sought.
```

## **Example**

The following example retrieves the index of column "xnew":

```
x = xpress.var (name = 'xnew')
[...]
print ("variable's index: ", p.getIndexFromName ('xnew'))
```

#### **Related topics**

problem.getIndexFromName,problem.getVariable,problem.getConstraint.

## problem.getindicators

#### **Purpose**

Returns the indicator constraint condition (indicator variable and complement flag) associated to the rows in a given range.

#### **Synopsis**

```
problem.getindicators (inds, comps, first, last)
```

#### **Arguments**

Array of length last-first+1 where the column indices of the indicator variables are to be placed.

Comps

Array of length last-first+1 where the indicator complement flags will be returned:

0 not an indicator constraint (in this case the corresponding entry in the inds array is ignored);

1 for indicator constraints with condition "bin = 1";

-1 for indicator constraints with condition "bin = 0";

first

First row in the range.

Last row in the range (inclusive).

### **Example**

The following example retrieves information about three indicator constraints in the problem and prints a list of their indices.

```
inds = []
comps = []
p.getindicators (inds, comps, 2, 4)
print ("indices:", inds)
print ("complement flags:", comps)
```

#### **Related topics**

problem.setindicators.

## problem.getinfeas

#### **Purpose**

Returns a list of infeasible primal and dual variables.

#### **Synopsis**

```
problem.getinfeas (mx, mslack, mdual, mdj)
```

#### **Arguments**

mx Array to store the primal infeasible variables. May be None if not required.

mslack Array to store the primal infeasible rows. May be None if not required.

mdual Array to store the dual infeasible rows. May be None if not required.

mdj Array to store the dual infeasible variables. May be None if not required.

#### **Example**

```
mx = []
mslack = []
p.getinfeas (mx, mslack, None, None)
print ("getinfeas --> mx and mslack:", mx, mslack)
```

#### **Further information**

To find the infeasibilities in a previously saved solution, the solution must first be loaded into memory with the problem.readbinsol function.

```
problem.getscaledinfeas, problem.getiisdata, problem.iisall, problem.iisclear, problem.iisfirst, problem.iisisolations, problem.iisnext, problem.iisstatus, problem.iiswrite.
```

# problem.getlasterror

#### **Purpose**

Returns the error message corresponding to the last error triggered by a library function.

## **Synopsis**

```
s = problem.getlasterror ()
```

## **Example**

The following shows how this function might be used in error-checking:

```
p.solve ()
print ("Current error status:", p.getlasterror ())
```

## **Related topics**

 ${\tt ERRORCODE, problem.addcbmessage, problem.setlog file.}$ 

## problem.getlb

#### **Purpose**

Returns the lower bounds on the columns in a given range.

#### **Synopsis**

```
problem.getlb (lb, first, last)
```

#### **Arguments**

1b Array where the lower bounds are to be placed.

first (optional, default 0) First column in the range.

last (optional, default COLS - 1) Last column in the range.

#### **Example**

The following example retrieves the lower bounds for the columns of the current problem:

```
newlb = []
p.getlb (newlb, 0, 4)
print ("lb: ", newlb)
```

#### **Further information**

Values greater than or equal to xpress.infinity should be interpreted as infinite; values less than or equal to - xpress.infinity should be interpreted as negative infinite.

## **Related topics**

problem.chgbounds,problem.getub.

## problem.getlpsol

#### **Purpose**

Used to obtain the LP solution values following optimization.

#### **Synopsis**

```
problem.getlpsol (x, slack, dual, dj)
```

#### **Arguments**

Array to store the values of the primal variables. May be None if not required. Array to store the values of the slack variables. May be None if not required. Array to store the values of the dual variables  $(c_B^T B^{-1})$ . May be None if not required. Array to store the reduced cost for each variable  $(c^T - c_B^T B^{-1}A)$ . May be None if not required.

#### **Example**

The following sequence of commands will get the LP solution (x) at the top node of a MIP and the optimal MIP solution (y):

```
p.mipoptimize ("1") \# only solve the LP relaxation x = [] p.getlpsol (x) print ("root LP solution:", x) p.mipoptimize () \# solve the MIP problem p.getmipsol (x) print ("final MIP solution", x)
```

#### **Further information**

- 1. If called during a global callback the solution of the current node will be returned.
- 2. When an integer solution is found during a global search, it is always set up as a solution to the current node; therefore the integer solution is available as the current node solution and can be retrieved with getlpsol and problem.getpresolvesol.
- 3. If the problem is modified after calling lpoptimize, then the solution will no longer be available.
- 4. If the problem has been presolved, then <code>getlpsol</code> returns the solution to the original problem. The only way to obtain the presolved solution is to call the related function, <code>problem.getpresolvesol</code>.

```
problem.getpresolvesol,problem.getmipsol,problem.writeprtsol,
problem.writesol.
```

## problem.getmessagestatus

### **Purpose**

Returns the current suppression status of a message: non-zero if the message is not suppressed; 0 otherwise.

#### **Synopsis**

status = problem.getmessagestatus (errcode)

#### **Argument**

errcode

The id number of the message. Refer to the Xpress Optimizer reference manual for a list of possible message numbers.

#### **Further information**

If a message is suppressed globally then the message will always have status return zero from getmessagestatus.

## **Related topics**

problem.setmessagestatus.

## problem.getmessagetype

## **Purpose**

Retrieve the message type corresponding to a message number

#### **Synopsis**

```
type = problem.getmessagetype (code)
```

#### **Arguments**

code The message number. type The message type.

### **Example**

The following example retrieves the last error message and finds its type.

```
(code, a) = p.getlasterror ()
type = p.getmessagetype (code)
print ("Error of type ", type)
```

#### **Further information**

The possible values returned in type are:

- o no such message number
- 1 information
- 3 warning
- **4** error

#### **Related topics**

problem.getlasterror

## problem.getmipsol

#### **Purpose**

Used to obtain the solution values of the last MIP solution that was found.

#### **Synopsis**

```
problem.getmipsol (x, slack)
```

#### **Arguments**

x Array to store the values of the primal variables. May be None if not required. slack Array to store the values of the slack variables. May be None if not required.

### **Example**

The following sequence of commands will get the solution (x) of the last MIP solution for a problem:

```
x = []
p.mipoptimize ()
p.getmipsol (x)
print ("solution:", x)
```

## **Related topics**

problem.getpresolvesol,problem.writeprtsol,problem.writesol.

## problem.getmqobj

#### **Purpose**

Returns the nonzeros in the quadratic objective coefficients' matrix for the columns in a given range. To achieve maximum efficiency, getmqobj returns the lower triangular part of this matrix only.

#### **Synopsis**

problem.getmqobj (mstart, mclind, dobjval, size, first, last)

#### **Arguments**

mstart	Array which will be filled with indices indicating the starting offsets in the mclind and dobjval arrays for each requested column. It must be length of at least last-first+2. Column i starts at position mstart[i] in the mrwind and dmatval arrays, and has mstart[i+1]-mstart[i] elements in it. May be None if size is 0.
mclind	Array which will be filled with at most size column indices of the nonzero elements in the lower triangular part of Q. May be None if size is 0.
dobjval	Array which will be filled with at most size nonzero element values. May be None if size is 0.
size	The maximum number of elements to be returned (size of the arrays).
first	First column in the range.
last	Last column in the range.

#### **Further information**

The objective function is of the form  $c^T x + 0.5 x^T Q x$  where Q is positive semi-definite for minimization problems and negative semi-definite for maximization problems. If this is not the case the optimization algorithms may converge to a local optimum or may not converge at all. Note that only the upper or lower triangular part of the Q matrix is returned.

#### **Related topics**

problem.chgmqobj,problem.chgqobj,problem.getqobj.

## problem.getobj

### **Purpose**

Returns the objective function coefficients for the columns in a given range.

## **Synopsis**

```
problem.getobj (obj, first, last)
```

## **Arguments**

obj Array of length last-first+1 where the objective function coefficients are to be

placed.

first First column in the range.

last Last column in the range.

## **Example**

The following example retrieves the objective function coefficients of the first five variables of the current problem:

```
obj = []
p.getobj (obj, 0, 4)
```

```
problem.chgobj.
```

# problem.getObjVal

#### **Purpose**

Returns the objective value of the solution found by the Optimizer.

## **Synopsis**

```
o = problem.getObjVal ()
```

## **Example**

The following prints the objective value of an optimal solution after the solve () command is run:

```
p.solve ()
print ("optimal solution:", p.getObjVal ())
```

## **Related topics**

problem.solve.

# problem.getpivotorder

#### **Purpose**

Returns the pivot order of the basic variables.

## **Synopsis**

```
problem.getpivotorder (mpiv)
```

#### **Argument**

mpiv

Array where the pivot order will be returned.

## **Example**

The following returns the pivot order of the variables into an array pPivot:

```
mpiv = []
p.getpivotorder (mpiv)
```

## **Further information**

Row indices are in the range 0 to ROWS-1, whilst columns are in the range ROWS+SPAREROWS to ROWS+SPAREROWS+COLS-1.

## **Related topics**

problem.getpivots.

## problem.getpivots

#### **Purpose**

Returns a list of potential leaving variables if a specified variable enters the basis. The return value is a tuple containing the objective function value that would result if in entered the basis; and an integer where the actual number of potential leaving variables will be returned.

#### **Synopsis**

```
dobj, npiv = problem.getpivots (in, outlist, x, maxpiv)
```

#### **Arguments**

in Index of the specified row or column to enter basis.

outlist Array of length at least maxpiv to hold list of potential leaving variables. May be None if

not required.

x Array of length problem.attributes.rows +

problem.attributes.sparerows + problem.attributes.cols to hold the values of all the variables that would result if in entered the basis. May be None if not

required.

maxpiv Maximum number of potential leaving variables to return.

#### **Example**

The following retrieves a list of up to 5 potential leaving variables if variable 6 enters the basis:

```
outlist = []
x = []
obj, npiv = p.getpivots (2, outlist, x, 10)
```

#### **Further information**

- 1. If the variable in enters the basis and the problem is degenerate then several basic variables are candidates for leaving the basis, and the number of potential candidates is returned in npiv. A list of at most maxpiv of these candidates is returned in outlist which must be at least maxpiv long. If variable in were to be pivoted in, then because the problem is degenerate, the resulting values of the objective function and all the variables do not depend on which of the candidates from outlist is chosen to leave the basis. The value of the objective is returned in dobj and the values of the variables into x.
- 2. Row indices are in the range 0 to ROWS-1, whilst columns are in the range ROWS+SPAREROWS to ROWS+SPAREROWS+COLS-1.

#### **Related topics**

problem.getpivotorder.

## problem.getpresolvebasis

#### **Purpose**

Returns the current basis from memory into the user's data areas. If the problem is presolved, the presolved basis will be returned. Otherwise the original basis will be returned.

### **Synopsis**

```
problem.getpresolvebasis (rstatus, cstatus)
```

#### **Arguments**

rstatus

Array of length problem.attributes.rows to the basis status of the stack, surplus or artificial variable associated with each row. The status will be one of:

- o slack, surplus or artificial is non-basic at lower bound;
- 1 slack, surplus or artificial is basic;
- 2 slack or surplus is non-basic at upper bound.

May be None if not required.

cstatus

Array of length problem.attributes.cols to hold the basis status of the columns in the constraint matrix. The status will be one of:

- variable is non-basic at lower bound, or superbasic at zero if the variable has no lower bound:
- 1 variable is basic;
- 2 variable is at upper bound;
- 3 variable is super-basic.

May be None if not required.

#### **Example**

The following obtains and outputs basis information on a presolved problem prior to the global search:

```
cs = []
p = xpress.problem ()
p.read ("global1", "")
p.mipoptimize ()
p.getpresolvebasis (cstatus = cs)
```

#### **Related topics**

problem.getbasis,problem.loadbasis,problem.loadpresolvebasis.

## problem.getpresolvemap

#### **Purpose**

Returns the mapping of the row and column numbers from the presolve problem back to the original problem.

#### **Synopsis**

```
problem.getpresolvemap (rowmap, colmap)
```

#### **Arguments**

rowmap Array to store the row maps.

colmap Array to store the column maps.

## **Example**

The following reads in a (Mixed) Integer Programming problem and gets the mapping for the rows and columns back to the original problem following optimization of the linear relaxation. The elimination operations of the presolve are turned off so that a one-to-one mapping between the presolve problem and the original problem.

```
p.read ("MyProb", "")
p.controls.presolveops = 255
p.mipoptimize ("1")
rowmap = []
colmap = []
p.getpresolvemap (rowmap, colmap)
```

#### **Further information**

The presolved problem can contain rows or columns that do not map to anything in the original problem. An example of this are cuts created during the MIP solve and temporarily added to the presolved problem. It is also possible that the presolver will introduce new rows or columns. For any row or column that does not have a mapping to a row or column in the original problem, the corresponding entry in the returned rowmap and colmap arrays will be -1.

## problem.getpresolvesol

#### **Purpose**

Returns the solution for the presolved problem from memory.

#### **Synopsis**

```
problem.getpresolvesol (x, slack, dual, dj)
```

#### **Arguments**

Array to store the values of the primal variables. May be None if not required.

Array to store the values of the slack variables. May be None if not required.

Array to store the values of the dual variables. May be None if not required.

Array to store the reduced cost for each variable. May be None if not required.

#### **Example**

The following reads in a (Mixed) Integer Programming problem and displays the solution to the presolved problem following optimization of the linear relaxation:

```
p.read ("MyProb", "")
p.mipoptimize ("1")
sol = []
p.getpresolvesol (x = sol)
print ("presolved sol", sol)
```

#### **Further information**

- 1. If the problem has not been presolved, the solution in memory will be returned.
- 2. The solution to the original problem should be returned using the related function problem.getlpsol.
- 3. If called during a global callback the solution of the current node will be returned.
- 4. When an integer solution is found during a global search, it is always set up as a solution to the current node; therefore the integer solution is available as the current node solution and can be retrieved with getlpsol and problem.getpresolvesol.

## problem.getprimalray

#### **Purpose**

Retrieves a primal ray (primal unbounded direction) for the current problem, if the problem is found to be unbounded.

### **Synopsis**

```
problem.getprimalray (ray)
```

#### **Argument**

ray

Array of length problem.attributes.cols to hold the ray. May be None if not required.

### **Example**

The following code tries to retrieve a primal ray:

```
if not p.hasprimalray ():
    print ("Could not retrieve a primal ray")
else:
    ray = []
    p.getprimalray (ray)
    print ("primal ray:", ray)
```

#### **Further information**

- 1. It is possible to retrieve a primal ray only when, after solving an LP problem, the final status (LPSTATUS) is xpress.lp\_unbounded.
- 2. Primal rays are not post-solved. If the problem is in a presolved state, the primal ray that is returned will be for the presolved problem. If the problem was solved with presolve on and has been restored to the original state (the default behavior), this function will not be able to return a ray. To ensure that a primal ray can be obtained, it is recommended to solve a problem with presolve turned off (PRESOLVE = 0).

```
problem.getdualray.
```

## problem.getProbStatus

#### **Purpose**

Returns the problem status before or after a solve () command. The returned number corresponds to the problem status described in the Xpress Optimizer reference manual. If the problem is an LP, the returned value is equal to p.attributes.lpstatus if the problem is an LP, and to p.attrobutes.mipstatus if the problem is a MIP.

### **Synopsis**

```
s = problem.getProbStatus ()
```

### **Example**

### **Related topics**

problem.solve,problem.getSolution,problem.getDual,problem.getSlack, problem.getRCost,problem.getProbStatusString.

## problem.getProbStatusString

#### **Purpose**

Returns the string corresponding to the the problem status before or after a solve () command.

## **Synopsis**

```
s = problem.getProbStatusString ()
```

#### **Example**

#### **Related topics**

problem.solve,problem.getSolution,problem.getDual,problem.getSlack, problem.getRCost,problem.getProbStatus.

## problem.getqobj

#### **Purpose**

Returns a single quadratic objective function coefficient corresponding to the variable pair (icol, jcol) of the Hessian matrix.

#### **Synopsis**

```
objqcoef = problem.getqobj (icol, jcol)
```

#### **Arguments**

icol Column index for the first variable in the quadratic term.

jcol Column index for the second variable in the quadratic term.

### **Example**

The following returns the coefficient of the  $x_0^2$  term in the objective function, placing it in the variable value:

```
print ("diagonal coeff of the Hessian:",
    [p.getqobj (i,i) for i in range (p.attributes.cols)])
```

#### **Further information**

For example, if the objective function has the term  $[3x_1x_2 + 3x_2x_1]/2$  the value retrieved by getqobj is 3.0 and if the objective function has the term  $[6x_1^2]/2$  the value retrieved by getqobj is 6.0.

```
problem.getmgobj,problem.chggobj,problem.chgmgobj.
```

## problem.getqrowcoeff

#### **Purpose**

Returns a single quadratic constraint coefficient corresponding to the variable pair (icol, jcol) of the Hessian of a given constraint.

#### **Synopsis**

```
coeff = problem.getqrowcoeff (irow, icol, jcol)
```

#### **Arguments**

row The quadratic row where the coefficient is to be looked up.

icol Column index for the first variable in the quadratic term.

jcol Column index for the second variable in the quadratic term.

## **Example**

The following returns the coefficient of the dist2 term in the constraint cons1:

```
print ("diagonal coeff of dist:", p.getqrowcoeff (cons1, dist, dist)
```

#### **Further information**

The coefficient returned corresponds to the Hessian of the constraint. That means the for constraint  $x + [x^2 + 6 xy] \le 10 \text{ getqrowcoeff}$  would return 1 as the coefficient of  $x^2$  and 3 as the coefficient of xy.

```
problem.loadproblem,problem.addqmatrix,problem.chgqrowcoeff,
problem.getqrowqmatrix,problem.getqrowqmatrixtriplets,problem.getqrows,
problem.chgqobj,problem.chgmqobj,problem.getqobj.
```

## problem.getqrowqmatrix

### **Purpose**

Returns the nonzeros in a quadratic constraint coefficients matrix for the columns in a given range. To achieve maximum efficiency, getqrowqmatrix returns the lower triangular part of this matrix only.

#### **Synopsis**

problem.getqrowqmatrix (irow, mstart, mclind, dqe, size, first, last)

#### **Arguments**

irow	Index of the row for which the quadratic coefficients are to be returned.		
mstart	Array which will be filled with indices indicating the starting offsets in the mclind and dobjval arrays for each requested column. It must be length of at least last-first+2. Column i starts at position mstart[i] in the mrwind and dmatval arrays, and has mstart[i+1]-mstart[i] elements in it. May be None if size is 0.		
mclind	Array of length size which will be filled with the column indices of the nonzero elements in the lower triangular part of Q. May be None if size is 0.		
dqe	Array of length $\mathtt{size}$ which will be filled with the nonzero element values. May be None if size is 0.		
size	Maximum number of elements to be returned in mclind and dqe.		
first	First column in the range.		
last	Last column in the range.		

#### **Related topics**

problem.loadproblem.problem.getqrowcoeff,problem.addqmatrix, problem.chgqrowcoeff,problem.getqrowqmatrixtriplets,problem.getqrows, problem.chgqobj,problem.chgmqobj,problem.getqobj.

## problem.getqrowqmatrixtriplets

#### **Purpose**

Returns the nonzeros in a quadratic constraint coefficients matrix as triplets (index pairs with coefficients). To achieve maximum efficiency, getqrowqmatrixtriplets returns the lower triangular part of this matrix only.

#### **Synopsis**

```
problem.getqrowqmatrixtriplets (irow, mqcol1, mqcol2, dqe)
```

#### **Arguments**

irow Index of the row for which the quadratic coefficients are to be returned.

nqelem Argument used to return the number of quadratic coefficients in the row.

mqcol1 First index in the triplets. May be None if not required.

mqcol2 Second index in the triplets. May be None if not required. dqe Coefficients in the triplets. May be None if not required.

#### **Further information**

If a row index of -1 is used, the function returns the quadratic coefficients for the objective function.

```
problem.loadproblem.getqrowcoeff,problem.addqmatrix,problem.chgqrowcoeff,problem.getqrowqmatrix,problem.getqrows,problem.chgqobj,problem.getqobj.
```

## problem.getqrows

### **Purpose**

Returns the list indices of the rows that have quadratic coefficients.

#### **Synopsis**

```
problem.getqrows (qcrows)
```

#### **Argument**

qcrows

Array to contain the indices of rows with quadratic coefficients in them. May be None if not required.

```
problem.loadproblem.problem.getqrowcoeff,problem.addqmatrix,
problem.chgqrowcoeff,problem.getqrowqmatrix,problem.getqrowqmatrixtriplets,
problem.chgqobj,problem.chgmqobj,problem.getqobj.
```

## problem.getRCost

### **Purpose**

Return the reduced cost of all variables of the problem w.r.t. the solution found by solve(). This function only works on continuous optimization problems.

## **Synopsis**

```
r = problem.getRCost ()
Example
    p.solve ()
```

print ("reduced costs:", p.getRCost ())

#### **Related topics**

problem.solve,problem.getlpsol,problem.getSolution,problem.getDual, problem.getSlack,problem.getProbStatus,problem.getProbStatusString.

## problem.getrhs

#### **Purpose**

Returns the right hand side elements for the rows in a given range.

### **Synopsis**

```
problem.getrhs (rhs, first, last)
```

### **Arguments**

rhs Array where the (last - first + 1) right hand side elements are to be placed.

first First row in the range.

last Last row in the range.

#### **Example**

The following example retrieves the right hand side values of the problem:

```
b = []
p.getrhs (b, 0, p.attributes.rows - 1)
```

### **Related topics**

problem.chgrhs, problem.chgrhsrange, problem.getrhsrange.

## problem.getrhsrange

## **Purpose**

Returns the right hand side range values for the rows in a given range.

### **Synopsis**

```
problem.getrhsrange (range, first, last)
```

## **Arguments**

range Array of length last-first+1 where the right hand side range values are to be placed.

first First row in the range.

last Last row in the range.

### **Related topics**

problem.chgrhs, problem.chgrhsrange, problem.getrhs.

## problem.getrowinfo

#### **Purpose**

Get current row information.

#### **Synopsis**

```
info = problem.getrowinfo (infotype, rowindex);
```

#### **Arguments**

infotype Type of information (see below)

rowindex Index of the row whose information is to be handled

info Information to be retrieved

#### **Further information**

If the data is not available, the type of the returned info is set to xpress.undefined.

The following constants are provided for row information handling:

rowinfo\_slack Get the current slack value of the row rowinfo\_dual Get the current dual multiplier of the row

rowinfo\_numpenaltyerrors Get the number of times the penalty error vector has been active for

the row

rowinfo\_maxpenaltyerror Get the maximum size of the penalty error vector activity for the row rowinfo\_totalpenaltyerror Get the total size of the penalty error vector activity for the row rowinfo\_currentpenaltyerror Get the size of the penalty error vector activity in the current iteration for the row

rowinfo\_currentpenaltyfactor Set the size of the penalty error factor for the current iteration for the row

rowinfo\_penaltycolumnplus Get the index of the positive penalty column for the row (+)
rowinfo\_penaltycolumnplusvalue Get the value of the positive penalty column for the row (+)
rowinfo\_penaltycolumnplusdj Get the reduced cost of the positive penalty column for the row
(+)

rowinfo\_penaltycolumnminus Get the index of the negative penalty column for the row (-)
rowinfo\_penaltycolumnminusvalue Get the value of the negative penalty column for the row (-)
rowinfo\_penaltycolumnminusdj Get the reduced cost of the negative penalty column for the
row (-)

# problem.getrows

## **Purpose**

Returns the nonzeros in the constraint matrix for the rows in a given range.

## **Synopsis**

problem.getrows (mstart, mclind, dmatval, size, first, last)

## **Arguments**

mstart	Array which will be filled with the indices indicating the starting offsets in the mclind and dmatval arrays for each requested row. It must be of length at least
	last-first+2. Column i starts at position mstart[i] in the mrwind and dmatval arrays, and has mstart[i+1]-mstart[i] elements in it. May be None if not required.
mclind	Arrays which will be filled with at most size column indices of the nonzero elements for each row. May be None if not required.
dmatval	Array which will be filled with at most size nonzero element values. May be None if not required.
size	Maximum number of elements to be retrieved.
first	First row in the range.
last	Last row in the range.

## **Related topics**

problem.getcols,problem.getrowtype.

## problem.getrowstatus

#### **Purpose**

Retrieve the status setting of a constraint

#### **Synopsis**

```
status = problem.getrowstatus (rowIndex)
```

#### **Arguments**

 ${\tt rowindex} \qquad {\tt The index of the matrix row whose data is to be obtained}.$ 

status The status settings.

## **Example**

This recovers the status of the rows of the matrix of the current problem and reports those which are flagged as enforced constraints.

```
m = p.getintattrib ('rows')
for i in range(m):
    status = p.getrowstatus (i)
    if (Status & 0x800) print ("Row {0} is enforced".format (i))
```

#### **Further information**

See the section on bitmap settings of the XSLP reference manual for details on the possible information in Status.

## **Related topics**

problem.chgrowstatus

## problem.getrowtype

## **Purpose**

Returns the row types for the rows in a given range.

#### **Synopsis**

```
problem.getrowtype (qrtype, first, last)
```

### **Arguments**

Character array of length last-first+1 characters where the row types will be
returned:
 N indicates a free constraint;
 L indicates a ≤ constraint;
 E indicates an = constraint;
 G indicates a ≥ constraint;
 R indicates a range constraint.

first First row in the range.
last Last row in the range.

#### **Example**

The following example retrieves the type of the first four rows of the problem into an array qrt:

```
qrt = []
p.getrowtype (qrt, 0, 3)
```

#### **Related topics**

problem.chgrowtype,problem.getrows.

## problem.getrowwt

#### **Purpose**

Get the initial penalty error weight for a row

#### **Synopsis**

```
value = problem.getrowwt (rowindex)
```

### **Arguments**

rowindex The index of the row whose weight is to be retrieved.

value The value of the weight.

## **Example**

The following example gets the initial weight of row number 2.

```
value = p.getrowwt (2)
```

#### **Further information**

The initial row weight is used only when the augmented structure is created. After that, the current weighting can be accessed using problem.getrowinfo.

#### **Related topics**

problem.chgrowwt,problem.getrowinfo

## problem.getscaledinfeas

#### **Purpose**

Returns a list of scaled infeasible primal and dual variables for the original problem. If the problem is currently presolved, it is postsolved before the function returns.

#### **Synopsis**

```
problem.getscaledinfeas (mx, mslack, mdual, mdj)
```

### **Arguments**

mx Array to store the primal infeasible variables. May be None if not required.

mslack Array to store the primal infeasible rows. May be None if not required.

mdual Array to store the dual infeasible rows. May be None if not required.

mdj Array to store the dual infeasible variables. May be None if not required.

#### **Example**

```
mx = []
mslack = []
mdual = []
mdj = []
p.getscaledinfeas (mx, mslack, mdual, mdj)
```

```
problem.getiinfeas, problem.getiisdata, problem.iisall, problem.iisclear,
problem.iisfirst, problem.iisisolations, problem.iisnext, problem.iisstatus,
problem.iiswrite.
```

## problem.getSlack

### **Purpose**

Return the slack for all constraints of the problem w.r.t. the solution found by solve(). This function works both with continuous and mixed-integer optimization problems.

### **Synopsis**

```
s = problem.getSlack ()
```

## **Example**

```
p.solve ()
print ("slack:", p.getSlack ())
```

```
problem.solve,problem.getlpsol,problem.getmipsol,problem.getSolution,
problem.getDual,problem.getRCost,problem.getProbStatus,
problem.getProbStatusString.
```

## problem.getslpsol

#### **Purpose**

Obtain the solution values for the most recent SLP iteration

#### **Synopsis**

```
problem.getslpsol (x, slack, dual, dj)
```

#### **Arguments**

х	Array of length problem.attributes.xslp_originalcols to hold the values of the primal variables. May be None if not required.
slack	Array of length problem.attributes.xslp_originalrows to hold the values of the slack variables. May be None if not required.
dual	Array of length problem.attributes.xslp_originalrows to hold the values of the dual variables. May be None if not required.
dj	Array of length problem.attributes.xslp_originalcols to hold the recuded costs of the primal variables. May be None if not required.

#### **Example**

The following code fragment recovers the values and reduced costs of the primal variables from the most recent SLP iteration:

```
ncol = p.getintattrib (prob,xpress.xslp_originalcols)
val = []
dj = []
p.getslpsol (val,None,None,dj)
```

#### **Further information**

getslpsol can be called at any time after an SLP iteration has completed, and will return the same values even if the problem is subsequently changed. getslpsol returns values for the columns and rows originally in the problem and not for any augmentation rows or columns. To access the values of any augmentation columns or rows, use getlpsol; accessing the augmented solution is only recommended if  $xslp\_presolvelevel$  indicates that the problem dimensions should not be changed in presolve.

## problem.getSolution

#### **Purpose**

Returns the solution to an optimization problem if called after the solve () function has terminated. This function works with both continuous and mixed-integer optimization problems.

### **Synopsis**

```
x = problem.getSolution (indices = None)
```

#### **Argument**

indices (optional) specify indices, datas, or names of the object whose solution is requested

## **Example**

```
y=xpress.var(name='var1')
x=xpress.var(name='var2')
[...]
p.solve ()
print ("solution:", p.getSolution ())
print ("x is", p.getSolution (x))
print ("first four var:", p.getSolution ([:4]))
print ("x and y are", p.getSolution (['var1', 'var2']))
```

#### **Further information**

For efficiency reasons it is preferable that one call to getSolution is made, as the whole vector is obtained at each call and only the desired portion is returned.

```
problem.getlpsol,problem.getmipsol,problem.getDual,problem.getSlack,
problem.getRCost,problem.getProbStatus,problem.getProbStatusString.
```

## problem.getSOS

#### **Purpose**

Returns one or more SOSs of a problem corresponding to one or more indices passed as arguments. These SOSs are returned as Python objects and can be used to access and manipulate the problem.

### **Synopsis**

```
x = problem.getSOS (index, first, last)
```

#### **Arguments**

first (optional) The first index of the SOSs to be returned.

last (optional) The last index of the SOSs to be returned.

index (optional) Either an integer or a list of integers (not necessarily sorted) with the

index/indices of all SOSs to be returned.

#### **Further information**

All arguments are optional. If neither of them is provided, the return value is a list with all SOSs of the problem. Otherwise, either first and last or just index can be passed.

## **Related topics**

problem.getVariable,problem.getConstraint,

## problem.gettolset

#### **Purpose**

Retrieve the values of a set of convergence tolerances for an SLP problem

#### **Synopsis**

```
status = problem.gettolset (nslptol, tols)
```

#### **Arguments**

nslptol The index of the tolerance set. status The bit-map of status settings.

Tols Array of 9 double-precision values to hold the tolerances. May be None if not required.

#### **Example**

The following example retrieves the values for tolerance set 3 and prints those which are set:

```
tols = []
status = p.gettolset (3, Tols)
for i in range(9):
   if status & (1<<i):
      print ("Tolerance {0} = {1}".format (i,Tols[i]))</pre>
```

#### **Further information**

If Tols is None, then the corresponding information will not be returned.

If Tols is not None, then a set of 9 values will always be returned. Status indicates which of these values is active as follows. Bit n of Status is set if Tols[n] is active, where n is:

Entry / Bit	Tolerance	XSLP constant	XSLP bit constant
0	Closure tolerance (TC)	xslp_TOLSET_TC	xslp_TOLSETBIT_TC
1	Absolute delta tolerance (TA)	xslp_TOLSET_TA	xslp_TOLSETBIT_TA
2	Relative delta tolerance (RA)	xslp_TOLSET_RA	xslp_TOLSETBIT_RA
3	Absolute coefficient tolerance (TM)	xslp_TOLSET_TM	xslp_TOLSETBIT_TM
4	Relative coefficient tolerance (RM)	xslp_TOLSET_RM	xslp_TOLSETBIT_RM
5	Absolute impact tolerance (TI)	xslp_TOLSET_TI	xslp_TOLSETBIT_TI
6	Relative impact tolerance (RI)	xslp_TOLSET_RI	xslp_TOLSETBIT_RI
7	Absolute slack tolerance (TS)	xslp_TOLSET_TS	xslp_TOLSETBIT_TS
8	Relative slack tolerance (RS)	xslp_TOLSET_RS	xslp_TOLSETBIT_RS

The xslp\_TOLSET constants can be used to access the corresponding entry in the value arrays, while the xslp\_TOLSETBIT constants are used to set or retrieve which tolerance values are used for a given SLP variable.

#### **Related topics**

#### **Related topics**

problem.addtolsets, problem.chgtolset, problem.deltolsets, problem.loadtolsets

# problem.getub

## **Purpose**

Returns the upper bounds on the columns in a given range.

## **Synopsis**

```
problem.getub (ub, first, last)
```

## **Arguments**

ub Array where the last - first + 1 upper bounds are to be placed.

first First column in the range.
last Last column in the range.

### **Related topics**

problem.chgbounds,problem.getlb.

## problem.getunbvec

#### **Purpose**

Returns the index vector which causes the primal simplex or dual simplex algorithm to determine that a problem is primal or dual unbounded respectively.

#### **Synopsis**

```
junb = problem.getunbvec ()
```

#### **Further information**

When solving using the dual simplex method, if the problem is primal infeasible then getunbvec returns the pivot row where dual unboundedness was detected. Also note that when solving using the dual simplex method, if the problem is primal unbounded then getunbvec returns -1 since the problem is dual infeasible and not dual unbounded.

#### **Related topics**

problem.getinfeas,problem.lpoptimize.

## problem.getvar

#### **Purpose**

Retrieve information about an SLP variable

#### **Synopsis**

#### **Arguments**

colindex The index of the column.

detrow Address of an integer to receive the index of the determining row. May be None if not required.

initstepbound Address of a double precision variable to receive the value of the initial step bound of the variable. May be None if not required.

stepbound Address of a double precision variable to receive the value of the current step bound of the variable. May be None if not required.

penalty Address of a double precision variable to receive the value of the penalty delta

weighting of the variable. May be None if not required.

damp Address of a double precision variable to receive the value of the current damping factor of the variable. May be None if not required.

initvalue Address of a double precision variable to receive the value of the initial value of the variable. May be None if not required.

value Address of a double precision variable to receive the current activity of the variable. May be None if not required.

Address of an integer to receive the index of the tolerance set of the variable. May be None if not required.

history Address of an integer to receive the SLP history of the variable. May be None if not required.

Address of an integer to receive the convergence status of the variable as defined in the "Convergence Criteria" section (The returned value will match the numbering of the tolerances). May be None if not required.

vartype Address of an integer to receive the status settings (a bitmap defining the existence of certain properties for this variable). The following bits are defined:

Bit 1: Variable has a delta vector
Bit 2: Variable has an initial value
Bit 14: Variable is the reserved "=" column

Other bits are reserved for internal use. May be None if not required.

delta Address of an integer to receive the index of the delta vector for the variable. May be None if not required.

penaltydelta Address of an integer to receive the index of the first penalty delta vector for the variable. The second penalty delta immediately follows the first. May be None if not required.

updaterow Address of an integer to receive the index of the update row for the variable. May be None if not required.

oldvalue Address of a double precision variable to receive the value of the variable at the previous SLP iteration. May be None if not required.

#### **Example**

The following example retrieves the current value, convergence history and status for column 3.

(a,b,c,d,e,value,g,history,converged,j,k,i,h,k,l) = p.getvar (3)

#### **Further information**

If colindex refers to a column which is not an SLP variable, then all the return values will indicate that there is no corresponding data.

detrow will be set to -1 if there is no determining row.

delta, penaltydelta and updaterow will be set to -1 if there is no corresponding item.

## **Related topics**

 $\verb|problem.addvars,problem.chgvar,problem.delvars,problem.loadvars|$ 

## problem.getVariable

#### **Purpose**

Returns one or more variables of a problem corresponding to one or more indices passed as arguments. These variables are returned as Python objects and can be used to access and manipulate the problem.

## **Synopsis**

```
x = problem.getVariable (index, first, last)
```

#### **Arguments**

first (optional) The first index of the variables to be returned. It must be between 0 and COLS

- 1.

last (optional) The last index of the variables to be returned. It must be between 0 and COLS

- 1.

index (optional) Either an integer or a list of integers (not necessarily sorted) with the

index/indices of all variables to be returned, all between 0 and COLS - 1

#### **Further information**

All arguments are optional. If neither of them is provided, the return value is a list with all variables of the problem. Otherwise, either first and last or just index can be passed.

#### **Related topics**

problem.getConstraint,problem.getSOS.

## problem.globalsol

#### **Purpose**

Initiate the Xpress Nonlinear mixed integer SLP (MISLP) algorithm

#### **Synopsis**

```
problem.globalsol ()
```

### **Example**

The following example solves the continuous relaxation of the problem and then finds the integer solution.

```
p.nlpoptimize ()
p.globalsol ()
```

#### **Further information**

The current Xpress Nonlinear mixed integer problem will be maximized or minimized using the algorithm defined by the control variable xslp\_mipalgorithm.

It is recommended that problem.nlpoptimize be used first to obtain a converged solution to the relaxed problem. If this is not done, ensure that xslp\_ojsense is set appropriately.

See the chapter on Mixed Integer Non-Linear Programming in the SLP Reference Manual for more information about the Xpress Nonlinear MISLP algorithms.

```
xslp_MIPALGORITHM, xslp_OBJSENSE
```

# problem.hasdualray

## **Purpose**

Returns true if a dual ray (dual unbounded direction) exists for the current problem, if the problem is found to be infeasible.

## **Synopsis**

```
v = problem.hasdualray ()
```

## **Related topics**

problem.getdualray.

# problem.hasprimalray

## **Purpose**

Returns true if a primal ray (primal unbounded direction) exists for the current problem, if the problem is found to be unbounded.

## **Synopsis**

```
v = problem.hasprimalray ()
```

## **Related topics**

problem.getprimalray.

## problem.iisall

#### **Purpose**

Performs an automated search for independent Irreducible Infeasible Sets (IIS) in an infeasible problem.

#### **Synopsis**

```
problem.iisall ()
```

#### **Example**

This example searches for IISs and then questions the problem attribute NUMIIS to determine how many were found:

```
p.iisall ()
print ("The problem has {0} IISs".format (p.attributes.numiis))
```

#### **Further information**

- 1. A model may have several infeasibilities. Repairing a single IIS may not make the model feasible. For this reason the Optimizer can find an IIS for each of the infeasibilities in a model. If the control MAXIIS is set to a positive integer value then the problem.iisall command will stop if MAXIIS IISs have been found. By default the control MAXIIS is set to -1, in which case an IIS is found for each of the infeasibilities in the model.
- 2. The problem attribute NUMIIS allows the user to recover the number of IISs found in a particular search. Alternatively, the problem.iisstatus function may be used to retrieve the number of IISs found by the problem.iisfirst, problem.iisnext, or problem.iisall functions.

#### **Related topics**

problem.getiisdata,problem.iisclear,problem.iisfirst,problem.iisisolations,problem.iisnext,problem.iisstatus,problem.iiswrite.

## problem.iisclear

#### **Purpose**

Resets the search for Irreducible Infeasible Sets (IIS).

#### **Synopsis**

```
problem.iisclear ()
```

#### **Further information**

- 1. The information stored internally about the IISs identified by problem.iisfirst, problem.iisnext or problem.iisall are cleared. Functions problem.getiisdata, problem.iisstatus, problem.iiswrite and problem.iisisolations cannot be called until the IIS identification procedure is started again.
- 2. This function is automatically called by problem.iisfirst and problem.iisall.

## **Related topics**

problem.getiisdata,problem.iisall,problem.iisfirst,problem.iisisolations, problem.iisnext,problem.iisstatus,problem.iiswrite.

## problem.iisfirst

#### **Purpose**

Initiates a search for an Irreducible Infeasible Set (IIS) in an infeasible problem. The returned value can be 0 for success, 1 if the problem is feasible, or 2 in case of error.

#### **Synopsis**

```
status_code = problem.iisfirst (iismode)
```

#### Argument

iismode The IIS search mode:
 stops after finding the initial infeasible subproblem;
 find an IIS, emphasizing simplicity of the IIS;
 find an IIS, emphasizing a quick result.

#### **Example**

This looks for the first IIS.

```
p.iisfirst (1)
```

#### **Further information**

- 1. A model may have several infeasibilities. Repairing a single IIS may not make the model feasible. For this reason the Optimizer can find an IIS for each of the infeasibilities in a model. For the generation of several independent IISs use functions problem.iisnext or problem.iisall.
- 2. IIS sensitivity filter: after an optimal but infeasible first phase primal simplex, it is possible to identify a subproblem containing all the infeasibilities (corresponding to the given basis) to reduce the size of the IIS working problem dramatically, i.e., rows with zero duals (thus with artificials of zero reduced cost) and columns that have zero reduced costs may be deleted. Moreover, for rows and columns with nonzero costs, the sign of the cost is used to relax equality rows either to less than or greater than equal rows, and to drop either possible upper or lower bounds on columns.
- 3. Initial infeasible subproblem: The subproblem identified after the sensitivity filter is referred to as initial infeasible subproblem. Its size is crucial to the running time of the deletion filter and it contains all the infeasibilities of the first phase simplex, thus if the corresponding rows and bounds are removed the problem becomes feasible.
- 4. problem.iisfirst performs the initial sensitivity analysis on rows and columns to reduce the problem size, and sets up the initial infeasible subproblem. This subproblem significantly speeds up the generation of IISs, however in itself it may serve as an approximation of an IIS, since its identification typically takes only a fraction of time compared to the identification of an IIS.
- 5. The IIS approximation and the IISs generated so far are always available.

```
problem.getiisdata,problem.iisall,problem.iisclear,problem.iisisolations,
problem.iisnext,problem.iisstatus,problem.iiswrite.
```

# problem.iisisolations

## **Purpose**

Performs the isolation identification procedure for an Irreducible Infeasible Set (IIS).

## **Synopsis**

```
problem.iisisolations (num)
```

#### **Argument**

num

The number of the IIS identified by either problem.iisfirst, problem.iisall in which the isolations should be identified.

## **Example**

This example finds the first IIS and searches for the isolations in that IIS.

```
if p.iisfirst (1) == 0:
    iisisolations (1)
```

#### **Further information**

- 1. An IIS isolation is a special constraint or bound in an IIS. Removing an IIS isolation constraint or bound will remove all infeasibilities in the IIS without increasing the infeasibilities in any row or column outside the IIS, thus in any other IISs. The IIS isolations thus indicate the likely cause of each independent infeasibility and give an indication of which constraint or bound to drop or modify. It is not always possible to find IIS isolations.
- 2. Generally, one should first look for rows or columns in the IIS which are both in isolation, and have a high dual multiplier relative to the others.
- 3. The num parameter cannot be zero: the concept of isolations is meaningless for the initial infeasible subproblem.

# **Related topics**

```
problem.getiisdata,problem.iisall,problem.iisclear,problem.iisfirst,problem.iisnext,problem.iisstatus,problem.iiswrite.
```

# problem.iisnext

# **Purpose**

Continues the search for further Irreducible Infeasible Sets (IIS), or calls problem.iisfirst if no IIS has been identified yet. The returned value is 0 in case of success; 1 if no more IIS could be found, or problem is feasible if no problem.iisfirst call preceded; or 2 in case of an error.

# **Synopsis**

```
status_code = problem.iisnext ()
```

## **Example**

This looks for a further IIS.

```
while p.iisnext () == 0:
   [...] # do something with the iis
```

#### **Further information**

- A model may have several infeasibilities. Repairing a single IIS may not make the model feasible. For this reason the Optimizer attempts to find an IIS for each of the infeasibilities in a model. Call the problem.iisnext function repeatedly, or use the problem.iisall function to retrieve all IIS at once.
- 2. This function is not affected by the control MAXIIS.
- 3. If the problem has been modified since the last call to problem.iisfirst or problem.iisnext, the generation process has to be started from scratch.

## **Related topics**

problem.getiisdata,problem.iisall,problem.iisclear,problem.iisfirst, problem.iisisolations,problem.iisstatus,problem.iiswrite.

# problem.iisstatus

# **Purpose**

Returns statistics on the Irreducible Infeasible Sets (IIS) found so far by problem.iisfirst, problem.iisnext, or problem.iisall. The returned value is the number of IISs found so far.

## **Synopsis**

```
iiscount = problem.iisstatus (rowsizes, colsizes, suminfeas, numinfeas)
```

# **Arguments**

```
rowsizes Number of rows in the IISs.

colsizes Number of bounds in the IISs.

suminfeas The sum of infeasibilities in the IISs after the first phase simplex.

numinfeas The number of infeasible variables in the IISs after the first phase simplex.
```

## **Example**

This example first retrieves the number of IISs found so far, and then retrieves their main properties. Note that the arrays have size count+1, since the first index is reserved for the initial infeasible subset.

```
rs = []
cs = []
ninf = []
p.iisstatus (rs, cs, numinfeas = ninf) # suminf is not of interest
```

#### **Further information**

- 1. The arrays are 0 based, index 0 corresponding to the initial infeasible subproblem.
- 2. The arrays may be None if not required.
- 3. For the initial infeasible problem (at position 0) the subproblem size is returned (which may be different from the number of bounds), while for the IISs the number of bounds is returned (usually much smaller than the number of columns in the IIS).
- 4. Note that the values in suminfeas and numinfeas heavily depend on the actual basis where the simplex has stopped.
- 5. iiscount is set to -1 if the search for IISs has not yet started.

#### **Related topics**

```
problem.getiisdata, problem.iisall, problem.iisclear, problem.iisfirst, problem.iisisolations, problem.iisnext, problem.iiswrite.
```

# problem.iiswrite

# **Purpose**

Writes an LP/MPS/CSV file containing a given Irreducible Infeasible Set (IIS). If 0 is passed as the IIS number parameter, the initial infeasible subproblem is written.

## **Synopsis**

```
problem.iiswrite (num, fn, type, typeflags)
```

## **Arguments**

num The ordinal number of the IIS to be written.

fn The name of the file to be created.

type Type of file to be created:

o creates an lp/mps file containing the IIS as a linear programming problem;

1 creates a comma separated (csv) file containing the description and supplementary

information on the given IIS.

typeflags Flags passed to the problem.write function.

## **Example**

This writes the first IIS (if one exists and is already found) as an Ip file.

```
p.iiswrite (1, "iis.lp", 0, "l")
```

#### **Further information**

- 1. Please note that there are problems on the boundary of being infeasible or not. For such problems, feasibility or infeasibility often depends on tolerances or even on scaling. This phenomenon makes it possible that after writing an IIS out as an LP file and reading it back, it may report feasibility. As a first check it is advised to consider the following options:
  - (a) save the IIS using MPS hexadecimal format to eliminate rounding errors associated with conversion between internal and decimal representation.
  - (b) turn presolve off since the nature of an IIS makes it necessary that during their identification the presolve is turned off.
  - (c) use the primal simplex method to solve the problem.
- 2. Note that the original sense of the original objective function plays no role in an IIS.
- 3. Even though an attempt is made to identify the most infeasible IISs first by the problem.iisfirst, problem.iisnext, and problem.iisall functions, it is also possible that an IIS becomes just infeasible in problems that are otherwise highly infeasible. In such cases, it is advised to try to deal with the more stable IISs first, and consider to use the infeasibility breaker tool if only slight infeasibilities remain.
- 4. The LP or MPS files created by problem.iiswrite corresponding to an IIS contain no objective function, since infeasibility is independent from the objective.

## **Related topics**

problem.getiisdata,problem.iisall,problem.iisclear,problem.iisfirst, problem.iisisolations,problem.iisnext,problem.iisstatus.

# problem.interrupt

# **Purpose**

Interrupts the Optimizer algorithms.

# **Synopsis**

```
problem.interrupt (reason)
```

## **Argument**

reason The reason for stopping. Possible reasons are:

xpress.stop\_timelimit time limit hit;
xpress.stop\_ctrlc control C hit;
xpress.stop\_nodelimit node limit hit;
xpress.stop\_iterlimit iteration limit hit;

xpress.stop\_mipgap MIP gap is sufficiently small;

xpress.stop\_sollimit solution limit hit; xpress.stop\_user user interrupt.

## **Further information**

The interrupt command can be called from any callback.

# problem.loadbasis

# **Purpose**

Loads a basis as specified by the user.

#### **Synopsis**

```
problem.loadbasis (rstatus, cstatus)
```

#### **Arguments**

rstatus

Array of length problem.attributes.rows containing the basis status of the slack, surplus or artificial variable associated with each row. The status must be one of:

- o slack, surplus or artificial is non-basic at lower bound;
- slack, surplus or artificial is basic;
- 2 slack or surplus is non-basic at upper bound.
- 3 slack or surplus is super-basic.

cstatus

Array of length problem.attributes.cols containing the basis status of each of the columns in the constraint matrix. The status must be one of:

- variable is non-basic at lower bound or superbasic at zero if the variable has no lower bound:
- variable is basic;
- 2 variable is at upper bound;
- 3 variable is super-basic.

# **Example**

This example loads a problem and then reloads a (previously optimized) basis from a similar problem to speed up the optimization:

```
p.read ("problem", "")
p.loadbasis (rstatus, cstatus)
p.lpoptimize ("")
```

#### **Further information**

If the problem has been altered since saving an advanced basis, one can alter the basis as follows before loading it:

- Make new variables non-basic at their lower bound (cstatus[icol]=0), unless a variable has an infinite lower bound and a finite upper bound, in which case make the variable non-basic at its upper bound (cstatus[icol]=2);
- Make new constraints basic (rstatus [ jrow] = 1);
- Try not to delete basic variables, or non-basic constraints.

## **Related topics**

problem.getbasis,problem.getpresolvebasis,problem.loadpresolvebasis.

# problem.loadbranchdirs

# **Purpose**

Loads directives into the current problem to specify which global entities the Optimizer should continue to branch on when a node solution is global feasible.

## **Synopsis**

problem.loadbranchdirs (mcols, mbranch)

# **Arguments**

mcols Array containing the column numbers. A negative value indicates a set number (the first

set being -1, the second -2, and so on).

mbranch Array containing either 0 or 1 for the entities given in mcols. Entities for which mbranch

is set to 1 will be branched on until fixed before a global feasible solution is returned. If

mbranch is None, the branching directive will be set for all entities in mcols.

# **Related topics**

problem.loaddirs,problem.readdirs.

# problem.loadcoefs

## **Purpose**

Load non-linear coefficients into the SLP problem

#### **Synopsis**

```
problem.loadcoefs (rowindex, colindex, factor, fstart, parsed, type, value)
```

## **Arguments**

rowindex Integer array holding index of row for the coefficient. Integer array holding index of column for the coefficient. colindex factor Double array holding factor by which formula is scaled. If this is None, then a value of 1.0 will be used. fstart Integer array holding the start position in the arrays Type and Value of the formula for the coefficients. FormulaStart[nSLPCoef] should be set to the next position after the end of the last formula. Integer indicating whether the token arrays are formatted as internal unparsed parsed (Parsed=0) or internal parsed reverse Polish (Parsed=1). Array of token types providing the formula for each coefficient. type value Array of values corresponding to the types in Type.

#### Example

Assume that the rows and columns of Prob are named Row1, Row2 ..., Col1, Col2 ... The following example loads coefficients representing:

```
Co12 * Co13 + Co16 * Co12^2 into Row1 and
Col2 ^ 2 into Row3.
      rowindex = [Row1, Row1, Row3]
      colindex = [Col2, Col6, Col2]
      formulastart = []
      n = 0
      ncoef = 0
      formulastart[ncoef], ncoef = n, ncoef + 1
      Type[n], Value[n], n = xslp_op_col, 3, n+1
      Type[n],
                          n = xslp_op_eof,
      formulastart[ncoef], ncoef = n, ncoef + 1
      Type[n], Value[n], n = xslp_op_col, 2,
                                                           n+1
      Type[n], Value[n], n = xslp\_op\_col, 2,
      Type[n], Value[n], n = xslp_op_op, xslp_MULTIPLY, n+1
      Type[n],
                          n = xslp_op_eof,
                                                            n+1
      formulastart[ncoef], ncoef = n, ncoef + 1
      Type[n], Value[n], n = xslp_op_col, 2, n+1
      Type[n],
                          n = xslp_op_eof,
                                               n+1
      formulastart [ncoef] = n
```

p.loadcoefs (rowindex, colindex, None, formulastart, 1, Type, Value)

The first coefficient in Row1 is in Co12 and has the formula Co13, so it represents Co12 \* Co13.

The second coefficient in Row1 is in Co16 and has the formula Co12  $\star$  Co12 so it represents Co16  $\star$  Co12^2. The formulae are described as parsed (parsed=1), so the formula is written as

Co12 Co12 \* rather than the unparsed form

Col2 \* Col2

The last coefficient, in Row3, is in Co12 and has the formula Co12, so it represents Co12 \* Co12.

#### **Further information**

The j<sup>th</sup> coefficient is made up of two parts: Factor and Formula. Factor is a constant multiplier, which can be provided in the Factor array. If Xpress Nonlinear can identify a constant factor in Formula, then it will use that as well, to minimize the size of the formula which has to be calculated. Formula is made up of a list of tokens in Type and Value starting at FormulaStart[j]. The tokens follow the rules for parsed or unparsed formulae as indicated by the setting of Parsed. The formula must be terminated with an xslp\_op\_eof token. If several coefficients share the same formula, they can have the same value in FormulaStart. For possible token types and values see the chapter on "Formula Parsing".

The loadcoefs function loads items into the SLP problem. Any existing items of the same type are deleted first. The corresponding addcoefs function adds or replace items leaving other items of the same type unchanged.

# **Related topics**

problem.addcoefs,problem.chgnlcoef,problem.chgccoef,problem.getcoefformula, problem.getcoef

# problem.loadcuts

# **Purpose**

Loads cuts from the cut pool into the matrix. Without calling loadcuts the cuts will remain in the cut pool but will not be active at the node. Cuts loaded at a node remain active at all descendant nodes unless they are deleted using problem.delcuts.

# **Synopsis**

```
problem.loadcuts (itype, interp, cutind)
```

## **Arguments**

#### **Related topics**

problem.addcuts, problem.delcpcuts, problem.delcuts, problem.getcpcutlist, Section
"Working with the cut manager" of the Xpress Optimizer reference manual.

# problem.loaddelayedrows

## **Purpose**

Specifies that a set of rows in the problem will be treated as delayed rows during a global search. These are rows that must be satisfied for any integer solution, but will not be loaded into the active set of constraints until required.

## **Synopsis**

```
problem.loaddelayedrows (mrows)
```

#### **Argument**

mrows

An array of row indices to treat as delayed rows.

# **Example**

This sets the first six matrix rows as delayed rows in the global problem prob.

```
p.loaddelayedrows ([0,1,2,3,4,5])
p.mipoptimize ("")
```

# **Further information**

Delayed rows must be set up before solving the problem. Any delayed rows will be removed from the problem after presolve and added to a special pool. A delayed row will be added back into the active matrix only when such a row is violated by an integer solution found by the Optimizer.

# **Related topics**

problem.loadmodelcuts.

# problem.loaddfs

# **Purpose**

Load a set of distribution factors

# **Synopsis**

```
problem.loaddfs (colindex, rowindex, value)
```

## **Arguments**

colindex Array of columns whose distribution factor is to be changed.

rowindex Array of rows where each distribution factor applies.
value Array of the new values of the distribution factors.

# **Example**

The following example loads distribution factors as follows:

```
column 282 in row 134 = 0.1
column 282 in row 136 = 0.15
column 285 in row 133 = 1.0.
```

Any other first-order derivative placeholders are set to xslp\_DELTA\_Z.

```
colindex = [282, 282, 285]
rowindex = [134, 136, 133]
value = [0.1, 0.15, 1]
p.loaddfs (colindex, rowindex, value)
```

#### **Further information**

The distribution factor of a column in a row is the matrix coefficient of the corresponding delta vector in the row. Distribution factors are used in conventional recursion models, and are essentially normalized first-order derivatives. Xpress SLP can accept distribution factors instead of initial values, provided that the values of the variables involved can all be calculated after optimization using determining rows, or by a callback.

The adddfs functions load additional items into the SLP problem. The corresponding loaddfs functions delete any existing items first.

#### **Related topics**

```
problem.adddfs,problem.chgdf,problem.getdf
```

# problem.loaddirs

# **Purpose**

Loads directives into the problem.

## **Synopsis**

problem.loaddirs (mcols, mpri, qbr, dupc, ddpc)

## **Arguments**

mcols Array containing the column numbers. A negative value indicates a set number (the first

set being -1, the second -2, and so on).

mpri Array containing the priorities for the columns or sets. Priorities must be between 0 and

1000. May be None if not required.

qbr Character array specifying the branching direction for each column or set:

the entity is to be forced up;the entity is to be forced down;

N not specified.

May be None if not required.

dupc Array containing the up pseudo costs for the columns or sets. May be None if not

required.

ddpc Array containing the down pseudo costs for the columns or sets. May be None if not

required.

# **Related topics**

problem.getdirs,problem.loadpresolvedirs,problem.readdirs.

# problem.loadlpsol

# **Purpose**

Loads an LP solution for the problem into the Optimizer. The returned status is either 0 if the solution is loaded or 1 if the solution is not loaded because the problem is in presolved status.

## **Synopsis**

```
status = problem.loadlpsol (x, slack, dual, dj)
```

# **Arguments**

х	Optional: Array of length problem.attributes.cols (for the original problem and not the presolve problem) containing the values of the variables.	
slack	Optional: double array of length problem.attributes.rows containing the values of slack variables.	
dual	Optional: double array of length problem.attributes.rows containing the values of dual variables.	
dj	Optional: double array of length problem.attributes.cols containing the values of reduced costs.	

# **Example**

This example loads a problem and loads a solution for the problem.

```
p.read ("problem", "")
status = p.loadlpsol (x, None, dual, None)
```

#### **Further information**

- 1. At least one of variables x and dual variables dual must be provided.
- 2. When variables x is None, the variables will be set to their bounds.
- 3. When slack variables slack is None, it will be computed from variables x. If slacks are provided, variables cannot be omitted.
- 4. When dual variables dual is None, both dual variables and reduced costs will be set to zero.
- 5. When reduced costs dj is None, it will be computed from dual variables dual. If reduced costs are provided, dual variables cannot be omitted.

#### **Related topics**

```
problem.getlpsol.
```

# problem.loadmipsol

## **Purpose**

Loads a MIP solution for the problem into the Optimizer. The returned status is one of the following values:

- -1: Solution rejected because an error occurred;
- 0: Solution accepted. When loading a solution before a MIP solve, the solution is always accepted. See Further Information below.
- 1: Solution rejected because it is infeasible;
- 2: Solution rejected because it is cut off;
- 3: Solution rejected because the LP reoptimization was interrupted.

# **Synopsis**

```
status = problem.loadmipsol (dsol)
```

#### **Argument**

dsol

Array of length problem.attributes.cols (for the original problem and not the presolve problem) containing the values of the variables.

# **Example**

This example loads a problem and then loads a solution found previously for the problem to help speed up the MIP search:

```
p.read ("problem", "")
status = p.loadmipsol (dsol)
p.mipoptimize ("")
```

#### **Further information**

- 1. When a solution is loaded before a MIP solve, the solution is simply placed in temporary storage until the MIP solve is started. Only after the MIP solve has commenced and any presolve has been applied, will the loaded solution be checked and possibly accepted as a new incumbent integer solution. There are no checks performed on the solution before the MIP solve and the returned status in <a href="mailto:problem.loadmipsol">problem.loadmipsol</a> will always be 0 for accepted.
- 2. Solutions can be loaded during a MIP solve using the optnode callback function. Any solution loaded this way is immediately checked and the returned status will be one of the values 0 through 3.
- 3. Loaded solution values will automatically be adjusted to fit within the current problem bounds.

#### **Related topics**

problem.getmipsol, problem.addcboptnode.

# problem.loadmodelcuts

## **Purpose**

Specifies that a set of rows in the problem will be treated as model cuts.

# **Synopsis**

```
problem.loadmodelcuts (mrows)
```

## **Argument**

mrows

An array of row indices to be treated as cuts.

## **Example**

This sets the first six matrix rows as model cuts in the global problem myprob.

```
p.loadmodelcuts ([0,1,2,3,4,5])
p.mipoptimize ("")
```

#### **Further information**

- 1. During presolve the model cuts are removed from the problem and added to an internal cut pool. During the global search, the Optimizer will regularly check this cut pool for any violated model cuts and add those that cuts off a node LP solution.
- 2. The model cuts must be "true" model cuts, in the sense that they are redundant at the optimal MIP solution. The Optimizer does not guarantee to add all violated model cuts, so they must not be required to define the optimal MIP solution.

# problem.loadpresolvebasis

# **Purpose**

Loads a presolved basis from the user's areas.

## **Synopsis**

```
problem.loadpresolvebasis (rstatus, cstatus)
```

#### **Arguments**

rstatus

Array containing the basis status of the slack, surplus or artificial variable associated with each row. The status must be one of:

- o slack, surplus or artificial is non-basic at lower bound;
- slack, surplus or artificial is basic;
- 2 slack or surplus is non-basic at upper bound.

cstatus

Array containing the basis status of each of the columns in the matrix. The status must be one of:

- variable is non-basic at lower bound or superbasic at zero if the variable has no lower bound:
- 1 variable is basic;
- 2 variable is at upper bound;
- 3 variable is super-basic.

# **Example**

The following example saves the presolved basis for one problem, loading it into another:

```
p1 = xpress.problem ()
p2 = xpress.problem ()

p1.read ("myprob", "")
p1.mipoptimize ("1")
rs = []
cs = []
p1.getpresolvebasis (rs, cs)

p2.read ("myprob2", "")
p2.mipoptimize ("1")
p2.loadpresolvebasis (rs, cs)
```

# **Related topics**

problem.getbasis,problem.getpresolvebasis,problem.loadbasis.

# problem.loadpresolvedirs

# **Purpose**

Loads directives into the presolved matrix.

#### **Synopsis**

```
problem.loadpresolvedirs (mcols, mpri, qbr, dupc, ddpc)
```

## **Arguments**

mcols Array containing the column numbers. A negative value indicates a set number (-1 being the first set, -2 the second, and so on).

mpri Array containing the priorities for the columns or sets. May be None if not required.

qbr Character array specifying the branching direction for each column or set:

the entity is to be forced up;the entity is to be forced down;

N not specified.

May be None if not required.

dupc Array containing the up pseudo costs for the columns or sets. May be None if not

required.

ddpc Array containing the down pseudo costs for the columns or sets. May be None if not

required.

## **Example**

The following loads priority directives for column 0 in the problem:

```
p.mipoptimize ("1")
p.loadpresolvedirs ([0], [1], None, None, None)
p.mipoptimize ("")
```

#### **Related topics**

problem.getdirs, problem.loaddirs.

# problem.loadproblem

## **Purpose**

Load an optimization problem, possibly with quadratic objective and/or constraints, and integer variables.

## **Synopsis**

# **Arguments**

probname A string of up to 200 characters containing the problem name.

qrtype Character array containing the row types:

L indicates a <= constraint;
E indicates an = constraint;
G indicates a >= constraint;
R indicates a range constraint;
N indicates a nonbinding constraint.

rhs Array containing the right hand side coefficients of the rows. The right hand side value

for a range row gives the **upper** bound on the row.

range Array containing the range values for range rows. Values for all other rows will be

ignored. May be  $\mathtt{None}$  if there are no ranged constraints. The lower bound on a range row is the right hand side value minus the range value. The sign of the range value is

ignored - the absolute value is used in all cases.

obj Array containing the objective function coefficients.

mstart Array containing the offsets in the mrwind and dmatval arrays of the start of the

elements for each column. This array is of length equal to the number ncol of added variables or, if mnel is None, ncol+1. If mnel is None the extra entry of mstart, mstart[ncol], contains the position in the mrwind and dmatval arrays at which an

extra column would start, if it were present.

mnel Array containing the number of nonzero elements in each column. May be None if all

elements are contiguous and mstart[ncol] contains the offset where the elements for column ncol+1 would start. This array is not required if the non-zero coefficients in the mrwind and dmatval arrays are continuous, and the mstart array has ncol+1

entries as described above. It may be None if not required.

mrwind Array containing the row indices for the nonzero elements in each column. If the indices

are input contiguously, with the columns in ascending order, the length of the mrwind is

mstart[ncol-1]+mnel[ncol-1] or, if mnel is None, mstart[ncol].

dmatval Array containing the nonzero element values; length as for mrwind.

dlb Array containing the lower bounds on the columns. Use -xpress.infinity to

represent a lower bound of minus infinity.

dub Array containing the upper bounds on the columns. Use xpress.infinity to

represent an upper bound of plus infinity.

mqc1 (optional) Array with the first variable in each quadratic term.
mqc2 (optional) Array with the second variable in each quadratic term.

dge (optional) Array with the quadratic coefficients.

qcrows (optional) Integer containing the indices of rows with quadratic matrices in them. Note

that the rows are expected to be defined in qrtype as type L.

qcnquads (optional) Array containing the number of nonzeros in each quadratic constraint matrix.

qcmqcol1 (optional) Array with a number of elements equal to the sum of the elements in qcnquads (i.e. the total number of quadratic matrix elements in all the constraints). It contains the first column indices of the quadratic matrices. Indices for the first matrix are listed from 0 to qcnquads [0]-1, for the second matrix from qcnquads [0] to

qcnquads[0]+ qcnquads[1]-1, etc.

qcmqcol2 (optional) Array containing the second index for the quadratic constraint matrices.

qcdqval (optional) Array containing the coefficients for the quadratic constraint matrices.

qgtype Character array containing the entity types:

B binary variables;

integer variables;

P partial integer variables;

s semi-continuous variables;

R semi-continuous integer variables.

mgcols (optional) Array containing the variables of the global entities.

(optional) Array containing the integer limits for the partial integer variables and lower bounds for semi-continuous and semi-continuous integer variables (any entries in the positions corresponding to binary and integer variables will be ignored). May be None if

not required.

qstype (optional) Character array of length equal to the number of sets specified,

problem.attributes.nsets, and specifies the set types:

1 SOS1 type sets;

2 SOS2 type sets.

May be None if not required.

msstart (optional) Array containing the offsets in the mscols and dref arrays indicating the

start of the sets. This array is of length nsets+1, the last member containing the offset

where set nsets+1 would start. May be None if not required.

mscols (optional) Array of length msstart [nsets] - 1 containing the columns in each set.

May be None if not required.

dref (optional) Array of length msstart[nsets]-1 containing the reference row entries for

each member of the sets. May be None if not required.

colname (optional) Array of containing the column names for all variables added.

rowname (optional) Array of containing the row names for all constraints added.

#### **Further information**

dlim

- 1. The objective function is of the form  $c^Tx + 1/2 x^TQx$  where Q is positive semi-definite for minimization problems and negative semi-definite for maximization problems. If this is not the case the optimization algorithms may converge to a local optimum or may not converge at all. Note that only the upper or lower triangular part of the Q matrix is specified.
- 2. All Q matrices in the constraints must be positive semi-definite. Note that only the upper or lower triangular part of the Q matrix is specified for constraints as well.
- 3. The row and column indices are from 0 to nrow-1 and 0 to ncol-1 respectively.
- 4. The row and column indices are from 0 to nrow-1 and 0 to ncol-1 respectively.
- 5. Semi-continuous lower bounds are taken from the dlim array. If this is None then they are given a default value of 1.0. If a semi-continuous variable has a positive lower bound then this will be used as the semi-continuous lower bound and the lower bound on the variable will be set to zero.

#### **Related topics**

problem.loadproblem, problem.read.

# problem.loadsecurevecs

# **Purpose**

Allows the user to mark rows and columns in order to prevent the presolve removing these rows and columns from the problem.

# **Synopsis**

```
problem.loadsecurevecs (mrow, mcol)
```

# **Arguments**

mrow Array containing the rows to be marked. May be None if not required.

mcol Array containing the columns to be marked. May be None if not required.

## **Example**

This sets the first six rows and the first four columns to not be removed during presolve.

```
p.read ("myprob", "")
p.loadsecurevecs (mrow = [0,1,2,3,4,5], mcol = [0,1,2,3])
p.mipoptimize ("")
```

# problem.loadtolsets

## **Purpose**

Load sets of standard tolerance values into an SLP problem

# **Synopsis**

```
problem.loadtolsets (slptol)
```

#### **Argument**

slptol Array of 9h items containing the 9 tolerance values for each set in order.

## **Example**

The following example creates two tolerance sets: the first has values of 0.005 for all tolerances; the second has values of 0.001 for relative tolerances (numbers 2,4,6,8), values of 0.01 for absolute tolerances (numbers 1,3,5,7) and zero for the closure tolerance (number 0).

tol = 
$$9*[0.005]+[0]+[0.01,0.001]*4$$
  
p.loadtolsets (tol)

#### **Further information**

A tolerance set is an array of 9 values containing the following tolerances:

Entry / Bit	Tolerance	XSLP constant	XSLP bit constant
0	Closure tolerance (TC)	xslp_TOLSET_TC	xslp_TOLSETBIT_TC
1	Absolute delta tolerance (TA)	xslp_TOLSET_TA	xslp_TOLSETBIT_TA
2	Relative delta tolerance (RA)	xslp_TOLSET_RA	xslp_TOLSETBIT_RA
3	Absolute coefficient tolerance (TM)	xslp_TOLSET_TM	xslp_TOLSETBIT_TM
4	Relative coefficient tolerance (RM)	xslp_TOLSET_RM	xslp_TOLSETBIT_RM
5	Absolute impact tolerance (TI)	xslp_TOLSET_TI	xslp_TOLSETBIT_TI
6	Relative impact tolerance (RI)	xslp_TOLSET_RI	xslp_TOLSETBIT_RI
7	Absolute slack tolerance (TS)	xslp_TOLSET_TS	xslp_TOLSETBIT_TS
8	Relative slack tolerance (RS)	xslp_TOLSET_RS	xslp_TOLSETBIT_RS

The xslp\_TOLSET constants can be used to access the corresponding entry in the value arrays, while the xslp\_TOLSETBIT constants are used to set or retrieve which tolerance values are used for a given SLP variable.

Once created, a tolerance set can be used to set the tolerances for any SLP variable. If a tolerance value is zero, then the default tolerance will be used instead. To force the use of a zero tolerance, use the problem.chqtolset function and set the Status variable appropriately.

See the section "Convergence Criteria" in the SLP reference manual for a fuller description of tolerances and their uses. The loadtolsets functions load items into the SLP problem. Any existing items of the same type are deleted first. The corresponding addtolsets functions add or replace items leaving other items of the same type unchanged.

# **Related topics**

problem.addtolsets, problem.deltolsets, problem.chqtolset, problem.gettolset

# problem.loadvars

## **Purpose**

Load SLP variables defined as matrix columns into an SLP problem

# **Synopsis**

# **Arguments**

colindex Integer array holding the index of the matrix column corresponding to each SLP variable.

vartype Bitmap giving information about the SLP variable as follows:

Bit 1 Variable has a delta vector;
Bit 2 Variable has an initial value;
Bit 14 Variable is the reserved "=" column;

May be None if not required.

detrow Integer array holding the index of the determining row for each SLP variable (a negative

value means there is no determining row)

May be None if not required.

segnum Integer array holding the index sequence number for cascading for each SLP variable (a

zero value means there is no pre-defined order for this variable)

May be None if not required.

tolindex Integer array holding the index of the tolerance set for each SLP variable (a zero value

means the default tolerances are used)

May be None if not required.

initvalue Double array holding the initial value for each SLP variable (use the VarType bit map to

indicate if a value is being provided)

May be None if not required.

stepbound Double array holding the initial step bound size for each SLP variable (a zero value

means that no initial step bound size has been specified). If a value of

xpress.infinity is used for a value in StepBound, the delta will never have step

bounds applied, and will almost always be regarded as converged.

May be None if not required.

#### **Example**

The following example loads two SLP variables into the problem. They correspond to columns 23 and 25 of the underlying LP problem. Column 25 has an initial value of 1.42; column 23 has no specific initial value

```
colindex = [23,25]
vartype = [0,2]
initvalue = [0,1.42]
p.loadvars (colindex, vartype, None, None, initvalue, None)
```

InitValue is not set for the first variable, because it is not used (VarType = 0). Bit 1 of VarType is set for the second variable to indicate that the initial value has been set. The arrays for determining rows, sequence numbers, tolerance sets and step bounds are not used at all, and so have been passed to the function as None.

# **Further information**

The loadvars functions load items into the SLP problem. Any existing items of the same type are deleted first. The corresponding addvars functions add or replace items leaving other items of the same type unchanged.

# **Related topics**

problem.addvars.problem.chgvar.problem.delvars.problem.getvar

# problem.lpoptimize

# **Purpose**

This function begins a search for the optimal continuous (LP) solution. The direction of optimization is given by OBJSENSE. The status of the problem when the function completes can be checked using LPSTATUS. Any global entities in the problem will be ignored.

# **Synopsis**

problem.lpoptimize (flags)

## **Argument**

flags

(optional) Flags to pass to lpoptimize. The default is "" or None, in which case the algorithm used is determined by the DEFAULTALG control. If the argument includes:

- b the model will be solved using the Newton barrier method;
- p the model will be solved using the primal simplex algorithm;
- d the model will be solved using the dual simplex algorithm;
- n (lower case N), the network part of the model will be identified and solved using the network simplex algorithm;

#### **Further information**

- 1. The algorithm used to optimize is determined by the DEFAULTALG control if no flags are provided. By default, the dual simplex is used for linear problems and the barrier is used for non-linear problems.
- 2. The d and p flags can be used with the n flag to complete the solution of the model with either the dual or primal algorithms once the network algorithm has solved the network part of the model.
- 3. The b flag cannot be used with the n flag.

#### **Related topics**

problem.mipoptimize, Chapter 4 of the Xpress Optimizer reference manual.

# problem.mipoptimize

## **Purpose**

This function begins a global search for the optimal MIP solution. The direction of optimization is given by OBJSENSE. The status of the problem when the function completes can be checked using MIPSTATUS.

## **Synopsis**

problem.mipoptimize (flags)

#### **Argument**

flags

(optional) Flags to pass to problem.mipoptimize, which specifies how to solve the initial continuous problem where the global entities are relaxed. If the argument includes:

- b the initial continuous relaxation will be solved using the Newton barrier method;
- p the initial continuous relaxation will be solved using the primal simplex algorithm;
- d the initial continuous relaxation will be solved using the dual simplex algorithm;
- n the network part of the initial continuous relaxation will be identified and solved using the network simplex algorithm;
- stop after having solved the initial continous relaxation.

#### **Further information**

- If the 1 flag is used, the Optimizer will stop immediately after solving the initial continuous relaxation.
   The status of the continuous solve can be checked with LPSTATUS and standard LP results are
   available, such as the objective value (LPOBJVAL) and solution (use problem.getlpsol), depending
   on LPSTATUS.
- 2. It is possible for the Optimizer to find integer solutions before solving the initial continuous relaxation, either through heuristics or by having the user load an initial integer solution. This can potentially result in the global search finishing before solving the continuous relaxation to optimality.
- 3. If the function returns without having completed the search for an optimal solution, the search can be resumed from where it stopped by calling problem.mipoptimize again.
- 4. The algorithm used to reoptimize the continuous relaxations during the global search is given by DEFAULTALG. The default is to use the dual simplex algorithm.

## **Related topics**

problem.mipoptimize.

# problem.msaddcustompreset

# **Purpose**

A combined version of msaddjob and msaddpreset. The preset described is loaded, topped up with the specific settings supplied

## **Synopsis**

## **Arguments**

description Text description of the job. Used for messaging, may be None if not required.

preset Which preset to load.

ivcols Indices of the variables for which to set an initial value. May be None if nIVs is zero. Initial values for the variables for which to set an initial value. May be None if nIVs is

zero.

control Python dictionary with control strings as keys and numbers as values. Note that only

numerical controls are allowed.

job\_object Job-specific user context object to be passed to the multistart callbacks.

#### **Further information**

This function allows for repeatedly calling the same multistart preset (e.g. initial values) using different basic controls.

# **Related topics**

problem.msaddpreset, problem.msaddjob, problem.msclear

# problem.msaddjob

# **Purpose**

Adds a multistart job to the multistart pool

# **Synopsis**

problem.msaddjob (description, ivcols, ivvalues, control, job\_object)

#### **Arguments**

description Text description of the job. Used for messaging, may be None if not required. ivcols Indices of the variables for which to set an initial value. May be None if nIVs is zero.

 ${\tt ivvalues}$  Initial values for the variables for which to set an initial value. May be None if nIVs is

zero.

control Python dictionary with control strings as keys and numbers as values. Note that only

numerical controls are allowed.

job\_object Job-specific user context object to be passed to the multistart callbacks.

#### **Further information**

Adds a mutistart job, applying the specified initial point and option combinations on top of the base problem, i.e. the options and initial values specified to the function is applied on top of the existing settigns.

This function allows for loading empty template jobs, that can then be identified using the pJobObject variable.

## **Related topics**

problem.msaddpreset,problem.msaddcustompreset,problem.msclear

# problem.msaddpreset

## **Purpose**

Loads a preset of jobs into the multistart job pool.

# **Synopsis**

```
problem.msaddpreset (description, preset, count, job_object)
```

## **Arguments**

description Text description of the preset. Used for messaging, may be None if not required.

preset Which preset to load.

count Maximum number of jobs to be added to the multistart pool.

job\_object Job-specific user context object to be passed to the multistart callbacks.

#### **Further information**

The following presets are defined:

msset\_initialvalues: generate count number of random base points.

msset\_solvers: load all solvers.

msset\_slp\_basic: load the most typical SLP tuning settings. A maximum of count jobs are loaded.

msset\_slp\_extended: load a comprehensive set of SLP tuning settings. A maximum of count jobs are loaded.

msset\_knitro\_basic: load the most typical Knitro tuning settings. A maximum of count jobs are loaded.

msset\_knitro\_extended: load a comprehensive set of Knitro tuning settings. A maximum of count jobs are loaded.

msset\_initialfiltered: generate count number of random base points, filtered by a merit function centred on initial feasibility.

See xslp\_MSMAXBOUNDRANGE for controlling the range in which initial values are generated.

#### **Related topics**

problem.msaddjob,problem.msaddcustompreset,problem.msclear

# problem.msclear

# **Purpose**

Removes all scheduled jobs from the multistart job pool

# **Synopsis**

```
problem.msclear ()
```

# **Related topics**

problem.msaddjob,problem.msaddpreset,problem.msaddcustompreset

# problem.name

# **Purpose**

Returns the name of the problem as a Python string.

# **Synopsis**

```
brian = problem.name ()
```

# **Related topics**

problem.setprobname.

# problem.nlpoptimize

# **Purpose**

Solves an SLP problem

# **Synopsis**

problem.nlpoptimize (flags)

# **Argument**

flags Flags affecting the solve. See the SLP reference manual for their meaning

# **Related topics**

problem.globalsol

# problem.objsa

# **Purpose**

Returns upper and lower sensitivity ranges for specified objective function coefficients. If the objective coefficients are varied within these ranges the current basis remains optimal and the reduced costs remain valid.

# **Synopsis**

```
problem.objsa (mindex, lower, upper)
```

## **Arguments**

mindex Array containing the indices of the columns whose objective function coefficients

sensitivity ranges are required.

lower Array of the same size as mindex where the objective function lower range values are

to be returned.

upper Array of the same size as mindex where the objective function upper range values are

to be returned.

## **Example**

Here we obtain the objective function ranges for the three columns: 2, 6 and 8:

```
1 = []
u = []
p.objsa ([2,8,6], 1, u)
```

After which 1 and u contain:

```
1 = [5, 3.8, 5.7]

u = [7, 5.2, 1e+20]
```

Meaning that the current basis remains optimal when  $5.0 \le C_2 \le 7.0$ ,  $3.8 \le C_8 \le 5.2$  and  $5.7 \le C_6$ ,  $C_i$  being the objective coefficient of column i.

#### **Further information**

objsa can only be called when an optimal solution to the current LP has been found. It cannot be used when the problem is MIP presolved.

# **Related topics**

problem.rhssa.

# problem.parsecformula

# **Purpose**

Parse a formula written as a character string into internal parsed (reverse Polish) format

# **Synopsis**

```
ntoken = problem.parsecformula (formula, type, value)
```

# **Arguments**

Number of tokens in the parsed formula (not counting the terminating xslp\_op\_eof token).

formula

Character string containing the formula, written in the same free-format style as used in formulae in Extended MPS format, with spaces separating tokens.

Type

Array of token types providing the parsed formula.

Value

Array of values corresponding to the types in Type.

# **Example**

Assuming that x and y are already defined as columns, the following example converts the formula "sin(x+y)" into internal parsed format, and then writes it out as a sequence of tokens.

```
type = []
value = []
ntoken = p.parsecformula ("sin ( x + y )", Type, Value)
i = 0
while type[i] != xslp_op_eof:
    str = p.itemname (type[i], value[i])
    printf (str)
    i += 1
```

#### **Further information**

Tokens are identified by name, so any columns or user functions which appear in the formula must already have been defined. Unidentified tokens will appear as type xslp\_UNKNOWN.

#### **Related topics**

problem.parseformula, problem.preparseformula

# problem.parseformula

## **Purpose**

Parse a formula written as an unparsed array of tokens into internal parsed (reverse Polish) format

## **Synopsis**

```
ntoken = problem.parseformula (intype, invalue, type, value)
```

## **Arguments**

intype Array of token types providing the unparsed formula.
 invalue Array of values corresponding to the types in inType.
 ntoken The number of tokens in the parsed formula (not counting the terminating xslp\_op\_eof token).
 type Array of token types providing the parsed formula.
 value Array of values corresponding to the types in type.

## Example

Assuming that x and y are already defined as columns with index ix and iy respectively, the following example converts the formula "sin(x+y)" into internal parsed format, and then writes it out as a sequence of tokens.

```
intype = []
invalue = []
intype = [xslp_op_ifun, xslp_op_lb, xslp_op_col, xslp_op_op,
          xslp_op_col, xslp_op_rb, xslp_op_eof]
invalue = [xslp_op_sin, 0,
                                    iΧ
                                               , xslp_op_plus,
                        0,
                                    01
           iΥ,
type = []
value = []
ntoken = p.parseformula (intype, invalue, type, value)
i=0
while type[n] != xslp_op_eof:
  str = p.itemname (type[i], value[i])
  print (str)
  i += 1
```

#### **Further information**

For possible token types and values, see the chapter on "Formula Parsing" in the SLP reference manual.

# **Related topics**

```
\verb|problem.parsecformula,problem.preparseformula|\\
```

# problem.postsolve

# **Purpose**

Postsolve the current problem when it is in a presolved state.

# **Synopsis**

```
problem.postsolve ()
```

# **Further information**

A problem is left in a presolved state whenever a LP or MIP optimization does not complete. In these cases postsolve can be called to get the problem back into its original state.

# **Related topics**

problem.lpoptimize.problem.mipoptimize.

# problem.preparseformula

#### **Purpose**

Perform an initial scan of a formula written as a character string, identifying the operators but not attempting to identify the types of the individual tokens

# **Synopsis**

```
(type, value, stringtable) = problem.preparseformula (formula)
```

#### **Arguments**

formula Character string containing the formula, written in the same free-format style as formulae in Extended MPS format, with spaces separating tokens.

type Array of token types providing the parsed formula.

value Array of values corresponding to the types in Type.

stringtable Character buffer to receive the names of the unidentified tokens.

# **Example**

The following example converts the formula  $\sin(x+y)$  into internal parsed format without trying to identify the tokens apart from operands and numbers, and then writes it out as a sequence of tokens.

```
(type, value, stab) = p.preparseformula ("sin ( x + y )")
i=0
while type[i] != xslp_op_eof:
  if type[n] == xslp_UNKNOWN:
    print ("? ", value[i])
  else:
    str = p.itemname (type[i], value[i])
    printf (str)
  i += 1
```

#### **Further information**

Only operands and numbers are identified by preparseformula. All other operands, including names of variables, functions are left as strings of type xslp\_op\_unknown. The Value of such a type is the index in stringtable of the start of the token name.

The parsed formula can be converted into a calculable formula by replacing the xslp\_op\_unknown tokens by the correct types and values.

#### **Related topics**

problem.parsecformula, problem.parseformula

# problem.presolve

#### **Purpose**

Perform a nonlinear presolve on the problem

### **Synopsis**

```
problem.presolve ()
```

## **Example**

The following example reads a problem from file, sets the presolve control, presolves the problem and then maximizes it.

```
p.readprob ("Matrix", "")
p.controls.xslp_presolve = 1
p.presolve ()
p.solve ("")
```

#### **Further information**

If bit 1 of xslp\_presolve is not set, no nonlinear presolve will be performed. Otherwise, the presolve will be performed in accordance with the bit settings. problem.presolve is called automatically by problem.construct, so there is no need to call it explicitly unless there is a requirement to interrupt the process between presolve and optimization.problem.presolve must be called before problem.construct or any of the SLP optimization procedures..

```
xslp_presolve
```

# problem.presolverow

#### **Purpose**

Presolves a row formulated in terms of the original variables such that it can be added to a presolved problem. Returns a tuple of two elements containing, respectively, the presolved right-hand side and the status of the presolved row:

- -3: Failed to presolve the row due to presolve dual reductions;
- -2: Failed to presolve the row due to presolve duplicate column reductions;
- -1: Failed to presolve the row due to an error. Check the Optimizer error code for the cause;
- 0: The row was successfully presolved;
- 1: The row was presolved, but may be relaxed.

## **Synopsis**

# **Arguments**

```
The type of the row:
grtype
                      indicates a \leq row;
               L
               G
                      indicates a \geq row.
               Array containing the column indices of the row to presolve.
mcolso
dvalo
               Array containing the non-zero coefficients of the row to presolve.
               The right-hand side constant of the row to presolve.
drhso
               Maximum number of elements to return in the mcolsp and dvalp arrays.
maxcoeffs
mcolsp
               Array which will be filled with the column indices of the presolved row.
dvalp
               Array which will be filled with the coefficients of the presolved row.
```

#### **Example**

Adding the row  $2x_1 + x_2 \le 1$  to our presolved problem can be done as follows:

```
presind = []
prescoe = []
prhs, status = p.presolverow ('L', [1,2], [2,1], 1.0,
    p.attributes.cols, presind, prescoe)
```

#### **Further information**

There are certain presolve operations that can prevent a row from being presolved exactly. If the row contains a coefficient for a column that was eliminated due to duplicate column reductions or singleton column reductions, the row might have to be relaxed to remain valid for the presolved problem. The relaxation will be done automatically by the problem.presolverow function, but a return status of +1 will be returned. If it is not possible to relax the row, a status of -2 will be returned instead. Likewise, it is possible that certain dual reductions prevents the row from being presolved. In such a case a status of -3 will be returned instead.

If problem.presolverow is used for presolving e.g. branching bounds or constraints, then dual reductions and duplicate column reductions should be disabled, by clearing the corresponding bits of PRESOLVEOPS. By clearing these bits, the default value for PRESOLVEOPS changes to 471.

If the user knows in advance which columns will have non-zero coefficients in rows that will be presolved, it is possible to protect these individual columns through the problem.loadsecurevecs function. This way the Optimizer is left free to apply all possible reductions to the remaining columns.

```
problem.addcuts, problem.loadsecurevecs, problem.setbranchcuts,
problem.storecuts.
```

# problem.printmemory

#### **Purpose**

Print the dimensions and memory allocations for a problem

### **Synopsis**

```
problem.printmemory ()
```

#### **Example**

The following example loads a problem from file and then prints the dimensions of the arrays.

```
p.readprob ("Matrix1", "")
p.printmemory ()
```

The output is similar to the following:

```
Arrays and dimensions: Array Item Used Max Allocated Memory Size Items Items Memory Control MemList 28 103 129 4K String 1 8779 13107 13K xslp_MEM_STRING Xv 16 2 1000 16K xslp_MEM_XV Xvitem 48 11 1000 47K xslp_MEM_XVITEM ....
```

#### **Further information**

printmemory lists the current sizes and amounts used of the variable arrays in the current problem. For each array, the size of each item, the number used and the number allocated are shown, together with the size of memory allocated and, where appropriate, the name of the memory control variable to set the array size. Loading and execution of some problems can be speeded up by setting the memory controls immediately after the problem is created. If an array has to be moved to re-allocate it with a larger size, there may be insufficient memory to hold both the old and new versions; pre-setting the memory controls reduces the number of such re-allocations which take place and may allow larger problems to be solved.

# problem.printevalinfo

# **Purpose**

Print a summary of any evaluation errors that may have occurred during solving a problem

# **Synopsis**

problem.printevalinfo ()

# **Related topics**

problem.setcbcoefevalerror

# problem.printmsg

#### **Purpose**

Print a message string according to the current settings for Xpress Nonlinear output

#### **Synopsis**

```
problem.printmsg (msgtype, msg)
```

## **Arguments**

MsgType Integer containing the message type. The following types are system-defined:

- Information messageWarning messageError message
- Other message types can be used and passed to a user-supplied message handler.

Msg Character string containing the message.

# **Example**

The following example checks the SLP optimization status and prints an informative message for some of the possible values.

```
status = p.attributes.xslp_status
if status == 0:
    p.printmsg (1, "Fully converged solution")
if status & xp.xslp_maxtime:
    p.printmsg (3, "Max time exceeded")
if status & xp.xslp_convergedobjucc:
    p.printmsg (1, "Solution with unimportant unconverged values")
```

#### **Further information**

If msgtype is outside the range 1 to 4, any message handler written to handle the standard message types may not print the message correctly. One of the uses of the function is to provide a unified means of logging from the callbacks.

# problem.read

#### **Purpose**

Read an optimization problem into a Python problem object created prior to the call. All formats allowed by the Xpress Optimizer C API are allowed.

# **Synopsis**

```
problem.read (filename, flags)
```

### **Arguments**

filename A string of up to 200 characters with the name of the file to be read.

flags (optional) Flags to pass to read:

only the .lp version of the file is searched.

read the input file in compressed .gz format.

### **Example**

Read problem problem1.1p and output an optimal solution:

```
p.read ("problem1", "1")
p.solve ("", "")
print ("solution of problem1.lp:", p.getSolution ())
```

```
problem.write.
```

# problem.readbasis

#### **Purpose**

Instructs the Optimizer to read in a previously saved basis from a file.

#### **Synopsis**

```
problem.readbasis (filename, flags)
```

#### **Arguments**

filename A string of up to 200 characters containing the file name from which the basis is to be

read. If omitted, the default problem\_name is used with a .bss extension.

flags (optional) Flags to pass to readbasis:

- i output the internal presolved basis.
- t input a compact advanced form of the basis;

### **Example**

If an advanced basis is available for the current problem the Optimizer input might be:

```
p.read ("filename", "")
p.readbasis ("", "")
p.mipoptimize ("")
```

This reads in a matrix file, inputs an advanced starting basis and maximizes the MIP.

#### **Further information**

- 1. The only check done when reading compact basis is that the number of rows and columns in the basis agrees with the current number of rows and columns.
- 2. readbasis will read the basis for the original problem even if the problem has been presolved. The Optimizer will read the basis, checking that it is valid, and will display error messages if it detects inconsistencies.

```
problem.loadbasis,problem.writebasis.
```

# problem.readbinsol

#### **Purpose**

Reads a solution from a binary solution file.

#### **Synopsis**

```
problem.readbinsol (filename, flags)
```

## **Arguments**

filename A string of up to 200 characters containing the file name from which the solution is to

be read. If omitted, the default *problem\_name* is used with a .sol extension.

flags (optional) Flags to pass to readbinsol:

load the solution as a solution for the MIP.

## **Example**

A previously saved solution can be loaded into memory and a print file created from it with the following commands:

```
p.read ("myprob", "")
p.readbinsol ("", "")
p.writeprtsol ("", "")
```

```
problem.getlpsol,problem.getmipsol,problem.writebinsol,problem.writesol,problem.writeprtsol.
```

# problem.readdirs

#### **Purpose**

Reads a directives file to help direct the global search.

### **Synopsis**

```
problem.readdirs (filename)
```

#### **Argument**

filename

A string of up to 200 characters containing the file name from which the directives are to be read. If omitted (or None), the default *problem\_name* is used with a .dir extension.

#### **Example**

The following example reads in directives from the file dirfile.dir for use with the problem, prob2:

```
p.read ("prob2","")
p.readdirs ("dirfile")
p.mipoptimize ("")
```

#### **Further information**

- 1. Directives cannot be read in after a model has been presolved, so unless presolve has been disabled by setting PRESOLVE to 0, this command must be issued before problem.mipoptimize.
- 2. Directives can be given relating to priorities, forced branching directions, pseudo costs and model cuts. There is a priority value associated with each global entity. The *lower* the number, the *more* likely the entity is to be selected for branching; the *higher*, the *less* likely. By default, all global entities have a priority value of 500 which can be altered with a priority entry in the directives file. In general, it is advantageous for the entity's priority to reflect its relative importance in the model. Priority entries with values in excess of 1000 are illegal and are ignored. A full description of the directives file format may be found in the Xpress Optimizer reference manual.
- 3. By default, problem.mipoptimize will explore the branch expected to yield the best integer solution from each node, irrespective of whether this forces the global entity up or down. This can be overridden with an UP or DN entry in the directives file, which forces mipoptimize to branch up first or down first on the specified entity.
- 4. Pseudo-costs are estimates of the unit cost of forcing an entity up or down. By default mipoptimize uses dual information to calculate estimates of the unit up and down costs and these are added to the default pseudo costs which are set to the PSEUDOCOST control. The default pseudo costs can be overridden by a PU or PD entry in the directives file.
- 5. If model cuts are used, then the specified constraints are removed from the problem and added to the Optimizer cut pool, and only put back in the problem when they are violated by an LP solution at one of the nodes in the global search.
- 6. If creating a directives file by hand, wild cards can be used to specify several vectors at once, for example PR x1\* 2 will give all global entities whose names start with x1 a priority of 2.

```
problem.loaddirs.
```

# problem.readslxsol

#### **Purpose**

Reads an ASCII solution file (.slx) created by the problem.writeslxsol function.

#### **Synopsis**

```
problem.readslxsol (filename, flags)
```

#### **Arguments**

filename A string of up to 200 characters containing the file name to which the solution is to be

read. If omitted, the default problem\_name is used with a .slx extension.

flags (optional) Flags to pass to writeslxsol:

- 1 read the solution as an LP solution in case of a MIP problem;
- m read the solution as a solution for the MIP problem;
- a reads multiple MIP solutions from the .slx file and adds them to the MIP problem;

#### **Example**

```
p.readslxsol ("lpsolution", "")
```

This loads the solution to the MIP problem if the problem contains global entities, or otherwise loads it as an LP (barrier in case of quadratic problems) solution into the problem.

#### **Further information**

- 1. When readslxsol is called before a MIP solve, the loaded solutions will not be checked before calling problem.mipoptimize. By default, only the last MIP solution read from the .slx file will be stored. Use the a flag to store all MIP solutions read from the file.
- 2. When using the a flag, read solutions will be queued similarly to the user of the problem.addmipsol function. Each name string given by the NAME field in the .slx file will be associated with the corresponding solution. Any registered usersolnotify callback will be fired when the solution has been checked, and will include the read name string as one of its arguments.
- 3. Refer to the Appendix of the Xpress Optimizer reference manual on Log and File Formats for a description of the ASCII Solution (.slx) file format.

#### **Related topics**

problem.readbinsol, problem.writeslxsol problem.writebinsol problem.readbinsol problem.addmipsol, problem.addcbusersolnotify.

# problem.refinemipsol

#### **Purpose**

Runs the MIP solution refiner.

#### **Synopsis**

problem.refinemipsol (options, flags, solution, refined\_solution)

#### **Arguments**

options Refinement options:

Reducing MIP fractionality is priority.Reducing LP infeasiblity is priority

flags Flags passed to any optimization calls during refinement.
solution The MIP solution to refine. Must be a valid MIP solution.
refined\_solution The refined MIP solution in case of success

refinestatus Refinement results:

- 0 An error has occurred
- 1 The solution has been refined
- 2 Current solution meets target criteria
- 3 Solution cannot be refined

#### **Further information**

The function provides a mechanism to refine the MIP solution by attempting to round any fractional global entity and by attempting to reduce LP infeasibility.

# **Related topics**

REFINEOPS.

# problem.reinitialize

# **Purpose**

Reset the SLP problem to match a just augmented system

# **Synopsis**

```
problem.reinitialize ()
```

### **Further information**

Can be used to rerun the SLP optimization process with updated parameters, penalties or initial values, but unchanged augmentation.

# **Related topics**

problem.unconstruct,problem.setcurrentiv,

# problem.removecbbariteration

#### **Purpose**

Removes a barrier iteration callback function previously added by addcbbariteration. The specified callback function will no longer be called after it has been removed.

# **Synopsis**

problem.removecbbariteration (callback, data)

### **Arguments**

callback The callback function to remove. If None then all bariteration callback functions added

with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all barrier iteration callbacks with the function callback will be

removed.

### **Related topics**

problem.addcbbariteration.

# problem.removecbbarlog

#### **Purpose**

Removes a newton barrier log callback function previously added by addcbbarlog. The specified callback function will no longer be called after it has been removed.

# **Synopsis**

problem.removecbbarlog (callback, data)

### **Arguments**

callback The callback function to remove. If None then all barrier log callback functions added

with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all barrier log callbacks with the function callback will be removed.

## **Related topics**

problem.addcbbarlog.

# problem.removecbchgbranchobject

#### **Purpose**

Removes a callback function previously added by addcbchgbranchobject. The specified callback function will no longer be called after it has been removed.

# **Synopsis**

problem.removecbchgbranchobject (callback, data)

### **Arguments**

callback The callback function to remove. If None then all branch object callback functions

added with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, the object value will not be

checked and all branch object callbacks with the function callback will be removed.

## **Related topics**

problem.addcbchgbranchobject.

# problem.removecbcutlog

### **Purpose**

Removes a cut log callback function previously added by addcbcutlog. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

problem.removecbcutlog (callback, data)

### **Arguments**

callback The callback function to remove. If None then all cut log callback functions added with

the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all cut log callbacks with the function callback will be removed.

## **Related topics**

problem.addcbcutlog.

# problem.removecbdestroymt

#### **Purpose**

Removes a slave thread destruction callback function previously added by addcbdestroymt. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

problem.removecbdestroymt (callback, data)

### **Arguments**

callback The callback function to remove. If None then all thread destruction callback functions

added with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all thread destruction callbacks with the function callback will be

removed.

### **Related topics**

problem.addcbdestroymt.

# problem.removecbgapnotify

#### **Purpose**

Removes a callback function previously added by problem.addcbgapnotify. The specified callback function will no longer be removed after it has been returned.

#### **Synopsis**

problem.removecbgapnotify (callback, data)

### **Arguments**

callback The callback function to remove. If None then all gapnotify callback functions added

with the given user-defined value will be removed.

data The user-defined object that the callback was added with. If None then the object will

not be checked and all the gapnotify callbacks with the function callback will be

removed.

### **Related topics**

problem.addcbgapnotify.

# problem.removecbgloballog

#### **Purpose**

Removes a global log callback function previously added by addcbgloballog. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

```
problem.removecbgloballog (callback, data)
```

#### **Arguments**

callback The callback function to remove. If None then all global log callback functions added

with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all global log callbacks with the function callback will be removed.

#### **Example**

The following code sets and removes a callback function:

```
prob.controls.miplog = 3
prob.addcbgloballog (globalLog, None, 0)
prob.mipoptimize ("")
prob.removecbgloballog (globalLog, None)
```

#### **Related topics**

problem.addcbgloballog.

# problem.removecbinfnode

#### **Purpose**

Removes a user infeasible node callback function previously added by addcbinfnode. The specified callback function will no longer be called after it has been removed.

# **Synopsis**

problem.removecbinfnode (callback, data)

### **Arguments**

callback The callback function to remove. If None then all user infeasible node callback

functions added with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all user infeasible node callbacks with the function callback will be

removed.

# **Related topics**

problem.addcbinfnode.

# problem.removecbintsol

#### **Purpose**

Removes an integer solution callback function previously added by addcbintsol. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

problem.removecbintsol (callback, data)

### **Arguments**

callback The callback function to remove. If None then all integer solution callback functions

added with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all integer solution callbacks with the function callback will be

removed.

### **Related topics**

problem.addcbintsol.

# problem.removecblplog

#### **Purpose**

Removes a simplex log callback function previously added by addcblplog. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

```
problem.removecblplog (callback, data)
```

### **Arguments**

callback The callback function to remove. If None then all lplog callback functions added with

the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all lplog callbacks with the function callback will be removed.

#### **Example**

The following code sets and removes a callback function:

```
prob.controls.lplog = 10
prob.addcblplog (lpLog, None, 0)
prob.readprob ("problem", "")
prob.lpoptimize ("")
prob.removecblplog (lpLog, None)
```

```
problem.addcblplog.
```

# problem.removecbmessage

### **Purpose**

Removes a message callback function previously added by addcbmessage. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

problem.removecbmessage (callback, data)

### **Arguments**

callback The callback function to remove. If None then all message callback functions added

with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all message callbacks with the function callback will be removed.

# **Related topics**

problem.addcbmessage.

# problem.removecbmipthread

# **Purpose**

Removes a callback function previously added by addcbmipthread. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

problem.removecbmipthread (callback, data)

### **Arguments**

callback The callback function to remove. If None then all variable branching callback functions

added with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all variable branching callbacks with the function callback will be

removed.

# **Related topics**

problem.addcbmipthread.

# problem.removecbnewnode

#### **Purpose**

Removes a new-node callback function previously added by addcbnewnode. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

problem.removecbnewnode (callback, data)

### **Arguments**

callback The callback function to remove. If None then all separation callback functions added

with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all separation callbacks with the function callback will be removed.

## **Related topics**

problem.addcbnewnode.

# problem.removecbnodecutoff

### **Purpose**

Removes a node-cutoff callback function previously added by addcbnodecutoff. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

problem.removecbnodecutoff (callback, data)

### **Arguments**

callback The callback function to remove. If None then all node-cutoff callback functions added

with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all node-cutoff callbacks with the function callback will be removed.

## **Related topics**

problem.addcbnodecutoff.

# problem.removecboptnode

### **Purpose**

Removes a node-optimal callback function previously added by addcboptnode. The specified callback function will no longer be called after it has been removed.

# **Synopsis**

problem.removecboptnode (callback, data)

### **Arguments**

callback The callback function to remove. If None then all node-optimal callback functions

added with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all node-optimal callbacks with the function callback will be removed.

# **Related topics**

problem.addcboptnode.

# problem.removecbpreintsol

#### **Purpose**

Removes a pre-integer solution callback function previously added by addcbpreintsol. The specified callback function will no longer be called after it has been removed.

# **Synopsis**

problem.removecbpreintsol (callback, data)

### **Arguments**

callback The callback function to remove. If None then all user infeasible node callback

functions added with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all user infeasible node callbacks with the function callback will be

removed.

### **Related topics**

problem.addcbpreintsol.

# problem.removecbprenode

#### **Purpose**

Removes a preprocess node callback function previously added by addcbprenode. The specified callback function will no longer be called after it has been removed.

# **Synopsis**

problem.removecbprenode (callback, data)

## **Arguments**

callback The callback function to remove. If None then all preprocess node callback functions

added with the given user-defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all preprocess node callbacks with the function callback will be

removed.

### **Related topics**

problem.addcbprenode.

# problem.removecbusersolnotify

#### **Purpose**

Removes a user solution notification callback previously added by problem.addcbusersolnotify. The specified callback function will no longer be called after it has been removed.

#### **Synopsis**

problem.removecbusersolnotify (callback, data)

## **Arguments**

callback The callback function to remove. If None then all user solution notification callback

functions added with the given user defined object value will be removed.

data The object value that the callback was added with. If None, then the object value will not

be checked and all integer solution callbacks with the function callback will be

removed.

### **Related topics**

problem.addcbusersolnotify.

# problem.repairinfeas

#### **Purpose**

Provides a simplified interface for problem.repairweightedinfeas. The returned value is as follows:

- 0: relaxed optimum found;
- 1: relaxed problem is infeasible;
- 2: relaxed problem is unbounded;
- 3: solution of the relaxed problem regarding the original objective is nonoptimal;
- 4: error (when return code is nonzero);
- 5: numerical instability;
- 6: analysis of an infeasible relaxation was performed, but the relaxation is feasible.

#### **Synopsis**

### **Arguments**

pflags The type of penalties created from the preferences:

each penalty is the reciprocal of the preference (default);
 the penalties are placed in the scaled problem.

s the penalties are placed in the scaled p

oflags Controls the second phase of optimization:

use the objective sense of the original problem (default);

x maximize the relaxed problem using the original objective;

f skip optimization regarding the original objective;

n minimize the relaxed problem using the original objective;

if the relaxation is infeasible, generate an irreducible infeasible subset for the analys of the problem;

if the relaxation is infeasible, generate all irreducible infeasible subsets for the analys of the problem.

gflags Specifies if the global search should be done:

q do the global search (default);

solve as a linear model ignoring the discreteness of variables.

1rp Preference for relaxing the less or equal side of row.

grp Preference for relaxing the greater or equal side of a row.

1bp Preferences for relaxing lower bounds.ubp Preferences for relaxing upper bounds.

delta The relaxation multiplier in the second phase -1. A positive value means a relative

relaxation by multiplying the first phase objective with (delta-1), while a negative

value means an absolute relaxation, by adding abs (delta) to the first phase objective.

#### **Further information**

- 1. A row or bound is relaxed by introducing a new nonnegative variable that will contain the infeasibility of the row or bound. Suppose for example that row a<sup>T</sup>x = b is relaxed from below. Then a new variable (infeasibility breaker) s>=0 is added to the row, which becomes a<sup>T</sup>x +s = b. Observe that a<sup>T</sup>x may now take smaller values than b. To minimize such violations, the weighted sum of these new variables is minimized.
- 2. A preference of 0 results in the row or bound not being relaxed.
- 3. A negative preference indicates that a quadratic penalty cost should be applied. This can specified on a per constraint side or bound basis.
- 4. Note that the set of preferences are scaling independent.
- 5. If a feasible solution is identified for the relaxed problem, with a sum of violations p, then the sum of violations is restricted to be no greater than (1+delta)p, and the problem is optimized with respect to the original objective function. A nonzero delta increases the freedom of the original problem.
- 6. Note that on some problems, slight modifications of delta may affect the value of the original objective drastically.
- 7. Note that because of their special associated modeling properties, binary and semi-continuous variables are not relaxed.
- 8. The default algorithm for the first phase is the simplex algorithm, since the primal problem can be efficiently warm started in case of the extended problem. These may be altered by setting the value of control DEFAULTALG.
- 9. If pflags is set such that each penalty is the reciprocal of the preference, the following rules are applied while introducing the auxiliary variables:

Preference	Affects	Relaxation	Cost if pref.>0	Cost if pref.<0
lrp	= rows	$a^Tx - aux_var = b$	1/lrp*aux_var	1/lrp*aux_var <sup>2</sup>
lrp	<= rows	a <sup>T</sup> x - aux_var <= b	1/lrp*aux_var	1/lrp*aux_var <sup>2</sup>
grp	= rows	$a^Tx + aux_var = b$	1/grp*aux_var	1/grp*aux_var <sup>2</sup>
grp	>= rows	$a^Tx + aux_var >= b$	1/grp*aux_var	1/grp*aux_var <sup>2</sup>
ubp	upper bounds	$x_i$ - aux_var <= u	1/ubp*aux_var	1/ubp*aux_var <sup>2</sup>
lbp	lower bounds	$x_i + aux_var >= 1$	1/lbp*aux_var	1/lbp*aux_var <sup>2</sup>

10. If an irreducible infeasible set (IIS) has been identified, the generated IIS(s) are accesible through the IIS retrieval functions, see NUMIIS and problem.getiisdata.

#### **Related topics**

problem.repairweightedinfeas.

# problem.repairweightedinfeas

#### **Purpose**

By relaxing a set of selected constraints and bounds of an infeasible problem, it attempts to identify a 'solution' that violates the selected set of constraints and bounds minimally, while satisfying all other constraints and bounds. Among such solution candidates, it selects one that is optimal regarding to the original objective function. Similar to repairinfeas, the returned value is as follows:

- 1: relaxed problem is infeasible;
- 2: relaxed problem is unbounded;
- 3: solution of the relaxed problem regarding the original objective is nonoptimal;
- 4: error (when return code is nonzero);
- 5: numerical instability;
- 6: analysis of an infeasible relaxation was performed, but the relaxation is feasible.

# **Synopsis**

## **Arguments**

Array of size ROWS containing the preferences for relaxing the less or equal side of row. lrp\_array Array of size ROWS containing the preferences for relaxing the greater or equal side of a grp\_array Array of size COLS containing the preferences for relaxing lower bounds. lbp\_array Array of size COLS containing preferences for relaxing upper bounds. ubp\_array Controls the second phase of optimization: phase2 use the objective sense of the original problem (default); maximize the relaxed problem using the original objective; Х f skip optimization regarding the original objective; minimize the relaxed problem using the original objective; n if the relaxation is infeasible, generate an irreducible infeasible subset for the i analys of the problem; if the relaxation is infeasible, generate all irreducible infeasible subsets for the

delta The relaxation multiplier in the second phase -1.

optflags Specifies flags to be passed to the Optimizer.

analys of the problem.

#### **Further information**

- 1. A row or bound is relaxed by introducing a new nonnegative variable that will contain the infeasibility of the row or bound. Suppose for example that row a<sup>T</sup>x = b is relaxed from below. Then a new variable ('infeasibility breaker') s>=0 is added to the row, which becomes a<sup>T</sup>x +s = b. Observe that a<sup>T</sup>x may now take smaller values than b. To minimize such violations, the weighted sum of these new variables is minimized.
- 2. A preference of 0 results in the row or bound not being relaxed. The higher the preference, the more willing the modeller is to relax a given row or bound.
- 3. The weight of each infeasibility breaker in the objective minimizing the violations is 1/p, where p is the preference associated with the infeasibility breaker. Thus the higher the preference is, the lower a penalty is associated with the infeasibility breaker while minimizing the violations.
- 4. If a feasible solution is identified for the relaxed problem, with a sum of violations p, then the sum of violations is restricted to be no greater than (1+delta)p, and the problem is optimized with respect to the original objective function. A nonzero delta increases the freedom of the original problem.
- 5. Note that on some problems, slight modifications of delta may affect the value of the original objective drastically.
- 6. Note that because of their special associated modeling properties, binary and semi-continuous variables are not relaxed.
- 7. If pflags is set such that each penalty is the reciprocal of the preference, the following rules are applied while introducing the auxiliary variables:

Pref. array	Affects	Relaxation	Cost if pref.>0	Cost if pref.<0
lrp_array	= rows	$a^Tx - aux_var = b$	1/lrp*aux_var	1/lrp*aux_var <sup>2</sup>
lrp_array	<= rows	a <sup>T</sup> x - aux_var <= b	1/lrp*aux_var	1/lrp*aux_var <sup>2</sup>
grp_array	= rows	$a^Tx + aux_var = b$	1/grp*aux_var	1/grp*aux_var <sup>2</sup>
grp_array	>= rows	$a^Tx + aux_var >= b$	1/grp*aux_var	1/grp*aux_var <sup>2</sup>
ubp_array	upper bounds	$x_i$ - aux_var <= u	1/ubp*aux_var	1/ubp*aux_var <sup>2</sup>
lbp_array	lower bounds	$x_i + aux_var >= 1$	1/lbp*aux_var	1/lbp*aux_var <sup>2</sup>

8. If an irreducible infeasible set (IIS) has been identified, the generated IIS(s) are accesible through the IIS retrieval functions, see NUMIIS and problem.getiisdata.

#### **Related topics**

problem.repairinfeas, problem.repairweightedinfeasbounds.

# problem.repairweightedinfeasbounds

# **Purpose**

An extended version of <a href="mailto:problem.repairweightedinfeas">problem.repairweightedinfeas</a> that allows for bounding the level of relaxation allowed. The returned value is the same as repairweightedinfeas.

### **Synopsis**

### **Arguments**

lrp_array	Array of size ROWS containing the preferences for relaxing the less or equal side of row.		
grp_array	Array of size ROWS containing the preferences for relaxing the greater or equal side of a row.		
lbp_array	Array of size COLS containing the preferences for relaxing lower bounds.		
ubp_array	Array of size COLS containing preferences for relaxing upper bounds.		
lrb_array	Array of size ROWS containing the upper bounds on the amount the less or equal side of a row can be relaxed.		
grb_array	Array of size ROWS containing the upper bounds on the amount the greater or equal side of a row can be relaxed.		
lbb_array	Array of size COLS containing the upper bounds on the amount the lower bounds can be relaxed.		
ubb_array	Array of size COLS containing the upper bounds on the amount the upper bounds can be relaxed.		
phase2	Controls the second phase of optimization:  o use the objective sense of the original problem (default);  x maximize the relaxed problem using the original objective;  f skip optimization regarding the original objective;  n minimize the relaxed problem using the original objective;  i if the relaxation is infeasible, generate an irreducible infeasible subset for the analys of the problem;  a if the relaxation is infeasible, generate all irreducible infeasible subsets for the analys of the problem.		
delta	The relaxation multiplier in the second phase -1.		
optflags	Specifies flags to be passed to the Optimizer.		

#### **Further information**

- 1. A row or bound is relaxed by introducing a new nonnegative variable that will contain the infeasibility of the row or bound. Suppose for example that row a<sup>T</sup>x = b is relaxed from below. Then a new variable ('infeasibility breaker') s>=0 is added to the row, which becomes a<sup>T</sup>x +s = b. Observe that a<sup>T</sup>x may now take smaller values than b. To minimize such violations, the weighted sum of these new variables is minimized.
- 2. A preference of 0 results in the row or bound not being relaxed. The higher the preference, the more willing the modeller is to relax a given row or bound.
- 3. A negative preference indicates that a quadratic penalty cost should be applied. This can specified on a per constraint side or bound basis.
- 4. If a feasible solution is identified for the relaxed problem, with a sum of violations p, then the sum of violations is restricted to be no greater than (1+delta)p, and the problem is optimized with respect to the original objective function. A nonzero delta increases the freedom of the original problem.
- 5. Note that on some problems, slight modifications of delta may affect the value of the original objective drastically.
- 6. Note that because of their special associated modeling properties, binary and semi-continuous variables are not relaxed.
- 7. Given any row j with preferences lrp=lrp\_array[j] and grp=grp\_array[j], or variable i with bound preferences ubp=ubp\_array[i] and lbp=lbp\_array[i], the following rules are applied while introducing the auxiliary variables:

Preference	Affects	Relaxation	Cost if pref.>0	Cost if pref.<0
lrp	= rows	$a^Tx - aux_var = b$	1/lrp*aux_var	1/lrp*aux_var <sup>2</sup>
lrp	<= rows	a <sup>T</sup> x - aux_var <= b	1/lrp*aux_var	1/lrp*aux_var <sup>2</sup>
grp	= rows	$a^Tx + aux_var = b$	1/grp*aux_var	1/grp*aux_var <sup>2</sup>
grp	>= rows	$a^Tx + aux_var >= b$	1/grp*aux_var	1/grp*aux_var <sup>2</sup>
ubp	upper bounds	$x_i$ - aux_var <= u	1/ubp*aux_var	1/ubp*aux_var <sup>2</sup>
lbp	lower bounds	$x_i + aux_var >= 1$	1/lbp*aux_var	1/lbp*aux_var <sup>2</sup>

- 8. Only positive bounds are applied; a zero or negative bound is ignored and the amount of relaxation allowed for the corresponding row or bound is not limited. The effect of a zero bound on a row or bound would be equivalent with not relaxing it, and can be achieved by setting its preference array value to zero instead, or not including it in the preference arrays.
- 9. If an irreducible infeasible set (IIS) has been identified, the generated IIS(s) are accesible through the IIS retrieval functions, see NUMIIS and problem.getiisdata.

### **Related topics**

problem.repairinfeas.

# problem.reset

# **Purpose**

Clears all information regarding an optimization problem and returns it to the same status as it would be after creation (i.e. after the instruction p = xpress.problem ()).

# **Synopsis**

```
problem.reset ()
```

# **Example**

```
p = xpress.problem ()
p.read ("problem0", "1")
p.solve ()
x0 = p.getSolution ()
p.reset ()
p.read ("problem1", "")
p.solve ()
x1 = p.getSolution ()
```

# **Related topics**

```
problem.read.
```

# problem.restore

## **Purpose**

Restores the Optimizer's data structures from a file created by problem.save. Optimization may then recommence from the point at which the file was created.

# **Synopsis**

```
problem.restore (probname, flags)
```

# **Arguments**

probname A string of up to 200 characters containing the problem name.

flags f Force the restoring of a save file even if its from a different version.

# **Example**

```
p.restore ("", "")
```

#### **Further information**

- 1. This routine restores the data structures from the file *probname*.svf that was created by a previous execution of save. The file *probname*.sol is also required and, if recommencing optimization in a global search, the files *problem\_name*.glb and *problem\_name*.ctp are required too. Note that .svf files are particular to the release of the Optimizer used to create them. They can only be read using the same release Optimizer as used to create them.
- 2. The use of the 'f' flag is not recommended and can cause unexpected results.

# **Related topics**

problem.save.

# problem.rhssa

# **Purpose**

Returns upper and lower sensitivity ranges for specified right hand side (RHS) function coefficients. If the RHS coefficients are varied within these ranges the current basis remains optimal and the reduced costs remain valid.

# **Synopsis**

```
problem.rhssa (mindex, lower, upper)
```

## **Arguments**

mindex Array containing the indices of the rows whose RHS coefficients sensitivity ranges are required.

Array where the RHS lower range values are to be returned.

lower Array where the RHS lower range values are to be returned.

upper Array where the RHS upper range values are to be returned.

# **Example**

Here we obtain the RHS function ranges for the three columns: 2, 6 and 8:

```
1 = []
u = []
p.rhssa ([2,8,6], 1, u)
```

After which lower and upper contain:

```
1 = [5, 3.8, 5.7]

u = [7, 5.2, 1e+20]
```

Meaning that the current basis remains optimal when  $5.0 \le \text{rhs}_2$ ,  $3.8 \le \text{rhs}_8 \le 5.2$  and  $5.7 \le \text{rhs}_6$ ,  $\text{rhs}_i$  being the RHS coefficient of row i.

#### **Further information**

rhssa can only be called when an optimal solution to the current LP has been found. It cannot be used when the problem is MIP presolved.

## **Related topics**

```
problem.objsa.
```

# problem.save

# **Purpose**

Saves the current data structures, i.e. matrices, control settings and problem attribute settings to file and terminates the run so that optimization can be resumed later.

# **Synopsis**

```
problem.save ()
```

## **Example**

p.save ()

#### **Further information**

The data structures are written to the file <code>problem\_name.svf</code>. Optimization may recommence from the same point when the data structures are restored by a call to <code>problem.restore</code>. Under such circumstances, the file <code>problem\_name.sol</code> and, if a branch and bound search is in progress, the global files <code>problem\_name.glb</code> and <code>problem\_name.ctp</code> are also required. These files will be present after execution of <code>save</code>, but will be modified by subsequent optimization, so no optimization calls may be made after the call to <code>save</code>. Note that the <code>.svf</code> files created are particular to the release of the Optimizer used to create them. They can only be read using the same release Optimizer as used to create them.

### **Related topics**

problem.restore.

# problem.scale

# **Purpose**

Re-scales the current problem.

# **Synopsis**

```
problem.scale (mrscal, mcscal)
```

## **Arguments**

mrscal Array of size ROWS containing the exponents of the powers of 2 with which to scale the

rows, or None if not required.

mcscal Array of size COLS containing the exponents of the powers of 2 with which to scale the

columns, or None if not required.

# **Example**

```
p.read ("prob1", "")
p.scale ([1] * p.attributes.rows, [3] * p.attributes.cols)
p.lpoptimize ("")
```

This reads the MPS file prob1.mat, rescales the problem and seeks the minimum objective value.

#### **Further information**

- 1. If mrscal and mcscal are both non-None then they will be used to scale the problem. Otherwise the problem will be scaled according to the control SCALING. This routine may be useful when the current problem has been modified by calls to routines such as problem.chgmcoef and problem.addrows.
- 2. scale cannot be called if the current problem is presolved.

# **Related topics**

```
problem.read.
```

# problem.scaling

# **Purpose**

Analyze the current matrix for largest/smallest coefficients and ratios

# **Synopsis**

```
problem.scaling ()
```

## **Example**

The following example analyzes the matrix

```
p.scaling ()
```

#### **Further information**

The current matrix (including augmentation if it has been carried out) is scanned for the absolute and relative sizes of elements. The following information is reported:

- Largest and smallest elements in the matrix;
- Counts of the ranges of row ratios in powers of 10 (e.g. number of rows with ratio between 10 and 100);
- List of the rows (with largest and smallest elements) which appear in the highest range;
- Counts of the ranges of column ratios in powers of 10;
- List of the columns (with largest and smallest elements) which appear in the highest range;
- Element ranges in powers of 10.

Where any of the reported items (largest or smallest element in the matrix or any reported row or column element) is in a penalty error vector, the results are repeated, excluding all penalty error vectors.

# problem.setbranchbounds

# **Purpose**

Specifies the bounds previously stored using problem.storebounds that are to be applied in order to branch on a user global entity.

# **Synopsis**

problem.setbranchbounds (mindex)

# **Argument**

mindex

Object previously defined in a call to problem.storebounds that references the stored bounds to be used to separate the node.

# **Related topics**

problem.loadcuts, problem.storebounds, Section "Working with the cut manager" of the Xpress
Optimizer reference manual.

# problem.setbranchcuts

# **Purpose**

Specifies the cuts in the cut pool that are to be applied in order to branch on a user global entity..

# **Synopsis**

problem.setbranchcuts (mindex)

# **Argument**

mindex

Array containing cuts in the cut pool that are to be applied. Typically obtained from problem.storecuts.

# **Related topics**

problem.getcpcutlist, problem.storecuts, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

# problem.setcbcascadeend

## **Purpose**

Set a user callback to be called at the end of the cascading process, after the last variable has been cascaded

## **Synopsis**

```
problem.setcbcascadeend (callback, data)
value = callback (prob, myobject)
```

## **Arguments**

callback The function to be called at the end of the cascading process. callback returns an

integer value. The return value is noted by Xpress SLP but it has no effect on the

optimization.

prob The problem passed to the callback function.

myobject The user-defined object passed as data to setcbcascadeend.

data User-defined object, which can be used for any purpose by the function. data is passed

to callback as my\_object.

# **Example**

The following example sets up a callback to be executed at the end of the cascading process which checks if any of the values have been changed significantly:

```
csol = [1,2,3,4]
p.setcbcascadeend (CBCascEnd, csol)
```

A suitable callback function might resemble this:

```
def CBCascEnd (prob, obj):
   for iCol in range (prob.controls.cols):
      (a,b,c,s,d,e,f,value,g,h,i,j,k,l,m,n) = prob.getvar (iCol)
   if (abs (value - obj[iCol]) > .01):
      print ("Col {0} changed from {1} to {2}".format (iCol, obj[iCol], value)
   return 0
```

The obj argument is used here to hold the original solution values.

#### **Further information**

This callback can be used at the end of the cascading, when all the solution values have been recalculated.

# **Related topics**

```
problem.cascade, problem.setcbcascadestart, problem.setcbcascadevar,
problem.setcbcascadevarfail
```

# problem.setcbcascadestart

## **Purpose**

Set a user callback to be called at the start of the cascading process, before any variables have been cascaded

## **Synopsis**

```
problem.setcbcascadestart (callback, data)
retval = callback (my_prob, my_object)
```

## **Arguments**

callback The function to be called at the start of the cascading process. callback returns an

integer value. If the return value is nonzero, the cascading process will be omitted for

the current SLP iteration, but the optimization will continue.

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as data to setcbcascadestart.

data Address of a user-defined object, which can be used for any purpose by the function.

data is passed to callback as my\_object.

# **Further information**

This callback can be used at the start of the cascading, before any of the solution values have been recalculated.

# **Related topics**

problem.cascade, problem.setcbcascadeend, problem.setcbcascadevar, problem.setcbcascadevarfail

# problem.setcbcascadevar

# **Purpose**

Set a user callback to be called after each column has been cascaded

#### **Synopsis**

```
problem.setcbcascadevar (callback, data)
retval = callback (my_prob, my_object, colindex)
```

## **Arguments**

The function to be called after each column has been cascaded. callback returns an integer value. If the return value is nonzero, the cascading process will be omitted for the remaining variables during the current SLP iteration, but the optimization will continue.

my\_prob
The problem passed to the callback function.

my\_object
The user-defined object passed as data to problem.setcbcascadevar.

The number of the column which has been cascaded.

data
User-defined object, which can be used for any purpose by the function. data is passed to callback as my\_object.

# **Example**

The following example sets up a callback to be executed after each variable has been cascaded:

```
obj = []
p.setcbcascadevar (CBCascVar, obj)
```

The following sample callback function resets the value of the variable if the cascaded value is of the opposite sign to the original value:

The data argument is used here to hold the address of the array csol which we assume has been populated with the original solution values.

#### **Further information**

This callback can be used after each variable has been cascaded and its new value has been calculated.

### **Related topics**

problem.cascade, problem.setcbcascadeend, problem.setcbcascadestart, problem.setcbcascadevarfail

# problem.setcbcascadevarfail

# **Purpose**

Set a user callback to be called after cascading a column was not successful

## **Synopsis**

```
problem.setcbcascadevarfail (callback, data)
retval = callback (my_prob, my_object, colindex)
```

## **Arguments**

callback The function to be called after cascading a column was not successful. callback

returns an integer value. If the return value is nonzero, the cascading process will be omitted for the remaining variables during the current SLP iteration, but the optimization

will continue.

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as data to setcbcascadevarfail.

colindex The number of the column which has been cascaded.

data Address of a user-defined object, which can be used for any purpose by the function.

data is passed to callback as my\_object.

#### **Further information**

This callback can be used to provide user defined updates for SLP variables having a determining row that were not successfully cascaded due to the determining row being close to singular around the current values. This callback will always be called in place of the cascadevar callback in such cases, and in no situation will both the cascadevar and the cascadevarfail callback be called in the same iteration for the same variable.

## **Related topics**

problem.cascade, problem.setcbcascadeend, problem.setcbcascadestart, problem.setcbcascadevar

# problem.setcbcoefevalerror

## **Purpose**

Set a user callback to be called when an evaluation of a coefficient fails during the solve

# **Synopsis**

```
problem.setcbcoefevalerror (callback, data)
retval = callback (my_prob, my_object, rowindex, colindex)
```

### **Arguments**

callback The function to be called when an evaluation fails.

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as data to setcbcoefevalerror.

rowindex The row position of the coefficient.

colindex The column position of the coefficient.

data Address of a user-defined object, which can be used for any purpose by the function.

data is passed to callback as my\_object.

### **Further information**

This callback can be used to capture when an evaluation of a coefficient fails. The callback is called only once for each coefficient.

### **Related topics**

problem.printevalinfo

# problem.setcbconstruct

#### **Purpose**

Set a user callback to be called during the Xpress SLP augmentation process

# **Synopsis**

```
problem.setcbconstruct (callback, data)
retval = callback (my_prob, my_object)
```

# **Arguments**

callback
The function to be called during problem augmentation. callback returns an integer value. See below for an explanation of the values.

my\_prob
The problem passed to the callback function.

my\_object
The user-defined object passed as data to setcbconstruct.

Address of a user-defined object, which can be used for any purpose by the function.

data is passed to callback as my\_object.

# **Example**

The following example sets up a callback to be executed during the Xpress SLP problem augmentation:

```
value = []
p.setcbconstruct (CBConstruct, value)
```

The following sample callback function sets values for the variables the first time the function is called and returns to problem.construct to recalculate the initial matrix. The second time it is called it frees the allocated memory and returns to problem.construct to proceed with the rest of the augmentation.

```
def CBConstruct (myprob, obj) {
  if (obj == None):
    n = myprob.attributes.cols
    cValue = n * [0]
    # initialize with values (not shown here)
    for i in range (n):
    # store into SLP structures
    myprob.chgvar (i, None, None, None, None,
                   None, None, cValue[i], None, None, None,
                   None)
    # set Object non-null to indicate we have processed data
    obj = cValue
    return -1
  else:
    obj = None
 return 0
```

#### **Further information**

This callback can be used during the problem augmentation, generally (although not exclusively) to change the initial values for the variables.

The following return codes are accepted:

Normal return: augmentation continues

Return to recalculate matrix values

Return to recalculate row weights and matrix entries

ther Error return: augmentation terminates, problem.construct terminates with a nonzero error code.

The return values -1 and -2 will cause the callback to be called a second time after the matrix has been recalculated. It is the responsibility of the callback to ensure that it does ultimately exit with a return value of zero.

# **Related topics**

problem.construct

# problem.setcbdestroy

## **Purpose**

Set a user callback to be called when an SLP problem is about to be destroyed

# **Synopsis**

```
problem.setcbdestroy (callback, data)
callback (prob, my_object)
```

### **Arguments**

callback
The function to be called when the SLP problem is about to be destroyed. callback
returns an integer value. At present the return value is ignored.

my\_prob
The problem passed to the callback function.

my\_object
The user-defined object passed as object to setcbdestroy.

Address of a user-defined object, which can be used for any purpose by the function.
object is passed to callback as my\_object.

# Example

The following example sets up a callback to be executed before the SLP problem is destroyed:

```
p.setcbdestroy (CBDestroy, cSol)
```

The following sample callback function frees the memory associated with the user-defined object:

```
def CBDestroy (myprob, Obj):
   if (Obj != None):
     Obj.inuse = 0
   return 0
```

The object argument is used here to hold the address of the array csol which we assume was assigned using one of the malloc functions.

#### **Further information**

This callback can be used when the problem is about to be destroyed to free any user-defined resources which were allocated during the life of the problem.

# problem.setcbdrcol

#### **Purpose**

Set a user callback used to override the update of variables with small determining column

# **Synopsis**

## **Arguments**

callback The function to be called after each column has been cascaded. callback returns an

integer value. If the return value is positive, it will indicate that the value has been fixed, and cascading should be omitted for the variable. A negative value indicates that a previously fixed value has been relaxed. If no action is taken, a 0 return value should be

used.

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as object to setcbcascadevar.

Colindex The index of the column for which the determining columns is checked.

DrColindex The index of the determining column for the column that is being updated.

DrColValue The value of the determining column in the current SLP iteration.

NewValue Used to return the new value for column ColIndex, should it need to be updated, in

which case the callback must return a positive value to indicate that this value should be

used.

VLB The original lower bound of column Colindex. The callback provides this value as a

reference, should the bound be updated or changed during the solution process.

VUB The original upper bound of column ColIndex. The callback provides this value as a

reference, should the bound be updated or changed during the solution process.

object Address of a user-defined object, which can be used for any purpose. by the function.

object is passed to callback as my\_object.

## **Further information**

If set, this callback is called as part of the cascading procedure. Please see the chapter on cascading of the SLP Reference Manual for more information.

### **Related topics**

xslp\_DRCOLTOL, problem.cascade, problem.setcbcascadeend, problem.setcbcascadestart

# problem.setcbformula

# **Purpose**

Set a callback to be used in formula evaluation when an unknown token is found

#### **Synopsis**

```
problem.setcbformula (callback, object)
(retval = result) = callback (my_prob, my_object, value)
```

### **Arguments**

The function to be called during formula evaluation. callback returns an integer value. At present the value is ignored.

my\_prob
The problem passed to the callback function.

my\_object
The user-defined object passed as object to setcbformula.

The Value of the unknown token.

result
Address of a double precision value to hold the result of the calculation.

Address of a user-defined object, which can be used for any purpose by the function.

object is passed to callback as my\_object.

## **Example**

The following example sets a callback to process unknown tokens in formulae. It then creates a formula with an unknown token, and evaluates it.

```
def MyCB (MyProb, MyObject, MyValue):
    if (MyValue == None):
        Result = 1
    else:
        Result = 0
    return (0, Result)

p.setcbformula (MyCB, None)

nToken = 0
type = [xslp_op_con, xslp_op_unknown, xslp_op_op, xslp_op_eof]
value = [10, z, xslp_op_plus, 0]

answer = p.evaluateformula (1, type, value)

printf ("Answer:", answer)
```

This demonstrates how the value of an unknown token can be set in any way, as long as the routine that sets the token up and the callback agree on how it is to be interpreted. In this case, the value actually contains the address of a character string, which is converted by the callback into a real number.

#### **Related topics**

problem.evaluateformula

# problem.setcbiterend

# **Purpose**

Set a user callback to be called at the end of each SLP iteration

#### **Synopsis**

```
problem.setcbiterend (callback, object)
retval = callback (my_prob, my_object)
```

## **Arguments**

callback The function to be called at the end of each SLP iteration. callback returns an integer

value. If the return value is nonzero, the SLP iterations will stop.

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as object to setcbiterend.

object Address of a user-defined object, which can be used for any purpose by the function.

object is passed to callback as my\_object.

# **Example**

The following example sets up a callback to be executed at the end of each SLP iteration. It records the number of LP iterations in the latest optimization and stops if there were fewer than 10:

```
p.setcbiterend (CBIterEnd, None)
```

A suitable callback function might resemble this:

```
def CBIterEnd (MyProb, Obj):
  niter = MyProb.attributes.simplexiter
  return (niter < 10)</pre>
```

The object argument is not used here, and so is passed as None.

### **Further information**

This callback can be used at the end of each SLP iteration to carry out any further processing and/or stop any further SLP iterations.

# **Related topics**

problem.setcbiterstart,problem.setcbitervar

# problem.setcbiterstart

## **Purpose**

Set a user callback to be called at the start of each SLP iteration

# **Synopsis**

```
problem.setcbiterstart (callback, object)
retval = callback (my_prob, my_object)
```

### **Arguments**

The function to be called at the start of each SLP iteration. callback returns an integer value. If the return value is nonzero, the SLP iterations will stop.

my\_prob
The problem passed to the callback function.

my\_object
The user-defined object passed as object to setcbiterstart.

Address of a user-defined object, which can be used for any purpose by the function.

object is passed to callback as my\_object.

# **Example**

The following example sets up a callback to be executed at the start of the optimization to save to save the values of the variables from the previous iteration:

```
p.setcbiterstart (CBIterStart, cSol)
```

A suitable callback function might resemble this:

```
def CBIterStart (MyProb, Obj):
   niter = MyProb.attributes.xslp_iter
   if nIter == 0:
      return 0 # no previous solution
   Obj = []
   MyProb.getsol(xprob, Obj, None, None, None)
   return 0
```

The object argument is used here to hold the address of the array csol which we populate with the solution values.

#### **Further information**

This callback can be used at the start of each SLP iteration before the optimization begins.

## **Related topics**

problem.setcbiterend,problem.setcbitervar

# problem.setcbitervar

## **Purpose**

Set a user callback to be called after each column has been tested for convergence

# **Synopsis**

```
problem.setcbitervar (callback, object)
retval = callback (my_prob, my_object, colindex)
```

# **Arguments**

callback The function to be called after each column has been tested for convergence. callback returns an integer value. The return value is interpreted as a convergence status. The possible values are: The variable has not converged; < 0 The convergence status of the variable is unchanged; 1 to 10 The column has converged on a system-defined convergence criterion (these values should not normally be returned); > 10 The variable has converged on user criteria. The problem passed to the callback function. my\_prob The user-defined object passed as object to setcbitervar. my\_object ColIndex The number of the column which has been tested for convergence. A user-defined object, which can be used for any purpose by the function. object is object passed to callback as my\_object.

# **Example**

The following example sets up a callback to be executed after each variable has been tested for convergence. The user object Important is an integer array which has already been set up and holds a flag for each variable indicating whether it is important that it converges.

```
Obj = None
p.setcbitervar (CBIterVar, Obj)
```

The following sample callback function tests if the variable is already converged. If not, then it checks if the variable is important. If it is not important, the function returns a convergence status of 99.

```
def CBIterVar (MyProb, Obj, iCol):
    (a,b,c,d,e,f,g,h,i,converged,j,k,l,m,n) = MyProb.getvar (iCol)
    if (converged):
        return 0
    if Obj[iCol]:
        return 99
    return -1
```

The object argument is used here to hold the address of the array Important.

# **Further information**

This callback can be used after each variable has been checked for convergence, and allows the convergence status to be reset if required.

## **Related topics**

problem.setcbiterend,problem.setcbiterstart

# problem.setcbmessage

## **Purpose**

Set a user callback to be called whenever Xpress Nonlinear outputs a line of text

## **Synopsis**

```
problem.setcbmessage (callback, object)
callback (my_prob, my_object, msg, msgtype)
```

## **Arguments**

callback The function to be called whenever Xpress Nonlinear outputs a line of text. callback

does not return a value.

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as object to setcbmessage.

msg Character buffer holding the string to be output.

msgtype Type of message. The following are system-defined:

Information messageWarning messageError message

A negative value indicates that the Optimizer is about to finish and any buffers should be flushed at this time. User-defined values are also possible for msgtype which can be

passed using problem.printmsg

object Address of a user-defined object, which can be used for any purpose by the function.

object is passed to callback as my\_object.

# **Example**

The following example creates a log file into which all messages are placed. System messages are also printed on standard output:

```
log = ''
p.setcbmessage (CBMessage, log)
```

A suitable callback function could resemble the following:

```
def CBMessage (Obj, msg, msgtype):
  if msgtype < 0:
    print (log)
    log = ''
    return
  if msgtype >= 1 and msgtype <= 4:
    print (msg)
  else:
    log += msg + ';'</pre>
```

# **Further information**

If a user message callback is defined then screen output is automatically disabled.

Output can be directed into a log file by using problem.setlogfile.

### **Related topics**

```
problem.setlogfile
```

# problem.setcbmsjobend

# **Purpose**

Set a user callback to be called every time a new multistart job finishes. Can be used to overwrite the default solution ranking function

# **Synopsis**

```
problem.setcbmsjobend (callback, object)
status = callback (my_prob, my_object, job_object, description)
```

## **Arguments**

callback The function to be called when a new multistart job is created

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as object to setcbmsjobend.

<code>job\_object</code> Job specific user-defined object, as specified in by the multistart job creating API

functions.

description The description of the problem as specified in by the multistart job creating API

functions.

status User return status variable:

0 - use the default evaluation of the finished job

1 - disregard the result and continue

2 - stop the multistart search

#### **Further information**

The multistart pool is dynamic, and this callback can be used to load new multistart jobs using the normal API functions.

#### **Related topics**

problem.setcbmsjobstart,problem.setcbmswinner

# problem.setcbmsjobstart

## **Purpose**

Set a user callback to be called every time a new multistart job is created, and the pre-loaded settings are applied

## **Synopsis**

```
problem.setcbmsjobstart (callback, object)
status = callback (my_prob, my_object, job_object, description)
```

## **Arguments**

callback The function to be called when a new multistart job is created;

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as object to setcbmsjobstart.

job\_object Job specific user-defined object, as specified in by the multistart job creating API

functions.

description The description of the problem as specified in by the multistart job creating API

functions.

status User return status variable:

0 - normal return, solve the job,1 - disregard this job and continue,

2 - Stop multistart.

#### **Further information**

All mulit-start jobs operation on an independent copy of the original problem, and any modification to the problem is allowed, including structural changes. Please note however, that any modification will be carried over to the base problem, should a modified problem be declared the winner prob.

# **Related topics**

problem.setcbmsjobend,problem.setcbmswinner

# problem.setcbmswinner

# **Purpose**

Set a user callback to be called every time a new multistart job is created, and the pre-loaded settings are applied

## **Synopsis**

```
problem.setcbmswinner (callback, object)
callback (my_prob, my_object, job_object, description)
```

## **Arguments**

callback The function to be called when a new multistart job is created

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as object to setcbmswinner.

job\_object Job specific user-defined object, as specified in by the multistart job creating API

functions.

description The description of the problem as specified in by the multistart job creating API functions.

### **Further information**

The multistart pool is dynamic, and this callback can be used to load new multistart jobs using the normal API functions.

# **Related topics**

problem.setcbmsjobstart,problem.setcbmsjobend

# problem.setcbslpend

## **Purpose**

Set a user callback to be called at the end of the SLP optimization

# **Synopsis**

```
problem.setcbslpend (callback, object)
callback (my_prob, my_object)
```

### **Arguments**

The function to be called at the end of the SLP optimization. callback returns an integer value. If the return value is nonzero, the optimization will return an error code and the "User Return Code" error will be set.

my\_prob
The problem passed to the callback function.

my\_object
The user-defined object passed as object to setcbslpend.

object Address of a user-defined object, which can be used for any purpose by the function.

object is passed to callback as my\_object.

## **Example**

The following example sets up a callback to be executed at the end of the SLP optimization. It frees the memory allocated to the object created when the optimization began:

```
ObjData = None
p.setcbslpend (CBSlpEnd, ObjData)
```

A suitable callback function might resemble this:

```
def CBSlpEnd (MyProb, Obj):
   if (Obj != None)
     Obj = []
   else Obj = None
   return 0
```

### **Further information**

This callback can be used at the end of the SLP optimization to carry out any further processing or housekeeping before the optimization function returns.

### **Related topics**

problem.setcbslpstart

# problem.setcbslpnode

## **Purpose**

Set a user callback to be called during MISLP after the SLP optimization at each node.

## **Synopsis**

```
problem.setcbslpnode (callback, object)
(retval, feas) = callback (my_prob, my_object)
```

## **Arguments**

callback The function to be called after the set-up of the SLP problem to be solved at a node.

callback returns an integer value. If the return value is nonzero, or if the feasibility flag is set nonzero, then further processing of the node will be terminated (it is declared

infeasible).

my\_prob The problem passed to the callback function.

my\_object The user-defined object passed as object to setcbslpnode.

feas Address of an integer containing the feasibility flag. If callback sets the flag nonzero,

the node is declared infeasible.

object Address of a user-defined object, which can be used for any purpose by the function.

object is passed to callback as my\_object.

# **Example**

The following example sets up a callback function to be executed at each node after the SLP optimization finishes. If the solution value is worse than a target value (referenced through the user object), the node is cut off (it is declared infeasible).

```
objtarget = []
p.setcbslpnode (CBSLPNode, objtarget)
```

A suitable callback function might resemble the following:

```
def CBSLPNode (my_prob, my_obj):
   lpval = my_prob.attributes.lpobjval
   return (0, (lpval < my_obj))</pre>
```

#### **Further information**

If a node can be cut off by the callback function, then further exploration of the node is avoided.

# problem.setcbslpstart

## **Purpose**

Set a user callback to be called at the start of the SLP optimization

# **Synopsis**

```
problem.setcbslpstart (callback, object)
retval = callback (my_prob, my_object)
```

# **Arguments**

The function to be called at the start of the SLP optimization. callback returns an integer value. If the return value is nonzero, the optimization will not be carried out.

my\_prob
The problem passed to the callback function.

my\_object
The user-defined object passed as object to setcbslpstart.

User-defined object, which can be used for any purpose by the function. object is passed to callback as my\_object.

# **Example**

The following example sets up a callback to be executed at the start of the SLP optimization:

```
Objdata = []
p.setcbslpstart (CBSlpStart, Objdata)
```

A suitable callback function might resemble this:

```
def CBSlpStart (object):
   object.append (1)
   return 0
```

#### **Further information**

This callback can be used at the start of the SLP optimization to carry out any housekeeping before the optimization actually starts. Note that a nonzero return code from the callback will terminate the optimization immediately.

## **Related topics**

problem.setcbslpend

# problem.setControl

## **Purpose**

Sets one or more controls of a problem.

# **Synopsis**

```
problem.setControl (string, value)
```

# **Example**

```
p = xpress.problem ()
p.setControl ('miprelstop', 1e-4)
p.setControl ({'feastol': 1e-4, 'presolve': 0})
```

#### **Further information**

- 1. As mentioned in the previous chapter, there is an alternative way to set and retrieve controls. It works by querying the data structure controls of each problem or, if one wants to set a control to be used by all problems defined subsequently, the global control object xpress.controls.
- 2. This function can be used in two ways depending on whether one wants to set one or more controls. In the first case, the arguments form a pair (string, value) where the first element is the lower-case name of a control (see the Xpress Optimizer reference manual for a complete list of controls). In the second case, the argument is a Python *dictionary* whose keys are control name string and whose values are the value of the control.

## **Related topics**

```
problem.getControl.
```

# problem.setcurrentiv

# **Purpose**

Transfer the current solution to initial values

# **Synopsis**

problem.setcurrentiv ()

# **Further information**

Provides a way to set the current iterates solution as initial values, make changes to parameters or to the underlying nonlinear problem and then rerun the SLP optimization process.

# **Related topics**

problem.reinitialize,problem.unconstruct

# problem.setdefaultcontrol

## **Purpose**

Sets one control to its default values. Must be called before the problem is read or loaded by problem.read and problem.loadproblem.

## **Synopsis**

```
problem.setdefaultcontrol (control)
```

# **Argument**

control Name of the control to be set to default.

## **Example**

The following turns off presolve to solve a problem, before resetting the control defaults, reading it and solving it again:

```
p.controls.presolve = 0
p.mipoptimize ("")
p.writeprtsol ()
p.setdefaultcontrol ('presolve')
p.read ()
p.mipoptimize ("")
```

# **Related topics**

xpress.setdefaultcontrol, xpress.setdefaults, problem.setdefaultcontrol.

# problem.setdefaults

# **Purpose**

Sets all controls to their default values. It must be called before the problem is read with problem.read or loaded with problem.loadproblem.

# **Synopsis**

```
problem.setdefaults ()
```

# **Example**

The following turns off presolve to solve a problem, before resetting the control defaults, reading it and solving it again:

```
p.controls.presolve = 0
p.mipoptimize ("")
p.writeprtsol ()
p.setdefaults ()
p.read ()
p.mipoptimize ("")
```

# **Related topics**

xpress.setdefaultcontrol, xpress.setdefaults, problem.setdefaults.

# problem.setindicators

## **Purpose**

Specifies that a set of rows in the problem will be treated as indicator constraints during a global search. An indicator constraint is made of a condition and a linear inequality. The condition is of the type "bin = value", where bin is a binary variable and value is either 0 or 1. The linear inequality is any linear row in the problem with type <= (L) or >= (G). During global search, a row configured as an indicator constraint is enforced only when condition holds, that is only if the indicator variable bin has the specified value.

## **Synopsis**

```
problem.setindicators (mrows, inds, comps)
```

## **Arguments**

Array containing the indices of the rows that define the linear inequality part for the indicator constraints.

inds

Array containing the column indices of the indicator variables.

comps

Array with the complement flags:

not an indicator constraint (in this case the corresponding entry in the inds array is ignored);

for indicator constraints with condition "bin = 1";

for indicator constraints with condition "bin = 0";

# **Example**

This sets the first two matrix rows as indicator rows in the global problem prob; the first row controlled by condition x4=1 and the second row controlled by condition x5=0 (assuming x4 and x5 correspond to columns indices 4 and 5).

```
p.setindicators ([0,1],[4,5],[1,-1])
p.mipoptimize ("")
```

## **Further information**

Indicator rows must be set up before solving the problem. Any indicator row will be removed from the problem after presolve and added to a special pool. An indicator row will be added back into the active matrix only when its associated condition holds. An indicator variable can be used in multiple indicator rows and can also appear in normal rows and in the objective function.

# **Related topics**

problem.getindicators.

# problem.setlogfile

## **Purpose**

This directs all Optimizer output to a log file.

#### **Synopsis**

```
problem.setlogfile (filename)
```

# **Argument**

filename

The name of the file to which all output will be directed. If set to None, redirection of the output will stop and all screen output will be turned back on (except for DLL users where screen output is always turned off).

## **Example**

The following directs output to the file logfile.log:

```
p = xpress.problem ()
p.setlogfile ("logfile.log")
```

### **Further information**

- 1. It is recommended that a log file be set up for each problem being worked on, since it provides a means for obtaining any errors or warnings output by the Optimizer during the solution process.
- 2. If output is redirected with setlogfile all screen output will be turned off.
- 3. Alternatively, an output callback can be defined using problem.addcbmessage, which will be called every time a line of text is output. Defining a user output callback will turn all screen output off. To discard all output messages the OUTPUTLOG integer control can be set to 0.

# **Related topics**

 ${\tt problem.addcbmessage}.$ 

# problem.setmessagestatus

## **Purpose**

Manages suppression of messages.

# **Synopsis**

```
problem.setmessagestatus (errcode, status)
```

# **Arguments**

errcode The id number of the message. Refer to the Section 9 of the Xpress Optimizer reference

manual for a list of possible message numbers.

status Non-zero if the message is not suppressed; 0 otherwise.

## **Example**

Attempting to optimize a problem that has no matrix loaded gives error 91. The following code uses setmessagestatus to suppress the error message:

```
p = xpress.problem ()
p.setmessagestatus (91, 0)
p.lpoptimize ("")
```

#### **Further information**

If a message is suppressed globally then the message can only be enabled for any problem once the global suppression is removed with a call to setmessagestatus with prob passed as None.

# **Related topics**

problem.getmessagestatus.

## problem.setObjective

#### **Purpose**

Sets the objective function of the problem.

#### **Synopsis**

```
problem.setObjective (expr)
```

#### **Argument**

expr

A linear or quadratic function of the variables that were added to the problem prior to this call. An error will be returned if any variable in the linear or quadratic part of the objective was not added to the problem via addVariable.

#### **Example**

The following example sets the objective function of the problem to  $[2x_1^2 + 3x_1x_2 + 5x_2^2 + 4x_1 + 4]$ :

```
x1 = xpress.var ()
x2 = xpress.var ()
p = xpress.problem ()
p.addVariables (x1, x2)
p.setObjective (2*x1**2 + 3*x1*x2 + 5*x2**2 + 4*x1 + 4)
```

#### **Further information**

Multiple calls to setObjective are allowed, and each replaces the old objective function with a new one.

```
problem.addVariable.
```

## problem.setprobname

#### **Purpose**

Sets the current default problem name.

#### **Synopsis**

problem.setprobname (probname)

#### **Argument**

probname A string of up to MAXPROBNAMELENGTH characters containing the problem name.

#### **Related topics**

problem.read, problem.name, MAXPROBNAMELENGTH.

## problem.setuniqueprefix

#### **Purpose**

Find a prefix character string which is different from all the names currently in use within the SLP problem

#### **Synopsis**

```
problem.setuniqueprefix ()
```

#### **Example**

The following example reads a problem from file and then finds a unique prefix so that new names can be added without fear of duplications:

```
p.read ("Matrix", "")
p.setuniqueprefix ()
s = p.attributes.xslp_uniqueprefix
print ("No names start with ", s)
```

#### **Further information**

The unique prefix may be more than one character in length, and may change if new names are added to the problem. The value of the unique prefix can be obtained from the string attribute xslp\_uniqueprefix.

## problem.solve

#### **Purpose**

Solves the current problem.

## Synopsis

problem.solve (flags)

### Argument

flags (optional) a string with flags expressed as characters.

## problem.storebounds

#### **Purpose**

Stores bounds for node separation using user separate callback function.

#### **Synopsis**

mindex = problem.storebounds (mcols, type, bds)

#### **Arguments**

mcols Array containing the column indices.

type Array containing the bounds types:

U indicates an upper bound;

L indicates a lower bound.

bds Array containing the bound values.

mindex Object that the user will use to reference the stored bounds for the Optimizer in

problem.setbranchbounds.

#### **Related topics**

problem.setbranchbounds.

### problem.storecuts

#### **Purpose**

Stores cuts into the cut pool, but does not apply them to the current node. These cuts must be explicitly loaded into the matrix using problem.loadcuts or problem.setbranchcuts before they become active.

#### **Synopsis**

#### **Arguments**

do not exclude duplicates from the cut pool; nodupl 0 duplicates are to be excluded from the cut pool; 1 duplicates are to be excluded from the cut pool, ignoring cut type. Array containing the cut types. The cut types can be any integer and are used to identify mtype the cuts. Character array containing the row types: rtype indicates a < row; Ε indicates an = row; indicates a  $\geq$  row. G Array containing the right hand side elements for the cuts. rhs Array containing offsets into the mcols and dmtval arrays indicating the start of each mstart cut. This array is of length ncuts+1 where ncuts is the length of drhs, with the last element mstart[ncuts] being where cut ncuts+1 would start. Array where the cuts will be returned. mindex mcols Array containing the column indices in the cuts. dmatval Array containing the matrix values for the cuts.

#### **Further information**

- 1. storecuts can be used to eliminate duplicate cuts. If the nodup1 parameter is set to 1, the cut pool will be checked for duplicate cuts with a cut type identical to the cuts being added. If a duplicate cut is found the new cut will only be added if its right hand side value makes the cut stronger. If the cut in the pool is weaker than the added cut it will be removed unless it has been applied to an active node of the tree. If nodup1 is set to 2 the same test is carried out on all cuts, ignoring the cut type.
- 2. storecuts returns a list of the cuts added to the cut pool in the mindex array. If the cut is not added to the cut pool because a stronger cut exits a None will be returned. The mindex array can be passed directly to problem.loadcuts or problem.setbranchcuts to load the most recently stored cuts into the matrix.
- 3. The columns and elements of the cuts must be stored contiguously in the mcols and dmtval arrays passed to storecuts. The starting point of each cut must be stored in the mstart array. To determine the length of the final cut the mstart array must be of length ncuts+1 with the last element of this array containing where the cut ncuts+1 would start.

#### **Related topics**

problem.loadcuts problem.setbranchcuts, Section "Working with the cut manager" of the Xpress Optimizer reference manual.

## problem.strongbranch

#### **Purpose**

Performs strong branching iterations on all specified bound changes. For each candidate bound change, strongbranch performs dual simplex iterations starting from the current optimal solution of the base LP, and returns both the status and objective value reached after these iterations.

#### **Synopsis**

#### **Arguments**

mbndind	Array containing the indices of the columns on which the bounds will change.	
cbndtype	Character array indicating the type of bound to change:  U indicates change the upper bound;  L indicates change the lower bound;  B indicates change both bounds, i.e. fix the column.	
dbndval	Array giving the new bound values.	
itrlimit	Maximum number of LP iterations to perform for each bound change.	
dsobjval	Objective value of each LP after performing the strong branching iterations.	
msbstatus	Status of each LP after performing the strong branching iterations, as detailed for the LPSTATUS attribute.	

#### Example

Suppose that the current LP relaxation has two integer columns (columns 0 and 1 which are fractionals at 0.3 and 1.5, respectively, and we want to perform strong branching in order to choose which to branch on. This could be done in the following way:

#### **Further information**

Prior to calling strongbranch, the current LP problem must have been solved to optimality and an optimal basis must be available.

### problem.strongbranchcb

#### **Purpose**

Performs strong branching iterations on all specified bound changes. For each candidate bound change, strongbranched performs dual simplex iterations starting from the current optimal solution of the base LP, and returns both the status and objective value reached after these iterations.

#### **Synopsis**

#### **Arguments**

bndind Array containing the indices of the columns on which the bounds will change.

bndtype Character array indicating the type of bound to change:

U indicates change the upper bound;L indicates change the lower bound;

B indicates change both bounds, i.e. fix the column.

bndval Array giving the new bound values.

itrlimit Maximum number of LP iterations to perform for each bound change.

objval Objective value of each LP after performing the strong branching iterations.

status Status of each LP after performing the strong branching iterations, as detailed for the

LPSTATUS attribute.

sbsolvecb Function to be called after each strong branch has been reoptimized.

vContext User context to be provided for sbsolvecb.

ibnd The index of bound for which sbsolvecb is called.

#### **Further information**

Prior to calling strongbrancheb, the current LP problem must have been solved to optimality and an optimal basis must be available.

strongbranchcb is an extension to problem. strongbranch. If identical input arguments are provided both will return identical results, the difference being that for the case of PRSstrongbranchcb the sbnodecb function is called at the end of each LP reoptimization. For each branch optimized, the LP can be interrogated: the LP status of the branch is available through checking LPSTATUS, and the objective function value is available through LPOBJVAL. It is possible to access the full current LP solution by using problem.getlpsol.

## problem.tokencount

#### **Purpose**

Count the number of tokens in a free-format character string

#### **Synopsis**

```
token = problem.tokencount (record)
```

#### **Argument**

record The character string to be processed. This must be terminated with a null character.

#### **Return value**

The number of tokens (strings separated by one or more spaces) in record.

#### **Example**

The following example counts the number of tokens in the string " $\sin (x + y)$ ":

```
nToken = p.tokencount ("sin (x + y)")
```

#### **Further information**

Record should follow the conventions for Extended MPS Format, with each token being separated by one or more spaces from the previous token.

### problem.tune

#### **Purpose**

Begin a tuner session for the current problem. The tuner will solve the problem multiple times while evaluating a list of control settings and promising combinations of them. When finished, the tuner will select and set the best control setting on the problem. Note that the direction of optimization is given by xpress.attributes.objsense.

#### **Synopsis**

problem.tune (flags)

#### **Argument**

flags

Flags to specify whether to tune the current problem as an LP or a MIP problem, and the algorithm for solving the LP problem or the initial LP relaxation of the MIP. The flags are optional. If the argument includes:

- will tune the problem as an LP (mutually exclusive with flag g);
- g will tune the problem as a MIP (mutually exclusive with flag 1);
- d will use the dual simplex method;
- p will use the primal simplex method;
- b will use the barrier method;
- n will use the network simplex method.

#### **Example**

```
p.tune ('dp')
```

This tunes the current problem. The problem type is automatically determined. If it is an LP problem, it will be solved with a concurrent run of the dual and primal simplex method. If it is a MIP problem, the initial LP relaxation of the MIP will be solved with a concurrent run of primal and dual simplex.

#### **Further information**

Please refer to the Xpress Optimizer reference manual for a detailed guide of how to use the tuner.

## problem.tunerreadmethod

#### **Purpose**

Load a user defined tuner method from the given file.

#### **Synopsis**

```
problem.tunerreadmethod (methodfile)
```

#### **Argument**

methodfile The method file name, from which the tuner can load a user-defined tuner method.

#### **Example**

```
p.tunerreadmethod ('method.xtm')
```

This loads the tuner method from the method.xtm file.

#### **Further information**

Please refer to the Xpress Optimizer reference manual for more information about the tuner method and for the format of the tuner method file.

## problem.tunerwritemethod

#### **Purpose**

Writes the current tuner method to a given file or prints it to the console.

#### **Synopsis**

```
problem.tunerwritemethod (methodfile)
```

#### **Argument**

methodfile The file name to which the tuner will write the current tuner method. If the input is stdout or STDOUT, then the tuner will print the method to the console instead.

#### **Example 1 (Library)**

```
p.tunerwritemethod ('method.xtm')
```

This writes the tuner method to the file method.xtm.

#### **Example 2 (Library)**

```
p.tunerwritemethod ('stdout')
```

This prints the tuner method to the console.

#### **Further information**

Please refer to the Xpress Optimizer reference manual for more information about the tuner method and for the format of the tuner method file.

## problem.unconstruct

#### **Purpose**

Reset the SLP problem and removes the augmentation structures

#### **Synopsis**

```
problem.unconstruct ()
```

#### **Further information**

Can be used to rerun the SLP optimization process with changed parameters or underlying lienar / nonlienar strutures.

#### **Related topics**

problem.reinitialize,problem.setcurrentiv,

## problem.updatelinearization

#### **Purpose**

Updates the current linearization

#### **Synopsis**

problem.updatelinearization ()

#### **Further information**

Updates the augmented probem (the linearization) to match the current base point. The base point is the current SLP solution. The values of the SLP variables can be changed using problem.chgvar.

The linearization must be present, and this function can only be called after the problem has been augmented by problem.construct.

#### **Related topics**

problem.construct

### problem.validate

#### **Purpose**

Validate the feasibility of constraints in a converged solution

#### **Synopsis**

```
problem.validate ()
```

#### **Example**

The following example sets the validation tolerance parameters, validates the converged solution and retrieves the validation indices.

```
p.controls.xslp_validationtol_a = 0.001
p.controls.xslp_validationtol_r = 0.001
p.validate ()
indexA = p.attributes.xslp_validationindex_a
indexR = p.attributes.xslp_validationindex_r
```

#### **Further information**

XSLPvalidate checks the feasibility of a converged solution against relative and absolute tolerances for each constraint. The left hand side and the right hand side of the constraint are calculated using the converged solution values. If the calculated values imply that the constraint is infeasible, then the difference (D) is tested against the absolute and relative validation tolerances.

```
If D < XSLP_VALIDATIONTOL_A
```

then the constraint is within the absolute validation tolerance. The total positive (*TPos*) and negative contributions (*TNeg*) to the left hand side are also calculated.

```
If D < MAX(ABS(TPos), ABS(TNeg)) * XSLP_VALIDATIONTOL_R
```

then the constraint is within the relative validation tolerance. For each constraint which is outside both the absolute and relative validation tolerances, validation factors are calculated which are the factors by which the infeasibility exceeds the corresponding validation tolerance; the smallest factor is printed in the validation report.

The validation index xslp\_validationindex\_a is the largest absolute validation factor multiplied by the absolute validation tolerance; the validation index xslp\_validationindex\_r is the largest relative validation factor multiplied by the relative validation tolerance.

```
xslp_validationindex_A, xslp_validationindex_R, xslp_validationtol_A,
xslp_validationtol_R
```

## problem.validatekkt

#### **Purpose**

Validates the first order optimality conditions also known as the Karush-Kuhn-Tucker (KKT) conditions versus the currect solution

#### **Synopsis**

#### **Arguments**

160			
calculationmode The	e calculation mode can be:		
0	recalculate the reduced costs at the current solution using the current dual		
	solution.		
1	minimize the sum of KKT violations by adjusting the dual solution.		
2	perform both.		
respectbasisstatus	The following ways are defined to assess if a constraint is active:		
0	evaluate the recalculated slack activity versus xslp_ECFTOL_R.		
1	use the basis status of the slack in the linearized problem if available.		
2	use both.		
updatemultipliers	The calculated values can be:		
0	only used to calculate the xslp_validationindex_k measure.		
1	used to update the current dual solution and reduced costs.		
kktviolationtarget	When calculating the best KKT multipliers, it is possible to enforce an even		
distribution of reduced costs violations by enforcing a bound on them.			

#### **Further information**

The bounds enforced by kktviolationtarget are automatically relaxed if the desired accuracy cannot be achieved.

## problem.validaterow

#### **Purpose**

Prints an extensive analysis on a given constraint of the SLP problem

#### **Synopsis**

problem.validate (row)

#### **Argument**

row

The index of the row to be analyzed.

#### **Further information**

The analysis will include the readable format of the original constraint and the augmented constraint. For infeasible constraints, the absolute and relative infeasibility is calculated. Variables in the constraints are listed including their value in the solution of the last linearization, the internal value (e.g. cascaded), reduced cost, step bound and convergence status. Scaling analysis is also provided.

## problem.validatevector

#### **Purpose**

Validate the feasibility of constraints for a given solution

#### **Synopsis**

```
(suminf, sumscaledinf, obj) = problem.validate (vector)
```

#### **Arguments**

vector A vector of length xpress.attributes.cols containing the solution vector to be

checked.

suminf The sum of infeasibilities.

sumscaledinf The sum of scaled (relative) infeasibilities.

obj The net objective.

#### **Further information**

```
validatevector works the same way as problem.validate, and will update xslp_validationindex_a and xslp_validationindex_r.
```

## problem.validformula

#### **Purpose**

Check a formula in internal (parsed or unparsed) format for unknown tokens

#### **Synopsis**

(token, name, stringtable) = problem.validformula (type, value)

#### **Arguments**

type Array of token types providing the formula.

value Array of values corresponding to the types in inType

ntoken Number of the first invalid token in the formula. A value of zero means that the formula

is valid. May be None if not required.

name Character buffer to hold the name of the first invalid token. May be None if not required. stringtable Character buffer holding the names of the unidentified tokens (this can be created by

problem.preparseformula).

#### **Related topics**

problem.preparseformula

### problem.write

#### **Purpose**

Writes the current problem to an MPS or LP file.

#### **Synopsis**

```
problem.write (filename, flags)
```

#### **Arguments**

filename A string of up to 200 characters to contain the file name to which the problem is to be

written. If omitted, the default problem\_name is used with a .mps extension, unless the

1 flag is used in which case the extension is .1p.

flags (optional) Flags, which can be one or more of the following:

h single precision of numerical values;

o one element per line;

n scaled;

s scrambled vector names;

1 output in LP format;

x output MPS file in hexadecimal format.

p obsolete flag (now default behavior).

#### **Example**

The following example outputs the current problem in full precision, LP format with scrambled vector names to the file *problem\_name*.lp.

```
p.write ("", "lps")
```

#### **Further information**

- 1. If problem.loadproblem is used to obtain a problem then there is no association between the objective function and the N rows in the problem and so a separate N row (called \_\_OBJ\_\_\_) is created upon a write. Also, if after a call to read either the objective row or the N row in the problem corresponding to the objective row are changed, the association between the two is lost and the \_\_OBJ\_\_\_ row is created with an write. To remove the objective row from the problem when doing a read, set keepnrows to -1 before read.
- 2. The hexadecimal format is useful for saving the exact internal precision of the problem.
- 3. **Warning:** If problem.read is used to input a problem, then the input file will be overwritten by write if a new filename is not specified.

#### **Related topics**

problem.read.

### problem.writebasis

#### **Purpose**

Writes the current basis to a file for later input into the Optimizer.

#### **Synopsis**

```
problem.writebasis (filename, flags)
```

#### **Arguments**

filename A string of up to 200 characters containing the file name from which the basis is to be written. If omitted, the default *problem\_name* is used with a .bss extension.

flags (optional) Flags to pass to writebasis:

- i output the internal presolved basis.
- t output a compact advanced form of the basis.
- n output basis file containing current solution values.
- h output values in single precision.
- x output values in hexadecimal format.
- p obsolete flag (now default behavior).

#### **Example**

After an LP has been solved it may be desirable to save the basis for future input as an advanced starting point for other similar problems. This may save significant amounts of time if the LP is complex. The Optimizer input commands might then be:

```
p.read ("myprob", "")
p.lpoptimize ("")
p.writebasis ("", "")
```

This reads in a problem file, maximizes the LP and saves the basis. Loading a basis for a MIP problem can disable some MIP presolve operations which can result in a large increase in solution times so it is generally not recommended.

#### **Further information**

- 1. The t flag is only useful for later input to a similar problem using the t flag with problem.readbasis.
- 2. If the Newton barrier algorithm has been used for optimization then crossover must have been performed before there is a valid basis. This basis can then only be used for restarting the simplex (primal or dual) algorithm.
- 3. writebasis will output the basis for the original problem even if the problem has been presolved.

```
problem.getbasis,problem.readbasis.
```

### problem.writebinsol

#### **Purpose**

Writes the current MIP or LP solution to a binary solution file for later input into the Optimizer.

#### **Synopsis**

```
problem.writebinsol (filename, flags)
```

#### **Arguments**

filename A string of up to 200 characters containing the file name to which the solution is to be

written. If omitted, the default *problem\_name* is used with a .sol extension.

flags (optional) Flags to pass to writebinsol:

x output the LP solution.

#### **Example**

After an LP has been solved or a MIP solution has been found the solution can be saved to file. If a MIP solution exists it will be written to file unless the x flag is passed to writebinsol in which case the LP solution will be written.

```
p.read ("myprob", "")
p.mipoptimize ("")
p.writebinsol ("", "")
```

```
problem.getlpsol,problem.getmipsol,problem.readbinsol,problem.writesol,
problem.writeprtsol.
```

## problem.writedirs

#### **Purpose**

Writes the global search directives from the current problem to a directives file.

#### **Synopsis**

problem.writedirs (filename)

#### **Argument**

filename

A string of up to 200 characters containing the file name to which the directives should be written. If omitted (or None), the default  $problem\_name$  is used with a .dir

extension.

#### **Further information**

If the problem has been presolved, only the directives for columns in the presolved problem will be written to file.

#### **Related topics**

problem.loaddirs.

### problem.writeprtsol

#### **Purpose**

Writes the current solution to a fixed format ASCII file, problem\_name.prt.

#### **Synopsis**

```
problem.writeprtsol (filename, flags)
```

#### **Arguments**

filename A string of up to 200 characters containing the file name to which the solution is to be

written. If omitted, the default problem\_name will be used. The extension .prt will be

appended.

flags (optional) Flags for writeprtsol are:

write the LP solution instead of the current MIP solution.

#### **Example**

This example shows the standard use of this function, outputting the solution to file immediately following optimization:

```
p.read ("myprob", "")
p.lpoptimize ("")
p.writeprtsol ("", "")
```

#### **Further information**

- The fixed width ASCII format created by this command is not as readily useful as that produced by problem.writesol. The main purpose of writeprtsol is to create a file that can be sent directly to a printer. The format of this fixed format ASCII file is described in the Xpress Optimizer reference manual.
- 2. To create a prt file for a previously saved solution, the solution must first be loaded with the problem.readbinsol function.

```
problem.getlpsol,problem.getmipsol,problem.readbinsol,problem.writebinsol,problem.writesol.
```

### problem.writeslxsol

#### **Purpose**

Creates an ASCII solution file (.slx) using a similar format to MPS files. These files can be read back into the Optimizer using the problem.readslxsol function.

#### **Synopsis**

```
problem.writeslxsol (filename, flags)
```

#### **Arguments**

filename A string of up to 200 characters containing the file name to which the solution is to be

written. If omitted, the default *problem\_name* is used with a .slx extension.

flags (optional) Flags to pass to writeslxsol:

- write the LP solution in case of a MIP problem;
- m write the MIP solution;
- p use full precision for numerical values;
- x use hexadecimal format to write values;
- d LP solution only: including dual variables;
- s LP solution only: including slack variables;
- r LP solution only: including reduced cost.

#### **Example**

```
p.writeslxsol ("lpsolution", "")
```

This saves the MIP solution if the problem contains global entities, or otherwise saves the LP (barrier in case of quadratic problems) solution of the problem.

```
problem.readslxsol problem.writeprtsol,problem.writebinsol,
problem.readbinsol.
```

### problem.writesol

#### **Purpose**

Writes the current solution to a CSV format ASCII file, problem\_name.asc (and .hdr).

#### **Synopsis**

```
problem.writesol (filename, flags)
```

#### **Arguments**

filename

A string of up to 200 characters containing the file name to which the solution is to be written. If omitted, the default *problem\_name* will be used. The extensions .hdr and .asc will be appended.

flags

(optional) Flags to control which optional fields are output:

- s sequence number;
- n name;
- t type;
- b basis status;
- a activity;
- c cost (columns), slack (rows);
- 1 lower bound;
- u upper bound;
- d dj (column; reduced costs), dual value (rows; shadow prices);
- r right hand side (rows).

If no flags are specified, all fields are output.

#### Additional flags:

- outputs every MIP or goal programming solution saved;
- p outputs in full precision;
- q only outputs vectors with nonzero optimum value;
- x output the current LP solution instead of the MIP solution.

#### **Example**

In this example the basis status is output (along with the sequence number) following optimization:

```
p.read ("prob1", "")
p.lpoptimize ("")
p.writesol ("", "sb")
```

#### **Further information**

- 1. The command produces two readable files: filename.hdr (the solution header file) and filename.asc (the CSV foramt solution file). The header file contains summary information, all in one line. The ASCII file contains one line of information for each row and column in the problem. Any fields appearing in the .asc file will be in the order the flags are described above. The order that the flags are specified by the user is irrelevant.
- 2. Additionally, the mask control OUTPUTMASK may be used to control which names are reported to the ASCII file. Only vectors whose names match OUTPUTMASK are output. OUTPUTMASK is set by default to "???????", so that all vectors are output.

```
problem.getlpsol, problem.getmipsol, problem.writeprtsol.
```

## branchobj.addbounds

#### **Purpose**

Adds new bounds to a branch of a user branching object.

#### **Synopsis**

branchobj.addbounds (ibranch, bndtype, bndcol, bndval)

#### **Arguments**

ibranch The number of the branch to add the new bounds for. This branch must already have

been created using branchobj.addbranches. Branches are indexed starting from

zero.

bndtype Character array indicating the type of bounds to add:

L Lower bound.
U Upper bound.

bndcol Array containing the columns for the new bounds.

bndval Array giving the bound values.

## branchobj.addbranches

#### **Purpose**

Adds new, empty branches to a user defined branching object.

#### **Synopsis**

branchobj.addbranches (nbranches)

### Argument

nbranches Number of new branches to create.

## branchobj.addcuts

#### **Purpose**

Adds stored user cuts as new constraints to a branch of a user branching object.

#### **Synopsis**

branchobj.addcuts (ibranch, cutind)

#### **Arguments**

ibranch The number of the branch to add the cuts for. This branch must already have been

created using <a href="mailto:branchobj.addbranches">branchobj.addbranches</a>. Branches are indexed starting from zero.

cutind Array containing the user cuts that should be added to the branch.

#### **Related topics**

branchobj.addrows.

### branchobj.addrows

#### **Purpose**

Adds new constraints to a branch of a user branching object.

#### **Synopsis**

```
branchobj.addrows (ibranch, rtype, rhs, beg, mcol, val)
```

#### **Arguments**

ibranch The number of the branch to add the new constraints for. This branch must already have been created using branchobj. addbranches. Branches are indexed starting from zero. Character array indicating the type of constraints to add: rtype Less than type. G Greater than type. Ε Equality type. Array containing the right-hand side values. rhs Array containing the offsets of the mcol and dval arrays of the start of the non zero beg coefficients in the new constraints.

mcol Array containing the column indices for the non zero coefficients.

dval Array containing the non-zero coefficient values.

#### **Example**

The following function will create a branching object that branches on constraints  $x_1 + x_2 \ge 1$  or  $x_1 + x_2 \le 0$ :

```
def CreateConstraintBranch (mip, icol):

# Create the new object with two empty branches.
bo = xpress.branchobj (mip, isoriginal = True)
bo.addbranches (2)

# Add the constraint of the branching object:
# x1 + x2 >= 1
# x1 + x2 <= 0
bo.addrows (0, 1, 2, ['G'], [1.0], [0], [0,1], [1.0,1.0])
bo.addrows (1, 1, 2, ['L'], [0.0], [0], [0,1], [1.0,1.0])

# Set a low priority value so our branch object is picked up
# before the default branch candidates.
bo.setpriority (100)

return bo</pre>
```

## branchobj.getbounds

#### **Purpose**

Returns the bounds for a branch of a user branching object. The returned value is the actual number of bounds returned in the output arrays.

#### **Synopsis**

branchobj.getbounds (ibranch, nbounds\_size, bndtype, bndcol, bndval)

#### **Arguments**

ibranch The number of the branch to get the bounds for. nbounds\_size Maximum number of bounds to return.

bndtype Character array of length nbounds\_size where the types of bounds twill be returned:

L Lower bound.
U Upper bound.

bndcol Array of length nbounds\_size where the column indices will be returned.

bndval Array of length nbounds\_size where the bound values will be returned.

#### **Related topics**

branchobj.addbounds.

## branchobj.getbranches

#### **Purpose**

Returns the number of branches of a branching object.

### Synopsis

branchobj.getbranches ()

## **Related topics**

branchobj.addbranches.

## branchobj.getid

#### **Purpose**

Returns the unique identifier assigned to a branching object.

#### **Synopsis**

branchobj.getid ()

#### **Further information**

- 1. Branching objects associated with existing column entities (binaries, integers, semi-continuous and partial integers), are given an identifier from 1 to MIPENTS.
- 2. Branching objects associated with existing Special Ordered Sets are given an identifier from MIPENTS+1 to MIPENTS+SETS.
- 3. User created branching objects will always have a negative identifier.

## branchobj.getlasterror

#### **Purpose**

Returns the last error encountered during a call to the given branch object.

#### **Synopsis**

```
(id,msg) = branchobj.getlasterror ()
```

#### **Arguments**

id Error code.

msg A string with the last error message relating to the branching object will be returned.

#### **Example**

The following shows how this function might be used in error checking:

```
obranch = xpress.branchobj ()

try:
    obranch.setpreferredbranch (3)
except:
    (i,m) = obranch.getlasterror ()
    print ("ERROR when setting preferred branch:", m)
```

### branchobj.getrows

#### **Purpose**

Returns the constraints for a branch of a user branching object.

#### **Synopsis**

#### **Arguments**

ibranch The number of the branch to get the constraints from.

nrows\_size Maximum number of rows to return.

nelems\_size Maximum number of non zero coefficients to return.

rtype Character array of length nrows\_size where the types of the rows will be returned:

L Less than type.G Greater than type.E Equality type.

rhs Array of length nrows\_size where the right hand side values will be returned.

mbeg Array of length nrows\_size which will be filled with the offsets of the mcol and dval

arrays of the start of the non zero coefficients in the returned constraints.

mcol Array of length nelems\_size which will be filled with the column indices for the non

zero coefficients.

dval Array of length nelems\_size which will be filled with the non zero coefficient values.

#### **Related topics**

branchobj.addrows.

## branchobj. setpreferred branch

#### **Purpose**

Specifies which of the child nodes corresponding to the branches of the object should be explored first.

#### **Synopsis**

branchobj.setpreferredbranch (ibranch)

#### **Argument**

ibranch The number of the branch to mark as preferred.

### branchobj.setpriority

#### **Purpose**

Sets the priority value of a user branching object.

#### **Synopsis**

```
branchobj.setpriority (ipriority)
```

#### **Argument**

ipriority The new priority value to assign to the branching object, which must be a number from 0 to 1000. User branching objects are created with a default priority value of 500.

#### **Further information**

- 1. A candidate branching object with lowest priority number will always be selected for branching before an object with a higher number.
- 2. Priority values must be an integer from 0 to 1000. User branching objects and global entities are by default assigned a priority value of 500. Special branching objects, such as those arising from structural branches or split disjunctions are assigned a priority value of 400.

### branchobj.store

#### **Purpose**

Adds a new user branching object to the Optimizer's list of candidates for branching. This function is available only through the callback function set by problem.addcboptnode.

#### **Synopsis**

```
status = branchobj.store ()
```

#### **Argument**

status

The returned status from checking the provided branching object:

- 0 The object was accepted successfully.
- Failed to presolve the object due to dual reductions in presolve.
- 2 Failed to presolve the object due to duplicate column reductions in presolve.
- The object contains an empty branch.

The object was not added to the candidate list if a non zero status is returned.

#### **Further information**

- 1. To ensure that a user branching object expressed in terms of the original matrix columns can be applied to the presolved problem, it might be necessary to turn off certain presolve operations.
- 2. If any of the original matrix columns referred to in the object are unbounded, dual reductions might prevent the corresponding bound or constraint from being presolved. To avoid this, dual reductions should be turned off in presolve, by clearing bit 3 of the integer control PRESOLVEOPS.
- 3. If one or more of the original matrix columns of the object are duplicates in the original matrix, but not in the branching object, it might not be possible to presolve the object due to duplicate column eliminations in presolve. To avoid this, duplicate column eliminations should be turned off in presolve, by clearing bit 5 of PRESOLVEOPS.
- 4. As an alternative to turning off the above mentioned presolve features, it is possible to protect individual columns of a the problem from being modified by presolve. Use the problem.loadsecurevecs function to mark any columns that might be branched on using branching objects.

#### **Related topics**

branchobj.validate.

## branchobj.validate

#### **Purpose**

Verifies that a given branching object is valid for branching on the current branch-and-bound node of a MIP solve. The function will check that all branches are non-empty, and if required, verify that the branching object can be presolved.

#### **Synopsis**

status = branchobj.validate ()

#### **Argument**

status

The returned status from checking the provided branching object:

- 0 The object is acceptable.
- 1 Failed to presolve the object due to dual reductions in presolve.
- 2 Failed to presolve the object due to duplicate column reductions in presolve.
- 3 The object contains an empty branch.

### **APPENDIX A**

# **Contacting FICO**

FICO provides clients with support and services for all our products. Refer to the following sections for more information.

## **Product support**

FICO offers technical support and services ranging from self-help tools to direct assistance with a FICO technical support engineer. Support is available to all clients who have purchased a FICO product and have an active support or maintenance contract. You can find support contact information on the Product Support home page (www.fico.com/support).

On the Product Support home page, you can also register for credentials to log on to FICO Online Support, our web-based support tool to access Product Support 24x7 from anywhere in the world. Using FICO Online Support, you can enter cases online, track them through resolution, find articles in the FICO Knowledge Base, and query known issues.

Please include 'Xpress' in the subject line of your support queries.

#### Product education

FICO Product Education is the principal provider of product training for our clients and partners. Product Education offers instructor-led classroom courses, web-based training, seminars, and training tools for both new user enablement and ongoing performance support. For additional information, visit the Product Education homepage at www.fico.com/en/product-training or email producteducation@fico.com.

#### **Product documentation**

FICO continually looks for new ways to improve and enhance the value of the products and services we provide. If you have comments or suggestions regarding how we can improve this documentation, let us know by sending your suggestions to techpubs@fico.com.

#### Sales and maintenance

USA, CANADA AND ALL AMERICAS

Email: XpressSalesUS@fico.com

**WORLDWIDE** 

Email: XpressSalesUK@fico.com

Tel: +44 207 940 8718 Fax: +44 870 420 3601

Xpress Optimization, FICO FICO House International Square Starley Way Birmingham B37 7GN UK

#### **Related services**

**Strategy Consulting:** Included in your contract with FICO may be a specified amount of consulting time to assist you in using FICO Optimization Modeler to meet your business needs. Additional consulting time can be arranged by contract.

**Conferences and Seminars:** FICO offers conferences and seminars on our products and services. For announcements concerning these events, go to www.fico.com or contact your FICO account representative.

#### **About FICO**

FICO (NYSE:FICO) delivers superior predictive analytics solutions that drive smarter decisions. The company's groundbreaking use of mathematics to predict consumer behavior has transformed entire industries and revolutionized the way risk is managed and products are marketed. FICO's innovative solutions include the FICO® Score—the standard measure of consumer credit risk in the United States—along with industry-leading solutions for managing credit accounts, identifying and minimizing the impact of fraud, and customizing consumer offers with pinpoint accuracy. Most of the world's top banks, as well as leading insurers, retailers, pharmaceutical companies, and government agencies, rely on FICO solutions to accelerate growth, control risk, boost profits, and meet regulatory and competitive demands. FICO also helps millions of individuals manage their personal credit health through www.myfico.com. Learn more at www.fico.com. FICO: Make every decision count TM.

# Index

В	problem.calcsolinfo,119
branchobj.addbounds, <mark>377</mark>	problem.cascade,120
branchobj.addbranches, <mark>378</mark>	problem.cascadeorder,121
branchobj.addcuts, <mark>379</mark>	problem.chgbounds, 122
branchobj.addrows, <mark>380</mark>	problem.chgcascadenlimit,125
branchobj.getbounds,381	problem.chgccoef, 126
branchobj.getbranches,382	problem.chgcoef, 123
branchobj.getid,383	problem.chgcoltype, 124
branchobj.getlasterror, <mark>384</mark>	problem.chgdeltatype,127
branchobj.getrows,385	problem.chgdf, 128
branchobj.setpreferredbranch,386	problem.chgglblimit, 129
branchobj.setpriority,387	problem.chgmcoef, 130
branchobj.store, 388	problem.chgmqobj, 131
branchobj.validate, <mark>389</mark>	problem.chgnlcoef, 132
-	problem.chgobj, 133
P	problem.chgobjsense, 134
problem.addcbbariteration,80	problem.chgqobj,135
problem.addcbbarlog,82	problem.chgqrowcoeff, 136
problem.addcbchgbranchobject,83	problem.chgrhs, 137
problem.addcbcutlog,84	problem.chgrhsrange, 138
problem.addcbdestroymt,85	problem.chgrowstatus, 139
problem.addcbgapnotify, <mark>86</mark>	problem.chgrowtype, 140
problem.addcbgloballog,88	problem.chgrowwt, 141
problem.addcbinfnode,89	problem.chgtolset, 142
problem.addcbintsol, 90	problem.chgvar, 143
problem.addcblplog, <mark>91</mark>	problem.construct, 145
problem.addcbmessage, <mark>92</mark>	problem.copy, 146
problem.addcbmipthread, 93	problem.copycallbacks, 147
problem.addcbnewnode, 94	problem.copycontrols, 148
problem.addcbnodecutoff, 95	problem.delcoefs, 149
problem.addcboptnode, <mark>96</mark>	problem.delConstraint,150
problem.addcbpreintsol,97	problem.delcpcuts, 151
problem.addcbprenode, 98	problem.delcuts, 152
problem.addcbusersolnotify,99	problem.delqmatrix, 153
problem.addcoefs,100	problem.delSOS, 154
problem.addcols, <mark>102</mark>	problem.deltolsets, 155
problem.addConstraint,103	problem.delVariable, 156
problem.addcuts, <mark>104</mark>	problem.delvars, 157
problem.adddfs, <mark>105</mark>	problem.dumpcontrols, 158
problem.addIndicator, <mark>106</mark>	problem.estimaterowdualranges, 159
problem.addmipsol,107	problem.evaluatecoef, 160
problem.addqmatrix,108	problem.evaluateformula, 161
problem.addrows, 109	problem.filesol, 162
problem.addSOS, 110	problem.fixglobals, 163
problem.addtolsets, 111	problem.fixpenalties, 164
problem.addVariable, <mark>112</mark>	problem.ftran, 165
problem.addvars, 113	problem.getAttrib, 166
problem.basisstability,114	problem.getattribinfo, 167
problem.btran, 115	problem.getbasis, 168
problem.calcobjective, 116	problem.getccoef, 169
problem.calcreducedcosts, 117	problem.getcoef, 170
problem.calcslacks,118	problem.getcoefformula,171
,	prostom. godoocriormara, 1/1

problem.getcoefs,172	problem.getunbvec,233
problem.getcolinfo,173	problem.getvar, <mark>234</mark>
problem.getcols, <mark>174</mark>	problem.getVariable, <mark>236</mark>
problem.getcoltype,175	problem.globalsol,237
<pre>problem.getConstraint,176</pre>	problem.hasdualray, <mark>238</mark>
<pre>problem.getControl, 177</pre>	problem.hasprimalray,239
problem.getcontrolinfo,178	problem.iisall,240
problem.getcpcutlist,179	problem.iisclear, 241
problem.getcpcuts, 180	problem.iisfirst, 242
problem.getcutlist, 181	problem.iisisolations, 243
problem.getcutmap, 182	problem.iisnext, 244
problem.getcutslack, 183	problem.iisstatus, 245
problem.getdf, 185	problem.iiswrite, 246
problem.getdirs, 184	problem.interrupt, 247
problem.getdtime, 186	problem.loadbasis,248
problem.getDual, 187	problem.loadbranchdirs, 249
problem.getdualray, 188	problem.loadcoefs, 250
problem.getglobal, 189	problem.loadcuts, 252
problem.getiisdata, 190	problem.loaddelayedrows, 253
problem.getIndex, 192	problem.loaddfs, 254
problem.getIndexFromName, 193	problem.loaddirs, 255
problem.getindicators, 194	problem.loadlpsol, 256
problem.getinfeas, 195	problem.loadmipsol, 257
problem.getlasterror, 196	problem.loadmodelcuts, 258
problem.getlb, 197	problem.loadpresolvebasis, 259
problem.getlpsol, 198	problem.loadpresolvedirs, 260
problem.getmessagestatus, 199	problem.loadproblem, 261
problem.getmessagetype, 200	problem.loadsecurevecs, 263
problem.getmipsol, 201	problem.loadtolsets, 264
problem.getmqobj, 202	problem.loadvars, 265
problem.getobj, 203	problem.lpoptimize, 267
problem.getObjVal,204	problem.mipoptimize, 268
problem.getpivotorder, 205	problem.msaddcustompreset, 269
problem.getpivots, 206	problem.msaddjob, <mark>270</mark>
problem.getpresolvebasis,207	problem.msaddpreset,271
problem.getpresolvemap, 208	problem.msclear,272
problem.getpresolvesol, 209	problem.name, 273
problem.getprimalray,210	problem.nlpoptimize,274
<pre>problem.getProbStatus, 211</pre>	problem.objsa, <mark>275</mark>
<pre>problem.getProbStatusString,212</pre>	problem.parsecformula,276
problem.getqobj, <mark>213</mark>	problem.parseformula,277
<pre>problem.getqrowcoeff, 214</pre>	problem.postsolve,278
problem.getqrowqmatrix,215	problem.preparseformula,279
problem.getqrowqmatrixtriplets,216	problem.presolve, 280
problem.getqrows, 217	problem.presolverow, 281
<pre>problem.getRCost, 218</pre>	problem.printevalinfo,283
problem.getrhs, 219	problem.printmemory, 282
problem.getrhsrange, <mark>220</mark>	problem.printmsg, 284
problem.getrowinfo, 221	problem.read, <mark>285</mark>
problem.getrows, 222	problem.readbasis,286
problem.getrowstatus, 223	problem.readbinsol,287
problem.getrowtype, 224	problem.readdirs,288
problem.getrowwt, 225	problem.readslxsol,289
problem.getscaledinfeas, 226	problem.refinemipsol, 290
problem.getSlack, 227	problem.reinitialize, <mark>291</mark>
problem.getslpsol,228	problem.removecbbariteration, 292
<pre>problem.getSolution, 229</pre>	problem.removecbbarlog,293
problem.getSOS, 230	problem.removecbchgbranchobject, 294
problem.gettolset, 231	problem.removecbcutlog, 295
problem.getub, 232	problem.removecbdestroymt, 296

problem.removecbgapnotify,297	problem.tunerreadmethod,361
problem.removecbgloballog,298	problem.tunerwritemethod, 362
problem.removecbinfnode,299	problem.unconstruct,363
problem.removecbintsol,300	problem.updatelinearization, 364
problem.removecblplog, 301	problem.validate,365
problem.removecbmessage, 302	problem.validatekkt,366
problem.removecbmipthread, 303	problem.validaterow,367
problem.removecbnewnode, 304	problem.validatevector,368
problem.removecbnodecutoff, 305	problem.validformula,369
problem.removecboptnode, 306	problem.write, 370
problem.removecbpreintsol, 307	problem.writebasis, 371
problem.removecbprenode, 308	problem.writebinsol, 372
problem.removecbusersolnotify, 309	problem.writedirs, 373
problem.repairinfeas, 310	problem.writeprtsol, 374
problem.repairweightedinfeas, 312	problem.writeslxsol, 375
problem.repairweightedinfeasbounds, 314	problem.writesol, 376
problem.reset, 316	problem. writesor, or o
problem.restore, 317	X
	xpress.abs,72
problem.rhssa, 318	xpress.acos, 68
problem.save, 319	
problem.scale, 320	xpress.addcbmsghandler,78
problem.scaling, 321	xpress.asin,67
problem.setbranchbounds,322	xpress.atan,69
problem.setbranchcuts, 323	xpress.cos, 65
problem.setcbcascadeend, 324	xpress.Dot, 58
problem.setcbcascadestart, 325	xpress.erf, 74
problem.setcbcascadevar,326	xpress.erfc,75
problem.setcbcascadevarfail,327	xpress.exp,61
problem.setcbcoefevalerror,328	xpress.free,46
problem.setcbconstruct, 329	xpress.getbanner,47
problem.setcbdestroy,331	xpress.getcheckedmode,48
problem.setcbdrcol, 332	xpress.getdaysleft,49
problem.setcbformula,333	xpress.getlasterror,50
problem.setcbiterend, 334	xpress.getlicerrmsg,51
problem.setcbiterstart,335	xpress.getversion,52
problem.setcbitervar, 336	xpress.init, <mark>53</mark>
problem.setcbmessage, 337	xpress.log,62
problem.setcbmsjobend, 338	xpress.log10,63
problem.setcbmsjobstart,339	xpress.max, <mark>70</mark>
problem.setcbmswinner, 340	xpress.min,71
problem.setcbslpend, 341	xpress.Prod,60
problem.setcbslpnode, 342	xpress.removecbmsghandler,79
problem.setcbslpstart, 343	xpress.setcheckedmode, 54
problem.setControl,344	xpress.setdefaultcontrol, 56
problem.setcurrentiv, 345	xpress.setdefaults, 55
problem.setdefaultcontrol, 346	xpress.sign, 73
problem.setdefaults, 347	xpress.sin, 64
problem.setindicators, 348	xpress.sqrt,76
problem.setlogfile, 349	xpress.Sum, 57
problem.setmessagestatus, 350	xpress.tan, 66
problem.setObjective, 351	xpress.user, 77
	Apress. aser, "
problem.setprobname, 352	
problem.setuniqueprefix, 353	
problem.solve, 354	
problem.storebounds, 355	
problem.storecuts, 356	
problem.strongbranch, 357	
problem.strongbranchcb, 358	
problem.tokencount, 359	
problem.tune, 360	