DVA218 - Lab 3b: Transmission Protocol

Sebastian Lindfors

May 16, 2018

Description

UTP - User (Datagram) Transmission Protocol - attempts to implement a reliable packet transmission protocol over unreliable UDP sockets, using MD5-verified checksums and control signaling to mimic the reliability of TCP. It consists of two separate parts: an example program that transmits messages peer-to-peer, and an interface that handles everything related to packaging, sending, and receiving data. Since the P2P program uses the interface, but not the other way around, the P2P program uses camel case and the interface uses C macro notation to differentiate between them.

This particular implementation prioritizes reliability over speed, which makes it suitable for data required to be intact on the receiving end, even when the connection is unreliable (paying bills when you're in Antarctica). It's however not well suited for data transfers that require close to real-time communication (a VOIP call or streaming media on your yacht in the Riviera).

The interface is generally applicable to any type of data where the smallest data fragment is one byte, since it's casting messages as arrays of characters. The program itself uses the interface without type casting to transfer a buffered input stream over the socket.

Control signaling

A frame (packet within window) contains parameters to notify the receiver of the contents of the packet, and how it should be interpreted. These parameters are payload size, packet sequence number, time stamp when the packet was sent, control flags, checksum and finally the payload itself. Some packets are sent purely for control signaling, and contain no payload. An exception from this is the handshake packet, which utilizes the same packet structure, but contains payload and window limits where you'd normally find payload information.

State machine comparison

The handshake state machines are close to identical to the actual implementation in terms of handling the process from idle to connected. The teardown state machines are somewhat different; instead of sending plain FINs in both directions, the code will just respond to a FIN in either direction with a FIN+ACK. The responder of the initial FIN will wait for a final ACK to tear the connection down, but will eventually timeout if the processes are out of sync (initiator closes down and exits due to packet loss and timeout, or one process is scheduled with processing time longer than the timeout span when running both instances on the same machine). In either case, the initial FIN always has to be accepted first before the initiator goes into the closing state.

The sliding window has changed the most from conceptual design to implementation. The conceptual design uses modulus operations to wrap around in a frame buffer to continuously serve and accept packets, whereas the actual code uses shifting buffers that exclude the lowest sequentially marked frame when it has been sent and acknowledged.

The reason for this change is that sequence numbers are generated as offsets of 64-bit timestamps defined during the handshake. It's easier to calculate a buffer index as the difference of a sequence number and a tracking offset. The window implementation can be imagined as a span of frames sliding over a continuous array, rather than looping around in a closed circuit.

For example, given an initial sequence number 5, the next expected frame will be 6. 6-5=1, meaning it fits in the first index in the buffer. When checking the window, the receiver can tell that the first frame has been received and therefore shift the window forward and also increment the tracker value. The new tracker value will therefore be 6. Let's assume the next frame received has number 7, and the same principle applies; 7-6=1. Should it however receive frame 8 due to packet loss, it will be stored in the 2nd index; 8-6=2. In reality, the initial tracker value is incremented by one after the handshake, so that the first expected frame will be placed at index 0 (since C has zero-based arrays).

When a frame exists in the lowest buffer index, it's shifted out of the window buffer, and the payload of the frame is stored in an output buffer, until a frame in the first window buffer index is flagged with END (end of message). At that point, the output buffer prints its content and resets to await the next message. Out-of-bounds packets are handled by simply acknowledging them on the receiving end, but not storing them anywhere, which handles the problem of desynchronization between sender and receiver, and also guarantees that rogue packets will not be stored in the window buffer.

Send and receive, resend and request

The example program code uses three distinct threads to handle packet tranmission. The main thread handles everything on its own when everything works as expected; the sending window is filled with packets and sent on the link in sequence. The receiving window stores arriving frames in sequence and returns ACKs to the sender. The sender compares the sequence numbers in its send and ACK buffer and slides the window accordingly.

Should something go wrong, two other threads run in conjunction with the main thread to handle these packets. The resending thread looks through the send and ACK buffers for misaligned sequence numbers (an ACK is missing) and resends the frame that was never acknowledged. The request thread does the opposite; it goes through the receive buffer and looks for empty indices (gaps

between frames) and calculates the expected sequence number that should be in that particular index, then sends a request for that frame.

Using this approach, all scenarios are eventually handled; packets arriving in perfect sequence, packets arriving out of order, packets that are out of bounds in the current window, and packets that never arrived at all. Because of the double-checking on both sides, the specific frames needed to complete the message will eventually arrive on the receiving end.

Running the example program:

```
$ cd lab3
$ gcc -g -o main main.c utp.c -lssl -lcrypto -pthread
$ ./main
UTP Interface Simulation Help:
./main server [-flags]
./main client <address> [-flags]
-wsize <num>: Window size
-psize <num>: Payload size
-port <num>: Port number
-error <num>: Error sim percent
-timer <num>: Timeout in usec

$ ./main server -error 50 -wsize 6 -psize 4 -timer 20000
> Window: 6 frames. Frame: 52 bytes. Payload: 4 bytes. Error: 50%. Timeout: 20000 usec.
$ ./main client 127.0.0.1
> Window: 16 frames. Frame: 80 bytes. Payload: 32 bytes. Error: 0%. Timeout: 60000 usec.
```

Example (1a) sending a message in perfect sequence:

```
Initial sequence: 00189. Window: 6 frames. Frame: 52 bytes. Payload: 4 bytes.
Verbose printout notation:
< IN | OUT> [frame] [time] [sequence] [msg]
_____
Hello world. This is a packet transmission example with 0\% error rate.
<___ | MSG> +000 00186 00057 Hell
<___ | MSG> +001
                  00218
                         00058 o wo
<___ | MSG> +002
                  00224
                         00059 rld.
<___ | MSG> +003
                  00230
                         00060 Thi
<___ | MSG> +004
                  00235
                         00061 s is
<___ | MSG> +005
                  00241
                         00062 a p
<ACK | ___> +000
                  00230
                         00057
<___ | MSG> +005
                  00255
                         00063 acke
<ACK | ___> +000
                  00245
                         00058
<___ | MSG> +005
                         00064 t tr
                  00012
<ACK | ___> +000
                  00255
                         00059
<___ | MSG> +005
                  00026
                         00065 ansm
<ACK | ___> +000
                  00009
                         00060
<___ | MSG> +005
                  00038
                         00066 issi
<ACK | ___> +000
                  00019
                         00061
                         00067 on e
<___ | MSG> +005
                  00051
<ACK | ___> +000
                         00062
                  00029
<___ | MSG> +005
                  00064
                         00068 xamp
<ACK | ___> +000
                  00038
                         00063
<___ | MSG> +005
                         00069 le w
                  00077
<ACK | ___> +000
                  00048
                         00064
<___ | MSG> +005
                         00070 ith
                  00089
<ACK | ___> +000
                  00058
                         00065
<___ | MSG> +005
                  00102
                         00071 0% e
<ACK | ___> +000
                  00068
                         00066
<___ | MSG> +005
                  00114
                         00072 rror
<ACK | ___> +000
                  00077
                         00067
<___ | MSG> +005
                  00127
                         00073
                                rat
<ACK | ___> +000
                  00087
                         00068
<___ | END> +005
                  00139
                         00074 e.
<ACK | ___> +000
                  00097
                         00069
<ACK | ___> +000
                  00107
                         00070
<ACK | ___> +000
                  00117
                         00071
<ACK | ___> +000
                  00127
                         00072
<ACK | ___> +000
                  00137
                         00073
<ACK | ___> +000
                  00158
                         00074
```

Example (1b) receiving and acknowledging a message in perfect sequence:

Initial sequence: 00056. Window: 6 frames. Frame: 52 bytes. Payload: 4 bytes.

```
Verbose printout notation:
```

< IN | OUT> [frame] [time] [sequence] [msg]

```
_____
<MSG | ACK> +000 00186 00057 Hell
<MSG | ACK> +000 00218 00058 o wo
<MSG | ACK> +000 00224 00059 rld.
<MSG | ACK> +000
                00230 00060 Thi
<MSG | ACK> +000
                00235 00061 s is
<MSG | ACK> +000
                00241 00062 a p
<MSG | ACK> +000
                00255 00063 acke
<MSG | ACK> +000
                00012 00064 t tr
<MSG | ACK> +000
                00026 00065 ansm
<MSG | ACK> +000
                00038 00066 issi
<MSG | ACK> +000
                00051 00067 on e
<MSG | ACK> +000
                00064 00068 xamp
<MSG | ACK> +000
                00077 00069 le w
<MSG | ACK> +000
                00089 00070 ith
<MSG | ACK> +000
                00102 00071 0% e
<MSG | ACK> +000
                00114 00072 rror
<MSG | ACK> +000
                00127 00073 rat
<END | ACK> +000 00139 00074 e.
```

> Hello world. This is a packet transmission example with 0% error rate.

Example (2a) sending a message where roughly half of the packets are lost in both directions, with low timeout:

```
$ ./main connect 127.0.0.1 -error 50 -wsize 6 -psize 4
_____
50% chance to go bonkers. Local timeout in usec: 60000
_____
Initial sequence: 00083. Window: 6 frames. Frame: 52 bytes. Payload: 4 bytes.
_____
Verbose printout notation:
< IN | OUT> [frame] [time] [sequence] [msg]
_____
Hello world. This is a packet transmission example with 50% error rate.
<___ | MSG> +000 00253 00084 Hell
<___ | MSG> +001
                00048 00085 o wo
<___ | MSG> +002
                00062 00086 rld.
<___ | MSG> +003
                00081 00087 Thi
<___ | MSG> +004
                00102 00088 s is
<___ | MSG> +005
                00118
                       00089 a p
<ACK | ___> +000
                00105 00084
<___ | MSG> +005
                00155
                      00090 acke
<ACK | ___> +003
                00181 00088
<ACK | ___> +005
                00250
                       00090
<REQ | MSG> +000
                00010 00085
<REQ | MSG> +001
                00043
                       00086
<REQ | MSG> +003
                00085
                       00088
<REQ | MSG> +004
                00103
                       00089
<ACK | ___> -085
                00161
                       00000
<REQ | MSG> +001
                00187
                       00086
<REQ | MSG> +002
                00212 00087
<REQ | MSG> +004
                00239
                       00089
<REQ | MSG> +003
                00084 00088
<REQ | MSG> +005
                00118
                       00090
<ACK | ___> -085
                00228
                       00000
<___ | RES> +000
                00062 00085 o wo
<REQ | MSG> +001
                00103
                       00086
<REQ | MSG> +002
                00195
                       00087
<REQ | MSG> +003
                00046
                       00088
<ACK | ___> -085
                00167
                       00000
<REQ | MSG> +002
                00032
                       00087
<REQ | MSG> +003
                00124
                       00088
<REQ | MSG> +001
                00183
                       00086
<REQ | MSG> +003
                00044 00088
<REQ | MSG> +004
                00061
                       00089
<REQ | MSG> +005
                00073
                       00090
<ACK | ___> -085
                00179 00000
```

```
<ACK | ___> -085
                  00241
                          00000
<___ | RES> +000
                  00202
                          00085 o wo
<REQ | MSG> +000
                  00215
                          00085
<REQ | MSG> +002
                  00031
                          00087
<REQ | MSG> +004
                  00077
                          00089
<REQ | MSG> +005
                  00096
                          00090
<ACK | ___> -085
                  00209
                          00000
<ACK | ___> -085
                  00000
                          00000
<REQ | MSG> +002
                  00250
                          00087
<REQ | MSG> +003
                  00057
                          00088
<ACK | ___> -085
                  00218
                          00000
<REQ | MSG> +002
                  00233
                          00087
<REQ | MSG> +003
                  00019
                          00088
<REQ | MSG> +005
                  00042
                         00090
<REQ | MSG> +003
                  00073
                          00088
<REQ | MSG> +004
                  00083
                          00089
<REQ | MSG> +005
                  00092
                         00090
<___ | RES> +000
                  00057
                          00085 o wo
<REQ | MSG> +004
                  00073
                         00089
<___ | RES> +000
                  00029
                          00085 o wo
                  80000
<REQ | MSG> +003
                         00088
<REQ | MSG> +004
                  00055
                          00089
<REQ | MSG> +005
                  00071
                          00090
<ACK | ___> -085
                  00151
                          00000
<REQ | MSG> +003
                  00037
                          00088
<ACK | ___> -085
                  00099
                          00000
<REQ | MSG> +002
                  00227
                          00087
<REQ | MSG> +003
                  00022
                          00088
<REQ | MSG> +004
                  00027
                          00089
<REQ | MSG> +005
                  00035
                          00090
<ACK | ___> -085
                  00134
                          00000
<ACK | ___> -085
                  00181
                          00000
<___ | RES> +000
                  00213
                          00085 o wo
                          00087
<REQ | MSG> +002
                  00172
<REQ | MSG> +005
                  00204
                          00090
<REQ | MSG> +003
                  00163
                          00088
<REQ | MSG> +004
                  00172
                          00089
<REQ | MSG> +005
                  00178
                          00090
<ACK | ___> -085
                  00227
                          00000
<ACK | ___> -085
                  00002
                          00000
<REQ | MSG> +002
                  00099
                          00087
<REQ | MSG> +003
                  00164
                          00088
<___ | RES> +000
                  00112
                          00085 o wo
<ACK | ___> +000
                  00144
                          00085
<___ | MSG> +005
                          00091 t tr
                  00195
<REQ | MSG> +001
                  00074
                         00087
```

```
<REQ | MSG> +002
                  00114
                          00088
<___ | RES> +000
                  00062
                          00086 rld.
<REQ | MSG> +002
                   00040
                          00088
<REQ | MSG> +003
                  00075
                          00089
<REQ | MSG> +004
                  00098
                          00090
<ACK | ___> -086
                  00182
                          00000
<REQ | MSG> +001
                  00040
                          00087
<REQ | MSG> +002
                  00091
                          00088
<REQ | MSG> +004
                  00115
                          00090
<ACK | ___> -086
                  00179
                          00000
<REQ | MSG> +002
                  00136
                          00088
<REQ | MSG> +003
                  00144
                          00089
<___ | RES> +000
                  00021
                          00086 rld.
<REQ | MSG> +002
                  00082
                          00088
<REQ | MSG> +003
                  00119
                          00089
<REQ | MSG> +003
                  00198
                          00089
<REQ | MSG> +004
                  00211
                          00090
<REQ | MSG> +002
                   00095
                          00088
<REQ | MSG> +003
                  00127
                          00089
<REQ | MSG> +004
                   00135
                          00090
<REQ | MSG> +005
                  00141
                          00091
<___ | RES> +000
                  00023
                          00086 rld.
<REQ | MSG> +001
                  00069
                          00087
<REQ | MSG> +004
                  00176
                          00090
<REQ | MSG> +001
                  00109
                          00087
<REQ | MSG> +005
                  00183
                          00091
<REQ | MSG> +005
                  00193
                          00091
<___ | RES> +000
                  00023
                          00086 rld.
<REQ | MSG> +003
                  00135
                          00089
<REQ | MSG> +002
                  00086
                          00088
<REQ | MSG> +004
                  00131
                          00090
<REQ | MSG> +005
                  00148
                          00091
<ACK | ___> -086
                  00210
                          00000
<ACK | ___> -086
                  00229
                          00000
<REQ | MSG> +003
                  00101
                          00089
<REQ | MSG> +005
                  00155
                          00091
<___ | RES> +000
                   00044
                          00086 rld.
<REQ | MSG> +001
                   00064
                          00087
<REQ | MSG> +002
                   00118
                          00088
<REQ | MSG> +005
                  00171
                          00091
                   00063
<REQ | MSG> +002
                          00088
<REQ | MSG> +003
                  00089
                          00089
<ACK | ___> -086
                  00140
                          00000
<REQ | MSG> +002
                  00009
                          00088
<REQ | MSG> +003
                  00060
                          00089
<REQ | MSG> +004
                  00074
                          00090
```

```
<REQ | MSG> +005
                  00090
                         00091
<ACK | ___> -086
                  00159
                         00000
<ACK | ___> -086
                  00194
                         00000
<___ | RES> +000
                  00248
                         00086 rld.
<ACK | ___> +000
                  00042
                         00086
<___ | MSG> +005
                  00083
                         00092 ansm
<REQ | MSG> +002
                  00071
                         00089
<REQ | MSG> +003
                  00106
                         00090
<REQ | MSG> +004
                  00138
                         00091
<ACK | ___> -087
                  00228
                         00000
<___ | RES> +000
                  00081
                         00087
                                 Thi
<ACK | ___> +000
                  00052
                         00087
<___ | MSG> +004
                  00102
                         00093 issi
<___ | MSG> +005
                  00106
                         00094 on e
                         00089 a p
<___ | RES> +000
                  00118
<___ | RES> +000
                  00188
                         00089 a p
                         00089 a p
<___ | RES> +000
                  00240
<ACK | ___> +000
                  00050
                         00089
<___ | MSG> +004
                  00091
                         00095 xamp
<___ | MSG> +005
                  00107
                         00096 le w
<ACK | ___> +005
                  00138
                         00096
<REQ | MSG> +003
                  00061
                         00094
<REQ | MSG> +005
                         00096
                  00073
<___ | RES> +000
                  00195
                         00091 t tr
<REQ | MSG> +001
                  00192
                         00092
<REQ | MSG> +002
                  00234
                         00093
<REQ | MSG> +004
                  00255
                         00095
<REQ | MSG> +005
                  00013
                         00096
<ACK | ___> -091
                  00127
                         00000
<REQ | MSG> +001
                  00202
                         00092
<REQ | MSG> +002
                  00039
                         00093
<REQ | MSG> +003
                  00050
                         00094
<REQ | MSG> +005
                  00066
                         00096
<ACK | ___> -091
                  00232
                         00000
<ACK | ___> -091
                  00249
                         00000
<REQ | MSG> +004
                  00225
                         00095
<___ | RES> +000
                  00193
                         00091 t tr
<REQ | MSG> +004
                  00010
                         00095
<REQ | MSG> +005
                  00021
                         00096
<REQ | MSG> +001
                  00135
                         00092
<REQ | MSG> +004
                  00184
                         00095
<ACK | ___> -091
                  00218
                         00000
<REQ | MSG> +002
                  00086
                         00093
<REQ | MSG> +004
                  00204
                         00095
<REQ | MSG> +005
                  00213
                         00096
<ACK | ___> -091
                  00064
                         00000
```

```
<ACK | ___> -091
                  00008 00000
<___ | RES> +000
                  00075
                          00091 t tr
<REQ | MSG> +002
                  00145
                          00093
<REQ | MSG> +003
                  00183
                          00094
<REQ | MSG> +004
                  00195
                          00095
<ACK | ___> -091
                  00005
                          00000
<ACK | ___> -091
                  00023
                          00000
<REQ | MSG> +001
                  00071
                          00092
<REQ | MSG> +002
                  00105
                          00093
<REQ | MSG> +005
                  00120
                          00096
<ACK | ___> -091
                          00000
                  00207
<ACK | ___> -091
                  00222
                          00000
<REQ | MSG> +001
                  00020
                          00092
<REQ | MSG> +004
                  00117
                          00095
<REQ | MSG> +005
                  00134
                          00096
<ACK | ___> -091
                  00230
                          00000
<ACK | ___> -091
                  00009
                          00000
<___ | RES> +000
                  00167
                          00091 t tr
<REQ | MSG> +001
                  00037
                          00092
<REQ | MSG> +002
                  00087
                          00093
<REQ | MSG> +005
                  00099
                          00096
<REQ | MSG> +001
                  00214
                          00092
<REQ | MSG> +002
                  00242
                          00093
<REQ | MSG> +004
                  00002
                          00095
<REQ | MSG> +002
                  00193
                          00093
<REQ | MSG> +003
                  00207
                          00094
<REQ | MSG> +004
                  00219
                          00095
<REQ | MSG> +005
                  00001
                          00096
<ACK | ___> -091
                  00046
                          00000
<___ | RES> +000
                  00029
                          00091 t tr
<REQ | MSG> +003
                  00172
                          00094
<REQ | MSG> +004
                  00184
                          00095
<REQ | MSG> +005
                  00194
                          00096
<REQ | MSG> +002
                  00139
                          00093
<REQ | MSG> +003
                  00238
                          00094
<REQ | MSG> +004
                  00254
                          00095
<ACK | ___> -091
                  00092
                          00000
<ACK | ___> -091
                  00126
                          00000
<___ | RES> +000
                  00204
                          00091 t tr
<ACK | ___> +000
                  00189
                          00091
<___ | MSG> +005
                  00224
                          00097 ith
<ACK | ___> +005
                  00246
                          00097
<REQ | MSG> +001
                  00182
                          00093
<REQ | MSG> +002
                  00222
                          00094
<REQ | MSG> +003
                  00236
                          00095
<REQ | MSG> +004 00251
                          00096
```

```
<REQ | MSG> +005
                          00097
                  80000
<___ | RES> +000
                  00083
                          00092 ansm
<REQ | MSG> +002
                  00236
                          00094
<REQ | MSG> +003
                  00072
                          00095
<REQ | MSG> +004
                  00085
                          00096
<ACK | ___> -092
                  00191
                          00000
<REQ | MSG> +002
                  00058
                          00094
<REQ | MSG> +004
                  00074
                          00096
<REQ | MSG> +005
                  00082
                          00097
<ACK | ___> -092
                  00135
                          00000
<REQ | MSG> +002
                  00127
                          00094
<___ | RES> +000
                  00095
                          00092 ansm
<REQ | MSG> +001
                  00046
                          00093
<REQ | MSG> +002
                  08000
                          00094
<REQ | MSG> +004
                  00099
                          00096
<ACK | ___> -092
                  00183
                          00000
<REQ | MSG> +004
                  00126
                          00096
<REQ | MSG> +000
                  00063
                          00092
<REQ | MSG> +001
                  00102
                          00093
<REQ | MSG> +002
                  00114
                          00094
<REQ | MSG> +003
                  00122
                          00095
<REQ | MSG> +004
                  00130
                          00096
<REQ | MSG> +005
                  00138
                          00097
<REQ | MSG> +002
                  00076
                          00094
<REQ | MSG> +003
                  00090
                          00095
<REQ | MSG> +005
                  00109
                          00097
<REQ | MSG> +001
                  00239
                          00093
<REQ | MSG> +003
                  00022
                          00095
<REQ | MSG> +004
                  00034
                          00096
<REQ | MSG> +005
                  00044
                          00097
<ACK | ___> -092
                  00073
                          00000
<REQ | MSG> +001
                  00210
                          00093
<REQ | MSG> +003
                  00057
                          00095
<REQ | MSG> +004
                  00076
                          00096
<ACK | ___> -092
                  00164
                          00000
<___ | RES> +000
                  00130
                          00092 ansm
<ACK | ___> +000
                  00070
                          00092
<___ | MSG> +005
                  00117
                          00098 50%
<REQ | MSG> +000
                  00023
                          00093
<REQ | MSG> +001
                  00064
                          00094
<REQ | MSG> +002
                  00076
                          00095
<REQ | MSG> +003
                  00084
                          00096
<REQ | MSG> +004
                  00091
                          00097
<ACK | ___> +000
                  00125
                          00093
<___ | MSG> +005
                  00179
                          00099 erro
<ACK | ___> -094
                  00180
                          00000
```

```
00106 00094 on e
<___ | RES> +000
<REQ | MSG> +001
                  00240
                         00095
<REQ | MSG> +002
                  00031
                         00096
<REQ | MSG> +003
                  00046
                         00097
<ACK | ___> -094
                  00122
                         00000
<REQ | MSG> +000
                  00237
                         00094
<REQ | MSG> +003
                  00122
                         00097
<ACK | ___> -094
                  00017
                         00000
<REQ | MSG> +002
                  00096
                         00096
<REQ | MSG> +003
                  00109
                         00097
<REQ | MSG> +002
                  00134
                         00096
<REQ | MSG> +003
                  00159
                         00097
<REQ | MSG> +000
                  00089
                         00094
<___ | RES> +000
                  00184
                         00094 on e
<ACK | ___> +000
                  00032
                         00094
<___ | MSG> +005
                  00061
                         00100 r ra
                         00095 xamp
<___ | RES> +000
                  00091
<___ | RES> +000
                  00211
                         00095 xamp
<ACK | ___> +000
                         00095
                  00213
<___ | END> +003
                  00243
                         00101 te.
<ACK | ___> +003
                  00014
                         00101
<REQ | MSG> +000
                  00253
                         00098
<REQ | MSG> +003
                  00024
                         00101
<REQ | MSG> +000
                  00143
                         00098
<REQ | MSG> +002
                  00181
                         00100
<ACK | ___> +000
                  00226
                         00098
<ACK | ___> -099
                  00248
                         00000
                         00099 erro
<___ | RES> +000
                  00179
<ACK | ___> +000
                  00012
                         00099
<REQ | MSG> +000
                  00114
                         00100
<REQ | MSG> +001
                  00162
                         00101
<___ | RES> +000
                  00202 00100 r ra
<___ | RES> +000
                  00142 00100 r ra
<___ | RES> +000
                  00183
                         00100 r ra
<___ | RES> +000
                  00250
                         00100 r ra
<___ | RES> +000
                  00039
                         00100 r ra
<___ | RES> +000
                  00059
                         00100 r ra
<___ | RES> +000
                  00079
                         00100 r ra
<___ | RES> +000
                  00109
                         00100 r ra
<___ | RES> +000
                  00130
                         00100 r ra
<___ | RES> +000
                  00053
                         00100 r ra
<ACK | ___> +000
                  00020
                         00100
```

Example (2b): receiving a message where roughly half of the packets are lost in both directions, with low timeout:

```
$ ./main server -error 50 -wsize 6
_____
50% chance to go bonkers. Local timeout in usec: 60000
_____
Initial sequence: 00083. Window: 6 frames. Frame: 52 bytes. Payload: 4 bytes.
_____
Verbose printout notation:
< IN | OUT> [frame] [time] [sequence] [msg]
_____
<MSG | ACK> +000 00253 00084 Hell
<MSG | ACK> +001
                00062 00086 rld.
<MSG | ACK> +003
                00102 00088 s is
<MSG | ACK> +004
                00118 00089 a p
<MSG | ACK> +005
                00155
                      00090 acke
<___ | NAK> +000
                00250
                       00085
<___ | NAK> +001
                00010
                       00086
<___ | NAK> +002
                00043 00087
<___ | NAK> +003
                00061
                      00088
<___ | NAK> +004
                00085
                       00089
<___ | NAK> +005
                00103
                       00090
<MSG | ACK> -085
                00113 00000
<MSG | ACK> -085
                00161
                       00000
<___ | NAK> +000
                00192
                       00085
<___ | NAK> +001
                00140
                       00086
<___ | NAK> +002
                00187
                       00087
<___ | NAK> +003
                00212
                       00088
<___ | NAK> +004
                00232
                       00089
<___ | NAK> +005
                00239
                       00090
<MSG | ACK> -085
                00250 00000
<___ | NAK> +000
                00048
                       00085
<___ | NAK> +001
                00205
                       00086
<___ | NAK> +002
                00037
                       00087
<___ | NAK> +003
                00072
                       00088
<___ | NAK> +004
                00084
                       00089
<___ | NAK> +005
                00108
                       00090
<MSG | ACK> -085
                00138
                       00000
<MSG | ACK> -085
                00186
                       00000
<___ | NAK> +000
                00228
                       00085
<___ | NAK> +001
                00000
                       00086
<___ | NAK> +002
                00103
                       00087
<___ | NAK> +003
                00195
                       00088
<___ | NAK> +004
                00046
                       00089
<___ | NAK> +005
                00077
                       00090
```

```
<MSG | ACK> -085
                  00153
                          00000
<___ | NAK> +000
                          00085
                  00101
<___ | NAK> +001
                  00227
                          00086
<___ | NAK> +002
                  00020
                          00087
<___ | NAK> +003
                  00032
                          00088
<___ | NAK> +004
                  00124
                          00089
<___ | NAK> +005
                  00189
                          00090
<___ | NAK> +000
                  00055
                          00085
                          00086
<___ | NAK> +001
                  00157
<___ | NAK> +002
                  00183
                          00087
<___ | NAK> +003
                  00038
                          00088
<___ | NAK> +004
                  00044
                          00089
<___ | NAK> +005
                  00061
                          00090
<MSG | ACK> -085
                  00107
                          00000
<MSG | ACK> -085
                  00167
                          00000
<___ | NAK> +000
                  00241
                          00085
<___ | NAK> +001
                  00215
                          00086
<___ | NAK> +002
                  00016
                          00087
<___ | NAK> +003
                  00031
                          00088
<___ | NAK> +004
                  00069
                          00089
<___ | NAK> +005
                  00077
                          00090
<MSG | ACK> +000
                  00057
                          00085 o wo
<MSG | ACK> -087
                  00115
                          00000
<MSG | ACK> -087
                  00133
                          00000
<___ | NAK> +000
                  00000
                          00087
<___ | NAK> +001
                  00250
                          00088
<___ | NAK> +002
                  00057
                          00089
<___ | NAK> +003
                  00074
                          00090
<MSG | ACK> -087
                  00089
                          00000
<___ | NAK> +000
                  00161
                          00087
<___ | NAK> +001
                  00233
                          00088
<___ | NAK> +002
                  00019
                          00089
<___ | NAK> +003
                  00035
                          00090
<MSG | ACK> -087
                  00111
                          00000
<___ | NAK> +000
                  00136
                          00087
<___ | NAK> +001
                  00246
                          00088
<___ | NAK> +002
                  00073
                          00089
<___ | NAK> +003
                  00083
                          00090
<MSG | ACK> -087
                  00157
                          00000
<MSG | ACK> -087
                  00172
                          00000
<___ | NAK> +000
                  00240
                          00087
<___ | NAK> +001
                  00018
                          00088
<___ | NAK> +002
                  00053
                          00089
<___ | NAK> +003
                  00058
                          00090
<___ | NAK> +000
                  00062
                          00087
<___ | NAK> +001
                  00250
                          00088
```

```
00070
<___ | NAK> +002
                          00089
<___ | NAK> +003
                  00073
                          00090
<___ | NAK> +000
                  08000
                          00087
<___ | NAK> +001
                  00004
                          00088
<___ | NAK> +002
                  00044
                          00089
<___ | NAK> +003
                  00061
                          00090
<___ | NAK> +000
                  00066
                          00087
<___ | NAK> +001
                  00249
                          00088
<___ | NAK> +002
                  80000
                          00089
<___ | NAK> +003
                  00055
                          00090
<MSG | ACK> -087
                  00093
                          00000
<MSG | ACK> -087
                  00137
                          00000
<___ | NAK> +000
                  00193
                          00087
<___ | NAK> +001
                  00253
                          00088
<___ | NAK> +002
                  00037
                          00089
<___ | NAK> +003
                  00049
                          00090
<MSG | ACK> -087
                  00067
                          00000
<___ | NAK> +000
                  00099
                          00087
<___ | NAK> +001
                  00227
                          00088
<___ | NAK> +002
                  00022
                          00089
<___ | NAK> +003
                  00027
                          00090
<MSG | ACK> -087
                   00056
                          00000
<MSG | ACK> -087
                  00073
                          00000
<MSG | ACK> -087
                  00083
                          00000
<MSG | ACK> -087
                  00092
                          00000
<___ | NAK> +000
                  00112
                          00087
<___ | NAK> +001
                  00172
                          00088
<___ | NAK> +002
                  00187
                          00089
<___ | NAK> +003
                  00196
                          00090
<MSG | ACK> -087
                  00205
                          00000
<___ | NAK> +000
                  00232
                          00087
<___ | NAK> +001
                  00118
                          00088
<___ | NAK> +002
                  00163
                          00089
<___ | NAK> +003
                  00172
                          00090
<MSG | ACK> -087
                  00202
                          00000
<MSG | ACK> -087
                  00219
                          00000
<___ | NAK> +000
                  00236
                          00087
<___ | NAK> +001
                  00099
                          00088
<___ | NAK> +002
                  00164
                          00089
<___ | NAK> +003
                  00178
                          00090
<MSG | ACK> -087
                  00185
                          00000
<MSG | ACK> -087
                  00207
                          00000
<MSG | ACK> -002
                  00024
                          00085 o wo
<MSG | ACK> +004
                  00195
                          00091 t tr
<___ | NAK> +000
                  00230
                          00087
<___ | NAK> +001
                  00074
                          00088
```

```
<___ | NAK> +002
                  00114
                          00089
<___ | NAK> +003
                  00125
                          00090
<___ | NAK> +004
                  00135
                          00091
<MSG | ACK> -001
                  00021
                          00086 rld.
<___ | NAK> +000
                  00168
                          00087
<___ | NAK> +001
                  00036
                          00088
<___ | NAK> +002
                  00040
                          00089
<___ | NAK> +003
                  00075
                          00090
<___ | NAK> +004
                  00098
                          00091
<MSG | ACK> -087
                  00099
                          00000
<MSG | ACK> -087
                          00000
                  00151
<___ | NAK> +000
                  00226
                          00087
<___ | NAK> +001
                  00040
                          00088
<___ | NAK> +002
                  00091
                          00089
<___ | NAK> +003
                  00103
                          00090
<___ | NAK> +004
                  00115
                          00091
                  00129
<MSG | ACK> -087
                          00000
<___ | NAK> +000
                  00210
                          00087
<___ | NAK> +001
                  00051
                          00088
<___ | NAK> +002
                  00136
                          00089
<___ | NAK> +003
                  00144
                          00090
<___ | NAK> +004
                  00151
                          00091
<MSG | ACK> -087
                  00187
                          00000
<MSG | ACK> -087
                  00216
                          00000
<MSG | ACK> -001
                  00023
                          00086 rld.
<___ | NAK> +000
                  00085
                          00087
<___ | NAK> +001
                  00077
                          00088
<___ | NAK> +002
                  00082
                          00089
<___ | NAK> +003
                  00119
                          00090
<___ | NAK> +004
                  00131
                          00091
<___ | NAK> +000
                  00139
                          00087
<___ | NAK> +001
                  00074
                          00088
<___ | NAK> +002
                  00193
                          00089
<___ | NAK> +003
                  00198
                          00090
<___ | NAK> +004
                  00211
                          00091
<___ | NAK> +000
                  00001
                          00087
<___ | NAK> +001
                   00089
                          00088
<___ | NAK> +002
                  00095
                          00089
<___ | NAK> +003
                  00127
                          00090
<___ | NAK> +004
                  00135
                          00091
<MSG | ACK> -001
                  00023
                          00086 rld.
<___ | NAK> +000
                  00184
                          00087
<___ | NAK> +001
                  00069
                          00088
<___ | NAK> +002
                  00160
                          00089
<___ | NAK> +003
                  00165
                          00090
<___ | NAK> +004
                  00176
                          00091
```

```
<___ | NAK> +000
                  00000
                          00087
<___ | NAK> +001
                          00088
                  00109
<___ | NAK> +002
                  00144
                          00089
<___ | NAK> +003
                  00154
                          00090
<___ | NAK> +004
                  00160
                          00091
<___ | NAK> +000
                  00185
                          00087
<___ | NAK> +001
                  88000
                          00088
<___ | NAK> +002
                  00176
                          00089
<___ | NAK> +003
                  00179
                          00090
<___ | NAK> +004
                  00187
                          00091
<___ | NAK> +000
                  00244
                          00087
<___ | NAK> +001
                  00079
                          00088
<___ | NAK> +002
                  00091
                          00089
<___ | NAK> +003
                  00135
                          00090
<___ | NAK> +004
                  00164
                          00091
<MSG | ACK> -087
                  00186
                          00000
<___ | NAK> +000
                  00223
                          00087
<___ | NAK> +001
                  08000
                          00088
<___ | NAK> +002
                  00086
                          00089
<___ | NAK> +003
                  00123
                          00090
<___ | NAK> +004
                  00131
                          00091
<MSG | ACK> -087
                  00161
                          00000
<MSG | ACK> -087
                  00189
                          00000
<MSG | ACK> -087
                  00210
                          00000
<___ | NAK> +000
                  00229
                          00087
<___ | NAK> +001
                  00050
                          00088
<___ | NAK> +002
                  00056
                          00089
<___ | NAK> +003
                  00101
                          00090
<___ | NAK> +004
                  00136
                          00091
<MSG | ACK> -001
                  00248
                          00086 rld.
<___ | NAK> +000
                  00080
                          00087
<___ | NAK> +001
                  00064
                          00088
<___ | NAK> +002
                  00118
                          00089
<___ | NAK> +003
                  00136
                          00090
<___ | NAK> +004
                  00155
                          00091
<MSG | ACK> -087
                  00233
                          00000
<___ | NAK> +000
                  00012
                          00087
<___ | NAK> +001
                  00059
                          00088
<___ | NAK> +002
                  00063
                          00089
<___ | NAK> +003
                  00089
                          00090
<___ | NAK> +004
                  00098
                          00091
<MSG | ACK> -087
                  00113
                          00000
<MSG | ACK> -087
                  00134
                          00000
<___ | NAK> +000
                  00157
                          00087
<___ | NAK> +001
                  00253
                          00088
<___ | NAK> +002
                  00009
                          00089
```

```
<___ | NAK> +003
                  00060
                          00090
<___ | NAK> +004
                  00074
                          00091
<MSG | ACK> -087
                  00092
                          00000
<MSG | ACK> -087
                  00122
                          00000
<MSG | ACK> -087
                  00158
                          00000
<MSG | ACK> -001
                  00234
                          00086 rld.
<___ | NAK> +000
                  00083
                          00087
<___ | NAK> +001
                  00003
                          00088
<___ | NAK> +002
                  00010
                          00089
<___ | NAK> +003
                  00071
                          00090
<___ | NAK> +004
                  00106
                          00091
<MSG | ACK> -087
                  00166
                          00000
<MSG | ACK> +000
                  00217
                          00087
                                 Thi
<MSG | ACK> -003
                  00188
                          00089
<MSG | ACK> -003
                  00240
                          00089
                                 ар
<MSG | ACK> -003
                  00238
                          00089 a p
<MSG | ACK> +003
                  00091
                          00095 xamp
<MSG | ACK> +004
                  00107
                          00096 le w
<___ | NAK> +000
                  00138
                          00092
<___ | NAK> +001
                  00254
                          00093
<___ | NAK> +002
                  00042
                          00094
<___ | NAK> +003
                  00061
                          00095
<___ | NAK> +004
                  00069
                          00096
<MSG | ACK> -092
                  00086
                          00000
<MSG | ACK> -092
                  00112
                          00000
<___ | NAK> +000
                  00127
                          00092
                  00192
<___ | NAK> +001
                          00093
<___ | NAK> +002
                  00234
                          00094
<___ | NAK> +003
                  00248
                          00095
<___ | NAK> +004
                  00255
                          00096
<MSG | ACK> -092
                  00095
                          00000
<___ | NAK> +000
                  00127
                          00092
<___ | NAK> +001
                  00202
                          00093
<___ | NAK> +002
                  00039
                          00094
<___ | NAK> +003
                  00050
                          00095
<___ | NAK> +004
                  00056
                          00096
<MSG | ACK> -092
                  00158
                          00000
<MSG | ACK> -092
                  00185
                          00000
<___ | NAK> +000
                  00202
                          00092
<___ | NAK> +001
                  00183
                          00093
<___ | NAK> +002
                  00213
                          00094
<___ | NAK> +003
                  00219
                          00095
<___ | NAK> +004
                  00225
                          00096
<___ | NAK> +000
                  00231
                          00092
<___ | NAK> +001
                  00148
                          00093
<___ | NAK> +002
                  00244
                          00094
```

```
<___ | NAK> +003
                  00003
                          00095
<___ | NAK> +004
                  00010
                          00096
<___ | NAK> +000
                  00021
                          00092
<___ | NAK> +001
                  00135
                          00093
<___ | NAK> +002
                  00169
                          00094
<___ | NAK> +003
                  00180
                          00095
<___ | NAK> +004
                  00184
                          00096
<MSG | ACK> -092
                  00192
                          00000
<MSG | ACK> -092
                  00224
                          00000
<___ | NAK> +000
                  00244
                          00092
<___ | NAK> +001
                  00073
                          00093
<___ | NAK> +002
                  00086
                          00094
<___ | NAK> +003
                  00188
                          00095
<___ | NAK> +004
                  00204
                          00096
<MSG | ACK> -092
                  00255
                          00000
<MSG | ACK> -092
                  00053
                          00000
<___ | NAK> +000
                  00167
                          00092
<___ | NAK> +001
                  00140
                          00093
<___ | NAK> +002
                  00145
                          00094
<___ | NAK> +003
                  00183
                          00095
<___ | NAK> +004
                  00195
                          00096
<MSG | ACK> -092
                  00204
                          00000
<MSG | ACK> -092
                  00230
                          00000
<___ | NAK> +000
                  00245
                          00092
<___ | NAK> +001
                  00071
                          00093
<___ | NAK> +002
                          00094
                  00105
<___ | NAK> +003
                  00111
                          00095
<___ | NAK> +004
                  00114
                          00096
<MSG | ACK> -092
                  00160
                          00000
<MSG | ACK> -092
                  00187
                          00000
<___ | NAK> +000
                  00222
                          00092
<___ | NAK> +001
                  00020
                          00093
<___ | NAK> +002
                  00106
                          00094
<___ | NAK> +003
                  00113
                          00095
<___ | NAK> +004
                  00117
                          00096
<MSG | ACK> -092
                  00207
                          00000
<MSG | ACK> -092
                  00229
                          00000
<___ | NAK> +000
                  00009
                          00092
<___ | NAK> +001
                  00037
                          00093
<___ | NAK> +002
                  00087
                          00094
<___ | NAK> +003
                  00094
                          00095
<___ | NAK> +004
                  00096
                          00096
<___ | NAK> +000
                  00099
                          00092
<___ | NAK> +001
                  00214
                          00093
<___ | NAK> +002
                  00242
                          00094
<___ | NAK> +003
                  00251
                          00095
```

```
<___ | NAK> +004
                  00002
                          00096
<MSG | ACK> -092
                  00063
                          00000
<___ | NAK> +000
                  00086
                          00092
<___ | NAK> +001
                  00150
                          00093
<___ | NAK> +002
                  00193
                          00094
<___ | NAK> +003
                  00207
                          00095
<___ | NAK> +004
                  00219
                          00096
<MSG | ACK> -092
                  00223
                          00000
<___ | NAK> +000
                  00050
                          00092
<___ | NAK> +001
                  00203
                          00093
<___ | NAK> +002
                  00108
                          00094
<___ | NAK> +003
                  00128
                          00095
<___ | NAK> +004
                  00168
                          00096
<___ | NAK> +000
                  00199
                          00092
<___ | NAK> +001
                  00120
                          00093
<___ | NAK> +002
                  00127
                          00094
                  00172
<___ | NAK> +003
                          00095
<___ | NAK> +004
                  00184
                          00096
<MSG | ACK> -092
                  00240
                          00000
<MSG | ACK> -092
                  00037
                          00000
<___ | NAK> +000
                  00070
                          00092
<___ | NAK> +001
                  00131
                          00093
<___ | NAK> +002
                          00094
                  00139
<___ | NAK> +003
                  00238
                          00095
<___ | NAK> +004
                  00254
                          00096
<MSG | ACK> -092
                  00038
                          00000
<MSG | ACK> -092
                  00076
                          00000
<MSG | ACK> -001
                  00119
                          00091 t tr
<MSG | ACK> +005
                  00224
                          00097 ith
<___ | NAK> +000
                  00246
                          00092
<___ | NAK> +001
                  00171
                          00093
<___ | NAK> +002
                  00182
                          00094
<___ | NAK> +003
                  00222
                          00095
<___ | NAK> +004
                  00236
                          00096
<___ | NAK> +005
                  00251
                          00097
<MSG | ACK> -092
                  00033
                          00000
<MSG | ACK> -092
                  00118
                          00000
<___ | NAK> +000
                  00095
                          00092
<___ | NAK> +001
                  00203
                          00093
<___ | NAK> +002
                  00231
                          00094
<___ | NAK> +003
                  00236
                          00095
<___ | NAK> +004
                  00072
                          00096
<___ | NAK> +005
                  00085
                          00097
<MSG | ACK> -092
                  00136
                          00000
<___ | NAK> +000
                  00176
                          00092
<___ | NAK> +001
                  00013
                          00093
```

```
<___ | NAK> +002
                  00049
                          00094
<___ | NAK> +003
                  00058
                          00095
<___ | NAK> +004
                  00066
                          00096
<___ | NAK> +005
                  00074
                          00097
<MSG | ACK> -092
                  00102
                          00000
<___ | NAK> +000
                  00119
                          00092
<___ | NAK> +001
                  00012
                          00093
<___ | NAK> +002
                  00123
                          00094
<___ | NAK> +003
                  00127
                          00095
<___ | NAK> +004
                  00146
                          00096
<___ | NAK> +005
                  00149
                          00097
<___ | NAK> +000
                  00113
                          00092
<___ | NAK> +001
                  00041
                          00093
<___ | NAK> +002
                  00046
                          00094
<___ | NAK> +003
                  08000
                          00095
<___ | NAK> +004
                  00092
                          00096
<___ | NAK> +005
                  00099
                          00097
<MSG | ACK> -092
                  00150
                          00000
<___ | NAK> +000
                  00183
                          00092
<___ | NAK> +001
                  00011
                          00093
<___ | NAK> +002
                  00024
                          00094
<___ | NAK> +003
                  00076
                          00095
<___ | NAK> +004
                  00106
                          00096
<___ | NAK> +005
                  00126
                          00097
<___ | NAK> +000
                  00159
                          00092
                          00093
<___ | NAK> +001
                  00063
<___ | NAK> +002
                  00102
                          00094
<___ | NAK> +003
                  00114
                          00095
<___ | NAK> +004
                  00122
                          00096
<___ | NAK> +005
                  00130
                          00097
<MSG | ACK> +000
                  00130
                          00092 ansm
<MSG | ACK> -093
                  00211
                          00000
<___ | NAK> +000
                  00227
                          00093
<___ | NAK> +001
                  00027
                          00094
<___ | NAK> +002
                  00076
                          00095
<___ | NAK> +003
                  00090
                          00096
<___ | NAK> +004
                  00102
                          00097
<MSG | ACK> -093
                  00145
                          00000
<MSG | ACK> -093
                  00181
                          00000
<___ | NAK> +000
                  00208
                          00093
<___ | NAK> +001
                  00239
                          00094
<___ | NAK> +002
                  00014
                          00095
<___ | NAK> +003
                  00022
                          00096
<___ | NAK> +004
                  00034
                          00097
<MSG | ACK> -093
                  00045
                          00000
<MSG | ACK> -093
                  00066
                          00000
```

```
<___ | NAK> +000
                          00093
                  00089
<___ | NAK> +001
                  00210
                          00094
<___ | NAK> +002
                  00032
                          00095
<___ | NAK> +003
                  00057
                          00096
<___ | NAK> +004
                  00076
                          00097
<MSG | ACK> -093
                  00129
                          00000
<MSG | ACK> -001
                  00198
                          00092 ansm
<___ | NAK> +000
                  00070
                          00093
<___ | NAK> +001
                  00023
                          00094
<___ | NAK> +002
                  00064
                          00095
<___ | NAK> +003
                          00096
                  00076
<___ | NAK> +004
                  00084
                          00097
<MSG | ACK> +000
                  00091
                          00093 issi
<MSG | ACK> -094
                  00118
                          00000
<MSG | ACK> -094
                  00162
                          00000
<___ | NAK> +000
                  00179
                          00094
<___ | NAK> +001
                  00230
                          00095
<___ | NAK> +002
                  00240
                          00096
<___ | NAK> +003
                  00031
                          00097
<MSG | ACK> -094
                  00070
                          00000
<MSG | ACK> -094
                  00104
                          00000
<___ | NAK> +000
                  00123
                          00094
<___ | NAK> +001
                  00237
                          00095
<___ | NAK> +002
                  00070
                          00096
<___ | NAK> +003
                  00095
                          00097
<MSG | ACK> -094
                  00187
                          00000
<___ | NAK> +000
                  00017
                          00094
<___ | NAK> +001
                  00034
                          00095
<___ | NAK> +002
                  00048
                          00096
<___ | NAK> +003
                  00096
                          00097
<___ | NAK> +000
                  00109
                          00094
<___ | NAK> +001
                  00044
                          00095
<___ | NAK> +002
                  00125
                          00096
<___ | NAK> +003
                  00134
                          00097
<MSG | ACK> -094
                  00198
                          00000
<MSG | ACK> -094
                  00242
                          00000
<___ | NAK> +000
                  00067
                          00094
<___ | NAK> +001
                  00089
                          00095
<___ | NAK> +002
                  00135
                          00096
<___ | NAK> +003
                  00146
                          00097
<MSG | ACK> +000
                  00184
                          00094 on e
<MSG | ACK> -004
                  00229
                          00094 on e
<MSG | ACK> -003
                  00211
                          00095 xamp
<MSG | ACK> -003
                  00170
                          00095 xamp
<END | ACK> +003
                  00243
                          00101 te.
<___ | NAK> +000
                  00014
                          00098
```

```
<___ | NAK> +001 00253 00099
<___ | NAK> +002 00015 00100
<___ | NAK> +003
                 00021 00101
<___ | NAK> +000
                 00035 00098
<___ | NAK> +001
                 00143 00099
<___ | NAK> +002
                 00177 00100
<___ | NAK> +003
                 00181
                        00101
<MSG | ACK> +000
                 00195
                        00098 50%
<MSG | ACK> -099
                 00214 00000
<MSG | ACK> +000 00220 00099 erro
<___ | NAK> +000 00012 00100
<___ | NAK> +001 00114 00101
<MSG | ACK> +000 00202 00100 r ra
> Hello world. This is a packet transmission example with 50% error rate.
<MSG | ACK> -102 00231 00000
<MSG | ACK> -002
                 00250 00100 r ra
{MSG \mid ACK > -002 \quad 00059 \quad 00100 \ r \ ra}
<MSG | ACK> -002
                 00130 00100 r ra
<MSG | ACK> -002 00202 00100 r ra
```