JavaScript is disabled on your browser.

compact1, compact2, compact3
java.util.jar

Interface Pack200.Unpacker

Enclosing class:

Pack200

---

public static interface **Pack200.Unpacker**

The unpacker engine converts the packed stream to a JAR file. An instance of the engine can be obtained using Pack200.newUnpacker().

Every JAR file produced by this engine will include the string "PACK200" as a zip file comment. This allows a deployer to detect if a JAR archive was packed and unpacked.

Note: Unless otherwise noted, passing a null argument to a constructor or method in this class will cause a NullPointerException to be thrown.

This version of the unpacker is compatible with all previous versions.

Since:

1.5

Field Summary

Fields

Modifier and Type	Field	Description

static String	DEFLATE_HINT	Property indicating that the unpacker should ignore all transmitted values for DEFLATE_HINT, replacing them by the given value, TRUE or FALSE.
static String	FALSE	The string "false", a possible value for certain properties.
static String	KEEP	The string "keep", a possible value for certain properties.
static String	PROGRESS	The unpacker's progress as a percentage, as periodically updated by the unpacker.
static String	TRUE	The string "true", a possible value for certain properties.

Method Summary

Deprecated

Modifier and Type	Method
default void	addPropertyChangeListener(PropertyChangeListener listen
SortedMap<String,String>	properties()
default void	removePropertyChangeListener(PropertyChangeListener lis

void	**unpack**(**File** in, **JarOutputStream** out)
void	**unpack**(**InputStream** in, **JarOutputStream** out)

Field Detail

KEEP

```
static final String KEEP
```

The string "keep", a possible value for certain properties.

See Also:

DEFLATE_HINT, Constant Field Values

TRUE

```
static final String TRUE
```

The string "true", a possible value for certain properties.

See Also:

DEFLATE_HINT, Constant Field Values

FALSE

```
static final String FALSE
```

The string "false", a possible value for certain properties.

See Also:

DEFLATE_HINT, Constant Field Values

DEFLATE_HINT

```
static final String DEFLATE_HINT
```

Property indicating that the unpacker should ignore all transmitted values for DEFLATE_HINT, replacing them by the given value, `TRUE` or `FALSE`. The default value is the special string `KEEP`, which asks the unpacker to preserve all transmitted deflation hints.

See Also:

Constant Field Values

PROGRESS

```
static final String PROGRESS
```

The unpacker's progress as a percentage, as periodically updated by the unpacker. Values of 0 - 100 are normal, and -1 indicates a stall. Progress can be monitored by polling the value of this property.

At a minimum, the unpacker must set progress to 0 at the beginning of a packing operation, and to 100 at the end.

See Also:

Constant Field Values

Method Detail

properties

```
SortedMap<String,String> properties()
```

Get the set of this engine's properties. This set is a "live view", so that changing its contents immediately affects the Packer engine, and changes from the engine (such as progress indications) are immediately visible in the map.

The property map may contain pre-defined implementation specific and default properties. Users are encouraged to read the information and fully understand the implications, before modifying pre-existing properties.

Implementation specific properties are prefixed with a package name associated with the implementor, beginning with `com.` or a similar prefix. All property names beginning with `pack.` and `unpack.` are reserved for use by this API.

Unknown properties may be ignored or rejected with an unspecified error, and invalid entries may cause an unspecified error to be thrown.

Returns:

A sorted association of option key strings to option values.

unpack

```
void unpack(InputStream in,
            JarOutputStream out)
     throws IOException
```

Read a Pack200 archive, and write the encoded JAR to a JarOutputStream. The entire contents of the input stream will be read. It may be more efficient to read the Pack200 archive to a file and pass the File object, using the alternate method described below.

Closes its input but not its output. (The output can accumulate more elements.)

Parameters:

in - an InputStream.

out - a JarOutputStream.

Throws:

IOException - if an error is encountered.

unpack

```
void unpack(File in,
            JarOutputStream out)
     throws IOException
```

Read a Pack200 archive, and write the encoded JAR to a JarOutputStream.

Does not close its output. (The output can accumulate more elements.)

Parameters:

in - a File.

out - a JarOutputStream.

Throws:

IOException - if an error is encountered.

addPropertyChangeListener

```
@Deprecated
default void addPropertyChangeListener(PropertyChangeListener listener)
```

Deprecated. *The dependency on `PropertyChangeListener` creates a significant impediment to future modularization of the Java platform. This method will be removed in a future release. Applications that need to monitor progress of the unpacker can poll the value of the `PROGRESS` property instead.*

Registers a listener for PropertyChange events on the properties map. This is typically used by applications to update a progress bar.

The default implementation of this method does nothing and has no side-effects.

WARNING: This method is omitted from the interface declaration in all subset Profiles of Java SE that do not include the `java.beans` package.

Parameters:

`listener - An object to be invoked when a property is changed.`

See Also:

`properties()`, `PROGRESS`

removePropertyChangeListener

```
@Deprecated
default void removePropertyChangeListener(PropertyChangeListener listener)
```

Deprecated. *The dependency on `PropertyChangeListener` creates a significant impediment to future modularization of the Java platform. This method will be removed in a future release.*

Remove a listener for PropertyChange events, added by the `addPropertyChangeListener(java.beans.PropertyChangeListener)`.

The default implementation of this method does nothing and has no side-effects.

WARNING: This method is omitted from the interface declaration in all subset Profiles of Java SE that do not include the `java.beans` package.

Parameters:

`listener - The PropertyChange listener to be removed.`

See Also:

`addPropertyChangeListener(java.beans.PropertyChangeListener)`

Submit a bug or feature
For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.
Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.