
NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA SRWE	Switching, Routing, and Wireless Essentials (SRWE)	

CCNA SRWE Lab 1 Homework Deadline: 25.1.2021

Name: Shabnaz Khanam

VLANs and 802.1Q Trunks Inter-VLAN-Routing



NP Course NP Chapter 8

SRWE Modules 1 - 4:

Switching Concepts, VLANs, and InterVLAN Routing Exam

Upload

Record your answers in this PDF File SRWE-Lab1-Homework.pdf.

Write your answers in **red color**. You may use the comment capabilities of the free Adobe reader.

Upload the PDF file with your answers is Ilias.

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA SRWE	Switching, Routing, and Wireless Essentials (SRWE)	

Homework / Preparation

Part 1: Cisco IOS Basic Configuration Commands

- a. Read the Lab Instructions of this Lab, and read NP chapters 8
- b. Check the **IOS Command List**, provided for the Labs and Review already used and new configuration commands.

Part 2: Recall Basic Configuration Commands

- a. Basic router interface commands
 - Configure router interface g0/1 with description "Link to LAN-A", IP address 172.16.10.1/29 and activate it

```
R1 (config) #int g0/1
R1 (config-if) # description Link to LAN-A
R1 (config-if) # ip address 172.16.10.1 255.255.255.248
```

Display the status of all interfaces in brief. R1(config)#exit

```
R1# show ip interface brief
```

R1(config-if)#no shutdown

- Display the status of all interfaces in brief.

```
R1# show interface brief
```

Display the detailed status of the interface g0/1

```
R1\# show ip int g0/1
```

- Display the routing table.

```
R1#show ip route
```

Display the running configuration.

```
R1#show running-config
```

Part 3: Cisco IOS Switch VLAN / Trunk Commands

- a) Basic VLAN switch configurations
- Create VLAN 57 with name "students" on switch S1

```
S1(config) # vlan 57
S1(config-vlan) # name student
```

- Configure S1 switch port f0/23 to be access port for VLAN 57

```
S1(config) #int f0/23
S1(config-if) # switchport mode access
S1(config-if) #switchport access vlan 57
```

- Display the VLAN database in brief

```
S1# show vlan brief
```

b) Basic Trunk switch configurations

Configure the interface f0/5 as trunk port with native VLAN 99, VLAN allowed 57, 58, 59, 99

```
S1(config)# int f0/5
S1(config-if)# switchport mode trunk
S1(config-if)# switchport trunk native vlan 99
S1(config-if)# switchport trunk allowed vlan 57,58,59,99
```

- Display the status of **trunk interface** f0/5

```
$1#show interface f0/5 trunk
```

c) Basic SVI switch configurations

- Create management VLAN 100 (Name Management)

```
S1(config) # vlan 100
S1(config-vlan) #name management
```

Create the interface, configure IP address 192.168.100.11/24 for the management VLAN 100

```
S1(config) # int vlan 100
S1(config-if) #ip address 192.168.100.11 255.255.255.0
S1(config-if) #no shutdown
```

- Set switch port f0/1 to be access port for VLAN 100.

```
S1(config) # int f0/1
S1(config-if) # switchport mode access
S1(config-if) # switchport access Vlan 100
```

- Configure an IP default gateway with IP address 192.168.100.1 on switch S1.

```
S1(config) #ip default-gateway 192.168.100.1
```

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA SRWE	Switching, Routing, and Wireless Essentials (SRWE)	

Part 4: Cisco IOS Inter-VLAN-Routing Commands

a) Switch Trunk to Router configurations

Configure the interface f0/5 of switch S1 as trunk port with native VLAN 100, VLAN allowed 10,20,100 S1 (config) # int f0/5
S1 (config-if) # switchport mode trunk
S1 (config-if) # switchport trunk native vlan 100
S1 (config-if) # switchport trunk allowed vlan 10,20,100
S1 (config-if) # end

b) Router sub-interface and physical interface

- Create a sub-interface for VLAN 10 at router R1 interface g0/0 with description "VLAN 10 interface", IEEE 802.1q encapsulation and IP address 10.0.0.1 / 24.

```
R1(config) # int g0/0
R1(config-subif) #switchport trunk encapsulation dot1q
R1(config-subif) # ip address 10.0.0.1 255.255.255.0
R1(config-subif) #exit
```

- Configure router R1 interface g0/0 as native trunk interface for VLAN 100 with description "VLAN 100 interface", IP address 192.168.100.1 / 24 and switch-on this physical interface.

```
R1(config)# int g0/0
R1(config-if)# description vlan 100 interface
R1(config-if)#ip address 192.168.100.1 255.255.255.0
R1(config-if)#no shutdown
```