11.3 Lab: Implement Intrusion Prevention

Candidate: COMPTIA COMPTIA ()
Time Spent: 00:55

Score: 0%
Task Summary
Required Actions
× Configure Snort rules Show Details
X Configure Sourcefire OpenAppID Detectors Show Details
X Configure the Rules Update Settings Show Details
X Configure General Settings Show Details
X Configure the Snort Interface settings for the WAN interface Show Details

Explanation 6

Complete this lab as follows:

- 1. Sign in to the pfSense management console.
 - a. In the Username field, enter admin.
 - b. In the Password field, enter P@ssw0rd (zero).
 - c. Select SIGN IN or press Enter.
- 2. Access Snort Global Settings.
 - a. From the pfSense menu bar, select **Services** > **Snort**.
 - b. Under the Services breadcrumb, select Global Settings.
- 3. Configure the required rules to be downloaded.
 - a. Select Enable Snort VRT.
 - b. In the Snort Oinkmaster Code field, enter **992acca37a4dbd7**. You can copy and paste this from the scenario.
 - c. Select Enable Snort GPLv2.
 - d. Select Enable ET Open.
- 4. Configure the Sourcefire OpenAppID Detectors to be downloaded.
 - a. Under Sourcefire OpenAppID Detectors, select Enable OpenAppID.
 - b. Select **Enable RULES OpenAppID**.
- 5. Configure when and how often the rules will be updated.
 - a. Under Rules Update Settings, use the Update Interval drop-down menu to select 4 DAYS.
 - b. For Update Start Time, change to 00:10 (12:10 a.m. in 24-hour format).

- c. Select Hide Deprecated Rules Categories.
- 6. Configure Snort General Settings.
 - a. Under General Settings, use the **Remove Blocked Hosts Interval** drop-down menu to select **1 Day**.
 - b. Select Startup/Shutdown Logging.
 - c. Select **Save**.
- 7. Configure the Snort Interface settings for the WAN interface.
 - a. Under the Services breadcrumb, select Snort Interfaces and then select Add.
 - b. Under General Settings, make sure **Enable interface** is selected.
 - c. For Interface, use the drop-down menu to select WAN (CorpNet_pfSense_L port 1).
 - d. For Description, use Snort-WAN.
 - e. Under Alert Settings, select Send Alerts to System Log.
 - f. Select **Block Offenders**.
 - g. Scroll to the bottom and select **Save**.
- 8. Start Snort on the WAN interface.
 - a. Under the Snort Status column, select the *arrow* to start Snort.
 - b. Wait for a checkmark to appear, indicating that Snort was started successfully.