

#### IIC2343 - Arquitectura de Computadores

# Ayudantía 2

Profesor: Yadran Eterovic

Ayudantes: Daniel Leal (dlleal@uc.cl), Jessica Hormazabal (jyhormazabal@uc.cl)

## Preguntas

Los ejercicios de esta ayudantía fueron resueltos utilizando la arquitectura ISA MEEP MEEP (solamente 4 registros s1, s2, s3, s4)y no la arquitectura ISA MIPS. Hay instrucciones que difieren de ambas arquitecturas, por lo tanto es importante que se fijen en la ISA que van a usar antes de escribir un programa. Notar además que las soluciones para esta ayudantía son soluciones posibles pero están lejos de ser las únicas soluciones válidas.

#### 1. Assembly

a) Cargue los valores 5 y 17 en los registros \$s1 y \$s2. Considere registros de 1 byte.

TIP: Para resolver este ejercicio con la ISA MIPS, se podría hacer lo siguiente:

```
^{1} addi $s1, $zero, 5 # s1 = 5 2 addi $s2, $zero, 17 # s2 = 17
```

b) Utilizando la arquitectura ISA MEEP MEEP, programe una multiplicación en assembly entre dos números guardados en memoria. Considere que los números a multiplicar están en las direcciones 8 y 9, mientras que el resultado desea guardarse en la dirección 13.

```
1 movi $s2, 8
                        \# s2 = 8
                        \# s3 = 9
2 movi $s3, 9
                        \# s1 = Memory [8]
зlb
        $s1, 0($s2)
4 lb
        $s2, 0($s3)
                        \# s2 = Memory [9]
5 movi $s3, 0
                        \# s3 = 0 (contador)
_{6} movi \$s4, 0
                        \# s4 = 0 (acumulado)
7 beq $s2, $s3, 4
8 addi $s3, $s3, 1
                        \# si contador == s2, saltar a 11 (7 + 4)
                        # s3 += 1 (aumentar contador)
9 add $s4, $s4, $s1 # s4 += s1
10 j
                        # saltar a 7
                        \# s1 = 13 (queremos escribir en Memory[13])
11 movi $s1, 13
        $s3, 0($s1)
                        \# \text{ Memory}[13] = s3
```

c) Utilizando la arquitectura ISA MEEP MEEP, programe en assembly un código que le permita sumar N números desde el número  $P_0$  en adelante. Asuma que N y  $P_0$  están guardados en la memoria RAM en las direcciones 13 y 21, respectivamente. Guarde el valor final en la dirección 4 de la memoria. Comente si lo encuentra necesario.

Lo primero que haremos será definir para qué usaremos cada registro. Usaremos s1 como un contador para saber qué número estamos sumando, s2 lo usaremos para saber hasta qué número sumar, s3 lo usaremos como un extractor temporal (un recipiente en el cual almacenar temporalmente los números extraídos de memoria) y s4 lo usaremos para almacenar el total sumado. Una vez definido esto, podemos empezar a escribir el programa.

```
1 movi $s2, 21
                        \# s2 = 21
        $s1, 0($s2)
                        # s1 = Memory[21] (ubicacion del primer numero a sumar)
2 lb
з movi $s2, 13
                        \# s2 = 13
                        \# s3 = Memory[13] (cantidad de numeros a sumar)
4 lb
        \$s3, 0(\$s2)
        $s2, $s1, $s3
5 add
                        \# s2 = s1 + s3 (ubicacion del ultimo numero a sumar)
6 movi $s4, 0
                        \# s4 = 0 (valor total sumado)
7 beq
        $s1, $s2, 5
                        \# \text{ si s1} = \text{s2}, \text{ saltar a 12 } (7 + 5)
        $s3, 0($s1)
                        \# s3 = Memory [s1]
8 lb
        \$s4, \$s4, \$s3
9 add
                        \# s4 += s3
10 addi $s1, $s1, 1
                        # s1 += 1 (contador)
11 j
                        # saltar a 7
12 movi $s1, 4
                        \# s1 = 4 (queremos escribir en Memory[4])
        $s4, 0($s1)
                        \# \text{ Memory } [4] = s4
13 sb
```

## 2. Anexos

## MIPS assembly language

Category	Instruction	Example	Meaning	Comments
Arithmetic	add	add \$s1,\$s2,\$s3	\$s1 = \$s2 + \$s3	Three register operands
	subtract	sub \$s1,\$s2,\$s3	\$s1 = \$s2 - \$s3	Three register operands
	add immediate	addi \$s1,\$s2,20	\$s1 = \$s2 + 20	Used to add constants
Data transfer	load word	lw \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Word from memory to register
	store word	sw \$s1,20(\$s2)	Memory[\$s2 + 20] = \$s1	Word from register to memory
	load half	1h \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Halfword memory to register
	load half unsigned	1hu \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Halfword memory to register
	store half	sh \$s1,20(\$s2)	Memory[\$s2 + 20] = \$s1	Halfword register to memory
	load byte	1b \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Byte from memory to register
	load byte unsigned	1bu \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Byte from memory to register
	store byte	sb \$s1,20(\$s2)	Memory[\$s2 + 20] = \$s1	Byte from register to memory
	load linked word	11 \$s1,20(\$s2)	\$s1 = Memory[\$s2 + 20]	Load word as 1st half of atomic swap
	store condition, word	sc \$s1,20(\$s2)	Memory[\$s2+20]=\$s1;\$s1=0 or 1	Store word as 2nd half of atomic swap
	load upper immed.	lui \$s1,20	\$s1 = 20 * 2 <sup>16</sup>	Loads constant in upper 16 bits
Logical	and	and \$s1,\$s2,\$s3	\$s1 = \$s2 & \$s3	Three reg. operands; bit-by-bit AND
	or	or \$s1,\$s2,\$s3	\$s1 = \$s2   \$s3	Three reg. operands; bit-by-bit OR
	nor	nor \$s1,\$s2,\$s3	\$s1 = ~ (\$s2   \$s3)	Three reg. operands; bit-by-bit NOR
	and immediate	andi \$s1,\$s2,20	\$s1 = \$s2 & 20	Bit-by-bit AND reg with constant
	or immediate	ori \$s1,\$s2,20	\$s1 = \$s2   20	Bit-by-bit OR reg with constant
	shift left logical	sll \$s1,\$s2,10	\$s1 = \$s2 << 10	Shift left by constant
	shift right logical	srl \$s1,\$s2,10	\$s1 = \$s2 >> 10	Shift right by constant
Conditional branch	branch on equal	beq \$s1,\$s2,25	if (\$s1 == \$s2) go to PC + 4 + 100	Equal test; PC-relative branch
	branch on not equal	bne \$s1,\$s2,25	if (\$s1!= \$s2) go to PC + 4 + 100	Not equal test; PC-relative
	set on less than	slt \$s1,\$s2,\$s3	if (\$s2 < \$s3) \$s1 = 1; else \$s1 = 0	Compare less than; for beq, bne
	set on less than unsigned	sltu \$s1,\$s2,\$s3	if (\$s2 < \$s3) \$s1 = 1; else \$s1 = 0	Compare less than unsigned
	set less than immediate	slti \$s1,\$s2,20	if (\$s2 < 20) \$s1 = 1; else \$s1 = 0	Compare less than constant
	set less than immediate unsigned	sltiu \$s1,\$s2,20	if (\$s2 < 20) \$s1 = 1; else \$s1 = 0	Compare less than constant unsigned
Unconditional jump	jump	j 2500	go to 10000	Jump to target address
	jump register	jr \$ra	go to \$ra	For switch, procedure return
	jump and link	jal 2500	\$ra = PC + 4; go to 10000	For procedure call

Figura 1: ISA de un computador MIPS

SAMPLE INSTRUCTION	Meaning
ADD \$51, \$52, \$53  SUB \$51, \$52, \$53  ADD: \$51, \$52, \$53  ADD: \$51, \$52, \$53  OR \$51, \$52, \$53  AND: \$51, \$52, \$53  AND: \$51, \$52, \$53  AND: \$51, \$52, \$57  OR: \$51, \$52, \$57  SRL \$51, \$52, \$57  SRL \$51, \$52, \$57  BEQ \$51, \$52, \$57  BEQ \$51, \$52, \$57  T \$57  LIT  LB \$51, \$52, \$57  SB \$51, \$52, \$52  MOV: \$51, \$52	\$51 = \$52 + \$53
SUB \$51, \$52, \$53	\$\$1 = \$\$2 - \$\$3
ADDI \$51, \$52, Lit	\$\$1 = \$\$2 + Lit \$\$1 = \$\$2 1 \$\$3
HND DAY, 352, 353	\$51 = \$52 x \$53
OR \$51, \$52, \$53	1 3 71 = 1 2 0 V 2 2 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1
AND \$51, \$52, Lit	\$51 = \$52 1 Lit \$51 = \$52 V Lit \$51 = \$52 << Lit \$51 = \$52 >> Lit if (\$51 == \$52) 60 TO PC + Lit
OR: \$51, \$52, Lit	\$\$1 = \$52 V Lit
SU \$51, \$52, Lit	\$51 = \$S2 << LiT
SRL \$51, \$52, Lit	\$51 = \$\$2 >> Lit
BEQ \$\$1, \$52, LIT	if (\$51 == \$52) 60 TO PC + Lit
BNE \$51, \$52, Lit	1F (\$51 != \$52) 60 79 1-C+LiT
7 47	60 TO L.+
LB \$51, Lit(\$52)	\$51= Monory [\$52+Li+]
SB \$51, Lit (\$52)	Monory ( \$52 + Lit = 851
MOV \$51, \$52	\$51 = \$52 \$51 = Lit
MOV: \$57, L.T	\$\$1 = L;T
* REGISTROS DE 1 BYTE,	Memoria BYTE-INDEXED

Figura 2: ISA de un computador MEEP MEEP