Hilbert Transform


Table of Contents


What is Hilbert Transform?	1
Why do we need it?	
Definition	
FFT-based Hilbert transform	
Properties of the Hilbert transform.	


What is Hilbert Transform?

The discrete Hilbert transform is a process used to generate complex-valued signals from real-valued signals.


It is a method for extracting the magnitude and phase information from a real-valued signal like a EEG data:







Notation used to define the continuous Hilbert transform:



 $x_{*}(t)$ = a real continuous time-domain input signal

h(t) = the time impulse response of a Hilbert transformer

 $x_{ht}(t)$ = the HT of $x_r(t)$, ($x_{ht}(t)$ is also a real time-domain signal)

 $X_{r}(\omega)$ = the Fourier transform of real input $x_{r}(t)$

 $H(\omega)$ = the frequency response (complex) of a Hilbert transformer

 $X_{\rm ht}(\omega)$ = the Fourier transform of output $x_{\rm ht}(t)$

ω = continuous frequency measured in radians/second

t = continuous time measured in seconds.




Figure 9-2 The complex frequency response of $H(\omega)$.




Figure 9-3 The Hilbert transform: (a) $\cos(\omega t)$; (b) its transform is $\sin(\omega t)$.

Why do we need it?

Typically, we start with a real-valued signal which can be conceptualised as:

$$x_r(t) = A\cos(\omega t)$$

Given a real-value signal, we cannot estimate or extract the phase angle and the power. What we need to represent the signal as a complex sinusoid

$$x_c(t) = A e^{j\omega t}$$

$$x_c(t) = A \cos(\omega t) + j A \sin(\omega t)$$

$$x_c(t) = x_r(t) + j x_i(t)$$

Using complex signals of the real signals simplifies and improves the performance of many signal processing operations.

The answer is: we need to understand the HT because it's useful in so many complex-signal (quadrature) processing applications. A brief search on the Internet reveals HT-related signal processing techniques being used in the following applications:

- Quadrature modulation and demodulation (communications)
- Automatic gain control (AGC)
- Analysis of two- and three-dimensional complex signals
 - · Medical imaging, seismic data and ocean wave analysis
 - · Instantaneous frequency estimation
 - Radar/sonar signal processing, and time-domain signal analysis using wavelets
 - Time difference of arrival (TDOA) measurements
 - High definition television (HDTV) receivers
 - · Loudspeaker, room acoustics, and mechanical vibration analysis
 - Audio and color image compression
 - · Nonlinear and nonstationary system analysis.

Definition

Typically, we start with a real-valued signal which can be conceptualised as:

$$x_r(t) = A\cos(\omega t)$$

Given a real-value signal, we cannot estimate or extract the phase angle and the power. What we need to represent the signal as a complex sinusoid using Euler's formula:

$$x_c(t) = A e^{j\omega t}$$

$$x_c(t) = A \cos(\omega t) + j A \sin(\omega t)$$


$$x_c(t) = x_r(t) + j x_i(t)$$

where

- $x_c(t)$ is known as an *analytic signal* because it has no negative-frequency spectral components.
- $j x_i(t)$ is called the *phase-quadrature component*.

The phase-quadrature component can be obtained by a 90 degree (quarter-cycle) shift on the complex plan.

The Hilbert transform of $cos(\theta)$ is $sin(\theta)$ i.e., a quarter-cycle shift.



The Hilbert transform rotates the Fourier coefficients in the complex space which converts the real components into the imaginary component. The quarter-cycle shifted signal is then added to the original signal.

In other words, a Hilbert transform takes each frequency component present in the original signal and shifts its phase by $-\frac{\pi}{2}$.




Figure 9-4 Functional relationship between the $x_c(t)$ and $x_r(t)$ signals.


FFT-based Hilbert transform

The FFT-based Hilbert transform can be implemented as three steps:


- 1. Take the FFT of a time-series signal
- 2. Rotate the Fourier coefficients
- 3. Take the inverse FFT of the rotated Fourier coefficients to get a time-series signal

```
clear variables;
n = 21;
% Generate a signal
```

```
x = randn(n, 1);
plot(x)
```




```
% Step 1: Take the FFT
f = fft(x);
plot(f.*conj(f))
```




```
% Create a copy of the Fourier coefficients
complexf = 1i*f;

% Identify the indices for the positive and negative frequencies
% because they are rotated in different ways.
pos_freq_idx = 2:floor(n/2) + mod(n, 2);
neg_freq_idx = ceil(n/2) + 1 + ~mod(n, 2):n;

% Rotate the Fourier coefficients by computing i*A*sin(wt) component.
% Note! Positive frequencies are rotated counter-clockwise while
% negative frequencies are rotated clockwise.
f(pos_freq_idx) = f(pos_freq_idx) + -1i*complexf(pos_freq_idx);
f(neg_freq_idx) = f(neg_freq_idx) + 1i*complexf(neg_freq_idx);
plot(f.*conj(f))
```



```
hilbert_x = ifft(f);
plot(abs(hilbert_x))
```



Properties of the Hilbert transform

- (1) A signal $x_r(t)$ and its Hilbert transform $x_i(t)$ have the same power density spectrum.
- (2) A signal $x_r(t)$ and its Hilbert transform $x_i(t)$ have the same autocorrelation function
- (3) A signal $x_r(t)$ and its Hilbert transform $x_i(t)$ are mutually orthogonal so we can write:

$$\int_{-\infty}^{\infty} x_r(t) x_i(t) \, \mathrm{d}t = 0$$

(4) If $x_i(t)$ is a Hilbert transform of a signal $x_r(t)$ then the Hilbert transform of signal $x_i(t)$ is $-x_r(t)$ i.e. the Hilbert transform of the Hilbert transform yields the negative signal:

if
$$H[x_r(t)] = x_i(t)$$
 then $H[x_i(t)] = -x_r(t)$