Question 6 (30 points):

A binary optimizer is a program that analyses and transforms the binary representation of a program into a more efficient version of the same program. In this question your task is to write functions that analyze the binary of a RISC-V assembly program and identify opportunities for improvement. We are interested in the load-use dependence issue. In most modern microprocessors, whenever a load instruction is immediately followed by an instruction that uses the value in the destination register of the load, a delay of at least one cycle will be needed in the pipeline. For example:

```
1b t3, 0(t4)
add t0, t1, t3
```

To eliminate this delay, first we need to find the occurrences of such cases in the binary program. This is the task that we will solve in this question. Our goal will be to create an array of bytes called **dependent** where each byte corresponds to one instruction in the program¹. Initially this array of bytes is already allocated, there is one byte for each instruction in the program, and the value of all the bytes is zero. After our functions are executed, the bytes that correspond to the immediate use of the value of a load instruction will contain the value OxFF.

In an actual binary optimizer we would have to analyze all instructions that use a register value. However, to simplify this question we will only look for loads that are immediately followed by R type instructions, also known as ALU instructions.

The binary for the program is already stored in memory with one word corresponding to each instruction. The end of the program is signalled by a sentinel value <code>0xFFFFFFFF</code>. You are asked to write the RISC-V assembly code for two functions: <code>Decode</code> and <code>LoadUse</code>. In both functions you must follow all the RISC-V register save/restore conventions.

The opcode for all types of load instruction is 0000011. The opcode for all ALU (R-type) instructions is 0110011. Load instructions are I-type instructions and ALU instructions are R-type instructions. The core instruction formats for RISC-V are shown in Figure ??.

31	27	26	25	24	20	19		15	14	12	11	7	6		0	
funct7			rs2		rs1		funct3		rd		opcode		R-type			
imm[11:0]				rs1			funct3		rd		opcode		I-type			
iı	imm[11:5] rs2		2	rs1		fun	ct3	imm[4:0]		opcode		S-type				
im	imm[12 10:5] rs2		rs1		fun	ct3	imm[4:1 11]		op	code		B-type				
	imm[31:12]										rd	op	code		U-type	
imm[20 10:1 11 19:12]										rd	op	code		J-type		

Figure 1: RISC-V Core Instruction Formats.

¹In a real compiler a bit vector is typically used for this purpose with one bit corresponding to each instruction. This question is using a whole byte to represent the immediate-use condition for each instruction to make the programming simpler.

1. (10 points) The function Decode has the following specification:

parameters:

• a0: binary representation of a single RISC-V assembly instruction

return value:

- a0:
 - 0: if it is a load instruction
 - 1: if it is an ALU instruction, also known as an R-type instruction
 - -1: if it is neither a load nor an ALU instruction
- a1:
 - if it is a load instruction: five bits specifying rd register in the five least-significant bits of a1. All other bits of a1 are zero.
 - if it is an ALU instruction: five bits specifying rs1 in the five least-significant bits of a1. All other bits of a1 are zero.
 - if it is another type of instruction: the value of a1 is does not matter
- a2:
 - if it is a load instruction: the value of a2 does not matter
 - if it is an ALU instruction: five bits specifying rs2 in the five least-significant bits of a2. All other bits of a2 are zero.
 - if it is another type of instruction: the value of a2 is does not matter
- 2. (20 points) Now you will write the LoadUse function that receives as parameters two memory addresses:
 - the address of the first instruction in a RISC-V assembly program; and
 - the address of the first byte of a preallocated array of bytes, called dependent, that already contains the value zero in each byte.

LoadUse analyzes the binary RISC-V assembly program and writes the value 0xFF in each byte of dependent whose position corresponds to an ALU instruction that uses the value of a register that was obtained by an immediate predecessor load instruction. Figure ?? provides an example illustrating the values that will be produced in the dependent array for a given RISC-V program. Your solution must be general and must work for any RISC-V program.

The function LoadUse must call the function Decode to decode each instruction and find out if it is an instruction of interest. The specification of LoadUse is as follows:

parameters:

- a0: address of the first instruction of a RISC-V Assembly Program
- a1: address of first element of the dependent array

return value: None

Binary Code	RISC-V Assembly	dependent array
0x00050283	lb t0, 0(a0)	0x00
0x00058303	lb t1, 0(a1)	0x00
0x00628e33	add t3, t0, t1	0xFF
0x00060383	lb t2, 0(a2)	0x00
0x006e7eb3	and t4, t3, t1	0x00
0x0006af03	lw t5, 0(a3)	0x00
0x01eeffb3	and t6, t4, t5	0xFF
0xfe0f06e3	beq t5, zero <label></label>	0x00
0xFFFFFFF	<pre># sentinel value</pre>	

Figure 2: Example illustrating the values to be returned in the dependent array.

$\operatorname{RISC-V}$ code for Decode

Draft RISC-V code for LoadUse