	dest-cpu	×64	ia32	x64	ia32	x64	ia32	arm	any	x64
config arch	dest-os	linux	linux	mac	mac	win	win	linux	linux,mac,others	win
Category	defines/arch in openssl	linux-x86_64	linux-elf	darwin64− x86_64−cc	darwin−i386 −cc	VC-WIN64A	VC-WIN32	linux-armv4	no-asm	VC-WIN64A VC-WIN32 no-asm
Endian	-DL_ENDIAN	0	0	0	0	0	0	0	0	
Thread	-DOPENSSL_THREADS	0	0	0	0	0	0	0	0	
1111000	-D_REENTRANT	0	0	0	0	×	×	0	0	
DSO	-DHAVE_DLFCN_H	0	0	0	0	×	X	0	0	
	-DDSO_DLFCN	0	0	0	0	×	×	0	0	
	-DOPENSSL_CPUID_OBJ -DSHA512 ASM	0	0	0	0	0	0	0	×	
	-DSHA256 ASM	0	00	0	Ö	Ö	0	0	×	
ASM	-DSHA1_ASM	Ö	0	Ö	Ö	Ö	Ö	Ö	×	
	-DOPENSSL BN ASM MONT	Ö	Ö	Ö	Ö	Ö	Ö	Ö	×	
	-DOPENSSL_BN_ASM_GF2m	0	0	0	0	0	0	0	×	
	-DGHASH_ASM	0	0	0	0	0	0	0	×	
	-DAES_ASM	0	0	0	0	0	0	0	×	
	-DWHIRLPOOL_ASM	0	0	0	0	0	0	×	×	
	-DVPAES_ASM	0	0	0	0	0	0	×	×	
	-DOPENSSL_IA32_SSE2	0	0	0	0	0	0	×	×	
	-DMD5_ASM -DBSAES ASM	0	O ×	0	O ×	0	0 ×	X O	×	
	-DBSAES_ASM -DOPENSSL BN ASM MONT5	0	×	0	×	0	×	×	×	
	-DECP_NISTZ256_ASM	0	×	0	×	Ö	×	×	×	
	-DRMD160 ASM	×	0	×	0	×	0	×	×	
	-DOPENSSL BN ASM PART WORDS	×	0	×	Ö	×	0	×	×	
	-DCPUID_ASM	×	×	×	×	×	×	×	×	
	-DBN_ASM	×	×	×	×	×	×	×	×]
	-DBF_ASM	×	×	×	×	×	×	×	×	Not supported in vcbuild.bat
	-DBNCO_ASM	×	×	×	×	×	×	×	×	
	-DDES_ASM	×	×	X	×	×	X	×	×	
	-DLIB_BN_ASM	×	×	X	×	×	X	×	×	
	-DOPENSSL_BN_ASM -DRIP_ASM	×	×	×	×	×	×	×	×	
	-DWP ASM	×	×	×	×	×	×	×	×	
	-DOPENSSL NO ASM	×	×	×	×	×	×	×	Ô	
termios	-DTERMIOS	0	0	×	×	×	×	0	Ö	
WIN	-D_CRT_SECURE_NO_DEPRECATE	×	×	×	×	0	0	×	×]
	-DWIN32_LEAN_AND_MEAN	×	×	×	×	0	0	×	×]
	-DOPENSSL_SYSNAME_WIN32	×	×	×	×	0	0	×	×	
	-DDSO_WIN32	×	×	×	×	0	0	×	×	
	-DMK1MF_BUILD	×	×	X	×	×	X	×	×	
WIN64	-D_UNICODE	×	×	X	×	0	X	×	×	-
iojs customized	-DUNICODE -DPURIFY	× O	×	×	×	0	X O	X O	× O	
	-DENGINESDIR	/dev/null	/dev/null	/dev/null	/dev/null	×	×	/dev/null	/dev/null	
	-DOPENSSLDIR	/etc/ssl	/etc/ssl	/System/Library/OpenSSL/	/System/Library/OpenSSL/	×	×	/etc/ssl	/etc/ssl or	
									/System/Library/OpenSSL/	
	-DOPENSSL_NO_SSL2 -DOPENSSL_NO_SSL3	0	00	0	0	0	0	0	0	
	-DOPENSSL_NO_SSL3 -DOPENSSL_NO_HEARTBEATS	0	0	0	0	0	0	0	0	1
				darwin64-	darwin-i386			i i	1	1
	other cflags	linux-x86_64	linux-elf	x86_64-cc	-cc	VC-WIN64A	VC-WIN32	linux-armv4	no-asm	4
optimize	-O3	0	0	0	0	×	X	0	0	1
warning	-Wall	00	00	0	00	×	×	0	0	-
	-Wno-old-style-declaration -arch x86_64	×	×	0	×	×	×	×	×	
	−arch i386	×	×	×	Ô	×	×	×	×	
used in opnssl for WIN	-nologo	×	×	×	×	• • • • • • • • • • • • • • • • • • • •	1	×	×	1
	/Ox	×	×	×	×	Not explicitly specified. Followed by vcbuld.bat	Not explicitly specified. Followed by vcbuld.bat	×	×	
	/MD	×	×	×	×			×	×	
	-W3	×	×	×	×			×	×	
	−Gy	×	×	×	×			×	×	
	-Gs0	×	×	×	×			×	×	
used in	/Ob2	×	×	×	×			×	×	
openssl	/02	×	×	X	×			×	×	
for WIN32	−GF	×	×	×	×			×	×	