

Adding Video Effects

ICT 412 – Audio and Video Editing Technology
By VPG Priyankara
Lecturer (Prob.) in ICT
gihanpri@ssl.sab.ac.lk



Working with video effects



- You already know how to apply effects and change their settings.
- You can drag a video effect onto a clip, as you have already done with effects, or you can select the clip (or multiple clips) and double-click the effect in the Effects panel.
- You can combine as many effects as you want on a single clip, which can produce surprising results.
- You can use an adjustment layer to add effects to a collection of clips.

Working with video effects



- When it comes to deciding which video effects to use, the number of choices in Premiere Pro can be a little overwhelming.
- Plus, many additional effects are available from third-party manufacturers for sale or free of charge.
- Although the range of effects and their controls can be complex, the techniques you'll use to apply, adjust, and remove effects are straightforward and consistent.

Modifying fixed effects



- When you add a clip to a sequence, it will automatically have a few effects applied.
- These effects are called fixed effects, or intrinsic effects, and you can think of them as controls for the usual geometric, opacity, speed, and audio properties that every clip should have.
- Although fixed effects are applied automatically, they don't change the appearance of clips until you modify their settings. The effects include:

Modifying fixed effects



- **Motion:** The Motion effect allows you to animate, rotate, and scale a clip. You can also use the Anti-flicker Filter control to decrease shimmering edges for an animated object. This comes in handy when you scale down a high-resolution or interlaced source and Premiere Pro must resample the image.
- **Opacity:** The Opacity effect lets you control how opaque or transparent a clip is. You can also access special blend modes to create visual effects from multiple layers of graphics or video.

Modifying fixed effects



- **Time Remapping:** This effect lets you slow down, speed up, or reverse playback, and it even lets you freeze a frame. Think of it as a more advanced version of the Clip Speed/Duration options in the Timeline panel. In fact, the two controls are linked.
- **Audio Effects:** If a clip has audio, Premiere Pro displays its Volume, Channel Volume, and Panner controls.

Navigating the Effects panel




- In addition to the fixed video effects, Premiere Pro has standard effects that change a clip's appearance.
- Because there are so many to choose from, effects are organized into categories such as Distort, Keying, and Time, so you can more easily navigate them.
- If you install third-party effects, you will have even more choices

Effect types




- If you are working on a smaller computer monitor, some additional useful icons may be hidden in the Effects panel.
- If necessary, resize the Effects panel until you can see all of the Effect Type buttons next to the search box.



Effect types



- If you widen the Effects panel a little more, you'll notice icons next to many of the effect names (you may need to resize the Effects panel to see the icons).
- Understanding these icons should influence your choices when working with effects. Only some effects have all three icons.
- Click the effect type buttons at the top of the Effects panel to display only effects with those features.



Accelerated effects



- The Accelerated Effect icon indicates that the effect can be accelerated by your graphics processing unit (GPU).
- The GPU (often called the video card or graphics card) can greatly enhance the performance of Premiere Pro.
- The range of cards supported by the Mercury Playback Engine is broad, and with the right card installed, these effects offer accelerated or even real-time performance and need rendering only on final export (which is also hardware accelerated).
- You'll find a list of recommended cards on the Premiere Pro product page.

32-bit color (high-bit-depth) effects



- Effects with the 32-Bit Color icon can be processed in 32 bits per channel (sometimes called high-bit-depth or float processing).
- For maximum quality, use 32-bit color effects.
- If you are editing without GPU acceleration, in Software mode, Premiere Pro will render effects in 8-bit color by default.
- To take advantage of 32-bit color effects, make sure your sequence settings have the Maximum Bit Depth video-rendering option selected.
- If your project is set to use a hardware-accelerated renderer (in the Project settings), supported accelerated effects will automatically be rendered in 32-bit.

YUV effects



- Effects with the YUV icon process color in YUV (processed in Premiere Pro as Luminance, Color-Blue, Color-Red channels).
- This is particularly important if you're applying color adjustments.
- Effects with the YUV icon process color in YUV color mode.
- YUV effects break down the video into a Y (or luminance) channel and two channels for color information, which is how most video footage is structured natively.
- Because the brightness of the image is separate from the colors, it's easy to adjust contrast and exposure without shifting the colors.
- Effects without the YUV icon are processed in the computer's native RGB space, which might make adjusting exposure and color less accurate.

Activity – Apply Effect



- Download a video clip with motion.
- Search for white in effect panel and find the black and white effect.
- Apply the effect by dragging and dropping.
- Search for directional blur in effects panel again and apply the effect.
- In the Effect Controls panel, expand the Directional Blur effect's controls.
- Set Direction to 75.0 degrees and Blur Length to 45 and see what happen.

Activity – Apply Effect



- It's an interesting result, but now it's impossible to tell what's going on in the image.
- This might work well if you were simulating a very fast pan effect (a so-called whip pan), but let's tone down the intensity.
- Click the disclosure triangle to expand the Blur Length control, and move the slider to reduce the strength of the effect
- As you change the setting, the result is displayed in the Program Monitor.

Activity – Apply Effect



- Click the panel menu (Hamburger menu) for the Effect Controls panel, and choose Remove Effects.
- The Remove Attributes dialog box opens.
- The Remove Attributes dialog box lets you select which effects to remove and deselect which effects you want to keep.
- By default, everything is selected.
- You want to remove them all, so click OK.
- This is an easy way to start fresh.

Effects



- Premiere Pro processes effects in a particular order, which can lead to unwanted scaling or resizing.
- You can't reorder fixed effects, but you can bypass them and use other, similar effects.
- For example, you can use the Transform effect to achieve similar results to the Motion effect, or you can use the Alpha Adjust effect instead of the Opacity effect.
- These effects are not identical, but they're a close match, they behave similarly, and they can be placed in any order you choose.

Using adjustment layers



- Adjustment layers offer a convenient way to apply effects to multiple clips.
- The concept is straightforward: Create an adjustment layer clip that can hold effects, and position it above other clips on the timeline, on a higher video track.
- Everything beneath the adjustment layer clip is viewed through it, receiving any effects it contains.
- You can easily adjust the duration and opacity of an adjustment layer clip, as you would adjust any graphics clip, making it easy to control which other clips on lower tracks are seen through it.
- An adjustment layer makes it faster to work with effects because you can change the settings on the layer (a single item) to influence the appearance of several other clips.

Activity



- Create a new sequence and add some effects. Make sure you have multiple clips.
- At the bottom right of the Project panel, click the New Item button, and choose Adjustment Layer.
- You may need to resize the Project panel to see the New Item button .
- The Adjustment Layer dialog box allows you to specify settings for the new item you're creating.
- The settings in the dialog box will reflect the settings in the current sequence.



Adjustment Layer

Video Settings

Width: 720

Height: 405

Timebase: 23.976 fps

Pixel Aspect Ratio: Square Pixels (1.0)

Cancel

OK

Activity



- Click OK. Premiere Pro adds a new adjustment layer to the Project panel.
- Drag the adjustment layer from the Project panel to the beginning of the track in the Timeline panel.
- Click the right edge of the adjustment layer clip in the Timeline panel to select just the Out point.
- A red trim handle icon appears on the end of the clip.
- Next, position the playhead at the end of the sequence, just after the last clip.
- You can achieve this quickly by pressing the End key.
- Now press E to perform an Extend edit. This extends the selected trim handle to the location of the playhead.

Activity



- Now that the adjustment layer is in place, let's apply an effect to it.
- Once the effect is set up, you can change the adjustment layer's opacity to alter the intensity of the effect.
- In the Effects panel, search for and locate the Gaussian Blur effect.
- Drag the effect onto the adjustment layer clip in the sequence.
- Move the timeline playhead to have a good shot to use when designing the effect.
- Audiences pay particular attention to the eyes of your subjects, so it can be helpful to use a reference when applying effects.

Activity



- By default, the Gaussian Blur effect doesn't change the image.
- Make sure the adjustment layer clip is selected.
- In the Effect Controls panel, set Blurriness to a high value, around 25.0. Make sure Repeat Edge Pixels is selected to apply the effect evenly.
- The effect is too strong.
- Let's blend the adjustment layer with the clips beneath it using a blend mode to create a film look.
- Blend modes let you mix two layers together based on their brightness and color values.

Masking and tracking video effects



- All standard video effects can be constrained within elliptical, polygon, or custom masks, which you can manually animate using keyframes.
- These masks can motion track your shots to animate their position, following the action with the constrained special effect.
- Masking and tracking effects are great ways to hide a detail like a face or logo behind a blur.
- You can also use the technique to apply subtle creative effects or modify the lighting in a shot.

Activity



- Download a cinematic type of a clip with persons upper body focused and make a sequence.
- Position the playhead over the first frame of the clip in the sequence.
- We will add a stronger light on the subject to help separate the foreground from the background.
- Search the Effects panel for the Brightness & Contrast effect and Apply this effect to the clip.
- In the Effect Controls panel, scroll down to the Brightness & Contrast controls.
- Add suitable brightness and contrast where the subject looks lightened.
- This effect changes the entire picture. You're going to constrain the effect to just one area of the shot.
- Just under the name of the Brightness & Contrast effect in the Effect Controls panel, you'll see three buttons that allow you to add a mask to the effect.

Activity



- Click the first button to add an elliptical mask.
- A mask is added to the Brightness & Contrast effect in the Effect Controls panel and, in the Program Monitor, the effect is constrained to the new mask region.
- You can add multiple masks to an effect. If you select a mask in the Effect Controls panel, you can click and modify the shape in the Program Monitor.
- Make sure the playhead is at the start of the clip, and use the mask control points (the small squares on the mask shape) in the Program Monitor to reshape the mask so it covers the subject's face and hair.
- You may find it helpful to adjust the Zoom level for the Program Monitor to see beyond the edges of the image.

Activity



- If you deselect the mask, the controls will disappear in the Program Monitor—in the Effect Controls panel, select the name of the mask, Mask (1), to display the controls again.
- Feathering softens the edge of the mask. In the Effect Controls panel, set Mask Feather to 240
- You have brightened the area around the subject's face, with a natural return to regular lighting in the rest of the picture.
- Now you just need the mask to follow the moving video.

Activity



- In the Effect Controls panel, to the right of the Mask Path item, there are several mask-tracking controls. 
- Click the Track Selected Mask Forward button .
- Premiere Pro tracks the contents of the clip to reposition and resize the mask to continue covering the subject's face as it moves in the frame.
- If the movement is quite subtle, so it's easy for Premiere Pro to follow the action.
- Scrub the Effect Controls panel playhead to see the movement of the mask.
- Deselect the mask by clicking away from the mask name in the Effect Controls panel or by clicking an empty track in the Timeline panel.
- The mask handles in the Program Monitor will be removed.

Keyframing effects



- Create a sequence with waterfall clip. Make sure the clip is not zoom in and out too much.
- View the sequence to get familiar with the footage, and then position the Timeline playhead over the first frame of the clip.
- In the Effects panel, locate the Lens Flare effect and apply it to the clip in the sequence.
- This is not a subtle effect, but it illustrates Motion keyframes beautifully.
- In the Effect Controls panel, select the Lens Flare effect heading.
- With the effect selected, the Program Monitor displays a small control handle. Use the handle to reposition the lens flare to match the following figure so that the center of the effect is near the top of the waterfall.

Keyframing effects



- Click the stopwatch icons to toggle animation on for the Flare Center and Flare Brightness properties.
- Clicking the stopwatch icon enables keyframing and adds a keyframe at the current location with the current settings.
- Move the playhead to the last frame of the clip.
- To do this, you can drag the playhead directly in the Effect Controls panel.
- Make sure you see the last frame of video and not black (which would be the first frame of the next clip if there were one).
- Adjust Flare Center and Flare Brightness settings so the flare drifts across the screen with the camera pan and gets brighter.
- With the Lens Flare effect selected in the Effect Controls panel, you can drag the lens flare center to a new position directly in the Program Monitor.
- Deselect the Lens Flare effect to hide the controls in the Program Monitor, and play the sequence to watch the effect animate over time.
- You may need to render the sequence for full-frame-rate playback, by choosing Sequence > Render Effects In To Out.

Saving effect presets



- Although there are several built-in effect presets to choose from, you can easily create your own.
- You can also import and export presets to share them between editing systems.

Activity



- Clear the sequence.
- Insert a clip to the sequence and add effects and customize it with keyframes.
- After that, select all the effect with Ctrl key.
- Right click on that selection and choose Save Preset.
- When you apply an animated preset to a clip with a different duration, Premiere Pro needs to know how to distribute the keyframes.
- There are three options.
- Scale: Scales the original preset keyframes to the duration of the new clip proportionally.
- Anchor To In Point: Preserves the position of the first keyframe as well as the relationship of other keyframes in a clip relative to its In point.
- Anchor To Out Point: Preserves the position of the last keyframe as well as the relationship of other keyframes in a clip relative to its Out point.

Activity



- For this preset, select Anchor To In Point so the timing matches at the start of each clip the preset is applied to.
- Click OK to store the effects and keyframes as a new preset.
- In the Effects panel, locate the Presets category and your newly created preset.
- Hover the pointer over the preset to see the description you added appear as a tool tip.
- Add a new clip and drag the effect you created to that clip.
- See in the effect panel that the effects you saved applied.

Use an adjustment layer with the Clip Name effect



- If you intend to send a review copy of a sequence to a client or colleague, you can apply the Clip Name effect to an adjustment layer and have it generate visible clip names for the entire sequence.
- This is helpful because it allows others to give feedback based on a particular clip. You can control the clip name format position, size, and opacity.
- You can enable a similar timecode overlay when exporting media, but the sequence clip effect has more options.

Activity



- Make a sequence with 05 clips.
- At the bottom right of the Project panel, click the New Item button, and choose Adjustment Layer from the menu.
- Click OK in the Adjustment Layer dialog box.
- In the Effects panel, search for the Clip Name effect.
- Apply the Clip Name effect to the adjustment layer clip
- By default, the effect shows the name of the clip you applied it to, which in this case is Adjustment Layer—not very useful!
- In the Effect Controls panel, in the Clip Name effect controls, choose Video 1 from the Source Track menu, and set the size to 25%.
- Now the clip names from the V1 track are displayed.

Rendering all sequences



- If you have several sequences with effects you want to render, you can render them all as a batch, without opening each sequence to render it individually.
- Select the sequences you would like to render in the Project panel, and choose Sequence > Render Effects In To Out.
- All effects that need to render in the selected sequences will be rendered.



THE END