Floating Point

Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

Fractional binary numbers

- **What is 1011.101_2?**

Fractional Binary Numbers



- **Representation**
  - Bits to right of "binary point" represent fractional powers of 2
  - Represents rational number: $\sum_{k=-j}^{i} b_k \times 2^k$

Fractional Binary Numbers: Examples

Value	**Representation**
5 3/4	`101.11`$_2$
2 7/8	`10.111`$_2$
1 7/16	`1.0111`$_2$

- **Observations**
  - Divide by 2 by shifting right (unsigned)
  - Multiply by 2 by shifting left
  - Numbers of form 0.111111…$_2$ are just below 1.0
    - 1/2 + 1/4 + 1/8 + … + $1/2^i$ + … ➞ 1.0
    - Use notation 1.0 – ε

Representable Numbers

- **Limitation #1**
  - Can only exactly represent numbers of the form $x/2^k$
    - Other rational numbers have repeating bit representations
    - Value Representation
    - 1/3 `0.0101010101[01]`…$_2$
    - 1/5 `0.001100110011[0011]`…$_2$
    - 1/10 `0.0001100110011[0011]`…$_2$
- **Limitation #2**
  - Just one setting of binary point within the *w* bits
    - Limited range of numbers (very small values? very large?)

Today: Floating Point

- Background: Fractional binary numbers
- **IEEE floating point standard: Definition**
- Example and properties
- Rounding, addition, multiplication
- Floating point in C
- Summary

IEEE Floating Point

- **IEEE Standard 754**
  - Established in 1985 as uniform standard for floating point arithmetic
    - Before that, many idiosyncratic formats
  - Supported by all major CPUs

- **Driven by numerical concerns**
  - Nice standards for rounding, overflow, underflow
  - Hard to make fast in hardware
    - Numerical analysts predominated over hardware designers in defining standard

Floating Point Representation

- **Numerical Form:**

$$(-1)^s\, M\ 2^E$$

  - **Sign bit *s*** determines whether number is negative or positive
  - **Significand *M*** normally a fractional value in range [1.0,2.0).
  - **Exponent *E*** weights value by power of two

- **Encoding**
  - MSB s is sign bit *s*
  - exp field encodes *E* (but is not equal to E)
  - frac field encodes *M* (but is not equal to M)

s	exp	frac

Precision options

- **Single precision: 32 bits**

s	exp	frac
1	8-bits	23-bits

- **Double precision: 64 bits**

s	exp	frac
1	11-bits	52-bits

- **Extended precision: 80 bits (Intel only)**

s	exp	frac
1	15-bits	63 or 64-bits

"Normalized" Values

$v = (-1)^s\, M\, 2^E$

- **When: exp ≠ 000…0 and exp ≠ 111…1**

- **Exponent coded as a *biased* value: $E = Exp - Bias$**
  - *Exp*: unsigned value of exp field
  - *Bias* = $2^{k-1} - 1$, where *k* is number of exponent bits
    - Single precision: 127 (Exp: 1…254, E: -126…127)
    - Double precision: 1023 (Exp: 1…2046, E: -1022…1023)

- **Significand coded with implied leading 1: $M = 1.xxx…x_2$**
  - xxx…x: bits of frac field
  - Minimum when frac=000…0 (M = 1.0)
  - Maximum when frac=111…1 (M = 2.0 – ε)
  - Get extra leading bit for "free"

Normalized Encoding Example

$v = (-1)^s\, M\, 2^E$
$E = Exp - Bias$

- **Value:** `float F = 15213.0;`
  - $15213_{10} = 11101101101101_2$
    $= 1.1101101101101_2 \times 2^{13}$

- **Significand**
  - *M* = `1.`$\underline{\texttt{1101101101101}}_2$
  - `frac=` $\underline{\texttt{1101101101101}}\texttt{0000000000}_2$

- **Exponent**
  - *E* = 13
  - *Bias* = 127
  - *Exp* = 140 = `10001100`$_2$

- **Result:**

0	10001100	11011011011010000000000
s	exp	frac

Denormalized Values

$v = (-1)^s\, M\, 2^E$
$E = 1 - Bias$

- **Condition: exp = 000…0**

- **Exponent value: $E = 1 - \text{Bias}$ (instead of $E = 0 - Bias$)**
- **Significand coded with implied leading 0: $M = 0.xxx\ldots x_2$**
  - `xxx…x`: bits of `frac`
- **Cases**
  - `exp` = 000…0, `frac` = 000…0
    - Represents zero value
    - Note distinct values: +0 and –0
  - `exp` = 000…0, `frac` ≠ 000…0
    - Numbers closest to 0.0
    - Equispaced

Special Values

- **Condition: `exp` = `111…1`**

- **Case: `exp` = `111…1`, `frac` = `000…0`**
  - Represents value ∞ (infinity)
  - Operation that overflows
  - Both positive and negative
  - E.g., 1.0/0.0 = −1.0/−0.0 = +∞, 1.0/−0.0 = −∞

- **Case: `exp` = `111…1`, `frac` ≠ `000…0`**
  - Not-a-Number (NaN)
  - Represents case when no numeric value can be determined
  - E.g., sqrt(–1), ∞ − ∞, ∞ × 0

Visualization: Floating Point Encodings



Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- **Example and properties**
- Rounding, addition, multiplication
- Floating point in C
- Summary

Tiny Floating Point Example

s	exp	frac
1	4-bits	3-bits

- **8-bit Floating Point Representation**
  - the sign bit is in the most significant bit
  - the next four bits are the exponent, with a bias of 7
  - the last three bits are the `frac`

- **Same general form as IEEE Format**
  - normalized, denormalized
  - representation of 0, NaN, infinity

Dynamic Range (Positive Only)

$v = (-1)^s\, M\, 2^E$
n: E = Exp – Bias
d: E = 1 – Bias

	s exp frac	E	Value	
	0 0000 000	-6	0	
	0 0000 001	-6	1/8*1/64 = 1/512	closest to zero
Denormalized numbers	0 0000 010	-6	2/8*1/64 = 2/512	
	…			
	0 0000 110	-6	6/8*1/64 = 6/512	
	0 0000 111	-6	7/8*1/64 = 7/512	largest denorm
	0 0001 000	-6	8/8*1/64 = 8/512	smallest norm
	0 0001 001	-6	9/8*1/64 = 9/512	
	…			
	0 0110 110	-1	14/8*1/2 = 14/16	
	0 0110 111	-1	15/8*1/2 = 15/16	closest to 1 below
Normalized numbers	0 0111 000	0	8/8*1 = 1	
	0 0111 001	0	9/8*1 = 9/8	closest to 1 above
	0 0111 010	0	10/8*1 = 10/8	
	…			
	0 1110 110	7	14/8*128 = 224	
	0 1110 111	7	15/8*128 = 240	largest norm
	0 1111 000	n/a	inf	

Distribution of Values

- **6-bit IEEE-like format**
  - e = 3 exponent bits
  - f = 2 fraction bits
  - Bias is $2^{3-1}-1 = 3$

s	exp	frac
1	3-bits	2-bits

- **Notice how the distribution gets denser toward zero.**



Distribution of Values (close-up view)

- **6-bit IEEE-like format**
  - e = 3 exponent bits
  - f = 2 fraction bits
  - Bias is 3

s	exp	frac
1	3-bits	2-bits



Special Properties of the IEEE Encoding

- **FP Zero Same as Integer Zero**
  - All bits = 0
- **Can (Almost) Use Unsigned Integer Comparison**
  - Must first compare sign bits
  - Must consider −0 = 0
  - NaNs problematic
    - Will be greater than any other values
    - What should comparison yield?
  - Otherwise OK
    - Denorm vs. normalized
    - Normalized vs. infinity

Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- **Rounding, addition, multiplication**
- Floating point in C
- Summary

Floating Point Operations: Basic Idea

- `x +f y = Round(x + y)`
- `x ×f y = Round(x × y)`
- **Basic idea**
  - First compute exact result
  - Make it fit into desired precision
    - Possibly overflow if exponent too large
    - Possibly round to fit into `frac`

Rounding

- **Rounding Modes (illustrate with $ rounding)**

	$1.40	$1.60	$1.50	$2.50	–$1.50
Towards zero	$1	$1	$1	$2	–$1
Round down (−∞)	$1	$1	$1	$2	–$2
Round up (+∞)	$2	$2	$2	$3	–$1
Nearest Even (default)	$1	$2	$2	$2	–$2

Closer Look at Round-To-Even

- **Default Rounding Mode**
  - Hard to get any other kind without dropping into assembly
  - All others are statistically biased
    - Sum of set of positive numbers will consistently be over- or under-estimated
- **Applying to Other Decimal Places / Bit Positions**
  - When exactly halfway between two possible values
    - Round so that least significant digit is even
  - E.g., round to nearest hundredth

7.8949999	7.89	(Less than half way)
7.8950001	7.90	(Greater than half way)
7.8950000	7.90	(Half way—round up)
7.8850000	7.88	(Half way—round down)

Rounding Binary Numbers

- **Binary Fractional Numbers**
  - "Even" when least significant bit is `0`
  - "Half way" when bits to right of rounding position = $100\ldots_2$
- **Examples**
  - Round to nearest 1/4 (2 bits right of binary point)

Value	Binary	Rounded	Action	Rounded Value
2 3/32	10.00011_2	10.00_2	(<1/2—down)	2
2 3/16	10.00110_2	10.01_2	(>1/2—up)	2 1/4
2 7/8	10.11100_2	11.00_2	(1/2—up)	3
2 5/8	10.10100_2	10.10_2	(1/2—down)	2 1/2

FP Multiplication

- $(-1)^{s1}\ M1\ \ 2^{E1}\ \ \times\ \ (-1)^{s2}\ M2\ \ 2^{E2}$
- **Exact Result:** $(-1)^{s}\ M\ \ 2^{E}$
  - Sign *s*: $s1 \wedge s2$
  - Significand *M*: $M1 \times M2$
  - Exponent *E*: $E1 + E2$
- **Fixing**
  - If $M \geq 2$, shift *M* right, increment *E*
  - If *E* out of range, overflow
  - Round *M* to fit `frac` precision
- **Implementation**
  - Biggest chore is multiplying significands

Floating Point Addition

- $(-1)^{s1}\ M1\ \ 2^{E1}\ \ +\ \ (-1)^{s2}\ M2\ \ 2^{E2}$
  - Assume $E1 > E2$
- **Exact Result:** $(-1)^{s}\ M\ \ 2^{E}$
  - Sign *s*, significand *M*:
    - Result of signed align & add
  - Exponent *E*: $E1$



- **Fixing**
  - If $M \geq 2$, shift *M* right, increment *E*
  - if $M < 1$, shift *M* left *k* positions, decrement *E* by *k*
  - Overflow if *E* out of range
  - Round *M* to fit `frac` precision

Today: Floating Point

- Background: Fractional binary numbers
- IEEE floating point standard: Definition
- Example and properties
- Rounding, addition, multiplication
- **Floating point in C**
- Summary

Floating Point in C

- **C Guarantees Two Levels**
  - `float` single precision
  - `double` double precision
- **Conversions/Casting**
  - Casting between `int`, `float`, and `double` changes bit representation
  - `double`/`float` → `int`
    - Truncates fractional part
    - Like rounding toward zero
    - Not defined when out of range or NaN: Generally sets to TMin
  - `int` → `double`
    - Exact conversion, as long as `int` has ≤ 53 bit word size
  - `int` → `float`
    - Will round according to rounding mode

Floating Point Puzzles

- **For each of the following C expressions, either:**
  - Argue that it is true for all argument values
  - Explain why not true

```
int x = …;
float f = …;
double d = …;
```

Assume neither `d` nor `f` is NaN

- `x == (int)(float) x`
- `x == (int)(double) x`
- `f == (float)(double) f`
- `d == (double)(float) d`
- `f == -(-f);`
- `2/3 == 2/3.0`
- `d < 0.0` ⇒ `((d*2) < 0.0)`
- `d > f` ⇒ `-f > -d`
- `d * d >= 0.0`
- `(d+f)-d == f`

Summary

- **IEEE Floating Point has clear mathematical properties**
- **Represents numbers of form M x 2^E**
- **One can reason about operations independent of implementation**
  - As if computed with perfect precision and then rounded
- **Not the same as real arithmetic**
  - Violates associativity/distributivity
  - Makes life difficult for compilers & serious numerical applications programmers