Lab 3: Iterative phase estimation

The quantum phase estimation (QPE) algorithm is one of the most important and famous quantum algorithms. It is a key subroutine of Shor's factoring algorithm, as well as algorithms for quantum simulation. The textbook version of the algorithm uses a number of auxiliary qubits which scales with the desired precision, leading to circuits that are challenging to execute on today's noisy devices with limited qubit number and connectivity.

Iterative phase estimation (IPE) is a variant of QPE which requires only one auxiliary qubit. In IPE, the auxiliary qubit is repeatedly measured, with the measurement results used to guide future quantum operations. Until the introduction of dynamic circuits, such classical feed-forward was impossible to execute on IBM's quantum hardware.

In this lab, we will use the recently introduced dynamic circuits capabilities to implement IPE.

Background

Like any phase estimation algorithm, IPE is designed to solve the following problem:

Problem statement: Given a unitary matrix \$U\$ and an eigenstate \$|\Psi\rangle\$ of \$U\$ with an unknown eigenvalue \$e^{i 2\pi \varphi}\$, estimate the value of \$\varphi\$.

A few important details need to be clarified in this problem statement, namely, how \$U\$ and \$|\Psi\rangle\$ are specified. We assume that \$U\$ is given as a quantum circuit implementing \$U\$, and in fact, we assume we have the ability to efficiently implement the operations *controlled*-\$U^{2^t}\$ for positive integers \$t\$. This is the same assumption used in the original QPE algorithm. The eigenstate is also given as a quantum circuit: we assume we have the ability to efficiently prepare \$|\Psi\rangle\$.

Now, suppose that we initialize q_0 in the state $|+\rangle = \frac{10^{2}}$ and q_1 in the state $|-\rangle$. What happens if we apply the *controlled*- u^{2^t} gate, with q_0 being the control and q_1 being the target? Since $|-\rangle$ is an eigenstate of u with eigenvalue e^{i}

Now, note that \$ e^{i 2 \pi 2^{t} \varphi} = e^{i 2 \pi 2^{t} (0.\varphi_1 \varphi_2 \cdots \varphi_m)} = e^{i 2 \pi (\varphi_1 \cdots \varphi_t . \varphi_{t + 1} \cdots \varphi_m)} = e^{i 2 \pi (0. \varphi_{t + 1} \cdots \varphi_m)}, \$ where in the last equality, the whole number part of the "decimal" representation of the phase has disappeared because $e^{i 2 \pi t}$ for any integer n. For example:

- for \$t=0\$, the phase would be \$e^{i 2 \pi 2^{0} \varphi} = e^{i 2 \pi \varphi} = e^{i 2 \pi 0.\varphi_1 \varphi_2 ... \varphi_m}\$
- for \$t=1\$, the phase would be \$e^{i 2 \pi 2^{1} \varphi}= e^{i 2 \pi \varphi_1} e^{i 2 \pi 0.\varphi_2 \varphi_3 ... \varphi_m} = e^{i 2 \pi 0.\varphi_2 \varphi_3 ... \varphi_m}\$
- for \$t=2\$, the phase would be \$e^{i 2 \pi 2^{2} \varphi} = e^{i 2 \pi 0.\varphi_3 \varphi_4 ... \varphi_m}\$
- for \$t=m-1\$, the phase would be \$e^{i 2 \pi 2^{m-1} \varphi} = e^{i 2 \pi 0.\varphi_m}\$.

In the last case where t = m - 1, the phase is $e^{i 2 \pi 0.\varphi_m}$, which is equal to 1 if $\alpha 0$ and $\alpha 0$ and $\alpha 0$ if $\alpha 0$ would be in the state $\alpha 0$ and in the second case it would be in the state $\alpha 0$ and in the Pauli $\alpha 0$ success rate. This is done by performing a Hadamard gate on the qubit before measuring it. In the first case we would measure 0 and in the second case we would measure 1; in other words, the measured bit would be equal to $\alpha 0$ are in the second case we would measure 1; in other words, the measured bit would be equal to $\alpha 0$ and in the second case we would measure 1; in other words, the measured bit

The algorithm

In the first step of the IPE algorithm, we directly measure the least significant bit of the phase \$\varphi\$, \$\varphi_m\$, by initializing the 2-qubit registers as described above (\$q_0 \rightarrow |+\rangle\$ and \$q_1 \rightarrow |\Psi \rangle\$), performing a controlled-\$U^{2^{m-1}}\$ operation, and measuring \$q_0\$ in the Pauli \$X\$ basis.

in the second step, we initialize the systems in the same way and apply a controlled-\$U^{2^{m-2}}\$ operation. The relative phase in \$q_0\$ after these operations is now \$e^{i 2 \pi 0.\sqrt{m-1}\sqrt{m-1}} e^{i 2 \pi 0.\sqrt{m-1}}. To extract the phase bit \$\varphi_{m-1}\$, first perform a phase correction by rotating around the \$Z\$-axis by an angle \$-2 \pi \pi \varphi_m/4=-

\pi \varphi_m/2\$, which results in the state of q_0 \$ to be $|0\rangle = e^{i 2 \pi} 0.\$ 0.\varphi_{m-1}} | 1 \rangle\$. Perform a measurement on q_0 \$ in the Pauli \$X\$ basis to obtain the phase bit $\$

Therefore, the k-th step of the IPE, getting (m-k+1), consists of the register initialization (q_0 in $+\$ (q_1 in $+\$), the application of a *controlled*- q_1 in q_1 in q_2 of angle q_1 in the application of a *controlled*- q_1 in q_1 in the Pauli q_1 in the Pauli q_1 in the Pauli q_2 in the Pauli q_1 in the Computational basis. Note that q_1 remains in the state q_1 in the algorithm.

Implementation

In this lab, we will perform IPE on the single-qubit \$\$\$-gate. The \$\$\$ gate is given by the matrix

 $S = \left[\frac{pmatrix} 1 \& 0 \right] - 2 \right]$ will use the eigenstate $\left[\frac{pmatrix} \right] - 2 \right]$ which has eigenvalue $e^{i\pi i} / 2 = e^{i2\pi i \cdot 1/4}$. So we have $\pi i = 1/4 = 0.01 = 0.$ Varphi_1 \varphi_2\$. Since $\pi i = 1/4 = 0.01 = 0.$ Varphi\$ can be represented exactly with 2 bits, our quantum circuit implementation will use a classical register with two bits to store the result.

Step 1

In the first step of the algorithm, we measure the least significant bit of \$\varphi\$.

Exercise 1

Obtain the least significant bit of \$\varphi\$ by performing the following steps:


- 1. Initialize the qubits:
 - Apply a Hadamard on the auxiliary qubit.
 - Apply an X gate on the system qubit to put it in the \$|1\rangle\$ state.
- 2. Apply a *controlled*-\$\$^{2}\$ gate by applying a CPhaseGate with the appropriate angle.
- 3. Measure the auxiliary qubit in the \$X\$ basis:
 - Apply a Hadamard gate on the auxiliary qubit.
 - Measure it in the computational basis.

The resulting circuit should look something like this:

step1-circuit

```
from qiskit import ClassicalRegister, QuantumCircuit, QuantumRegister
import numpy as np
def step_1_circuit(qr: QuantumRegister, cr: ClassicalRegister) -> Quantum
    # gr is a quantum register with 2 qubits
    # cr is a classical register with 2 bits
    qc = QuantumCircuit(qr, cr)
    ###### your code goes here ######
    qc.h(qr[0])
    qc.x(qr[1])
    qc.cp(np.pi, qr[0],qr[1])
    qc.h(qr[0])
    qc.measure(qr[0], cr[0])
     return qc
qr = QuantumRegister(2, "q")
cr = ClassicalRegister(2, "c")
qc = QuantumCircuit(qr, cr)
qc = step_1_circuit(qr, cr)
qc.draw("mpl")
```

Out[3]:



```
In [5]: # Submit your circuit
from qc_grader.challenges.spring_2023 import grade_ex3a
grade_ex3a(qc)
Submitting your answer. Please wait...
Congratulations **! Your answer is correct and has been submitted.
```

Step 2

In the first step, we measured the least significant bit \$\varphi_2\$. In the second (and final) step, we extract the next bit \$\varphi_1\$, which will involve applying a phase correction to cancel out the phase contribution from \$\varphi_2\$. The phase correction depends on the value of the classical register holding \$\varphi_2\$. We need dynamic circuits to perform this classical feedback! The phase correction can

be applied using PhaseGate or by directly calling the p method of a QuantumCircuit.

Exercise 2

In this exercise, we begin with the circuit from Step 1, which you should have constructed in Exercise 1.

Obtain the next bit of \$\varphi\$ by performing the following steps:

- 1. Reset and re-initialize the auxiliary qubit.
- 2. Apply the controlled unitary gate.
- 3. Measure the auxiliary qubit in the \$X\$ basis.

The resulting circuit should look something like this:

step1-circuit

```
In [23]: def step_2_circuit(qr: QuantumRegister, cr: ClassicalRegister) -> Quantum
             # qr is a quantum register with 2 qubits
             # cr is a classical register with 2 bits
             # begin with the circuit from Step 1
             qc = step_1_circuit(qr, cr)
             ###### your code goes here ######
             qc.reset(qr[0])
             qc.h(qr[0])
             with qc.if_test((cr[0],1)):
                 qc.p(-np.pi/2, 0)
             qc.cp(np.pi/2, qr[1], qr[0])
             qc.h(qr[0])
             qc.measure(qr[0], cr[1])
             return qc
         qr = QuantumRegister(2, "q")
         cr = ClassicalRegister(2, "c")
         qc = QuantumCircuit(qr, cr)
         qc = step_2_circuit(qr, cr)
         qc.draw("mpl")
```

Out[23]:

```
q_0 — H — H — q_1 — q_1 — q_2 — q_3 — q_4 — q_5 — q_6 — q_6
```

```
In []: # Submit your circuit
from qc_grader.challenges.spring_2023 import grade_ex3b
```

```
grade_ex3b(qc)
```

Run on simulator

Now that we have the complete circuit, let's first run it on a local simulator.

```
In [6]: from qiskit_aer import AerSimulator

sim = AerSimulator()
job = sim.run(qc, shots=1000)
result = job.result()
counts = result.get_counts()
counts
```

```
Out[6]: {'01': 1000}
```

If your circuit is correct, you should have gotten the bitstring **01** with 100% probability. This value corresponds to the phase written in binary as \$\varphi = 0.01 = 1/4\$. Indeed, this is the correct phase!


Exercise 3

Construct an IPE circuit to estimate the phase of the T gate, whose matrix is given by

 $T = \left[\frac{1 \& 0\\ 0 \& e^{i\pi} / 4} \right]$ How many bits are needed to represent the phase in this case?

```
In [7]:
        from qiskit import ClassicalRegister, QuantumCircuit, QuantumRegister
        import numpy as np
        def t_gate_ipe_circuit(qr: QuantumRegister, cr: ClassicalRegister) -> QuantumRegister, cr: ClassicalRegister)
             # qr is a quantum register with 2 qubits
             # cr is a classical register with 3 bits
             qc = step_1_circuit(qr, cr)
             ###### your code goes here ######
             qc.reset(qr[0])
             qc.h(qr[0])
             with qc.if_test((cr[0],1)):
                 qc.p(-np.pi/2, 0)
             qc.cp(np.pi/2, qr[1], qr[0])
             qc.h(qr[0])
             qc.measure(qr[0], cr[1])
             return qc
        gr = QuantumRegister(2, "g")
        cr = ClassicalRegister(3, "c")
        qc = QuantumCircuit(qr, cr)
        qc = t_gate_ipe_circuit(qr, cr)
         qc.draw("mpl")
```

Out[7]:



```
In [8]: from qiskit_aer import AerSimulator

sim = AerSimulator()
job = sim.run(qc, shots=1000)
result = job.result()
counts = result.get_counts()
counts

Out[8]: {'001': 1000}

In [9]: # Submit your circuit
from qc_grader.challenges.spring_2023 import grade_ex3c
grade_ex3c(qc)
Submitting your answer. Please wait...
```

Congratulations 🔀! Your answer is correct and has been submitted.

When the phase does not have an exact binary expansion

Let's consider the case when the phase does not have an exact binary expansion, for example, \$\varphi = 1/3\$. In this case, the single-qubit gate has the unitary

```
$ U = \begin{pmatrix} 1 & 0\\ 0 & e^{i2\pi / 3} \end{pmatrix} $$ The angle \gamma = 1/3 does not have an exact finite binary expansion. In contrast, it has the infinite binary expansion
```

```
$$ 1/3 = 0.010101 | dots $$
```

In practice we work with a fixed number of bits of precision, so our goal is to obtain the closest value that can be represented with those bits. In the following example, we will use two bits of precision. In this case, the closest value is 0.01 = 1/4. Because this value does not represent the exact phase, there is some probability that we will obtain a different, less precise result.


In the following code cells, we construct and simulate an IPE circuit to measure the phase of this gate.

```
In [10]: from qiskit import ClassicalRegister, QuantumCircuit, QuantumRegister
import numpy as np
```

```
def u_circuit(qr: QuantumRegister, cr: ClassicalRegister) -> QuantumCircu
    # qr is a quantum register with 2 qubits
    # cr is a classical register with 2 bits
    qc = QuantumCircuit(qr, cr)
    # Initialization
    q0, q1 = qr
    qc.h(q0)
    qc.x(q1)
    # Apply control-U operator as many times as needed to get the least s
    u_angle = 2 * np.pi / 3
    k = 1
    cphase_angle = u_angle * 2**k
    qc.cp(cphase_angle, q0, q1)
    # Measure the auxiliary qubit in x-basis into the first classical bit
    qc.h(q0)
    c0, c1 = cr
    qc.measure(q0, c0)
    # Reset and re-initialize the auxiliary qubit
    qc.reset(q0)
    qc.h(q0)
    # Apply phase correction conditioned on the first classical bit
    with qc.if_test((c0, 1)):
        qc.p(-np.pi / 2, q0)
    # Apply control-U operator as many times as needed to get the next ph
    k = 0
    cphase_angle = u_angle * 2**k
    qc.cp(cphase_angle, q0, q1)
    # Measure the auxiliary qubit in x-basis into the second classical bi
    qc.h(q0)
    qc.measure(q0, c1)
    return qc
qr = QuantumRegister(2, "q")
cr = ClassicalRegister(2, "c")
qc = QuantumCircuit(qr, cr)
qc = u_circuit(qr, cr)
qc.draw("mpl")
```

Success probability: 0.72

Out[10]:



```
In [11]: from qiskit_aer import AerSimulator

sim = AerSimulator()
job = sim.run(qc, shots=1000)
result = job.result()
counts = result.get_counts()
print(counts)
success_probability = counts["01"] / counts.shots()
print(f"Success probability: {success_probability}")

{'11': 39, '00': 56, '10': 185, '01': 720}
```

As you can see, this time, we are not guaranteed to obtain the desired result. A natural question to ask is: How can we boost the success probability?

One way that the algorithm fails is that the first measured bit is incorrect. In this case, the phase correction applied before measuring the second bit is also incorrect, causing the rest of the bits to be likely incorrect as well. A simple way to mitigate this problem is to repeat the measurement of the first few bits several times and take a majority vote to increase the likelihood that we measure the bit correctly. Implementing this procedure within a single circuit requires performing arithmetic on the measured outcomes. Due to a temporary limitation in Qiskit, it is currently not possible to perform arithmetic on measured bits and condition future circuit operations on the results. So, here we will measure each bit using separate circuits.

The following code cells construct and simulate an IPE circuit for measuring just the first bit of the phase.

```
In [12]: from qiskit import ClassicalRegister, QuantumCircuit, QuantumRegister
import numpy as np

def u_circuit(qr: QuantumRegister, cr: ClassicalRegister) -> QuantumCircu
    # qr is a quantum register with 2 qubits
    # cr is a classical register with 1 bits

qc = QuantumCircuit(qr, cr)

# Initialization
q0, q1 = qr
qc.h(q0)
qc.x(q1)

# Apply control-U operator as many times as needed to get the least s
```


```
u_angle = 2 * np.pi / 3
k = 1
cphase_angle = u_angle * 2**k
qc.cp(cphase_angle, q0, q1)

# Measure the auxiliary qubit in x-basis
qc.h(q0)
(c0,) = cr
qc.measure(q0, c0)

return qc

qr = QuantumRegister(2, "q")
cr = ClassicalRegister(1, "c")
qc = QuantumCircuit(qr, cr)
qc = u_circuit(qr, cr)
qc.draw("mpl")
```

Out[12]:



```
In [13]: job = sim.run(qc, shots=15)
    result = job.result()
    counts = result.get_counts()
    print(counts)

{'0': 2, '1': 13}
```

Hopefully, the correct bit was measured more often than not.

Exercise 4

Examine the counts dictionary from the output of the last code cell. What is the correct value for the first bit? Was it measured more often than not? If not, rerun the last code cell until it is. Then, write some code in the code cell below that sets the variable step1_bit equal to the value of the bit that was measured the majority of the time.

```
In [15]: step1_bit: int

####### your code goes here ######

step1_bit = 1
print(step1_bit)
```

```
In [16]: # Submit your result
    from qc_grader.challenges.spring_2023 import grade_ex3d
    grade_ex3d(step1_bit)
```

Submitting your answer. Please wait...


Congratulations *! Your answer is correct and has been submitted.

Exercise 5

Now construct the circuit to measure the second bit of the phase. Replace the first stage of the circuit with one which simply sets the auxiliary bit to the value we measured above, so that we always measure the correct value for the first bit of the phase.

```
In [17]: from qiskit import ClassicalRegister, QuantumCircuit, QuantumRegister
         import numpy as np
         def u_circuit(qr: QuantumRegister, cr: ClassicalRegister) -> QuantumCircu
             # qr is a quantum register with 2 qubits
             # cr is a classical register with 2 bits
             qc = QuantumCircuit(qr, cr)
             ###### your code goes here ######
             qc.h(qr[0])
             qc.x(qr[1])
             qc.cp(np.pi, qr[0], qr[1])
             qc.h(qr[0])
             qc.measure(qr[0], cr[0])
             qc.reset(qr[0])
             qc.h(qr[0])
             with qc.if_test((cr[0],1)):
                 qc.p(-np.pi/3, 0)
             qc.cp(np.pi/2, qr[0], qr[1])
             qc.h(qr[0])
             qc.measure(qr[0], cr[1])
             return qc
         gr = QuantumRegister(2, "g")
         cr = ClassicalRegister(2, "c")
         qc = QuantumCircuit(qr, cr)
         qc = u_circuit(qr, cr)
         qc.draw("mpl")
```

Out[17]:



Now, the success probability is much higher than before!

Run on hardware

In the final part of this lab, we will run some circuits on real hardware! The code cells below initialize and run the circuit you created in Exercise 2 to measure the phase of the \$S\$ gate. Because current quantum hardware suffers from noise, the results will not be as good as what you got on the simulator. Feel free to try running the other circuits you created in this lab, though be aware that larger circuits, like the one from Exercise 3 for measuring the phase of the \$T\$ gate, will suffer from even more noise.

```
In [22]: from giskit import transpile
         qr = QuantumRegister(2, "q")
         cr = ClassicalRegister(2, "c")
         qc = QuantumCircuit(qr, cr)
         qc = step_2_circuit(qr, cr)
         qc_transpiled = transpile(qc, backend)
         Traceback (most recent call last):
           Cell In[22], line 6
             qc = step_2_circuit(qr, cr)
         NameError: name 'step_2_circuit' is not defined
         Use %tb to get the full traceback.
          Search for solution online
 In [ ]: job = backend.run(qc_transpiled, shots=1000, dynamic=True)
         job_id = job.job_id()
         print(job_id)
         retrieve_job = provider.retrieve_job(job_id)
 In [ ]:
         retrieve_job.status()
 In [ ]: from qiskit.tools.visualization import plot_histogram
         counts = retrieve_job.result().get_counts()
         plot_histogram(counts)
```

This lab was adapted from the Qiskit Textbook lab on iterative phase estimation as well as material from the dynamic circuits documentation.